How-To Library

Informatica

Installing the JDBC and ODBC Drivers for MySQL Connector

© Copyright Informatica LLC 2017, 2021. © Copyright Informatica LLC 2017. Informatica, Informatica Cloud, and the Informatica logo are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html.

Abstract

To establish a MySQL connection, you must install the JDBC and ODBC drivers on your system. This article explains how to install the JDBC and ODBC drivers based on your Windows or Linux system.

Supported Versions

- Informatica Cloud® Data Integration MySQL

Table of Contents

Overview. 2
Installing MySQL JDBC Driver 2
Installing MySQL ODBC Driver. 3
Installing MySQL ODBC Driver on Windows. 3
Installing MySQL ODBC Driver on Linux. 3
Updating the DTM Flag. 4

Overview

Before you establish a MySQL connection, you must install the JDBC and ODBC drivers on your system. The MySQL ODBC driver that you need to install vary based on the operating system that you use.

To install the JDBC and ODBC drivers, perform the following tasks:

1. Install the MySQL JDBC driver.
2. Install the MySQL ODBC driver.

   Note: If you install a different version of the MySQL ODBC driver, you must update the DTM flag to update the MySQL ODBC driver name.
3. Restart the Secure Agent.

Installing MySQL JDBC Driver

Perform the following steps to install the MySQL JDBC drivers on Windows or Linux system:

1. Click on the following link to download the MySQL JDBC driver: https://downloads.mysql.com/archives/c-j/
2. Select the **Product Version** as **5.1.40**.
3. Select the **Operating System** as **Platform Independent**.
4. Download the **.tar** or **.zip** file based on your Windows or Linux system.
5. Extract the downloaded file and copy the `mysql-connector-java-5.1.40-bin.jar` file.
6. Paste the `mysql-connector-java-5.1.40-bin.jar` file to the following location from where the Secure Agent can load the MySQL JDBC driver:

   For Windows system: `<AGENT_HOME>\apps\Data_Integration_Server\ext\drivers`

   For Linux system: `<AGENT_HOME>/apps/Data_Integration_Server/ext/drivers`

   Note: You must copy only one MySQL JDBC driver to the location from where the Secure Agent reads the MySQL JDBC driver.

Installing MySQL ODBC Driver

You must install the MySQL ODBC driver based on your Windows or Linux system before you use MySQL Connector.

Installing MySQL ODBC Driver on Windows


Perform the following steps to install the MySQL ODBC driver on Windows:

1. Click on the following link to download the MySQL ODBC driver: https://downloads.mysql.com/archives/c-odbc/
2. Select the **Product Version** as **5.3.7**.

   Informatica recommends that you use the MySQL ODBC driver version 5.3.7.
3. Select the **Operating System** as **Microsoft Windows**.
4. Select the **OS Version** as **Windows (x86, 64-bit)**.
5. Download the **MSI Installer**.
6. Run the **MSI Installer** and follow the installation wizard to complete the MySQL ODBC driver installation.

After you install the MySQL ODBC driver, check if **MySQL ODBC 5.3 Unicode Driver** name appears as one of the available ODBC driver under the **ODBC Data Source Administrator (64-bit)** dialog box.

The following image shows the **MySQL ODBC 5.3 Unicode Driver** driver name in the **ODBC Data Source Administrator (64-bit)** dialog box when you try to create a new data source:



Installing MySQL ODBC Driver on Linux

Perform the following steps to install the MySQL ODBC driver on Linux:

1. Click on the following link to download the MySQL ODBC driver: https://downloads.mysql.com/archives/c-odbc/
2. Select the **Product Version** as **5.3.7**.

   Informatica recommends that you use the MySQL ODBC driver version 5.3.7.
3. Select the **Operating System** as **Linux- Generic**.
4. Select the **OS Version** as **All**.

5. Download the **Linux - Generic (glibc 2.5) (x86, 64-bit)** file.
6. Extract the downloaded file and copy the `libmyodbc5w.so` file to your local system.
7. Edit the `<AGENT_HOME>/odbcinst.ini` file and add the following values:

```
[MySQL ODBC 5.3 Unicode Driver]
Description   = ODBC for MySQL
Driver        = <DRIVER_INSTALL_FILEPATH>/lib/libmyodbc5w.so
Setup         = <DRIVER_INSTALL_FILEPATH>/lib/libmyodbc5w.so
FileUsage     = 1
```

In Driver and Setup fields, you must specify the file path of the `libmyodbc5w.so` files that you copied in your local system.


Updating the DTM Flag

If you install a different version of the `MySQL_ODBC_DRIVER` driver on your Windows or Linux system, you must update the DTM flag.

Perform the following tasks to update the DTM flag:

1. In Administrator, select **Runtime Environments**.
2. On the **Runtime Environments** page, select the Secure Agent from the list of available Secure Agents.
3. In the upper-right corner, click **Edit**.
4. In the **System Configuration Details** page, select the **Type** field as **DTM** for the Data Integration Service.

   The following image shows the **System Configuration Details** section:



5. Select the **MySQL_ODBC_DRIVER** driver name under the **Name** column and click on the pencil icon to edit the value.
6. Update the name of the driver that you installed in the **Value** field.
7. Click **Save**.

Author

Subhashree Salam

Acknowledgements

The author would like to acknowledge Tanjot Singh Uppal, for his technical assistance with this article.