Informatica® Cloud Data Integration
October 2026

Getting Started

Informatica Cloud Data Integration Getting Started
October 2026

© Copyright Informatica LLC 2016, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices and AI assistant acknowledgements are included with the product.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-10-16

Table of Contents

Preface 5

Informatica Resources 5

- Informatica Documentation 5
- IDMC web site 5
- IDMC Communities 5
- IDMC Marketplace 5
- Data Integration connector documentation 6
- Informatica Knowledge Base 6
- IDMC Trust Center 6
- IDMC Pulse Dashboard 6
- Informatica Global Customer Support 6

Chapter 1: Getting Started with Informatica Cloud Data Integration 7

Chapter 2: System requirements 9

Enabling CORS in Internet Explorer 11 9

Chapter 3: Runtime environment configuration 14

Hosted Agent 15

Runtime environment configuration in a cloud environment 17

- Installing on AWS 17
- Installing on Google Cloud 20
- Installing on Microsoft Azure 22

Installing on Windows 24

- Secure Agent requirements on Windows 24
- Downloading and installing the Secure Agent on Windows 26
- Configuring the proxy settings on Windows 28
- Configuring a login for a Windows Secure Agent service 29

Installing on Linux 30

- Secure Agent requirements on Linux 30
- Downloading and installing the Secure Agent on Linux 31
- Configuring the proxy settings on Linux 33

Chapter 4: Connection configuration 35

Configuring a connection 35

Object search and selection 36

Chapter 5: Project setup 38

Creating projects and project folders 38

Creating assets 39

Chapter 6: Enabling source control. 40

Configuring repository access. 40

Chapter 7: Notifications. 41

Chapter 8: Editing your user profile. 42

Chapter 9: Editing your user settings. 43

Chapter 10: Inviting users to join your organization. 44

Chapter 11: Primary cloud data warehouse setup. 45

Configuring a primary cloud data warehouse. 45

Changing or unselecting a primary cloud data warehouse. 46

Chapter 12: Switching to a different organization. 47

Index. 48

Preface

Refer to *Getting Started* for information about how to begin using Informatica Cloud® Data Integration. *Getting Started* explains how to configure a runtime environment, connect Data Integration to your system, and begin a project.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the Informatica® Intelligent Data Management Cloud™ (IDMC) web site at http://www.informatica.com/cloud.

IDMC Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the IDMC Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security, compliance, and privacy practices.

You can access the trust center at https://trust.informatica.com/.

IDMC Pulse Dashboard

The IDMC Pulse Dashboard provides system status and upgrade information for all PODs and services across IDMC.

Follow the services you use and subscribe to alerts to receive notifications about upgrades, maintenance, production incidents, and upcoming releases. The IDMC Pulse Dashboard displays the production status of all the IDMC products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single service or all IDMC services. Subscribing to all services is the best way to be certain you never miss an update.

For more information, see the Service Status and Communications guide.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Getting Started with Informatica Cloud Data Integration

You can create a data integration project in just a few steps.

Step 1. Check system requirements

Be sure you're using a compatible browser when you're designing your projects, and check the IDMC Product Availability Matrix for operating systems, databases, and other systems that Data Integration supports.

Step 2. Configure a runtime environment

A runtime environment is the execution platform for running tasks. A runtime environment consists of one or more Secure Agents. A Secure Agent is a lightweight program that runs tasks and enables secure communication across the firewall between your organization and IDMC. You must have at least one runtime environment in each organization so that users in the organization can run tasks.

Step 3. Create a connection

Before you can use Data Integration to run data integration tasks, you need to create a connection. When you configure the connection, you specify the connector that enables the exchange of data between Data Integration and the source and target objects. For example, if you want to create a task that uses Salesforce data, you create a Salesforce connection. The Salesforce connection uses the Salesforce connector which enables the exchange of data between Salesforce and Data Integration.

Step 4. Create your project

Organize your data integration projects in folders that contain assets such as mappings, tasks, and taskflows. Create a project folder and folders to contain the assets you need for your project.

After you set up folders, create your project assets. Assets include the following objects:

- Mappings
- Tasks
- Taskflows
- Components such as business services, mapplets, and hierarchical schemas

Step 5. Add your project to the source control repository (optional)

If your organization is enabled for source control and the organization has read-write access to the source control repository, add your project to the repository.

Before you can add your project, your organization administrator must configure a link between the organization and source control repository, and you must specify your source control user credentials in IDMC.

Step 6. Configure reference data properties (optional)

If your organization uses Data Quality, enter the license keys for verifier asset reference data files. You enter the license keys as runtime environment properties in Administrator. You do not need to take additional steps to download and install the reference data files.

When you run a mapping that uses a verifier asset, the Secure Agent checks for the presence of the reference data files that the asset reads and downloads any file that is absent in the runtime environment.

You can review and update the properties that relate to the reference data in Administrator.

CHAPTER 2

System requirements

You can find information about system requirements in the Product Availability Matrix (PAM) for IDMC.

The PAM indicates the versions of browsers, operating systems, databases, and other types of data sources and targets that a product release supports. You can access the PAM on Informatica Network at https://network.informatica.com/community/informatica-network/product-availability-matrices/.


Enabling CORS in Internet Explorer 11

IDMC requires that cross-origin support (CORS) be enabled in Internet Explorer 11. In Internet Explorer 11, CORS is not enabled by default.

Note: Some company security policies restrict the ability of users to enable CORS in a web browser. Before you update these settings, verify that your company or IT department allows you to change the CORS settings.


1. Open Internet Explorer 11.
2. On the **Tools** menu, select **Internet Options**.

3. On the **Security** tab, click **Trusted sites**, and then click **Sites** as shown in the following image:




4. In the **Trusted Sites** dialog box, add the IDMC domain to the zone, and click **Add**.

For example, the following image shows the domain `https://*.informaticacloud.com` added to the zone:




5. Click **Close**.

6. In the **Security level for this zone** area on the **Security** tab, click **Custom level** as shown in the following image:



7. In the **Security Settings - Trusted Sites Zone** dialog box, scroll down to the **Miscellaneous** heading, and enable **Access data sources across domains** as shown in the following image:



8. Click **OK**.
9. If prompted, confirm that you want to change the settings for the zone.
10. Click **OK**.
11. Restart Internet Explorer and re-open IDMC.

CHAPTER 3

Runtime environment configuration

A runtime environment is the execution platform for running tasks. You must have at least one runtime environment in each organization so that users in the organization can run tasks.

A runtime environment consists of one or more Secure Agents. A Secure Agent is a lightweight program that runs tasks and enables secure communication across the firewall between your organization and IDMC.

You can create and access a runtime environment in the following ways:

Use the Informatica Cloud Hosted Agent.

This is the simplest and quickest option. The Hosted Agent is included with every installation of Data Integration.

When you want to access data in an SaaS environment, you can use the Informatica Cloud Hosted Agent. The Hosted Agent runs within the IDMC hosting facility, so there's nothing to install.

The Hosted Agent can run mapping, synchronization, and replication tasks that use certain connectors. To find out if the connector that you use supports the Hosted Agent, see the help for the relevant connector.

Configure a runtime environment on the cloud.

This is the second simplest method. The installation wizard does all the work behind the scenes to set up and configure a Secure Agent on AWS, Google Cloud, or Microsoft Azure.

Note: Configuring a runtime environment on the cloud creates a virtual machine on the cloud platform, which can incur additional costs.

Download and install a Secure Agent.

When you need to access data on-premises or when you want to access SaaS data without using the Hosted Agent, you can download and install a Secure Agent manually.

Download and install a runtime environment manually when you need to perform any of the following tasks:

- Run the agent on Windows.
- Install the agent on a local machine or a VM on a cloud platform other than AWS, Google Cloud, or Microsoft Azure.
- Access data sources that are behind a firewall.
- Run tasks that can't run on other runtime environment types. For example, Data Ingestion and Replication tasks must run on a local Secure Agent.

You can install one Secure Agent on each physical or virtual machine. Each agent that you install is added to its own group by default. You can add multiple agents to a group to balance workloads and improve scalability.

Configure a serverless runtime environment.

A serverless runtime environment is an advanced serverless deployment solution that doesn't require downloading, installing, configuring, and maintaining a Secure Agent or Secure Agent group.

Compared to the multi-tenant model on the Hosted Agent, a serverless runtime environment uses an isolated, single-tenant model that provides a dedicated server with virtual machine resources to run tasks. The serverless runtime environment auto-scales with the size of the workload while your data remains in your cloud environment.

For more information about configuring a serverless runtime environment, see *Runtime Environments* in the Administrator help.

Hosted Agent

The Hosted Agent can run synchronization, mapping, and replication tasks that use certain connectors.

IDMC manages the Hosted Agent runtime environment, so you cannot add, delete, or configure a Hosted Agent.

The Hosted Agent can run synchronization, mapping, and replication tasks that use the following connectors:

- Amazon Athena Connector
- Amazon Aurora Connector
- Amazon Redshift Connector
- Amazon Redshift V2 Connector
- Amazon S3 Connector
- Amazon S3 V2 Connector
- Box Connector
- Box Oauth Connector
- Cloud Integration Hub
- Concur V2 Connector
- Coupa Connector
- Coupa V2 Connector
- Cvent Connector
- Databricks Delta Connector
- DB2 Warehouse on Cloud Connector
- Eloqua Bulk API Connector
- Google Analytics Connector
- Google Big Query Connector
- Google Big Query V2 Connector
- Google Cloud Storage Connector

- Google Cloud Storage V2 Connector
- JIRA Connector
- Marketo V3 Connector
- Microsoft Azure Blob Storage V2 Connector
- Microsoft Azure Blob Storage V3 Connector
- Microsoft Azure Cosmos DB SQL API Connector
- Microsoft Azure Data Lake Storage Gen1 V2 Connector
- Microsoft Azure Data Lake Storage Gen1 V3 Connector
- Microsoft Azure Data Lake Storage Gen2 Connector
- Microsoft Azure SQL Data Warehouse V2 Connector
- Microsoft Azure SQL Data Warehouse V3 Connector
- Microsoft Azure Synapse SQL Connector
- Microsoft CDM Folders V2 Connector
- Microsoft Dynamics 365 for Operations Connector
- Microsoft Dynamics 365 for Sales Connector
- Microsoft Fabric Data Warehouse Connector
- Microsoft Fabric Lakehouse Connector
- Microsoft Fabric OneLake Connector
- Microsoft SQL Server Connector
- MySQL Connector
- NetSuite Connector
- OData Connector
- Oracle Connector
- PostgreSQL Connector
- REST V2 Connector
- Salesforce Connector
- Salesforce Marketing Cloud Connector
- Salesforce Oauth Connector
- ServiceNow Connector
- Snowflake Cloud Data Warehouse V2 Connector
- SuccessFactors ODATA Connector
- UltiPro Connector
- Workday V2 Connector
- Xactly Connector
- Zendesk V2 Connector
- Zuora AQuA Connector

Note: The Hosted Agent support is specific to connectors. For more information, see the help for the relevant connector.


Runtime environment configuration in a cloud environment

You can install and run a Secure Agent on AWS, Google Cloud, or Microsoft Azure.


Install a Secure Agent in the following ways based on your cloud environment:

- If you choose AWS, you're redirected to the AWS Marketplace to continue the installation.
- If you choose Google Cloud, you log in using your Google credentials and then enter the Secure Agent configuration details.
- If you choose Microsoft Azure, you log in using your Azure credentials and then enter the Secure Agent configuration details.

You can install a Secure Agent in a cloud environment on the **Runtime Environments** page in Administrator. Click **Manage Cloud Secure Agents** to open the installer, as shown in the following image:



If your organization uses the unified **Home** page and your organization doesn't have any runtime environments, you can also install a Secure Agent in a cloud environment by clicking **Next** in the **To get started, you must first set up a runtime environment** panel, as shown in the following image:



Installing on AWS

The Secure Agent installer can help you create a runtime environment in supported regions on Amazon Web Services (AWS). The runtime environment you create is a Secure Agent group that contains one Secure Agent.

You can create a runtime environment in the following regions:

- us-east-1
- us-west-2
- ca-central-1
- eu-central-1
- eu-west-1

- eu-west-2
- ap-northeast-1
- ap-southeast-2

When you create a runtime environment on AWS, you create a new stack where the Secure Agent is deployed. You can create the stack in a new or existing virtual private cloud (VPC). The installer creates an Amazon Elastic Compute Cloud (EC2) instance within the VPC.

To create a runtime environment, you must have a subscription with AWS that includes create, modify, and delete privileges for the following resource types:

- EC2 instances
- Elastic IP addresses
- Elastic network interfaces
- Internet gateways
- Route tables
- Security groups
- Subnets
- VPCs

You must also have read and launch permissions for machine images.

Note: Exclude the following directory from security scans: `<Secure Agent installation directory>/apps`. Scanning files in this directory can interfere with the operation of the Secure Agent.

1. In Administrator, select **Runtime Environments**.
2. On the **Runtime Environments** page, click **Manage Cloud Secure Agents**.
3. Click **New Cloud Secure Agent**.
4. Select **Amazon Web Services**.
5. Click **Next**.
6. On the **Environment Configuration** page, copy the install token.

   The install token is valid for 24 hours and can't be reused.
7. Choose whether to create the runtime environment on an existing or new VPC.
8. Click **Continue Configuration in AWS**.

   The AWS **Sign in** screen opens in a new browser tab.
9. Sign in to your AWS account.

   The **Quick create stack** page opens.
10. In the **Stack name** area, enter a stack name.
11. In the **Parameters** area, under **Network Configuration**, configure the following properties based on whether you're using an existing VPC or a new VPC.

- For an existing VPC, configure the following properties:

Property	Value
VPC ID	Select the ID for the VPC where you want to deploy the Secure Agent.
Subnet ID	Enter or select a subnet within the VPC.
Allowed Remote Access CIDR	Enter the CIDR block that specifies the IP addresses where the Secure Agent can be installed. CIDR (Classless Inter-Domain Routing) is a method for allocating IP addresses. It configures a network rule to allow remote access to the Secure Agent. The "/x" portion of the address determines how many IP addresses are available in the subnet, for example: 108.124.81.10/32

- For a new VPC, configure the following properties:

Property	Value
Availability Zones	Select the availability zone for your region.
VPC CIDR	Enter the CIDR block that specifies the IP addresses where you want to create the VPC.
Subnet CIDR	Enter the CIDR block that specifies the IP addresses for the subnet in the availability zone that you selected.
Allowed Remote Access CIDR	Enter the CIDR block that specifies the IP addresses where the Secure Agent can be installed.

12. Under **Amazon EC2 Configuration**, configure the following properties:

Property	Value
Key Pair Name	Enter the name of an existing EC2 key pair to enable external access to the EC2 instance. Corresponding key pair files are required for SSH access to the server.
Instance Type	Select the instance type for the EC2 instance or accept the default. Default is m5.xlarge.
Enable Elastic IP Addressing	Choose whether to assign elastic IP addresses to the EC2 instance or accept the default. Default is no.

13. Under **Informatica Intelligent Data Management Cloud (IDMC) Account Details**, configure the following properties:

Property	Value
IDMC POD Master URL	Accept the default value for the IDMC POD Master URL. This is the URL that you use to access IDMC. **Warning:** Changing this URL can result in stack deployment failure.
IDMC User Name	Enter your IDMC user name.
IDMC User Token	Paste the install token that you copied. If you forgot to copy the install token, you can switch back to IDMC and generate a new one.
Secure Agent Group Name	Accept the default value for the Secure Agent group name. This is the name of the runtime environment that you're creating.

14. Click **Create stack**.

    It takes a few minutes to create the stack. Be sure to monitor the stack creation and address any issues that might occur.

    When the stack is created successfully, the EC2 Instance status changes from CREATE_IN_PROGRESS to CREATE_COMPLETE.

15. In IDMC, on the **Environment Configuration** page, click **Finish**.

    IDMC creates your runtime environment and displays it on the **Runtime Environments** page.

    Tip: To see the progress of your pending Secure Agents, click **Manage Cloud Secure Agents** on the **Runtime Environments** page. The status appears at the top of the page.

It takes a few minutes for the Secure Agent services to start. When the Secure Agent is ready to use, the status changes from "Pending Environment Set Up" to "Up and Running." You might need to refresh the page to see the updated status.

Installing on Google Cloud

The Secure Agent installer can create a runtime environment on Google Cloud for you, based on just a few properties that you enter on the configuration page. Ensure that you have a subscription with Google Cloud that includes permissions to deploy resources.

Note: Exclude the following directory from security scans: `<Secure Agent installation directory>/apps`. Scanning files in this directory can interfere with the operation of the Secure Agent.

1. In Administrator, select **Runtime Environments**.
2. On the **Runtime Environments** page, click **Manage Cloud Secure Agents**.
3. Select **Google Cloud Platform**.
4. Click **Next**.
5. Select the Google account to use.

6. Enter the following properties:

Property	Description
Project	A project defines how IDMC interacts with Google services and what resources it uses. Select your Google Cloud project from the drop-down list. **Note:** If you don't have a project, exit the installation wizard and create your project on Google Cloud. You can't create a project from within IDMC.
Secure Agent Name	Enter a name for your Secure Agent. The name needs to conform to the following rules: - The name can be up to 43 characters long, with a combination of letters, numbers, and hyphens. - The first character must be a lowercase letter. - The last character can't be a hyphen. - All letters must be lowercase. By default, the runtime environment uses the same name as the agent.
Region	Select the region to deploy the Secure Agent. Choose a region that's appropriate for your organization and your customers.
Machine Type	Select the machine type for your virtual machine. If you're not familiar with Google machine types, start with a size with at least 4 cores and 16 GB of memory.
Virtual Network	Specify whether to use an existing virtual network based on your Google subscription or create a new virtual network. A virtual network uses hardware and software to emulate a physical network.
Virtual Network Name	Select an existing virtual network or enter the name for a new virtual network.
Subnet	Select the subnet to use or enter a name for a new subnet.
Subnet Address	Select the subnet address that includes all the resources or enter a new subnet address. Subnet addressing allows a system made up of multiple networks to share the same Internet address.

7. Select the **I acknowledge this action will incur costs on Google Cloud Platform** check box to acknowledge that costs will be incurred on your Google account.
8. Click **Create**.
   IDMC creates your runtime environment and displays it on the **Runtime Environments** page.

Troubleshooting connection issues on Google Cloud

The firewall on Google Cloud can block access to your VM. If this occurs, add a firewall rule to allow RDP and SSH access to your VM instances.

When Google Cloud blocks access, the runtime environment fails to start with the following error:

```
Connection Failed. We are unable to connect to the VM on port 22.
```

1. On the Google Cloud console, go to the **Firewall Rules** page.
2. Click **Create firewall rule**.

3. Create a firewall rule with the following settings:

Setting	Value
Name	Enter a name for the firewall rule. For example: `allow-ingress-from-iap(<name>)`
Direction of traffic	Ingress
Action on match	allow
Target	All instances in the network
Source filter	IP ranges
Source IP ranges	35.235.240.0/20
Protocols and ports	Select **TCP** and enter `22,3389` to allow both RDP and SSH.

4. Click **Create**.

Installing on Microsoft Azure

The Secure Agent installer can configure a runtime environment on Microsoft Azure. Note that running data integration tasks on Azure incurs costs based on the workload and the VM size.

Note: Exclude the following directory from security scans: `<Secure Agent installation directory>/apps`. Scanning files in this directory can interfere with the operation of the Secure Agent.

Before you proceed, ensure that you have a Microsoft Azure subscription with permissions that allow you to deploy resources. If admin consent is enabled at your organization, reach out to the Azure administrator for app consent approvals. For more information about admin consent requests, see the Microsoft documentation.

1. In Administrator, select **Runtime Environments**.
2. On the **Runtime Environments** page, click **Manage Cloud Secure Agents**.
3. Click **New Cloud Secure Agent**.
4. Select **Microsoft Azure**.
5. Click **Next**.
6. Select the Microsoft account to use.

7. Enter the following properties:

Property	Description
Subscription	Select your Microsoft Azure subscription. The subscription must include permissions to deploy the following resources: - Network security group - Virtual network (including subnet) - Network interface - Public IP address - OS disk - Virtual machine Be sure to grant permission to the Hyperscalar Azure Integration App when prompted. **Note:** If you do not have an Azure subscription, exit the installer and sign up for one with Microsoft. You cannot sign up from within IDMC.
Resource Group	A resource group is a container that holds related resources for your runtime environment. IDMC uses one resource group for each Secure Agent to simplify management of the VM resources for that agent. You typically create new resource groups, but you can use any existing group that is empty. **Tip:** Use the same or similar name as the Secure Agent to more easily identify which resource group belongs with each agent.
Resource Group Name	Name of the resource group. Enter the name of a new group or select an existing group. Ensure that any existing resource group is empty, otherwise this message appears*: "API Input validation failed."*
Location	Select the region to deploy the Secure Agent. Choose the Azure region that's appropriate for your organization and your customers. Not every resource is available in every region.
VM Name	Enter a name for the virtual machine (VM) that will be created.
VM User Name	Enter your name as the virtual machine user.
VM Password	Enter a password to access the virtual machine.
Secure Agent Name	Enter a name for your Secure Agent. By default, the runtime environment has the same name as the agent. **Tip:** Use the same or similar name as the resource group, to more easily identify which resource group belongs with each agent.
VM Size	Select a size for your virtual machine. If you are unfamiliar with Azure image sizing, start with a size with at least 4 cores and 16 GB of memory. Note that your Azure hourly charges are affected by the VM size.
Virtual Network	Select an existing virtual network based on your Microsoft Azure subscription and location or create a new virtual network.
Virtual Network Name	Select an existing virtual network or enter the name for a new virtual network. When you select an existing virtual network, this associates the newly created VM with the existing VNet.
Virtual Network Address	Select an existing virtual network address or enter a new address.

Property	Description
Subnet Name	Select the subnet to use or enter a name for a new subnet. The subnet holds all the Azure resources that are deployed to the virtual network.
Subnet Address	Select the subnet address that includes all the resources or enter a new subnet address. Subnet addressing allows a system made up of multiple networks to share the same Internet address.
CIDR IP Address Range	Enter the CIDR IP address range. CIDR (Classless Inter-Domain Routing) is a method for allocating IP addresses. It configures a network rule to allow remote access to the Secure Agent. The "/x" portion of the address determines how many IP addresses are available in the subnet, for example: 108.124.81.10/32

Tip: For more information, refer to "Explore Azure Virtual Networks" in the Microsoft documentation.

8. Click **Create**. Administrator creates your runtime environment and displays it on the **Runtime Environments** page.

   Tip: To see the progress of your pending Secure Agents, click **Manage Cloud Secure Agents** on the **Runtime Environments** page. The status appears at the top of the page.

Installing on Windows

On Windows, the Secure Agent runs as a Windows service. When you install the Secure Agent, you also install the Informatica Cloud Secure Agent Manager.

By default, the Secure Agent starts when you start Windows. You can stop and restart the Secure Agent using the Secure Agent Manager or Windows Services. If you install the Secure Agent on a different volume than you use to run the installation program, you must start and stop the Secure Agent from Windows Services.

You can also use the Secure Agent Manager to check the Secure Agent status and configure proxy information. The Secure Agent works with BASIC, DIGEST, and NTLMv2 proxy authentication.

You can launch the Secure Agent Manager from the Start menu or desktop icon. When you close the Secure Agent Manager, it minimizes to the Windows taskbar notification area for quick access.

When you install a Secure Agent, you perform the following tasks:

1. Verify that the machine meets the minimum requirements.
2. Download the Secure Agent installer files.
3. Install and register the Secure Agent.

Secure Agent requirements on Windows

You can install the Secure Agent on any machine that has internet connectivity and can access IDMC.

Verify the following requirements before you install the Secure Agent on Windows:

- The Secure Agent machine uses a supported operating system. For the list of supported operating systems for the Secure Agent, see the Product Availability Matrix (PAM) for Intelligent Data Management Cloud on the Knowledge Base.

- The Secure Agent machine has the following attributes at a minimum:
  - x86 64-bit architecture
  - 4 CPU cores
  - 16 GB RAM
  - 5 GB free disk space
- The Secure Agent machine is on a volume with at least 250GB disk space, with at least 5 GB free space or three times the size of the Secure Agent installation, whichever is greater.
- The account you use to install the Secure Agent has access to all remote directories that contain flat source or target files.
- No other Secure Agent is installed on the machine. If another Secure Agent is installed on the machine, uninstall it first.

For more information, see this KB article:
Minimum requirements and best practices when installing Informatica Cloud Secure Agent.

Configuring the firewall

If your organization uses a protective firewall, include the IDMC domain name or IP address ranges in the list of approved domain names or IP addresses. To ensure that the Secure Agent can perform all necessary tasks through the firewall, enable the port that the Secure Agent uses.

The Secure Agent uses port 443 (HTTPS) to connect to the internet. Configure your firewall to allow traffic to pass over port 443. Also exclude the following directory from security scans: `<Secure Agent installation directory>/apps`. Scanning files in this directory can interfere with the operation of the Secure Agent.

The list of allowed domains and IP addresses can vary according to your POD (Point of Deployment). You can identify your POD through the URL that appears when you open any service. The first few characters of the URL string identify the POD. For example, if the URL starts with `usw3.dm-us.informaticacloud.com`, your POD is USW3.

For the list of all the domains and IP addresses that you must allow for the different PODs, see Pod Availability and Networking.

Setting Secure Agent permissions on Windows

A Secure Agent requires certain permissions to transfer data between sources and targets.

When you install a Secure Agent on Windows, the Secure Agent must be part of the local Administrators group.

Configuring Windows settings

Before you use the Secure Agent on Windows, configure proxy settings and a Windows Secure Agent service login.

You can configure proxy settings in Secure Agent Manager. Configure a login for the Windows Secure Agent service on Windows.

Note: If you use the Secure Agent for Informatica Cloud Data Wizard, you do not need to configure proxy settings or a Windows service login for the Secure Agent.

Downloading and installing the Secure Agent on Windows

To install the Secure Agent on a Windows machine, download and run the Secure Agent installer and then register the agent.

Before you download and install the Secure Agent, verify that no other Secure Agent is installed on the machine. If any other Secure Agent exists, you must uninstall it first.

Tip: To verify the checksum of the Secure Agent installation program, use the agent REST API version 2 resource. For more information about the agent resource, see *REST API Reference*.

1. Open Administrator and select **Runtime Environments**.
2. On the **Runtime Environments** page, click **Download Runtime Installer**.
3. Select **Secure Agent** as the environment type.
4. Select **Windows 64** as the platform.
5. Click **Copy** to copy the install token.


   You will need this token to install the Secure Agent. The token expires after 24 hours. If the token expires before you install the Secure Agent, repeat steps 1 to 5 to obtain a new token. You don't need to download the installer again.
6. Click **Download**.

   The installer is downloaded to your machine. The name of the installer is `agent64_install_ng_ext.<agent core version>.exe`.
7. Run the installer as an Administrator and complete the following steps:
   a. Specify the Secure Agent installation directory, and click **Next**.

      Note: Ensure that the file path doesn't contain multibyte characters. If the path contains multibyte characters, the Secure Agent might not start.

   b. Click **Install** to install the agent.

The **Cloud Secure Agent** dialog box opens and prompts you to register the agent as shown in the following image:



8. In the Secure Agent Manager, enter the following information, and then click **Register**:

Option	Description
User Name	User name that you use to access IDMC.
Install Token	Token that you copied when you downloaded the runtime installer.

The Secure Agent Manager displays the status of the Secure Agent. It takes a minute for all of the services to start.

Tip: When you register the agent, it is added to its own Secure Agent group by default. You can add the agent to a different Secure Agent group if necessary.

9. If your organization uses an outgoing proxy server to connect to the internet, enter the proxy server information.
10. Close the Secure Agent Manager.

    The Secure Agent Manager minimizes to the taskbar and continues to run as a service until stopped.

Configuring the proxy settings on Windows

If your organization uses an outgoing proxy server to connect to the internet, the Secure Agent connects to IDMC through the proxy server.

Important: Activating proxy settings might expose sensitive data to any user with Secure Agent installation privileges. This sensitive data can include connector configurations and credentials. To mitigate the risk of sensitive data leakage, you must strictly limit edit and update permissions on all connections to authorized personnel only. For more information about role privileges, see *User Administration*.

The Secure Agent installer configures default proxy server settings for the Secure Agent based on settings configured in the browser. The proxy settings are stored in the proxy configuration file, `proxy.ini`, in the following directory:

```
<Secure Agent installation directory>/apps/agentcore/conf
```

The following code shows the default contents of the proxy configuration file:

```
InfaAgent.ProxyPassword=ZU8KjIzgtVrVmfRMUPzPMw\=\=
InfaAgent.ProxyNtDomain=
InfaAgent.ProxyHost=foo.bar.com
InfaAgent.ProxyPasswordEncrypted=true
InfaAgent.NonProxyHost=localhost|127.*|[\:\:1]
InfaAgent.ProxyUser=
InfaAgent.ProxyPort=12345
InfaAgent.AuthenticationOrder=
```

To update proxy hosts and ports, as well as the username and password used to connect to the proxy server, use the Secure Agent Manager. The Secure Agent Manager validates the values that you enter. For more information, see "Updating proxy settings through the Secure Agent Manager" on page 28.

To update other properties, edit the proxy configuration file directly. When you edit the proxy configuration file, ensure that you use the correct formats to avoid errors. For more information, see "Updating proxy settings in the proxy configuration file" on page 29.

To allow the Secure Agent to connect to data sources and targets, configure proxy settings through JVM Options in addition to configuring the proxy configuration file. For more information, see the help for the appropriate connector.

Some use cases require the Secure Agent to bypass the proxy server and communicate directly with the instance metadata service (IMDS), which stores temporary security credentials. For example, bypassing the proxy server is required if you use an Azure managed identity to access sources and targets in a mapping in advanced mode and if you enable the **Use EC2 Role to Assume Role** property in an Amazon S3 V2 connection. To allow the agent to communicate directly with the IMDS, edit the proxy configuration file and set the IP address of the IMDS, 169.254.169.254, in the value for the property *InfaAgent.NonProxyHost*.

Contact your network administrator for the correct proxy settings.

Updating proxy settings through the Secure Agent Manager

To update proxy hosts, proxy ports, and the username and password used to connect to the proxy server, edit the proxy settings through the Secure Agent Manager.

1. In the Secure Agent Manager, click **Proxy**.
2. To enter proxy server settings, click **Use a Proxy Server**.

3. Enter the following information:

Field	Description
Proxy Host	Required. Host name of the outgoing proxy server that the Secure Agent uses.
Proxy Port	Required. Port number of the outgoing proxy server.
User Name	User name to connect to the outgoing proxy server.
Password	Password to connect to the outgoing proxy server.

4. Click **OK**.

   The Secure Agent Manager restarts the Secure Agent to apply the settings.

Updating proxy settings in the proxy configuration file

To update proxy settings that you can't update through the Secure Agent Manager, edit the proxy configuration file directly.

1. Open the `proxy.ini` file.
2. Update the property values as required. Use the pipe character (|) as a delimiter to combine a list of host names and IP addresses. You can enter a wildcard to the left for host names or to the right for IP addresses.

   For example, the following value uses two formats to exclude cluster IP addresses in the CIDR block 172.16.0.0/16:

   ```
   InfaAgent.NonProxyHost=localhost|127.|[\:\:1]|123.432.|172.16.*|172.16.0.0/16
   ```
3. Restart the Secure Agent for the changes to take effect.

The proxy details appear on the Secure Agent Manager settings page for the proxy server.

Configuring a login for a Windows Secure Agent service

On Windows, configure a network login for the Secure Agent service. The Secure Agent can access the network with the privileges and permissions associated with the login.

Configure a login for the Secure Agent machine to allow the Secure Agent to access directories to configure and run tasks. When you configure connections, configure tasks, and run tasks that use flat file or FTP/SFTP connection types, the Secure Agent might require read and write permissions on the related directories.

For example, to browse to a directory to configure a flat file or FTP/SFTP connection, the Secure Agent login might require permission to access the directory. Without a Secure Agent login with the appropriate permissions, IDMC cannot display the directory in the **Browse for Directory** dialog box.

1. Go to the **Services** window from the Windows Administrative tools.
2. In the **Services** window, right-click the Informatica Cloud Secure Agent service and choose **Properties**.
3. In the **Properties** dialog box, click the **Log On** tab.
4. To configure a login, select **This Account**.
5. Enter an account and password.

   Use an account with the required privileges and permissions for the network security defined for the domain. By default, the account format is <domain name>\<user name>.

6. Click **OK**.
7. In the **Services** window, restart the Secure Agent service for the changes to take effect.

Installing on Linux

On Linux, the Secure Agent runs as a process. You can use a shell command line to install, register, start, stop, and uninstall the Secure Agent.

You can also use the shell command line to check the Secure Agent status.

When you install a Secure Agent, you perform the following tasks:

1. Verify that the machine meets the minimum requirements.
2. Download the Secure Agent installer files.
3. Install and register the Secure Agent.

Consider the following guidelines:

- Create a specific user profile to install the Secure Agent with full access to all folders from the Secure Agent installation directory. Don't install the Secure Agent as the root user.
- You can't install more than one Secure Agent on the same machine under the same user account. Multiple agents may exist under different user accounts.
- Don't install the Secure Agent on any node within the Informatica domain.

Secure Agent requirements on Linux

You can install the Secure Agent on any machine that has internet connectivity and can access IDMC. Before you install the Secure Agent on Linux, verify the system requirements.

Verify the following requirements before you install the Secure Agent on Linux:

- Verify that the Secure Agent machine uses a supported operating system. For the list of supported operating systems for the Secure Agent, see the Product Availability Matrix (PAM) for Intelligent Data Management Cloud on the Knowledge Base.
- Verify that the Secure Agent machine is running the x86 64-bit architecture, with at least 11 GB free disk space.
- Verify that the `libidn.x86_64` package is installed.
  If the package isn't present, install it using the following command: `sudo yum install libidn.x86_64`

  Note: The command to install the package might vary based on your Linux distribution.
- Verify that the `libidn.so.*` libraries are installed.
  If the libraries aren't present, run the following commands:
  1. Change to the appropriate directory on the Secure Agent machine.
     - For 64-bit systems: `cd /usr/lib/x86_64-linux-gnu`
     - For 32-bit systems: `cd /usr/lib/i386-linux-gnu`
  2. Create a symbolic link using the following command:

     ```
     sudo ln -s libidn.so.12 libidn.so.11
     ```

If you are installing the Secure Agent on RHEL 9, create an additional symbolic link using the following command:

```
sudo ln -s libidn2.so.0 libidn.so.11
```

- The account that you use to install the Secure Agent must have access to all remote directories that contain flat source or target files.
- If you use PowerCenter, install the Secure Agent using a different user account than the account you used to install PowerCenter.
  IDMC and PowerCenter use some common environment variables. If the environment variables are not set correctly for IDMC, your jobs might fail at run time.

For more information, see this KB article:
Minimum requirements and best practices when installing Informatica Cloud Secure Agent.

Configure the firewall

If your organization uses a protective firewall, include the IDMC domain name or IP address ranges in the list of approved domain names or IP addresses. To ensure that the Secure Agent can perform all necessary tasks through the firewall, enable the port that the Secure Agent uses.

The Secure Agent uses port 443 (HTTPS) to connect to the internet. Configure your firewall to allow traffic to pass over port 443. Also exclude the following directory from security scans: `<Secure Agent installation directory>/apps`. Scanning files in this directory can interfere with the operation of the Secure Agent.

The list of allowed domains and IP addresses can vary according to your POD (Point of Deployment). You can identify your POD through the URL that appears when you open any service. The first few characters of the URL string identify the POD. For example, if the URL starts with `usw3.dm-us.informaticacloud.com`, your POD is USW3.

For the list of all the domains and IP addresses that you must allow for the different PODs, see Pod Availability and Networking.

Setting Secure Agent permissions on Linux

A Secure Agent requires certain permissions to transfer data between sources and targets.

When you install a Secure Agent on Linux, the Secure Agent must have read/write/execute permissions for the installation directory.

Downloading and installing the Secure Agent on Linux

To install the Secure Agent on a Linux machine, download and run the Secure Agent installer and then register the agent.

Before you download and install the Secure Agent, verify that no other Secure Agent is installed on the machine using the same Linux user account. If any other Secure Agent exists, you must uninstall it first.

Tip: To verify the checksum of the Secure Agent installation program, use the agent REST API version 2 resource. For more information about the agent resource, see *REST API Reference*.

1. Open Administrator and select **Runtime Environments**.
2. On the **Runtime Environments** page, click **Download Runtime Installer**.
3. Select **Secure Agent** as the Environment Type.
4. Select **Linux 64** as the Platform.
5. Click **Copy** to copy the install token.

You will need this token to install the Secure Agent. The token expires after 24 hours. If the token expires before you install the Secure Agent, repeat steps 1 to 5 to obtain a new token. You don't need to download the installer again.

6. Click **Download**.

   The installer is downloaded to your machine. The name of the installer is `agent64_install_ng_ext.<agent core version>.bin`.

7. Save the installer to a directory on the machine where you want to run the Secure Agent.

   Note: Ensure that the file path doesn't contain spaces or multibyte characters. If the file path contains spaces, the installation might fail. If the path contains multibyte characters, the Secure Agent might not start.

8. From a shell command line, navigate to the directory where you downloaded the installation program and enter the following command:

   ```
   ./agent64_install_ng_ext.bin -i console
   ```

9. When the installer completes, navigate to the following directory:

   ```
   <Secure Agent installation directory>/apps/agentcore
   ```

10. To start the Secure Agent, enter the following command:

    ```
    ./infaagent.sh startup
    ```

    The Secure Agent Manager starts. Register the agent using the user name that you use to access IDMC and also supply the install token.

11. To register the agent, in the `<Secure Agent installation directory>/apps/agentcore` directory, enter one of the following commands using your IDMC user name and the token that you copied:

    - To add the agent to its own Secure Agent group, use the following command:

      ```
      ./consoleAgentManager.sh configureToken <user name> <install token>
      ```

    - To add the agent to an existing Secure Agent group, use the following command:

      ```
      ./consoleAgentManager.sh configureTokenWithRuntime <user name> <install token>
      <Secure Agent group name>
      ```

      Note: If the command includes a Secure Agent group name that doesn't exist, the Secure Agent is not assigned to a group. Be sure to use a valid Secure Agent group name.

    The following table lists the command options:

Option	Description
User Name	Required. IDMC user name of the user installing the Secure Agent.
Install Token	Required. The install token that you copied when you downloaded the runtime installer.
Secure Agent group name	Optional. Include a group name when you want to add the agent to an existing Secure Agent group instead. If this option isn't included in the command, the agent will be in its own Secure Agent group.

You can check the registration status of a Secure Agent using the following command:

```
./consoleAgentManager.sh isConfigured
```

Configuring the proxy settings on Linux

If your organization uses an outgoing proxy server to connect to the internet, the Secure Agent connects to IDMC through the proxy server.

Important: Activating proxy settings might expose sensitive data to any user with Secure Agent installation privileges. This sensitive data can include connector configurations and credentials. To mitigate the risk of sensitive data leakage, you must strictly limit edit and update permissions on all connections to authorized personnel only. For more information about role privileges, see *User Administration*.

The Secure Agent installer configures default proxy server settings for the Secure Agent based on settings configured in the browser. The proxy settings are stored in the proxy configuration file, `proxy.ini`, in the following directory:

```
<Secure Agent installation directory>/apps/agentcore/conf
```

The following code shows the default contents of the proxy configuration file:

```
InfaAgent.ProxyPassword=ZU8KjIzgtVrVmfRMUPzPMw\=\=
InfaAgent.ProxyNtDomain=
InfaAgent.ProxyHost=foo.bar.com
InfaAgent.ProxyPasswordEncrypted=true
InfaAgent.NonProxyHost=localhost|127.*|[\:\:1]
InfaAgent.ProxyUser=
InfaAgent.ProxyPort=12345
InfaAgent.AuthenticationOrder=
```

To update proxy hosts and ports, as well as the username and password to connect to the proxy server, use the command line. The command line validates the values that you enter. For more information, see "Updating proxy settings through the command line" on page 33.

To update other properties, edit the proxy configuration file directly. When you edit the proxy configuration file, ensure that you use the correct formats to avoid errors. For more information, see "Updating proxy settings in the proxy configuration file" on page 34.

To allow the Secure Agent to connect to data sources and targets, configure proxy settings through JVM Options in addition to configuring the proxy configuration file. For more information, see the help for the appropriate connector.

Some use cases require the Secure Agent to bypass the proxy server and communicate directly with the instance metadata service (IMDS), which stores temporary security credentials. For example, bypassing the proxy server is required if you use an Azure managed identity to access sources and targets in a mapping in advanced mode and if you enable the **Use EC2 Role to Assume Role** property in an Amazon S3 V2 connection. To allow the agent to communicate directly with the IMDS, edit the proxy configuration file and set the IP address of the IMDS, 169.254.169.254, in the value for the property *InfaAgent.NonProxyHost*.

Contact your network administrator for the correct proxy settings.

Updating proxy settings through the command line

To update proxy hosts, proxy ports, and the username and password to connect to the proxy server, use the command line to update the proxy configuration file.

1. Navigate to the following directory:

   ```
   <Secure Agent installation directory>/apps/agentcore/conf
   ```

2. To update the proxy configuration file, `proxy.ini`, run the following command:

   ```
   ./consoleAgentManager.sh configureProxy <proxy host> <proxy port> <proxy user name>
   <proxy password>
   ```

3. Restart the Secure Agent.

Updating proxy settings in the proxy configuration file

To update proxy settings that you can't update through the command line, edit the proxy configuration file directly.

1. Open the `proxy.ini` file.
2. Update the property values as required. Use the pipe character (|) as a delimiter to combine a list of host names and IP addresses. You can enter a wildcard to the left for host names or to the right for IP addresses.

   For example, the following value uses two formats to exclude cluster IP addresses in the CIDR block 172.16.0.0/16:

   ```
   InfaAgent.NonProxyHost=localhost|127.|[\:\:1]|123.432.|172.16.*|172.16.0.0/16
   ```
3. Restart the Secure Agent for the changes to take effect.

CHAPTER 4

Connection configuration

When you create a connection, it's available to your Data Integration organization.

For most connection types, when you configure a connection, you specify the runtime environment for the connection. The runtime environment must contain an agent that is running when you configure the connection. For other connection types, you specify the runtime environment when you configure the task.

This section includes general information about setting up a connection. For more information about connections and for specific information about configuring flat file and FTP connections, see *Connections*. For specific information about other connection types, see the Data Integration Connector topics in the **Connectors** section of the help.

Configuring a connection

You can configure a connection on the **Connections** page, in a wizard as you configure a task or taskflow, or in the Mapping Designer as you configure a mapping.


To access the **Connections** page, in Administrator, select **Connections**.

1. Configure the following connection details:


Connection detail	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + - Maximum length is 100 characters. Connection names are not case sensitive.
Description	Description of the connection. Maximum length is 255 characters.
Type	Type of connection, such as Salesforce or Oracle.

2. Configure the connection-specific properties. For example, if this is a Flat File connection type, enter the runtime environment to be used with the connection, the directory where the flat file is stored, the date

format for date fields in the flat file, and the code page of the system that hosts the flat file. The following image shows the property fields for a flat file connection:



3. To test the connection, click **Test**. The results of the test display on the page, as shown in the following image:



If a database connection fails, contact the database administrator.

4. Click **Save** to save the connection.

Object search and selection

When you select a connection in a Data Integration mapping or task, you can search for the object or objects that you want to use.

When you search for an object, the **Select Object** dialog box displays the objects available for the connection. You can select one of the objects or you can enter a search string. To begin a search, click **Search** or press **Enter**.

Note: For some connection types, you must select the schema associated with the object in the **Packages** pane before you can view and select objects. You can search for the schema to use.

For synchronization and mapping tasks, use object search when the connection responds slowly.

Use the following guidelines when you enter a search string:

- Use an asterisk (*) as a wildcard character.
- Use quotation marks (") to perform an exact search. An exact search is case-sensitive.
- You can use the following search parameters based on the connection type:

Connection type	Search parameters
Databases	Name
CDC	Name
Flat File	Name

CHAPTER 5

Project setup

Create projects and project folders on the **Explore** page to organize your assets. After you have set up the runtime environment and connections that are required for a project, you can create the assets for the project.

You can't use the following characters:


```
# ? ' | { } " ^ & [ ] / \
```

Do not use these characters in project, folder, asset, or tag names.


Creating projects and project folders

Projects can contain multiple folders that you can use to organize the assets used in the project. Create projects using the **Explore** page.

To create a project, go to the **Explore** page and select to explore by projects and folders, and then click **New Project**.



To create a project folder, go to the **Explore** page and open the project, and then click **New Folder**.



You can create one level of folders in a project. You cannot create folders within folders.

For more information about working with projects, see *Asset Management*.

Creating assets


Create integration assets and assign them to projects.

You can create custom assets or create assets from a template.

To create a custom asset, click **New** and then select the asset type. For specific information on creating a particular type of asset, see the appropriate asset type in *Mappings* or *Tasks*.

To create an asset from a template, click **New**, select the asset type, and then select the appropriate template. Mapping task templates and mapping templates are listed below the heading that corresponds to the mapping type.

The following image shows the dialog box that appears when you create an asset:



1. Select the type of asset that you want to create. In this image, Tasks is selected.
2. Select one of these options to create a custom asset. Since Tasks is selected on the left, this area lists the tasks that you can create.
3. Select one of the options below a heading to create a task from a template. In this image, the Integration heading is expanded, so the templates listed are based on data integration mappings.

Tip: Informatica recommends that you use a standard naming convention that makes sense for your organization. Here are a few examples:

- You can begin all asset names with an abbreviation of the asset type. For example, mapping names begin with m_ and mapping tasks begin with mt_.
- Within mappings, you can begin all Source transformation names with src_, all parameter names with p_, and so on.
- You can use names that explain the purpose of the object, For example, filter names begin with flt_.

A standard naming convention is particularly helpful when you are working with large, complex mappings so that you can easily identify the type and purpose of each object.

For more information on working with assets, see *Asset Management*.

CHAPTER 6

Enabling source control

If your IDMC organization is licensed to use source control, specify your source control repository user credentials in IDMC.

Before your organization can use source control, the organization administrator must configure a link between the IDMC organization and a GitHub, Azure DevOps, or Bitbucket source control repository.

If your organization has read/write access to the source control repository, you can add your projects and assets to the repository. Each time you check out the objects, make changes, and then check them in to the repository, the source control system creates a new version of the objects.

If your organization has read-only access to the source control repository, you can pull versions of projects and assets to your organization, but you cannot add new or updated objects to the repository.

For more information about source control, see *Asset Management*.

Configuring repository access

To work with source-controlled objects, specify your repository credentials in IDMC.

Your credentials can include a personal access token or API token, depending on the repository service that you use. If your organization's repository is configured for OAuth access, you can enable OAuth access instead of providing a personal access token or app password.

Personal access tokens and API tokens must be configured to enable full control of private repositories. For information about generating tokens, see the GitHub, GitLab, Azure DevOps Git, or Bitbucket help.

Perform the following steps to configure access to the repository:

1. Click the **User** icon on the toolbar and then select **Settings**.

   Note: Depending on which service you are in, the user settings page might appear different and show different names for the sections.
2. In the **Source Control Access** section, perform one of the following tasks:
   - Enter your repository credentials.
   - Enable OAuth access to the repository.
     If you haven't already authorized access, a Git access app appears for GitHub and Azure DevOps Git repositories. Select to authorize access for IDMC.
3. Click **Save**.

CHAPTER 7

Notifications

You receive notifications in IDMC for certain events, including job status updates, license expiration, and workflow progress. You can manage how you receive notifications.

The Notifications icon on the toolbar displays the number of unread notifications. You can click the icon to view the latest unread notifications in the notifications tray. In some services, you can filter the tray to display only notifications from the current service.

You can also view and manage notifications on the **Notifications** page. To access the **Notifications** page, select **View All Unread** from the Actions menu in the notifications tray. On the **Notifications** page, you can filter notifications by service, category, subcategory, status, and date received.

CHAPTER 8

Editing your user profile

Your user profile contains the details of your IDMC user account.

You can update the following information in your profile:

- First and last name
- Job title
- Email address
- Phone number
- Time zone (used in the job execution time stamps on the **All Jobs**, **Running Jobs**, **My Jobs**, **Import/Export Logs**, and **My Import/Export Logs** pages)
- Password
- Security question and answer

Note: If you use SAML to log in to IDMC and your organization administrator has enabled SAML group and role mapping on the **SAML Setup** page in Administrator, you can update the time zone attribute. Your enterprise directory updates the other attributes directly each time you log in to IDMC.

1. Click the **User** icon in the top right corner of the IDMC window and then select **Profile**.
2. On the **Profile** page, add or edit personal information such as your name, job title, phone number, and time zone.
3. To update your email address, click **Update Email**.

   After you enter your password to initiate the change, IDMC sends a verification email to your new email address. The email contains a link that's valid for 24 hours. When you click the link in the email, IDMC verifies the new address, and it appears in your profile. If the link expires, you can resend the verification email.
   If multi-factor authentication is enabled in your organizaion, IDMC sends a verification code to your original email address. You must enter the code in the dialog box on your **Profile** page to receive the verification link in your new email address.
4. Optionally, change your password or security question.
5. Click **Save**.

CHAPTER 9

Editing your user settings

In your user settings, you can configure personal preferences, including how you receive email notifications and your source control repository credentials.

To access user settings, click the **User** icon on the toolbar and then select **Settings**. The user settings page includes the following sections:

Notifications

Choose whether and how you receive email notifications.

For more information, see *User Administration* in the Administrator help.

Source Control Access

Configure repository credentials that allow you to work with source-controlled objects.

For more information, see *Organization Administration* in the Administrator help.

Note: Depending on which service you are in, the user settings page might appear different and show different names for the sections.

CHAPTER 10

Inviting users to join your organization

If you have an appropriate role, you can invite users to join your organization when you configure a runtime environment or primary cloud data warehouse. Invite users to join your organization so they can help you set up a runtime environment or connect to your cloud data warehouse.

To invite users to join your organization, click **Invite a friend or colleague to help you**. To invite users, you must have the Admin role, or you must have the Designer role and a custom role that has the "read role" and "create user" Administrator asset privileges. You must assign the user you invite the Admin or Designer role.

If you don't see the **Invite a friend or colleague to help you** option or you want to assign the user a different role, you can add a user on the **Users** page in Administrator. For more information, see *User Administration* in the Administrator help.

1. Click **Invite a friend or colleague to help you**.
2. Enter the first name, last name, email address, user name, and role for the person you want to invite.

   The user name must be unique within the organization. You cannot change the user name after you invite the user.
3. Click **OK**.

   The user you invite receives an email with a link to join your organization.

CHAPTER 11

Primary cloud data warehouse setup

You can configure a primary cloud data warehouse where you normally load data. When you do this, the mappings in SQL ELT mode that you create are automatically configured to load data to this target. You can still change the target if you wish.

You can configure a primary cloud data warehouse destination only for one of the following types of data warehouses: Amazon Redshift, Databricks, Google BigQuery, Microsoft Fabric Data Warehouse, or Snowflake.

The cloud data warehouse that you choose applies to the organization that you're currently logged into. If you have access to multiple organizations, you can configure a different primary cloud data warehouse for each organization and sub-organization.

The setup steps vary based on whether you've already configured a primary cloud data warehouse. If you've already configured one, you can change or unselect it.

Configuring a primary cloud data warehouse

Configure a primary cloud data warehouse from the **Home** page.

1. On the **Home** page, click **Yes, let's go** in the **Do you use a cloud data warehouse as your primary destination?** panel.
2. On the **Destination** page, select your cloud data warehouse type, for example, Snowflake Data Cloud or Databricks Delta, and click **Next**.
3. On the **Connect** page, select a connection, or click **New** and enter the connection properties.
4. Click **Connect**.

Changing or unselecting a primary cloud data warehouse

If you've already configured a primary cloud data warehouse, you can change or unselect it. Change or unselect a primary cloud data warehouse from the **Home** page.

1. On the **Home** page, click the cloud data warehouse type in the upper right corner and select **Change primary cloud data warehouse**.
2. If you want to change your primary cloud data warehouse, select **I have a primary cloud data warehouse**.
3. To change the cloud data warehouse type, complete the following steps:
    a. Click **Change** next to **Type**.
    b. On the **Destination** page, select the data warehouse type, and then click **Next**.
    c. On the **Connect** page, select a connection, or click **New** and enter the connection properties.
    d. Click **Connect**.
4. To change the connection, complete the following steps:
    a. Click **Change** next to **Connection**.
    b. On the **Connect** page, select a connection, or click **New** and enter the connection properties.
    c. Click **Connect**.
5. If you no longer wish to use a primary cloud data warehouse, select **I don't have a primary cloud data warehouse**, and click **Save**.

CHAPTER 12

Switching to a different organization

If you are an administrator in a parent organization or a user in a parent organization that has privileges to view sub-organizations, you can switch among organizations. You do not have to log out and log back in to IDMC.

Note: If you switch from a parent organization to a sub-organization, you can't perform the following operations in the sub-organization:

- Create or import data transfer tasks
- Create or import dynamic mapping tasks
- Create, validate, publish, and run taskflows
- Export and import taskflows

To switch to a different organization:

▶ From the **Organization** menu in the upper right corner, select the organization that you want to view.

INDEX

A

allowlist
  Secure Agent domains 25, 31
  Secure Agent IP addresses 25, 31
assets
  creating 39
  source control 40
Azure DevOps user credentials 40

B

Bitbucket user credentials 40

C

Cloud Application Integration community
  URL 5
cloud data warehouses
  changing the primary cloud data warehouse 46
  configuring a primary cloud data warehouse destination 45
  primary cloud data warehouse destination setup 45
  unselecting a primary cloud data warehouse 46
Cloud Developer community
  URL 5
connections
  configuring properties 35
  creating 35
  testing 35
creating
  assets 39
  folders 38
  projects 38

D

Data Integration community
  URL 5
directories
  configuring Secure Agent login to access 29

E

email addresses
  for notification 42

F

firewall
  configuration 25, 31
folders
  creating 38

G

getting started
  activities 7
  runtime environment configuration 14
GitHub user credentials 40

H

Hosted Agent
  description 15

I

Informatica Global Customer Support
  contact information 6
Informatica Intelligent Data Management Cloud
  web site 5
Internet Explorer 11
  requirements 9

L

Linux
  configuring proxy settings 33
lookups
  searching in a task wizard 36

M

maintenance outages 6

O

object search
  in a task wizard 36
organizations
  switching to another organization 47

P

passwords
  changing 42
POD
  how to identify 25, 31
Product Availability Matrix 9

profiles
editing 42
projects
creating 38
creating folders 38
source control 40
proxy settings
configuring on Linux 33
configuring on Windows 28

R

requirements
Internet Explorer 11 9
Product Availability Matrix 9
Secure Agent 24, 30
runtime environments
Hosted Agent 15
configuring 14, 17, 20, 22
installing in a cloud environment 17

S

search
for objects for a task wizard 36
Secure Agent Manager
launching 24
Secure Agents
communication port 25, 31
configuring a Windows service login 29
domains allowlist 25, 31
installing in a cloud environment 17
installing on Linux 31
installing on Windows 26
IP address allowlist 25, 31
permissions on Linux 31
permissions on Windows 25
registering on Linux 31
registering on Windows 26
requirements on Linux 30
requirements on Windows 24
starting on Windows 24
security questions
editing 42
source control
configuring access to the repository 40
sources
searching in a task wizard 36
status
IDMC 6
sub-organizations
switching to another organization 47
system requirements 9
system status 6

T

targets
searching in a task wizard 36
time zones
changing user profile 42
trust site
description 6

U

upgrade notifications 6
user profiles
editing 42
users
adding, editing, and deleting 44
inviting 44

V

version control 40

W

web site 5
Windows
configuring proxy settings 28
Windows service
configuring Secure Agent login 29