Informatica® Application Integration
October 2026

SAP IDoc Connector Guide

Informatica Application Integration SAP IDoc Connector Guide
October 2026

© Copyright Informatica LLC 2025, 2026

Publication Date: 2026-10-16

Table of Contents

Preface. 4

Chapter 1: Introduction to SAP IDoc Connector. 5

SAP IDoc Connector overview. 5

SAP IDoc Connector administration. 6

Downloading and configuring SAP libraries for IDoc. 7

Chapter 2: SAP IDoc connections. 9

SAP IDoc connection overview. 9

Creating an SAP IDoc connection. 9

Basic connection properties. 10

SAP server connection types. 11

Application server connection. 11

Application server SNC connection. 12

Load balancing server connection. 13

Load balancing server SNC connection. 14

Listener connection properties. 16

Reader properties. 16

Writer properties. 17

Custom attributes. 17

Search filter. 17

Chapter 3: Event source properties. 19

Chapter 4: Event target properties. 21

Chapter 5: SAP IDoc connection metadata. 23

Chapter 6: Using an SAP IDoc connection in a process. 24

Reading IDoc messages from SAP. 24

Writing IDoc messages to SAP. 24

Index. 26

Preface

Read the *SAP IDoc Connector Guide* to learn how to set up and use connections with SAP IDocs.

This guide assumes that you are familiar with SAP and SAP IDoc concepts, and know how to create connections and processes in Application Integration.

CHAPTER 1

Introduction to SAP IDoc Connector

This chapter includes the following topics:

- SAP IDoc Connector overview, 5
- SAP IDoc Connector administration, 6

SAP IDoc Connector overview

You can use SAP IDoc Connector to read data from and write data to SAP through Intermediate Documents (IDocs). You can configure event sources to consume events from SAP IDoc listeners and configure event targets to publish messages to SAP IDocs. This connector facilitates the exchange of business documents in a standardized format, ensuring reliable and efficient data transfer.


You can use SAP IDocs as EDI-like documents to exchange information asynchronously. These structured data containers transfer data, such as sales orders, invoices, and delivery notices between your SAP system and trading partners or other external systems.

SAP IDoc Connector uses queued Remote Function Call (qRFC) for message sequencing. With qRFC, your system exchanges data between two application components through multiple queues, following a first-in, first-out (FIFO) sequence for function modules. Additionally, IDocs provide queuing and retry capabilities to ensure reliable and orderly message delivery.


SAP IDoc Connector administration

Before you use an SAP IDoc connection to access data from SAP through IDocs, an administrator must perform the following tasks:

- Verify that you have the license to the SAP IDoc Connector package and CCICOREAgent package in Administrator. For more information about licenses, see *Licenses* in Organization Administration.




- Enable the SAP IDoc Connector when you configure the runtime environment in Administrator. For more information, see Runtime Environments.



- Restart the Process Server.

After you configure the runtime environment, the packages highlighted in the following image are available on the agent.



Downloading and configuring SAP libraries for IDoc

Download the SAP JCo libraries and configure them on the machine where the Secure Agent runs. Contact SAP Customer Support if you encounter any issues with downloading the libraries.

1. Go to the SAP Service Marketplace: http://service.sap.com.

   Note: You must have SAP credentials to access the Service Marketplace.

2. Download the 64-bit version of the latest SAP JCo libraries for the operating system on which the Secure Agent runs:

Secure Agent System	SAP File Names
Windows	- sapjco3.jar - sapjco3.dll - sapidoc3.jar
Linux	- sapjco3.jar - libsapjco3.so - sapidoc3.jar

3. Copy the libraries to the following directory:

   `<Informatica Secure Agent installation directory>\apps\process-engine\ext`

4. Set the following permissions for each SAP NetWeaver RFC SDK library:
   - Read, write, and execute permissions for the current user.
   - Read and execute permissions for all other users.

- Set the SAP permissions that are on the SAP IDOC CDI connector guide and the S_IDOCDEFT Authorization Object. The **S_IDOCDEFT** authorization object requires the following fields for authorization:

  ACTVT: Indicates the activity being performed.

  EDI_CIM: Represents the EDI Component Interface Message.

  EDI_DOC: Refers to the EDI Document.

  EDI_TCD: Denotes the EDI Transaction Control Data.

  EDI_MES: Specifies the permitted message type.

  EDI_DIR: Indicates the direction of the IDoc (1 = outbound, 2 = inbound).

  EDI_PNR: Permitted partner number.

  EDI_PRT: Permitted partner type.

  These fields are essential to access IDoc monitoring and processing within the SAP system. For more information on configuring SAP user authorization, see Configure SAP user authorization.

5. Restart the Process Server. To ensure that the libraries are loaded correctly, restart the Process Server on the machine where Secure Agent is installed.

CHAPTER 2

SAP IDoc connections

This chapter includes the following topics:

- SAP IDoc connection overview, 9
- Creating an SAP IDoc connection, 9
- Basic connection properties, 10
- SAP server connection types, 11
- Listener connection properties, 16
- Reader properties, 16
- Writer properties, 17
- Custom attributes, 17
- Search filter, 17

SAP IDoc connection overview

Use an SAP IDoc connection to read data from or write data to SAP through IDocs. An SAP IDoc connection establishes the link between your integration platform and the SAP system by configuring connection details, such as the SAP application server, system number, and client ID. The connection supports various communication protocols including RFC and ensures secure authentication through user credentials. After configured, the connection enables the transmission of IDocs to and from SAP, facilitating processes, such as data synchronization, transactional messaging, and system interoperability.

After you create the connection, you can validate, save, and test it to ensure that it works correctly. You can then publish the SAP IDoc connection and click the **Metadata** tab to view the generated process objects for the connection. These process objects help you integrate and interact with SAP data using the IDoc format.

Creating an SAP IDoc connection

You can create an SAP IDoc connection to read data from or write data to SAP through IDocs.

1. In Application Integration, click **New** > **App Connections** > **App Connection** > **Create**.

   The **Connection** page appears.
2. Select **SAP IDoc** as the connection type.

3. Enter a name and description for the connection.
4. Select a runtime environment on which the connection must run.
5. Enter the SAP IDoc connection properties.

   The **OData-Enabled** option does not apply to the SAP IDoc connection.
6. Test the connection.
7. Save and publish the connection.

   Click the **Metadata** tab to view the IDoc metadata that the connection accesses in the SAP system.

Basic connection properties

When you select SAP IDoc as the connection type, you can configure the IDoc-specific connection properties on the connection creation page.

To create the SAP IDoc connection, configure the following properties on the **Properties** tab of the connection creation page:

Property	Description
Name	Required. Enter a unique name for the connection that identifies it in the Process Designer. The name must be unique within the organization. It can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Location	Required. The location of the project or folder where you want to save the connection. Click **Browse** to select a location. If the **Explore** page is currently active and a project or folder is selected, the default location for the connection is the selected project or folder. Otherwise, the default location is the location of the most recently saved asset.
Description	Description of the connection. Maximum length is 4000 characters.
Type	Required. The type of connection you want to use for the connector or service connector. Select **SAP IDoc**.
Runtime Environment	Required. The run-time environment for the connection. You can run the connection on a Secure Agent group or a Secure Agent machine.
Connection Test	Indicates whether the connection test was successful or not. By default, the property displays the results of the connection test.

Property	Description
OData-Enabled	Not supported for SAP IDoc Connector.
Use Secret Vault	Stores sensitive credentials for this connection in the secrets manager that is configured for your organization. This property appears only if secrets manager is set up for your organization. When you enable the secret vault in the connection, you can select which credentials the Secure Agent retrieves from the secrets manager. If you don't enable this option, the credentials are stored in the repository or on a local Secure Agent, depending on how your organization is configured. For information about how to configure and use a secrets manager, see "Secrets manager configuration" in the *Administrator* help.

Along with these basic properties, you must define the properties based on the authentication type. You must also configure the event source properties and event target properties for the SAP IDoc connection. After you publish the SAP IDoc connection, the **Metadata** tab displays the generated process objects.

SAP server connection types

You can configure application server, application server Secure Network Communications (SNC), load balancing server, and load balancing server SNC connection types to access SAP IDocs.

Select the required connection type, and configure the connection-specific parameters.

Application server connection

The application server connection is the default type and requires your SAP client details.

The following table describes the connection properties for an application server connection:

Property	Description
User Name	Required. The user name to connect to the SAP system.
Password	Required. The password to connect to the SAP system.
Client	Required. The client number of the SAP application server.
Language	Required. The language code of the SAP application server.
Application Server	Required. The host name or IP address of the SAP application server.
System Number	Required. The system number of the SAP application server.
RFC Trace	Required. The RFC trace records the logs in the trace file.

Property	Description
Additional Parameters	Enter a list of additional parameters to connect to the SAP system. Configure multiple parameters as key-value pairs separated by semicolons. Use the following format: `<parameter name1>=<value1>;<parameter name2>=<value2>;<parameter name3>=<value3>....`
Prefix Metadata with IDoc Type	Enable this option to prefix the metadata with the IDoc Type to make process objects unique when processing multiple IDocs.

For more information about listener connection properties, reader properties, writer properties, and custom attributes for a server connection, see "Listener connection properties" on page 16, "Reader properties" on page 16, "Writer properties" on page 17, and "Custom attributes" on page 17.

Application server SNC connection

The application server SNC connection requires your SAP client details, the Secure Agent PSE certificate name, the SAP server PSE certificate name, and the path to the X509 certificate file.

For more information, see the How-To article Configure the SAP Secure Network Communication Protocol.

The following table describes the basic connection properties for an application server SNC connection:

Property	Description
User Name	Required. The user name to connect to the SAP system.
Password	Required. The password to connect to the SAP system.
Client	Required. The client number of the SAP application server.
Language	Required. The language code of the SAP application server.
Application Server	Required. The host name or IP address of the SAP application server.
System Number	Required. The system number of the SAP application server.
RFC Trace	Required. The RFC trace records the logs in the trace file.
SNC My Name	The Personal Security Environment (PSE) or certificate name generated for the Secure Agent.
SNC Partner Name	The server PSE or certificate name generated on the SAP server.
SNC Quality of Protection (QoP)	The level of protection applied to a communication path when you create an SAP SNC connection. Select one of the following options from the list: - 1 - Apply authentication only - 2 - Apply authentication and integrity protection - 3 - Apply authentication, integrity, and privacy protection (encryption) - 8 - Apply global default protection (usually 3) - 9 - Apply the maximum protection Default is 3 - Apply authentication, integrity, and privacy protection (encryption).

Property	Description
SNC Cryptographic Library Path	The path to the SNC cryptographic library.
Use X509 Certificate	Select this option to use an X509 certificate to log in with SNC encryption. If you don't select this option, you need to enter your SAP user name in the **X509 Certificate Path or SAP Username** property. Default is disabled.
X509 Certificate Or User Name	The path and file name of the X509 certificate file. If the X509 certificate file name is abc.crt and the path is `\root\<folder name>`, enter both the path and file name in the following format: `\root\<folder name>\abc.crt` If you select to use the X509 certificate, you don't need to enter the SAP user name. If you don't want to use the X509 certificate, enter the SAP user name for which SNC is configured in the SAP server.
Additional Parameters	Enter a list of additional parameters to connect to the SAP system. Configure multiple parameters as key-value pairs separated by semicolons. Use the following format: `<parameter name1>=<value1>;<parameter name2>=<value2>;<parameter name3>=<value3>....`
Prefix Metadata with IDoc Type	Enable this option to prefix the metadata with the IDoc Type to make process objects unique when processing multiple IDocs.

For more information about listener connection properties, reader properties, writer properties, and custom attributes for a server connection, see "Listener connection properties" on page 16, "Reader properties" on page 16, "Writer properties" on page 17, and "Custom attributes" on page 17.

Load balancing server connection

Create a load balancing server connection when you want to connect to the SAP system with the least load at run time. You must provide your SAP client details and the message server group name.

The following table describes the basic connection properties for a load balancing server connection:

Property	Description
User Name	Required. The user name to connect to the SAP system.
Password	Required. The password to connect to the SAP system.
Client	Required. The client number of the SAP application server.
Language	Required. The language code of the SAP application server.
Message Server	Required. The host name or IP address of the SAP message server.
System ID	Required. The system ID of the SAP message server.

Property	Description
Group	Required. The name of the SAP logon group through which you want to connect. For example, PUBLIC.
RFC Trace	Required. The RFC trace records the logs in the trace file.
Additional Parameters	Enter a list of additional parameters to connect to the SAP system. Configure multiple parameters as key-value pairs separated by semicolons. Use the following format: `<parameter name1>=<value1>;<parameter name2>=<value2>;<parameter name3>=<value3>....`
Prefix Metadata with IDoc Type	Enable this option to prefix the metadata with the IDoc Type to make process objects unique when processing multiple IDocs.

For more information about listener connection properties, reader properties, writer properties, and custom attributes for a server connection, see "Listener connection properties" on page 16, "Reader properties" on page 16, "Writer properties" on page 17, and "Custom attributes" on page 17.

Load balancing server SNC connection

Create a load balancing server SNC connection when you want to use the SNC protocol to connect to the SAP system with the least load at run time.

You must provide your SAP client details, the message server group name, the Secure Agent PSE certificate name, the SAP server PSE certificate name, and the path to the X509 certificate file.

For more information, see the How-To article Configure the SAP Secure Network Communication Protocol.

The following table describes the basic connection properties for a load balancing server SNC connection:

Property	Description
User Name	Required. The user name to connect to the SAP system.
Password	Required. The password to connect to the SAP system.
Client	Required. The client number of the SAP application server.
Language	Required. The language code of the SAP application server.
Message Server	Required. The host name or IP address of the SAP application server.
System ID	Required. The system ID of the SAP message server.
Group	The name of the SAP logon group through which you want to connect. For example, PUBLIC.
RFC Trace	The RFC trace records the logs in the trace file.
SNC My Name	The Personal Security Environment (PSE) or certificate name generated for the Secure Agent.

Property	Description
SNC Partner Name	The server PSE or certificate name generated on the SAP server.
SNC Quality of Protection QoP*	The level of protection applied to a communication path when you create an SAP SNC connection. Select one of the following options from the list: - 1 - Apply authentication only - 2 - Apply authentication and integrity protection - 3 - Apply authentication, integrity, and privacy protection (encryption) - 8 - Apply global default protection (usually 3) - 9 - Apply the maximum protection Default is 3 - Apply authentication, integrity, and privacy protection (encryption).
SNC Cryptographic Library Path	The path to the SNC cryptographic library.
Use X509 Certificate	Select this option to use an X509 certificate to log in with SNC encryption. If you don't select this option, you need to enter your SAP user name in the **X509 Certificate Path or SAP Username** property. Default is disabled.
X509 Certificate Or User Name	The path and file name of the X509 certificate file. If the X509 certificate file name is abc.crt and the path is `\root\<folder name>`, enter both the path and file name in the following format: `\root\<folder name>\abc.crt` If you select to use the X509 certificate, you don't need to enter the SAP user name. If you don't want to use the X509 certificate, enter the SAP user name for which SNC is configured in the SAP server.
Additional Parameters	Enter a list of additional parameters to connect to the SAP system. Configure multiple parameters as key-value pairs separated by semicolons. Use the following format: `<parameter name1>=<value1>;<parameter name2>=<value2>;<parameter name3>=<value3>....`
Prefix Metadata with IDoc Type	Enable this option to prefix the metadata with the IDoc Type to make process objects unique when processing multiple IDocs.

For more information about listener connection properties, reader properties, writer properties, and custom attributes for a server connection, see "Listener connection properties" on page 16, "Reader properties" on page 16, "Writer properties" on page 17, and "Custom attributes" on page 17.

Listener connection properties

The following table describes the listener connection properties for a server connection:

Property	Description
Program ID	The ID of the SAP program. The Program ID must be the same as the Program ID for the logical system that you define in the SAP system to send or receive IDocs.
Gateway Host	The host name of the SAP gateway.
Gateway Server	The server name of the SAP gateway.

Reader properties

The following table describes the reader properties for a server connection:

Property	Description
Connection Pool Size	The maximum number of simultaneous connections that can be maintained for SAP communication. Default is 2.
Minimum Worker Threads	The minimum number of active worker threads available for processing the IDoc requests. Default is 5.
Gateway Thread Count	The number of dedicated gateway threads to handle communication between the SAP gateway and Application Integration. Default is 5.
Maximum Worker Threads	The maximum number of threads to process SAP IDoc requests in parallel. Default is 50.
Startup Delay	The number of seconds that the connector must wait before processing IDocs. Default is 30,000.
Trace Logging Level	Determines the level of detail to be written to the activity log for error and status messages. Default is 1.

Writer properties

The following table describes the writer properties for a server connection:

Property	Description
Destination Pool Capacity	Defines the maximum number of idle connections that can be kept in the destination pool for write operations. Increase this value for better performance under high concurrency. Default is 10.
Destination Peak Limit	Defines the maximum number of simultaneously active connections to the SAP destination. Active connections include both idle and in-use connections. This property helps in managing the SAP-side resource limits. Default is 50.
Destination Expiration Time (ms)	Defines the time in milliseconds before idle connections are closed. Default is 300000 (5 minutes).
Destination Expiration Check Period (ms)	Defines the interval in milliseconds for checking and cleaning up expired connections. Default is 60000 (1 minute).
Destination Max Get Client Time (ms)	Defines the maximum time in milliseconds to wait for a free connection from the pool. If no connection becomes available within this time, an error is thrown. This property prevents threads from waiting indefinitely for an SAP connection. Default is 60000 (1 minute).

Custom attributes

In the **Custom Attributes** section, add filters for the **Search Filter Options** property to read the IDoc metadata. You can separate multiple filter options with a comma. For more information about the **Search Filter Options** property, see "Search filter" on page 17.

Search filter

You must add filters to read the IDoc metadata. The event used in a process is an object that contains a process object with a payload representing the IDoc message. The message consists of two main parts:

- **Headers**. The headers include key metadata fields, such as `BasicIDocType`, `ExtensionIDocType`, and `DocumentNumber`. These provide essential information about the IDoc message and remain consistent across IDoc types.
- **Body**. The body is a string that contains the actual IDoc message data. This string represents the specific IDoc type sent from SAP. For example, it might contain data corresponding to the `MATMAS05` IDoc type.

When you use specific IDoc types like `MATMAS05`, configure a search filter in the custom attributes section to represent the IDoc type format. The search filter uses the syntax to specify the IDoc type, message type, and extension type.

For example, configure the search filters as follows:

```
{
    "searchFilter": [
        {  "IDoctype": "MATMAS05",
            "MessageType": "MATMAS",
            "extType": ""
        }
    ]
}
```

Including this filter ensures that when you publish the connection, metadata specific to that IDoc type is fetched automatically.

Handling multiple IDoc types in a single listener

If the listener receives multiple IDoc types on the same connection, such as `MATMAS05` and `MATMAS07`, specify multiple search filters to fetch the metadata for all these types simultaneously.

For example, the search filter would appear as:

```
{
  "searchFilter": [
    {
      "IDoctype": "MATMAS05",
      "MessageType": "MATMAS",
      "extType": ""
    },
    {
      "IDoctype": "MATMAS07",
      "MessageType": "MATMAS",
      "extType": ""
    }
  ]
}
```

With this configuration, you fetch metadata for both `MATMAS05` and `MATMAS07`, enabling the listener to process both the IDoc types.

At the message structure level, the **Headers** remain consistent with the same keys regardless of the IDoc type. The **Body** is a string that can represent different IDoc types, such as `MATMAS05` and `MATMAS07`, depending on the SAP settings, allowing you to handle multiple IDoc message formats.

CHAPTER 3


Event source properties

You define an SAP IDoc event source to read data from SAP through IDocs and consume events from SAP IDoc listeners.

For each SAP IDoc connection that you create, you can add only one event source. An event source serves as a start event that listens to or monitors a specified SAP IDoc queue for new messages. After you define an event source for an SAP IDoc connection, you must publish the connection only on a Secure Agent. You use the event source in a process to consume messages from a queue as process objects. Then, you deploy the process on the same Secure Agent where you published the SAP IDoc connection.

To create an event source in an SAP IDoc connection, click **Add Event Source** on the **Event Sources** tab. Select the event source type as **Event Source**.

The following image shows the event source properties:



The following table describes the basic event source properties that you can configure:

Properties	Description
Name	The event source name that appears in the Process Designer. The name must be unique for the connection.You can change this property after you create the connection. The name cannot exceed 128 characters, contain spaces, or contain the following special characters: ~ ` ! $ % ^ & * ( ) - + = { [}] | \ : ; " ' < , > . ? /
Description	Optional. Description for the event source that appears in the Process Designer. The description cannot exceed 4,000 characters.
Enabled	Select **Yes** to make the event source available immediately after it is published. Select **No** to disable the event source until you are ready to use it. Default is **Yes**.

The following table describes the event source properties that you can configure:

Properties	Description
Object Name	The name of the object from which you want to read messages. Enter the object name in the following format: `IDocListener_Dest_<username>_<client>`
Object Path	Optional. The path of the object from which you want to read messages.

CHAPTER 4


Event target properties

Create an event target to publish or write SAP IDoc messages.

For each SAP IDoc connection that you create, you can add only one event target that specifies an operation and call the event target from a process to send messages to an SAP IDoc exchange.

To create an event target in an SAP IDoc connection, click **Add Event Target** on the **Event Targets** tab. Select the event source type as **Event Target**.

The following image shows the event target properties:



The following table describes the basic target properties that you can configure:

Properties	Description
Name	The event target name that appears in the Process Designer. The name must be unique for the connection. The name cannot exceed 128 characters, contain spaces, or contain the following special characters: ~ ` ! $ % ^ & * ( ) - + = { [}] | \ : ; " ' < , > . ? /
Description	Optional. Description for the event target that appears in the Process Designer. The description cannot exceed 4,000 characters.

The following table describes the target properties that you can configure:

Properties	Description
Object Name	The name of the object where you want to publish messages. Enter the object name in the following format: `IDocListener_Dest_<username>_<client>`
Object Path	Optional. The path of the object where you want to publish messages.

CHAPTER 5

SAP IDoc connection metadata

After you create or update an SAP IDoc connection, you validate, save, and publish the connection. You can view the actions and process objects for the connection on the **Metadata** tab.

The **Metadata** tab displays the process objects generated when you publish the SAP IDoc connection. The process objects are based on the search filter options you provide.

In the **Actions** section on the **Metadata** tab, you can view the event source and event target configured for the connection.

In the **Objects** section on the **Metadata** tab, you can view the objects associated with the SAP IDoc connection.

The published metadata for the connection consists of the following objects:


Headers

The **Header** object contains name and type fields that represent the SAP IDoc header name and its type.

Messages

IDoc messages consist of headers and a body. The headers in an IDoc message are a list of name-value pairs that contain multiple attributes for the IDoc message. The IDoc message body contains the message payload, which the process accesses as a process object of type `$po:$any`.

The following image shows the published metadata of an SAP IDoc connection:



When you publish an SAP IDoc connection, the system refreshes the **Metadata** tab by default. When you create an SAP IDoc connection, you click **Save** and then click **Publish** to download the metadata.

CHAPTER 6

Using an SAP IDoc connection in a process

After you create an SAP IDoc connection, you can use it in a Service step within a process to read and write IDoc messages.

Reading IDoc messages from SAP

You can create and publish a process to read IDoc messages from an SAP system. When the SAP system sends an IDoc message, it invokes the Application Integration process you configured.

1. Create a process, and then click the **Start** step.
2. Click the **Start** tab and select the process binding type as **Event**.
3. In the **Event Source Name** field, select the event source you created.
4. Configure other steps and properties as needed.
5. Validate, save, and publish the process.


You can view the process run details in Application Integration Console. Click the **Processes** tab, select the Secure Agent or Secure Agent group where you configured the process to run, and then click the process ID to view the details.

Writing IDoc messages to SAP

You can create and publish a process to write IDoc messages to an SAP system. When you invoke the process, it writes the configured IDoc message to the SAP system.

1. Create a process.
2. Add a Service step to the process and perform the following steps:
    a. From the **Service Type** list, select **Connection**.
    b. From the **Connection** list, browse and select the SAP IDoc connection you created.
    c. From the **Action** list, select the target you created in the SAP IDoc connection.

d. In the **Input Fields** field, set the required IDoc message as shown in the following image:



3. Configure other steps and properties as needed.
4. Validate, save, and publish the process.
5. Invoke the process to write the configured IDoc message in the Service step to the SAP system.
6. Check the SAP user interface to confirm the new IDoc message written from the Application Integration process.

You can view the process execution details in Application Integration Console. Click the **Processes** tab, select the Secure Agent or cloud where you configured the process to run, and click the process ID to view the details.

INDEX

C

Connector
  SAP IDoc 5

E

Event source properties
  SAP IDoc 19

S

SAP IDoc
  Event source properties 19
SAP IDoc connection
  creating 9
  published metadata 23
SAP IDoc Connector administration
  overview 6
SAP libraries
  configuring 7