Informatica® Metadata Command Center
April 2026

Denodo Sources

Informatica Metadata Command Center Denodo Sources
April 2026

© Copyright Informatica LLC 2024, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica, Informatica Cloud, Informatica Intelligent Cloud Services, PowerCenter, PowerExchange, and the Informatica logo are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices are included with the product.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-07-23

Table of Contents

Preface 4

Chapter 1: Introduction to Denodo catalog sources 5

Extraction and view process 6

About the Denodo catalog source 6

Extracted metadata 7

Compatible connectors 7

Chapter 2: Before you begin 8

Verify permissions 8

Permissions to extract metadata 8

Create a connection 8

Create endpoint catalog sources for connection assignment 9

Chapter 3: Create catalog sources in Metadata Command Center 10

Step 1. Register a catalog source 10

Step 2. Configure capabilities 12

Configure metadata extraction 12

Configure lineage discovery 14

Step 3. Associate stakeholders and asset groups 15

Step 4. Run or schedule the job 16

Step 5. Assign reference catalog source connections to endpoint catalog source objects 17

Chapter 4: View results in Data Governance and Catalog 19

View metadata extraction results 19

View data lineage 21

View lineage at the catalog source level 21

View lineage at the data set level 21

View lineage at the data element level 22

Appendix A: Managing catalog sources 24

Cloning a catalog source configuration 24

Deleting or purging a catalog source 25

Purging obsolete objects from a catalog source 25

Curating CLAIRE recommendations 26

Managing configuration permissions for catalog sources 26

Preface

Read *Denodo Sources* to learn how to register and configure Denodo sources as catalog sources in Metadata Command Center. After you configure a catalog source, you extract metadata and then view the results in Data Governance and Catalog.

CHAPTER 1

Introduction to Denodo catalog sources

You can use Metadata Command Center to extract metadata from a source system.

A source system is any system that contains data or metadata. For example, Denodo is a source system from which you can extract metadata through a Denodo catalog source with Metadata Command Center. A catalog source is an object that represents and contains metadata from the source system.

Before you extract metadata from a source system, you first create and register a catalog source that represents the source system. Then you configure capabilities for the catalog source. A capability is a task that Metadata Command Center can perform, such as metadata extraction, lineage discovery, data profiling, data classification, or glossary association.

When Metadata Command Center extracts metadata, Data Governance and Catalog displays the extracted metadata and its attributes as technical assets. You can then perform tasks such as analyzing the assets, viewing lineage, and creating links between those assets and their business context.


The following table describes the capabilities of the catalog source:

Capability	Description
Lineage Discovery	Builds the complete lineage of a catalog source by recommending endpoint catalog source objects to assign to reference catalog source connections. When you run the catalog source job, Metadata Command Center assigns the reference catalog source connections to CLAIRE recommended endpoint catalog source objects. You can then view the list of CLAIRE recommendations and accept or reject them.

Extraction and view process

To extract metadata from a source system, configure the catalog source and run the extraction job in Metadata Command Center. Then view the results in Data Governance and Catalog.

The following image shows the process to extract metadata from Denodo:



After you verify prerequisites, perform the following tasks to extract metadata from Denodo:

1. Register a catalog source. Create a catalog source object, select Denodo, and then select and test the connection.
2. Configure the catalog source. Specify the runtime environment and configure parameters for metadata extraction. Optionally, add filters to include or exclude source system assets from metadata extraction. You can also configure other capabilities such as data profiling and quality, data classification, or glossary association.
3. Optionally, associate stakeholders. Associate users with technical assets, giving the users permission to perform actions determined by their roles.
4. Run or schedule the catalog source job.
5. Optionally, if the catalog source job generates referenced asset objects, you can assign a connection to referenced source system assets.
   You can view the lineage with object references without performing connection assignment. After connection assignment, you can view the objects.

   For connection-aware scans, run the catalog source again after you assign connections to referenced source system assets.

After you run the catalog source job, you view the results in Data Governance and Catalog.

About the Denodo catalog source

You can use the Denodo catalog source to extract metadata from a Denodo source system.

Denodo is a data virtualization platform that allows access to data from various sources without the need for physical data transfer or replication.

Extracted metadata

You can use the Denodo catalog source to extract metadata from a Denodo source system.

Metadata Command Center extracts the following metadata from a Denodo source system:

- Database
- Base view
- Derived view

Note: Base views and derived views appear as tables and views in Data Governance and Catalog.

Data sources

Metadata Command Center extracts metadata from Denodo Platform for the following data sources:

- PostgreSQL
- Snowflake
- Oracle
- Microsoft SQL Server
- Microsoft Azure SQL Server
- Databricks
- Google BigQuery

Compatible connectors

Before you configure a catalog source, you must connect to the Denodo source system.

Use the Denodo connector to connect to the Denodo source system.

For information about configuring a connection, see *Connections* in the Administrator service.

CHAPTER 2

Before you begin

Before you create a catalog source, ensure that you have the information required to connect to the source system.

Perform the following tasks:

- Download the Denodo drivers and copy the denodo-vdp-jdbcdriver.jar file to the following location in your Secure Agent:

  - On Windows: `<Agent installation location>\ext\connectors\thirdparty\infa.denodo`

  - On Linux: `<Agent installation location>/ext/connectors/thirdparty/infa.denodo`
- Create a connection to the Denodo source system in Administrator.
- Assign the required permissions.
- Create endpoint catalog sources for connection assignment.

Verify permissions

To extract metadata and to configure other capabilities that a catalog source might include, you need account access and permissions on the source system. The permissions required might vary depending on the capability.

Permissions to extract metadata

To extract metadata, you need account access and permissions to the source system.

Verify that the administrator grants the following privileges to the user account on the Denodo database:

- Connect
- Metadata
- Write

Create a connection

Before you configure the Denodo catalog source, create a connection object in Administrator.

1. In Administrator, select **Connections**.

2. Click **Add Connection** and select Denodo.
3. Enter the following connection details:

Property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.
Use Secret Vault	Stores sensitive credentials for this connection in the secrets manager that is configured for your organization. This property appears only if secrets manager is set up for your organization. When you enable the secret vault in the connection, you can select which credentials that the Secure Agent retrieves from the secrets manager. If you don't enable this option, the credentials are stored in the repository or on a local Secure Agent, depending on how your organization is configured. **Note:** If you're using this connection to apply data access policies through pushdown or proxy services, you cannot use the Secret Vault configuration option. For information about how to configure and use a secrets manager, see "Secrets manager configuration" in the Administrator help.
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent or serverless runtime environment.
Host	Host name or IP address of the machine that hosts the Denodo database.
Port	Network port number used to connect to the Denodo database. Default is 9999 for JDBC connections.
Database	The Denodo database name.
User Name	The user name to connect to the Denodo database.
Password	The password associated with the user name.

4. Click **Test**.
5. Click **Save**.

Create endpoint catalog sources for connection assignment

An endpoint catalog source represents a source system that the catalog source references. Before you perform connection assignment, create endpoint catalog sources and run the catalog source jobs.

You can then perform connection assignment to reference source systems and run connection-aware scans to view complete lineage with source system objects.

CHAPTER 3

Create catalog sources in Metadata Command Center

Use Metadata Command Center to configure a catalog source for Denodo and extract metadata.

When you configure a catalog source, you define the source system that you want to extract metadata from. Configure filters to include or exclude source system metadata before you run the job. Optionally, configure other capabilities, such as lineage discovery, data profiling and quality, data classification, relationship discovery, and glossary association.

To provide stakeholders access to technical assets, you can assign access through stakeholder roles. You can also associate technical assets extracted from the catalog source to asset groups. If your catalog source references other source systems, you can create a connection assignment to the endpoint catalog source to view complete lineage.

Step 1. Register a catalog source


When you register a catalog source, provide general information and connection values.

1. Log in to Intelligent Data Management Cloud.

   The **My Services** page appears.

2. Click **Metadata Command Center**.


   The **Metadata Command Center** box appears on the **My Services** page.



The Metadata Command Center home page appears.

3. Click **New**.
4. Select **Catalog Source** from the list of asset types.
5. Select Denodo from the list of catalog source types.

   The following image shows the Denodo catalog source type:



6. Click **Create**.

   The **New Catalog Source** page opens.
7. In the **General Information** section, enter a name and an optional description for the catalog source.

   Note: You can rename a catalog source after you create it, but to apply the change to all associated objects you must rerun the metadata extraction job.

   After you save the catalog source, you can update the description in Metadata Command Center and Data Governance and Catalog. The update appears only in the service in which you update it.
8. In the **Connection Information** area, select the connection that you created in Administrator.

   Note: To create or edit a catalog source, you need permissions on the connection to the source system. Select a connection that you have access to, or ask the administrator to grant the necessary permissions to the connection that you want to use.

9. Click **Connection Properties** to expand and view the connection properties for the selected connection.
10. Click **Test Connection** to test your connection to the source system.
11. Click **Next**.

The **Configuration** page appears.

Step 2. Configure capabilities

When you configure the Denodo catalog source, you define the settings for the metadata extraction capability.

The metadata extraction capability extracts source metadata from external source systems. You can also configure other capabilities that the catalog source includes.

You can save the catalog source configuration at any point after you enter the connection information. After you save the catalog source, you can choose to run the catalog source job. To run the job once, click **Run**. To run metadata extraction and other capabilities on a recurring schedule, configure schedules on the **Schedule** tab.

Configure metadata extraction

When you configure the Denodo catalog source, you choose a runtime environment, define filters, and enter configuration parameters for metadata extraction.

1. In the **Connection and Runtime** area, choose a serverless runtime environment or the Secure Agent group where you want to run catalog source jobs.

   Note: Serverless runtime environment options are available if the catalog source works with a serverless runtime environment.
2. Choose to retain, delete, or deprecate objects that are deleted from the source system in the catalog with the **Metadata Change Option**.
   - **Retain**. Retains objects that are deleted from the source system in the catalog. If you update or add a filter, the catalog retains objects extracted from the previous job and extracts additional objects that match the current filter. Objects deleted from the source system are not deleted from the catalog. Enrichments added on deleted objects and relationships are retained.
   - **Delete**. Deletes metadata from the catalog based on objects deleted from the source system and changes you make to the filter. Enrichments added on deleted objects and relationships are also permanently lost. Objects renamed in the source system are removed and recreated in the catalog.
   - **Deprecate**. When objects are deleted from the source system, the catalog changes the lifecycle of the imported objects to Obsolete. The lifecycle of objects also changes to Obsolete when you add exclusion filters or reduce the scope so that objects extracted in earlier jobs are no longer included. For example, the first job includes the sales schema. The second job also includes the sales schema, but excludes the sales.transactions table. In this case, the second job marks the sales.transactions object as Obsolete, even though the first job includes it. This does not impact enrichments applied to deprecated objects and relationships. Objects renamed in the source system are removed and recreated in the catalog. When you run the catalog source job again for other capabilities such as data classification, relationship discovery, or glossary association, the job doesn't consider obsolete objects. Obsolete objects remain in the catalog until they are purged when you run a **Purge Obsolete Objects** job on the **Explore** page.

   Note: You can also change the configured metadata change option when you run a catalog source.


3. In the **Filters** area, define one or more filter conditions to apply for metadata extraction:
   a. Select Yes to view filter options.
   b. From the Include or Exclude metadata list, choose to include or exclude metadata based on the filter parameters.
   c. From the Object type list, select Base views or Derived views, depending on the object that you want to extract metadata from. Select All to extract metadata from all objects.
   d. Enter the path to the object as the filter value.

      Filters can contain the following wildcards:

      - Question mark. Represents a single character.
      - Asterisk. Represents multiple characters.


      When you enter values for filters, enclose them in double quotes if the object name contains an asterisk or includes spaces before or after the string value.

      The following image shows the filter condition options:



   e. To define an additional filter with an OR condition, click the **Add** icon.

      The following image shows a filter that includes metadata from all base views with names that start with 'BaseView1' and all derived views with names that start with 'DerivedView' followed by two additional characters. The filter excludes metadata from all objects named 'Object1'.



4. Optional. In the **Configuration Parameters** area, enter additional settings.

   The following table describes the property that you enter for additional settings:

   Note: The **Additional Settings** section appears when you click **Show Advanced**.

Property	Description
Expert Parameters	Enter additional configuration options to be passed at runtime. Required if you need to troubleshoot the catalog source job. **Caution:** Use expert parameters when it is recommended by Informatica Global Customer Support.

5. Configure additional capabilities for the catalog source by clicking on the tabs.

Configure lineage discovery

Enable the lineage discovery capability and use CLAIRE to build complete lineage by recommending endpoint catalog source objects to assign to reference catalog source connections.

1. Click the **Lineage Discovery** tab.
2. Select **Enable Lineage Discovery**.
3. In the **Filters** area, define one or more filter conditions to apply for lineage discovery.

   To define filters, you can choose to select catalog source types, asset groups, or enter a catalog source name or search from a list of catalog sources.

   a. Select **Yes** to view filter options.


   b. From the Include/Exclude list, choose to include or exclude catalog sources for lineage discovery based on the filter parameters.

   c. From the filter type list, select catalog source type, catalog source name, or asset group.

   d. In the filter value field, select the required catalog source types, or click the Search button and select catalog sources or asset groups.

      Filters can contain the asterisk wildcard to represent multiple characters or empty text.

      The filter options appear.



      Examples:

      - To include or exclude all Oracle catalog sources, select **Catalog Source Type** as the filter type and select `Oracle` in the filter value field.
      - To include or exclude the 'Oracle_Retail' catalog source, select **Catalog Source Name** as the filter type and search for the catalog source or enter `Oracle_Retail` in the filter value field.
      - To include or exclude all catalog sources with names that start with 'Oracle', select **Catalog Source Name** as the filter type and search for the catalog source or enter `Oracle*` in the filter value field.
      - To include or exclude all catalog sources with names that end with 'Retail', select **Catalog Source Name** as the filter type and search for the catalog source or enter `*Retail` in the filter value field.
      - To include or exclude all catalog sources with names that contain 'Ret', select **Catalog Source Name** as the filter type and search for the catalog source or enter `*Ret*` in the filter value field.
      - To include or exclude all catalog sources that are part of the 'Financial Group' asset group, select **Asset Group** as the filter type and search `Financial Group` in the filter value field.

      Note: You can't add more than one include or exclude filter for the same filter type.

   e. Optionally, to define an additional filter with an AND condition, click the **Add** icon.

      For more information about lineage discovery, see *Lineage discovery* in the *Administration* help.


Step 3. Associate stakeholders and asset groups

Associate users or user groups within a stakeholder role as stakeholders for technical assets in Data Governance and Catalog. Also, you can choose to assign technical assets extracted from the catalog source to asset groups. You can then use access policies to control permissions on assets that are assigned to asset groups.

Verify that the administrator assigned users and user groups to the stakeholder role that you want to associate with technical assets.

1. To associate users or user groups as stakeholders with technical assets extracted from the catalog source, perform the following steps:
   a. On the **Associations** page, click **Stakeholders**.
   b. Select **Assign Stakeholders**.
   c. Select a stakeholder role.
   d. Click **Select** to add users and user groups from the stakeholder role as stakeholders for the technical assets.

      The **Add Users & User Groups** dialog box displays a list of users and user groups assigned to the selected stakeholder role.




   e. Select one or more users or user groups to assign as stakeholders for the technical assets, and click **OK**.

      Only the selected users and user groups belonging to the specified stakeholder role are granted the permissions to technical assets.
   f. To assign users or user groups from another stakeholder role, click **Add** and then repeat the steps.
2. To assign asset groups to technical assets extracted from the catalog source, perform the following steps:
   a. On the **Associations** page, click **Asset Groups**.
   b. Select **Assign Asset Groups**.
   c. Click **Select**.

      The **Select Asset Groups** dialog box displays the list of asset groups.

   If you enabled an access policy that includes an asset group, you can only view assets that belong to that asset group.

3. Select the asset groups to which you want to assign technical assets extracted from the catalog source, and click **OK**.



4. Choose to save and run the job or to schedule a recurring job.
   - To save and run the job, click **Save** and then **Run**.
   - To schedule a recurring job, click **Next** to open the **Schedule** page.

Step 4. Run or schedule the job

Choose to run a catalog source job manually, or configure it to run on schedule.

Note: You can't run multiple jobs simultaneously.

You can choose to perform a full or an incremental metadata extraction. A full metadata extraction extracts all objects from the source to the catalog. An incremental metadata extraction extracts only the changed and new objects since the last successful catalog source job run. Incremental metadata extraction doesn't remove deleted objects from the catalog and doesn't extract metadata of code-based objects if applicable.

When you run an incremental metadata extraction job with a filter to include metadata from objects, the job extracts only the objects that have the latest timestamp since the last successful job.

Note: If incremental metadata extraction is available for the catalog source, the option is always visible, but incremental metadata extraction jobs can run only after a scheduled full metadata extraction job. Manual jobs do not enable the incremental metadata extraction option.

Run the job manually

Click **Save** to save the catalog source and click **Run**. On the **Run Catalog Source Job** window, click **Run** to run the job.

You can override the capabilities that you selected while configuring your catalog source on the **Configuration** page. The first time you run the catalog source job, the metadata extraction capability is mandatory. From the second run onwards, you can choose to override the configured metadata change option. You can retain, delete, or deprecate objects that are deleted from the source in the catalog. For subsequent runs of the catalog source job, the metadata extraction capability is optional.

Note: You can choose incremental metadata extraction for subsequent runs only after one full metadata extraction job completes successfully. Incremental metadata extraction jobs run with the **Retain** metadata change option even if you set the option to **Delete** or **Deprecate** in the catalog source.

Note: To run a catalog source job, you need permissions on the connection to the source system. To run a catalog source job for catalog sources that reference other source systems, you need permissions on the connections for all the reference source systems.

Run the job on a schedule

You can choose to run metadata extraction and other capabilities on a recurring schedule. You can't choose incremental metadata extraction and full metadata extraction in the same schedule. To create a schedule for incremental metadata extraction, you must have completed at least one full metadata extraction job successfully. If not, first create a schedule for a full metadata extraction.

If an incremental metadata extraction is scheduled to run when the last run details aren't available, the job first performs a full metadata extraction, followed by incremental metadata extraction on subsequent runs.

For example, this can happen in the following scenarios:

- You create schedules for both incremental metadata extraction and full metadata extraction, but schedule the incremental extraction to run before the first full metadata extraction job.
- You create schedules for both incremental metadata extraction and full metadata extraction, but delete the full metadata extraction schedule before its first run.

1. On the **Schedule** tab, select **Run on Schedule**.
   The **Schedule** configuration page opens.
2. Click the checkbox corresponding to each capability that you want to include in the schedule.
3. Enter the start date, time zone, and the interval at which you want to run the job.
4. You can manage additional schedules using the following options:
   - To create a new schedule, click the **Add** button.
   - To delete a schedule, click the **Delete** button.
   - To enable or disable a schedule, click the **Enable Schedule** toggle button.

   Note: You can create a maximum of one schedule per capability that you enable. If you purged a catalog source or did not run the metadata extraction job, the catalog source job runs metadata extraction before running other scheduled capabilities.

   Note: To create a schedule, you need permissions on the connection to the source system. If you lose permissions on the connection after you create a schedule, the scheduled jobs continue to run.
5. Click **Save** to save the schedule.

Monitor job status

After the job runs, you can monitor the status of the job on the **Overview** page of the job.

For more information about job monitoring, see *Administration*.

Step 5. Assign reference catalog source connections to endpoint catalog source objects

When you run the catalog source job, if the catalog source references another source system, a reference catalog source and connection get created that point to the reference source system. To view the complete

lineage for your catalog source, you can perform connection assignment from the reference catalog source connection to the objects in the reference source system. A reference source system might be a database, such as Oracle. You must first create and run an endpoint catalog source that connects to the reference source system.

Before you assign a connection, ensure that you have created and run an endpoint catalog source for each reference source system.
Note: If the source schema contains case-sensitive tables or if the reference objects contain multiple objects with the same name in different cases, perform case-sensitive connection assignment to get correct lineage.

If you enabled the lineage discovery capability for your catalog source, you can either curate the CLAIRE recommended endpoint objects on the **Related Catalog Sources** tab or assign connections manually.

For more information about related catalog sources and lineage discovery, see *Lineage discovery* in the *Administration* help.

1. On the **Configure** page, select the **Lineage** tab, and then select the **Lineage Discovery** tab. On the **Catalog Sources** panel, select the required catalog source and click the **Assign Connections** tab.

   The **Assign Connections** tab displays a list of assigned and unassigned connections along with details for each connection. Use filters to view the connections based on the connection names. Click the **Add Filter** menu to add filters.
2. Select the connection to the reference source system and click **Assign**.

   The connection name appears prefixed to the reference catalog source name on the **Hierarchy** tab of your catalog source in Data Governance and Catalog.

   The **Assign Connection** dialog box appears with a list of recommended objects from the endpoint catalog sources. Click **All** to view all endpoint catalog source objects.
3. In the **Assign Connection** dialog box, select one or more objects from the endpoint catalog sources and click **Assign**.

   You can filter the list in the **Assign Connection** dialog box by name, type, or endpoint.

   You can connect to the following source systems:

   - PostgreSQL
   - Snowflake
   - Oracle
   - Microsoft SQL Server
   - Microsoft Azure SQL Server
   - Databricks
   - Google BigQuery

   The objects must be of the Database class type.

   Note: When you perform connection assignment, set Case-Sensitive to False.
4. Run the catalog source job again. If you configured the catalog source job to run on a regular schedule, the next scheduled run picks up the updated details. If you didn't configure a schedule, run the catalog source job again to view complete lineage.

When you click **Assign**, Metadata Command Center creates links between matching objects in the connected catalog sources, and it calculates the percentage of matched and unmatched objects. The higher the percentage of matched objects, the more accurate the lineage that you view in Data Governance and Catalog.

CHAPTER 4

View results in Data Governance and Catalog

After Metadata Command Center runs a job, you can view the results in Data Governance and Catalog where the catalog source and its elements are called technical assets. You can view a catalog source as a hierarchy. Expand each technical asset to see its components.

When referenced source systems are connected to a catalog source, you can expand the hierarchy to see details about the technical asset's component elements.

You can view the data lineage of an asset contained within a catalog source to see individual elements such as data sources, calculations, and filters. When you view data lineage, you can see the individual upstream elements that contribute data or expressions to each component of a data flow or catalog source.

View metadata extraction results


After a job runs in Metadata Command Center, view the results in Data Governance and Catalog. You can view details about source system contents in a hierarchical structure and trace data lineage.

1. Log in to Intelligent Data Management Cloud.

   The **My Services** page appears.

2. Click Data Governance and Catalog.

   The Data Governance and Catalog box appears on the **My Services** page.



3. On the Data Governance and Catalog home page, click the number in the **Technical Assets** panel.

   The **Technical Assets** page opens.


4. Select **Catalog Source** in the **Filter** list.

   The list of catalog sources opens.

5. Search for the catalog source from which you extracted metadata, and click the name.

   The **Overview** tab of the asset opens.

   The following image shows a sample asset page:



6. View the asset from different perspectives by clicking on the tabs.

For more information about working with assets, see Working with Assets in *Data Governance and Catalog* help.

View data lineage

Data lineage is a visual representation of the flow of data across the systems in your organization. Lineage depicts how the data flows from the system of its origin to the system of its destination.

Data lineage views are available for technical assets in the catalog source. You can view lineage at the catalog source, data set, or data element level.

The lineage at the catalog source level shows how data flows from one catalog source to another. The lineage at the data set and the data element levels show how other technical assets such as files or tables contribute to the selected asset.

If linking catalog sources is available for your catalog source, you can use Metadata Command Center to generate data lineage based on rules or by generating automated lineage with CLAIRE. You can choose source and target catalog sources and objects to link and generate lineage.

To determine whether linking catalog sources is available for your catalog source, navigate to the **Configuration** tab of the **Link Catalog Sources** page. The catalog source must appear in the list of source and target catalog sources.


For information about linking catalog sources, see *Link catalog sources* in the Administration help.

View lineage at the catalog source level

The catalog source level shows how data flows from one catalog source to another with the lineage aggregating data from the data set and data element levels.

To view data lineage at the catalog source level, open a technical asset, click the **Lineage** tab, and then verify that the level is set to **Catalog Source Level**.

The following image shows how the Denodo_Lineage_CA catalog source gets data from the Snowflake-CA and Oracle-CA catalog sources after connection assignment:




View lineage at the data set level


The data set level displays individual sets of data in the data flow.

To view lineage at the data set level, open a technical asset, click the **Lineage** tab, and then verify that the level is set to **Data Set Level**.

The following image shows data set level lineage where the join_view_oracle_snowflake target view gets data from the employee_view and emp source reference data sets using the emp and employee_view tables of the admin schema before connection assignment:



The following image shows how the join_view_oracle_snowflake view gets data from the EMPLOYEE_VIEW view and the EMP table using the emp and employee_view tables of the admin schema after connection assignment:




After connection assignment, the referenced object icons change to specific object icons.

View lineage at the data element level


The data element level displays details of the data set level. At the data element level, you can see the input sources for expressions or commands and calculations or transformations on the data.

To view data lineage at the data element level, open a technical asset, click the **Lineage** tab, and then verify that the level is set to **Data Element Level**.

The following image shows data element level lineage where the city view column of the join_view_oracle_snowflake view gets data from the city reference data element of the employee_view reference data set using the city column of the employee_view table before connection assignment:



The following image shows data element level lineage where the city view column of the join_view_oracle_snowflake view gets data from the CITY view column of the EMPLOYEE_VIEW view using the city column of the employee_view table after connection assignment:



After connection assignment, the referenced object icons change to specific object icons.

APPENDIX A

Managing catalog sources

You can update, copy, delete, purge, and run a catalog source. You can also grant configuration permissions for catalog sources to different roles in your organization.

On the **Catalog Sources** page of the **Explore** page, you can select a catalog source to see its overview and related catalog sources. The **Overview** tab displays the capabilities, filters, stakeholders, asset groups, and schedules enabled for a catalog source. The **Related Catalog Sources** tab displays a list of related catalog sources that are either assigned manually using connection assignment or are curated based on CLAIRE recommendations using the lineage discovery capability. You can view related catalog sources and accept or reject CLAIRE recommendations for catalog sources that are run with the lineage discovery capability.

Cloning a catalog source configuration

You can clone the configuration of a catalog source to create another catalog source with the same configuration.

Note: Cloning doesn't copy the content of the catalog source.

1. In Metadata Command Center, go to the **Explore** page.
2. Select **Catalog Sources** from the menu.
3. You can clone a catalog source in one of the following ways:
   - Hover your mouse over the catalog source that you want to clone and click **Clone** from the **Action** menu.
   - Open the catalog source that you want to clone and click **Clone**.

   Note: By default, the cloned catalog source has the same name suffixed with _Clone. You can change the name if needed.
4. If needed, modify the configuration of the catalog source by updating the parameters on each tab.

   Cloning doesn't copy the content of sensitive fields. If the catalog source contains sensitive fields such as Client Secret, enter the values.
5. Click **Save**.

Deleting or purging a catalog source

Delete or purge a catalog source based on your business requirements.

When you delete a catalog source, you delete all the configuration specific to that catalog source, along with all the metadata that was extracted and any enrichment made to the associated metadata. Purging a catalog source deletes all the metadata that was extracted, along with any enrichment made to the associated metadata.

Note: Before you delete or purge a catalog source, manually unassign the connections that are assigned to that catalog source.

1. Go to the **Explore** page in Metadata Command Center.
2. Select **Catalog Sources** from the menu.
3. From the list of catalog sources, search for the catalog source that you want to delete or purge.
4. Click the **Action** menu, and select **Delete** or **Purge**.

   Note: You can't delete or purge a catalog source if the catalog source job is in the running state.
5. To confirm delete or purge, click **OK**.

   The catalog source is triggered to delete or purge. You can monitor the status of the job on the **Monitor** page.

   Note: If the deletion job succeeds, the catalog source disappears from Metadata Command Center. If it fails, some associated objects might still be present in Data Governance and Catalog. Such catalog sources continue to appear in the list of catalog sources in Metadata Command Center, but are marked as **Deleted**. Delete the catalog sources to remove them along with any remaining objects present in Data Governance and Catalog.

Purging obsolete objects from a catalog source

You can purge obsolete objects from a catalog source.

When you configure or run a catalog source, you can choose to deprecate objects that are deleted from a source system. If you delete objects from the source system or make changes to the filter, the objects imported into the catalog before the change move to the Obsolete lifecycle in the catalog. You can purge obsolete objects from a catalog source. This permanently deletes all objects with the Obsolete lifecycle status, along with associated enrichments, from the catalog.

1. Go to the **Explore** page in Metadata Command Center.
2. Select **Catalog Sources** from the menu.
3. From the list of catalog sources, search for the catalog source from which you want to purge obsolete objects.
4. Click the **Action** menu, and select **Purge Obsolete Objects**.

   A warning message appears on the page.
5. Click **Yes** to confirm.

   A confirmation message appears on the page and the purge job starts. You can monitor the status of the job on the **Monitor** page. If the job succeeds, all obsolete objects present in the catalog source disappear from the catalog.

   Note: If the job fails, some obsolete objects might remain in the catalog. To remove the remaining obsolete objects, run the purge job again.

Curating CLAIRE recommendations

You can view related catalog sources and accept or reject CLAIRE recommendations for a catalog source.

Applicable to catalog sources that generate lineage.

1. Go to the **Explore** page in Metadata Command Center.
2. Select **Catalog Sources** from the menu.
3. From the list of catalog sources, search for the catalog source for which you want to curate CLAIRE recommendations.
4. Hover your mouse over the catalog source and click **View Lineage Discovery** from the **Action** menu.

   Note: The **View Lineage Discovery** option is available for catalog sources that are run with the lineage discovery capability.

   The **Configure** page appears with the catalog source filtered on the **Lineage Discovery** tab of the **Lineage** tab.
   The **Related Catalog Sources** tab displays a list of related catalog sources.
5. Hover your mouse over a related catalog source and click **Accept** or **Reject** from the **Action** menu.

   For more information about lineage discovery and curating CLAIRE recommendations, see *Lineage discovery* in the *Administration* help.

Managing configuration permissions for catalog sources

As a service administrator, you can grant configuration permissions for catalog sources to different roles in your organization, and add specific users and user groups to those roles so that they can perform operational activities on a catalog source.

To manage permissions for catalog source configuration, verify that at least one role has the catalog source configuration **Set Permissions** functionality enabled for Metadata Command Center in Administrator. In Administrator, create the required roles, assign users and user groups to the roles, and specify appropriate permissions to the roles.

You can select roles and add specific users or user groups to those roles to grant the following levels of permission for catalog source configuration:


- Create
- Read
- Update
- Run
- Set Permissions

Based on the permissions granted to the roles, the selected users and user groups belonging to that role can perform appropriate operations for configuring catalog sources.

1. Go to the **Explore** page in Metadata Command Center.
2. From the list of catalog sources, search for the catalog source for which you want to manage permissions.


3. Click the **Action** menu, and select **Permissions**.

   The **Catalog Source Permissions** dialog box appears.




4. In the **Roles** panel, click **Add Roles**.

   The **Add Roles** dialog box appears.



5. Select one or more roles, and click **OK** to add the roles.
6. In the **Add Users & User Groups** panel, by default, all users and user groups that belong to the selected role are granted the role-defined permissions for the catalog source configuration.

To assign permissions only to the selected users and user groups that belong to this role, choose **Specific Users and User Groups**.



7. Select **Add Specific Users and User Groups**.

   The **Add Users & User Groups** dialog box displays the list of users and user groups that the administrator has assigned to the selected role.

8. Select one or more users or user groups to assign to the selected role, and click **OK**.

   Only the selected users and user groups belonging to the specified role will be granted the role-defined permissions for catalog source configuration.

9. View the assigned permissions for each user and or group, and click **Save**.