How-To Library

Informatica

Enabling SAML Authentication with F5 Networks BIG-IP in Informatica 10.4.1

© Copyright Informatica LLC 2017, 2021. Informatica, the Informatica logo, Informatica Data Engineering Integration, and Informatica PowerCenter are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html.

Abstract

You can enable users to log in to Informatica web applications using single sign-on. This article explains how to configure single sign-on in an Informatica 10.4.1 domain using Security Assertion Markup Language (SAML) v2.0 and the F5 BIG-IP identity provider.

Supported Versions

- Informatica Data Engineering Integration 10.4.1
- Informatica Enterprise Data Catalog 10.4.1
- Informatica Enterprise Data Preparation 10.4.1
- Informatica Metadata Manager 10.4.1

Table of Contents

Overview. 2
SAML Authentication Process. 3
Enable SAML Authentication in a Domain. 3
Create a Security Domain. 4
Import the Assertion Signing Certificate into Truststore. 8
Create a Service Provider Connection 9
Configure the Identity Provider Service Settings. 10
Choose a SAML Service Provider. 10
Configure the Identity Provider for Login Workflow. 11
Configure the AAA Server. 11
Configure the Access Policy Using VPE. 11
Create a Client Protocol Profile 12
Create a Client HTTP Profile. 13
Create a Client SSL Profile. 14
Create a Virtual Server. 14
Enable Single Sign-on in Domain. 14
Enable Single Sign-on in on Gateway Nodes. 16

Overview

You can configure Security Assertion Markup Language (SAML) authentication in an Informatica version 10.4.1 domain using the F5 Networks BIG-IP identity provider.

Security Assertion Markup Language is an XML-based data format for exchanging authentication information between a service provider and an identity provider. In an Informatica domain, an Informatica web application is the service provider.

Informatica supports F5 Networks BIG-IP version 15.1.0. You can configure the following Informatica web applications to use SAML authentication:

- Informatica Administrator

- Informatica Analyst
- Metadata Manager
- Enterprise Data Catalog
- Enterprise Data Preparation

Note: SAML authentication cannot be used in an Informatica domain configured to use Kerberos authentication.

SAML Authentication Process

Informatica web applications and the identity provider exchange authentication information to enable SAML authentication in an Informatica domain.

The following steps describe the basic SAML authentication flow:

1. A user accesses an Informatica web application.
2. The user selects the security domain containing LDAP user accounts used for SAML authentication on the application log in page, and then clicks the log in button.

   If the user selects the native security domain, the user provides a user name and password and logs in to the application.
3. Based on the identity provider configuration, the user is prompted to provide the credentials required for first time authentication.
4. The identity provider validates the user's credentials and creates a session for the user.

   The identity provider also validates the target web application URL, and then redirects the user to the web application with a SAML token containing the user's identity information.
5. The application validates the SAML token and user identity information, creates a user session, and then completes the user log in process.

The existing user session in the browser is used for subsequent authentication. To access another Informatica web application configured to use SAML authentication, the user selects the LDAP security domain on the application log in page. The user does not need to supply a user name or password.

The user remains logged in to all Informatica web applications that are running in the same browser session. However, if the user logs out of an Informatica web application, the user is also logged out of other Informatica web applications running in the same browser session.

Enable SAML Authentication in a Domain

Configure the identity provider, the Informatica domain, and the gateway nodes within the domain to use SAML authentication.

To configure SAML authentication for supported Informatica web applications that run in a domain, perform the following tasks:

1. Create an LDAP configuration to connect to the LDAP identity store that contains Informatica web application user accounts. You also create an LDAP security domain, and then import the user accounts into the security domain.
2. Export the assertion signing certificate from the identity provider.
3. Import the assertion signing certificate into a truststore file on each gateway node in the domain. You can import the certificate into the Informatica default truststore file, or into a custom truststore file.
4. Add one or more relying party trusts or service providers in the identity provider.
5. Add the URL for each Informatica web application to the identity provider.

6. Enable SAML authentication in the domain.
7. Enable SAML authentication on every gateway node in the domain.
8. Sync the LDAP users by using the following infacmd commands:
   - addLDAPConnectivity: `infacmd.sh addLDAPConnectivity -dn <Domain Name> -un <Domain username> -pd <Domain user password> -la <LDAP host name:Port> -lt <LDAPType> -lp <ldap principal> -lc <ldap credential> -lcn <LDAP host configuration name>`
   - addNamespace: `infacmd.sh addNamespace -dn <Domain name> -un <Domain username> -pd <Domain user password> -ns <Name Space> -usb <User Search Base> -uf <User Filter> -gsb <Group Search Base> -gf <Group Filter> -lcn <LDAP host configuration name>`
   - SyncSecurityDomains: `infacmd.sh SyncSecurityDomains -dn <Domain Name> -un <Domain username> -pd <Domain user password> -ns <Name Space>`
9. Add the domain privileges to some user under the created namespace.
10. Add the Administrator tool URL in the Assertion Consumer Service URL endpoints in the F5 BIG-IP.
11. Log in by selecting the namespace. You will have to enter the username and password only once.

Create a Security Domain

When you configure an Informatica domain to use an identity provider, you use Microsoft Active Directory as the identity store. Use the Administrator tool to create an LDAP configuration and a security domain for web application user accounts stored in the identity store that contains user accounts, and then import each account from the identity store into the security domain.

You must import the LDAP accounts for all users that use SAML authentication into the security domain. After importing the accounts into the domain, assign the appropriate Informatica domain roles, privileges and permissions to the accounts within the LDAP security domain.

1. In the Administrator tool, click the **Users** tab, and then select the **Security** view.
2. Click the **Actions** menu and select **LDAP Configuration**.


   The **LDAP Configuration** dialog box opens.
3. Click the **LDAP Connectivity** tab.
4. Configure the connection properties for the Active Directory server.

   The following table describes the server connection properties:

Property	Description
Server Name	Host name or IP address of the Active Directory server.
Port	Listening port for the Active Directory server. The default value is 389.
LDAP Directory Service	Select **Microsoft Active Directory**.
Name	Distinguished name (DN) for the principal LDAP user. The user name often consists of a common name (CN), an organization (O), and a country (C). The principal user name is an administrative user with access to the directory. Specify a user that has permission to read other user entries in the directory service.
Password	Password for the principal LDAP user.

Property	Description
Use SSL Certificate	Indicates that the LDAP server uses the Secure Socket Layer (SSL) protocol. If the LDAP server uses SSL, you must import the certificate into a truststore file on every gateway node within the Informatica domain. You must also set the INFA_TRUSTSTORE and INFA_TRUSTSTORE_PASSWORD environment variables if you do not import the certificate into the default Informatica truststore.
Trust LDAP Certificate	Determines whether the Service Manager can trust the SSL certificate of the LDAP server. If selected, the Service Manager connects to the LDAP server without verifying the SSL certificate. If not selected, the Service Manager verifies that the SSL certificate is signed by a certificate authority before connecting to the LDAP server.
Not Case Sensitive	Indicates that the Service Manager must ignore case sensitivity for distinguished name attributes when assigning users to groups. Enable this option.
Group Membership Attribute	Name of the attribute that contains group membership information for a user. This is the attribute in the LDAP group object that contains the distinguished names (DNs) of the users or groups who are members of a group. For example, *member* or *memberof*.
Maximum size	Maximum number of user accounts to import into a security domain. If the number of user to be imported exceeds the value for this property, the Service Manager generates an error message and does not import any user. Set this property to a higher value if you have many users to import. The default value is 1000.

The following image shows the connection details for an LDAP server set in the LDAP Connectivity panel of the **LDAP Configuration** dialog box.




5. Click **Test Connection** to verify that the connection to the Active Directory server is valid.
6. Click the **Security Domains** tab.
7. Click **Add** to create a security domain.
8. Enter the security domain properties.

The following table describes the security domain properties:

Property	Description
Security Domain	Name of the LDAP security domain. The name is not case sensitive and must be unique within the domain. The name cannot exceed 128 characters or contain the following special characters: , + / < > @ ; \ % ? The name can contain an ASCII space character except for the first and last character. All other space characters are not allowed.
User search base	Distinguished name (DN) of the entry that serves as the starting point to search for user names in the LDAP directory service. The search finds an object in the directory according to the path in the distinguished name of the object. In Active Directory, the distinguished name of a user object might be cn=UserName,ou=OrganizationalUnit,dc=DomainName, where the series of relative distinguished names denoted by dc=DomainName identifies the DNS domain of the object. For example, to search the Users container that contains user accounts in the example.com Windows domain, specify CN=USERS,DC=EXAMPLE,DC=COM.
User filter	An LDAP query string that specifies the criteria for searching for users in Active Directory. The filter can specify attribute types, assertion values, and matching criteria. For Active Directory, format the query sting as: `sAMAccountName=<account>`
Group search base	Distinguished name (DN) of the entry that serves as the starting point to search for group names in Active Directory.
Group filter	An LDAP query string that specifies the criteria for searching for groups in the directory service.

The following image shows the properties for an LDAP security domain named SAML_USERS set in the Security Domains panel of the **LDAP Configuration** dialog box. The user filter is set to import all users beginning with the letter "s".



9. Click **Synchonize Now**.

   The security domain appears in the Users view.
10. Expand the domain in the Navigator to view the imported user accounts.
11. Set the appropriate roles, privileges, and permissions on the user accounts that will access each web application.

Import the Assertion Signing Certificate into Truststore

In the Administrator tool, import the assertion signing certificate used by the identity provider into the truststore file used for SAML authentication on every gateway node within the Informatica domain.

You can import the certificate into the default Informatica truststore file, or into a custom truststore file.

The file name of the default Informatica truststore file is `infa_truststore.jks`. The file is installed in the following location on each node:

```
<Informatica installation directory>\services\shared\security\infa_truststore.jks
```

Note: Do not replace the default `infa_truststore.jks` file with a custom truststore file.

If you import the certificate into a custom truststore file, you must save the truststore file in a different directory than the directory containing the default Informatica truststore file. The truststore file name must be `infa_truststore.jks`.

You can use the Java keytool key and certificate management utility to create an SSL certificate or a certificate signing request (CSR) as well as keystores and truststores in JKS format. The keytool is available in the following directory on domain nodes:

```
<Informatica installation directory>\java\bin
```

For example, `keytool -import -alias <Certificate Alias Name> -file "<Certificate Path>/Certificate Name.cer" -keystore <INFA HOME>/services/shared/security/infa_truststore.jks -storepass <Keystore password>`

If the domain nodes run on AIX, you can use the keytool provided with the IBM JDK to create an SSL certificate or a Certificate Signing Request (CSR) as well as keystores and truststores.

1. Copy the certificate files to a local folder on a gateway node within the Informatica domain.
2. From the command line, go to the location of the keytool utility on the node.
3. Run the keytool utility to import the certificate.
4. Restart the node.

Create a Service Provider Connection

Log in to the F5 Networks BIG-IP user interface to create a service provider connection.

1. Navigate to **Access** > **Federation** > **SAML Identity Provider** > **External SP Connectors**.
2. Add details for the general settings.

Option	Description
Service Provider Entity ID	Required. Enter an identifier for the service provider.
Service Provider Name Qualifier	Required. Enter a qualifier name for the service provider.
Description	Optional. Enter the description for the general settings.

3. Add details for the endpoint settings.

Option	Description
Relay State	Optional. Enter the relay state.
Assertion Consumer Service	Required. Enter the fully configured URLs. For example, • Administrator tool: https://<server>:<Port>/administrator/Login.do • EDC Admin: https://<server>:<Port>/ldmadmin/web.isp/login • EDC: https://<server>:<Port>/ldmcatalog/login

4. In the security settings, select the **Assertion must be signed**.
5. Add details for the single logout service (SLO) settings.

Option	Description
Single Logout Request URL	Optional. Enter the logout request URL.
Single Logout Response URL	Optional. Enter the logout response URL.

Option	Description
Single Logout Binding	Optional. Select **POST** for logout binding.

6. In the service provider location settings, select **External**.

Configure the Identity Provider Service Settings

In the F5 Networks BIG-IP user interface, configure the identity provider service settings.

1. Navigate to **Access** > **Federation** > **SAML Identity Provider** > **Local IdP Services**.
2. Add details for the general settings.

Option	Description
IdP Service Name	Required. Enter a service name for the identity provider.
IdP Entity ID	Required. Enter an entity identifier for the identity provider. For example, `https://<FQDN of F5 Big-IP server >/saml/idp/profile/redirectorpost/sso`
Name Qualifier	Optional. Enter a name qualifier for the identity provider.
IdP Hostname Settings	Optional. Select the URL scheme such as HTTPS and enter the hostname.
Description	Optional. Enter description for the general settings.
Log Settings	Optional. Set or create a path to store the logs.

3. In the SAML profiles, select the **Web Server SSO**.
4. In the endpoint settings, select `None` for the **Artifact Resolution Service**.
5. In the assertion settings, keep the auto-populated default values.

   Informatica doesn't use these values.
6. In the SAML attributes, create an `username` attribute. It must be mapped to a variable that contains the user name imported into the Informatica Domain using LDAP.
7. Add details for the security settings.

Option	Description
Signing Key	Optional. Select the key that is used to sign the assertion.
Signing Certificate	Optional. Select the corresponding certificate to sign the assertion. **Note:** This certificate must be added to a trust store in the Informatica server. Configure Informatica to use this certificate for validating SAML assertions.

Choose a SAML Service Provider

In the F5 Networks BIG-IP user interface, associate a SAML service provider to the identity provider.

1. Navigate to **Access** > **Federation** > **SAML Identify Provider** > **Local IdP Services** > **Bind/Unbind SP Connectors**.
2. To associate the SP with the IdP, select the SAML service provider connection name.

Configure the Identity Provider for Login Workflow

In the F5 Networks BIG-IP user interface, select the identity provider and create a login flow.

1. Navigate to **Access** > **Profiles / Policies** > **Access Profiles (Per-Session Policies)**.
2. On access profile page, click **SSO / Auth Domains**.
3. In SSO Configuration, select the identity provider that you configured earlier.
4. To create a login workflow, click **Access Policy** and create a flow.

   For example, create a simple login flow for username and password to authenticate against the active directory (AD).

Configure the AAA Server

In the F5 Networks BIG-IP user interface, configure the authentication, authorization, and accounting (AAA) server.

1. Navigate to **Access** > **Authentication** > **Active Directory**.
2. Click **Create**.
3. Add active directory configuration details.

Option	Description
Domain Name	Enter a name for domain.
Server Connection	Set the connection to **Direct**.
Domain Controller	Enter the domain controller.
Admin Name	Enter the administrator name.
Admin Password	Enter the administrator password.
Verify Admin Password	Repeat the administrator password.
Group Cache Lifetime	Set the group cache lifetime in days.
Password Security Object Cache Lifetime	Set the password security object cache lifetime in days.
Kerberos Cache	You can choose to clear the Kerberos cache.
Kerberos Preauthentication Encryption Type	Set it to **None**.
Timeout	Set the timeout value.

Configure the Access Policy Using VPE


In the F5 Networks BIG-IP user interface, configure the access policy.

1. In the main tab, navigate to **Access Policy** > **Access Profiles**.
2. Go to the previously created access profile, and under the **Access Policy** column, click **Edit**.

   The VPE window opens.
3. Click **+** located between **Start** and **Deny**.

4. Go to the **Logon Page** option and click **Add Item**.
   a. Configure the properties and click **Save**.
      You can choose the default settings.
5. Click **+** located between **Logon Page** and **Deny**.
6. In the authentication tab, navigate to **AD Auth** > **Add Item**.
   a. Select the AAA server that you configured.
   b. Click **Finished** and save the settings.
   Successful and fallback path appears.
7. Click **+** in the successful path located between **AD Auth** and **Deny**.
8. In the authentication tab, navigate to **AD Query** > **Add Item**.
   a. Select the AAA server that you created.
   b. Search for `samAccountName=%{session.logon.last.username}`.
   c. On the branch rule tab, remove the default and add a new branch rule.
   d. Enter `Successful` as the name.
   e. Click the change link.
   f. Click **Add Expression**.
   g. In the **Agent Sel** list, select `AD Query`.
   h. In the **Condition** list, select `AD Query Passed` and then click **Add Expression**.
   i. Click **Finished** and save the settings.
9. Click **+** in the successful path located between **AD Query** and **Deny**.
10. Click **Apply Access Policy** and close.

Access policy is configured.



Create a Client Protocol Profile

In the F5 Networks BIG-IP user interface, create a TCP client profile.

1. Navigate to **Local Traffic** > **Profiles** > **Protocol** > **TCP**.
2. Create a TCP profile.

Option	Description
Name	Enter a unique name. For example, tcp-saml.
Parent Profile	Set it to tcp-wan-optimized.

3. Keep the default values for other options and save the profile.

Create a Client HTTP Profile

In the F5 Networks BIG-IP user interface, create a client HTTP profile.

1. Navigate to **Local Traffic** > **Profiles** > **Services** > **HTTP**.
2. In general properties, set the parent profile to `http`.
3. In settings, set the following values:

Option	Description
Request Chunking	Sustain
Response Chunking	Sustain
OneConnect Transformations	Enabled
OneConnect Status Reuse	200 206
Redirect Rewrite	None
Insert X-Forwarded-For	Enabled
LWS Maximum Columns	80
Maximum Requests	0
Send Proxy Via Header in Request	Preserve
Send Proxy Via Header in Request	Preserve
Server Agent Name	BigIP

4. In enforcement, set the following values:

Option	Description
Allow Truncated Redirect	Disabled
Maximum Header Size	32768 Bytes
Maximum Header Count	64
Pipeline Action	Allow
Unknown Method	Allow
Known Methods	Connect, Delete, Get, Head, and Lock.

5. Set the **Polling Interval** and **Sampling Rate** to default values.

6. In HTTP strict transport security, set the following values:

Option	Description
Maximum Age	16070400
Include Subdomains	Enabled

7. Save the profile.

Create a Client SSL Profile

In the F5 Networks BIG-IP user interface, create a client SSL profile.

1. Navigate to **Local Traffic** > **Profiles** > **SSL** > **Client**.
2. In general properties, select the parent profile as `clientssl`.
3. In configuration, select **Basic**.
4. Add certificate and certificate key path to **Certificate Key Chain**.
5. Keep the auto-populated values for other options.
6. Save the profile.

Create a Virtual Server

In the F5 Networks BIG-IP user interface, create a virtual server.

1. Navigate to **Local Traffic** > **Virtual Servers** > **Virtual Server List** > **Virtual Server**.
2. Enter a unique name for the virtual server.
3. Enter the destination address mask. For example, 10.0.1.4.
4. Enter `443` for the service port.
5. In access policy, select the created access profile.
6. Click **Update**.

Enable Single Sign-on in Domain

You can enable SAML authentication in an existing Informatica domain, or you can enable it when you create a domain.

When you enable a domain to use SAML authentication, all web applications that run in the domain use the default identity provider you specify when you enable SAML authentication in the domain. For example, if you configure AD FS as the identity provider, all web applications use AD FS as the identity provider, unless you configure a web application to use a different identity provider.

Select one of the following options:

Enable SAML authentication when you run Informatica installer.

You can enable SAML authentication and specify the identity provider URL when you configure the domain as part of the installation process.

Enable SAML authentication in an existing domain.

Use the infasetup updateDomainSamlConfig command to enable SAML authentication in an existing Informatica domain. You can run the command on any gateway node within the domain.

Enable SAML authentication when you create a domain.

Use the infasetup defineDomain command to enable SAML authentication when you create a domain.

See the *Informatica Command Reference* for instructions on using the commands.

infasetup DefineDomain Command Options

Use the infasetup defineDomain command to enable SAML authentication when you create a domain.

The following example shows the options to configure a domain to use F5 Networks BIG-IP as the identity provider in the final six options at the command prompt:

```
infasetup defineDomain -cs "jdbc:company:oracle://host:1521;sid=DB2" -dt oracle -dn TestDomain -ad test_admin -pd test_admin -ld $HOME/ISP/1040/source/logs -nn TestNode1 -na host1.company.com -saml true -iu https://01.00.000.00:9031/idp/SSO.saml2 -spid F5_ProdDomain -cst 240 -asca f5cert -std \custom\security\ -stp password -mi 10000 -ma 10200 -rf $HOME/ISP/BIN/nodeoptions.xml
```

The following table describes the SAML options and arguments:

Option	Argument	Description
-EnableSaml -saml	true|false	Required. Set this value to true to enable SAML authentication for supported Informatica web applications within the Informatica domain. Set this value to false to disable SAML authentication for supported Informatica web applications within the Informatica domain.
-idpUrl -iu	identity_provider_url	Required. Specify the F5 Networks BIG-IP identity provider URL for the domain. You must specify the complete URL string.
-ServiceProviderId -spid	service_provider_id	Optional. The relying service provider identifier for the domain as defined in F5 Networks BIG-IP. If you specified "Informatica" as the service provider name, you do not need to specify a value.
-ClockSkewTolerance -cst	clock_skew_tolerance_in_seconds	Optional. The allowed time difference between the F5 Networks BIG-IP host system clock and the master gateway node's system clock. The lifetime of SAML tokens issued by the identity provider by is set according to the host system clock. The lifetime of a SAML token issued by the identity provider is valid if the start time or end time set in the token is within the specified number seconds of the master gateway node's system clock. Values must be from 0 to 600 seconds. Default is 120 seconds.
-AssertionSigningCertificateAlias -asca	idp_assertion_signing_certificate_aliaseAlias	Required. The alias name specified when importing the identity provider assertion signing certificate into the truststore file used for SAML authentication.
-SamlTrustStoreDir -std	saml_truststore_directory	Optional. The directory containing the custom truststore file required to use SAML authentication on gateway nodes within the domain. Specify the directory only, not the full path to the file. SAML authentication uses the default Informatica truststore if no truststore is specified.
-SamlTrustStorePassword -stp	saml_truststore_password	Required if you use a custom truststore. The password for the custom truststore file.

See the *Informatica Command Reference* for instructions on using the infasetup defineDomain command.

Infasetup updateDomainSamlConfig Command Options

Set the SAML options in the infasetup updateDomainSamlConfig command to enable SAML authentication in a domain. Shut down the domain before you run the command.

Specify the identity provider URL as the value for the `-iu` option. Use the following example to configure a domain:

```
infasetup updateDomainSamlConfig -saml true -iu <IDP URL> -spid <Service Provider Connection Name>
```

The default value of `-spid` is Informatica.

The following table describes the options and arguments:

Option	Argument	Description
-EnableSaml -saml	true|false	Required. Set this value to true to enable SAML authentication for supported Informatica web applications within the Informatica domain. Set this value to false to disable SAML authentication for supported Informatica web applications within the Informatica domain.
-idpUrl -iu	identity_provider_url	Required. Specify the F5 Networks BIG-IP identity provider URL for the domain. The IDP URL is the identity provider's entity ID.
-ServiceProviderId -spid	service_provider_id	Optional. The service provider identifier for the domain as defined in F5 Networks BIG-IP. The default is Informatica.
-ClockSkewTolerance -cst	clock_skew_tolerance_in_seconds	Optional. The allowed time difference between the F5 Networks BIG-IP host system clock and the master gateway node's system clock. The lifetime of SAML tokens issued by the identity provider by is set according to the host system clock. The lifetime of a SAML token issued by the identity provider is valid if the start time or end time set in the token is within the specified number seconds of the master gateway node's system clock. Values must be from 0 to 600 seconds. Default is 120 seconds.

See the *Informatica Command Reference* for instructions on using the infasetup updateDomainSamlConfig command.

Enable Single Sign-on in on Gateway Nodes

You must configure SAML authentication on every gateway node in the Informatica domain.

Select one of the following options to configure SAML authentication on a gateway node:

Enable SAML authentication when you define a gateway node on a machine.

Use the infasetup DefineGatewayNode command to enable SAML authentication on the gateway node.

Enable SAML authentication when you configure a gateway node to join a domain that uses SAML authentication.

Use the infasetup UpdateGatewayNode command to enable SAML authentication on the gateway node.

Enable SAML authentication when you convert a worker node to a gateway node.

Use the isp SwitchToGatewayNode command to enable SAML authentication on the node.

See the *Informatica Command Reference* for instructions on using the commands.

Gateway Node Command Options

Use the infasetup DefineGatewayNode command to enable SAML authentication when you create a gateway node. Use infasetup UpdateGatewayNode or infacmd isp SwitchToGatewayNode to enable SAML authentication on an existing node.

The SAML options are identical for all of these commands.

The following example shows the SAML options as the final four options on the infasetup DefineGatewayNode command line:

```
infasetup defineGatewayNode -cs "jdbc:informatica:oracle://host:1521;sid=xxxx" -du test_user -dp test_user -dt oracle -dn TestDomain -nn TestNode1 -na host2.company.com:1234 -ld $HOME/ISP/1011/source/logs -rf $HOME/ISP/BIN/nodeoptions.xml -mi 10000 -ma 10200 -ad test_admin -pd test_admin -saml true -asca f5cert -std \custom\security\ -stp password
```

The following example updates the gateway node with the certificate alias:

```
./infasetup.sh updateGatewayNode -saml true -asca <Certificate alias name>
```

The following table describes the options and arguments:

Option	Argument	Description
-EnableSaml -saml	true|false	Required. Enables SAML authentication in the Informatica domain. Set this value to true to enable SAML authentication in the domain. Set this value to false to disable SAML authentication in the domain.
-AssertionSigningCertificateAlias -asca	idp_assertion_signing_certificate_aliaseAlias	Required if SAML authentication is enabled for the domain. The alias name specified when importing the identity provider assertion signing certificate into the truststore file used for SAML authentication.
-SamlTrustStoreDir -std	saml_truststore_directory	Optional. The directory containing the custom truststore file required to use SAML authentication on gateway nodes within the domain. Specify the directory only, not the full path to the file. The default Informatica truststore is used if no truststore is specified.
-SamlTrustStorePassword -stp	saml_truststore_password	Required if you use a custom truststore. The password for the custom truststore file.

See the *Informatica Command Reference* for instructions on using the infasetup DefineGatewayNode, the infasetup UpdateGatewayNode, and the infacmd isp SwitchToGatewayNode commands.

Author

Saurabh Sugandh