Informatica® MDM SaaS
April 2026

Material 360

Informatica MDM SaaS Material 360
April 2026

© Copyright Informatica LLC 2023, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica and the Informatica logo are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-04-11

Table of Contents

Preface. . . . 5
Informatica Resources. . . . 5
Informatica Documentation. . . . 5
IDMC web site. . . . 5
Intelligent Data Management Cloud Communities. . . . 5
IDMC Marketplace. . . . 5
Informatica Knowledge Base. . . . 5
IDMC Trust Center. . . . 6
Informatica Global Customer Support. . . . 6

Chapter 1: Introducing Material 360. . . . 7
Guidelines for importing assets. . . . 7
Guidelines for migrating assets. . . . 8
Prerequisites. . . . 8

Chapter 2: Material 360 and SAP integration. . . . 9
Processing data in batches. . . . 9
Ingress data. . . . 9
Egress data. . . . 10

Chapter 3: Material 360 assets. . . . 11
Data model attributes. . . . 11
Material business entity model. . . . 12
Material Category business entity model. . . . 17
Predefined batch jobs. . . . 18
Batch jobs of the Material business entity for SAP ECC. . . . 19
Batch jobs of the Material business entity for SAP S/4HANA. . . . 22
Batch jobs of the Material Category business entity for SAP ECC. . . . 25
Batch jobs of the Material Category business entity for SAP S/4HANA. . . . 26
Field mapping. . . . 26
General fields of the Material business entity. . . . 27
Alternative Unit of Measurement field group of the Material business entity. . . . 28
Identifier field group of the Material business entity. . . . 28
Material Description field group of the Material business entity. . . . 29
Material Plant field group of the Material business entity. . . . 29
Relationships. . . . 29
Predefined pages. . . . 30
Search result layout components. . . . 31
Data quality rule associations. . . . 31
Reports. . . . 32

Business process workflow . . . 32
Predefined user roles. . . . 33
Sample workflow to create material records. . . . 33
Sample workflow to update a material record. . . . 34

Chapter 4: Deploying Material 360 on MDM SaaS. . . . 36

Downloading and extracting the Material 360 package. . . . 36
Importing the authorization assets. . . . 37
Importing data model, pages, source systems, and reports. . . . 38
Adding predefined pages and components. . . . 38
Importing reference data assets. . . . 39
Prerequisites. . . . 40
Importing the reference data. . . . 40

Chapter 5: Integrating Material 360 with SAP. . . . 42

Importing the Cloud Data Integration assets. . . . 42
Importing the predefined batch jobs. . . . 43
Importing the Cloud Application Integration assets. . . . 43
Publishing the Cloud Application Integration processes. . . . 44
Adding a Secure Agent. . . . 44
Importing parameter files. . . . 44
Configuring the flat file connection. . . . 45
Configuring Business 360 Connector. . . . 45
Configuring the SAP connection. . . . 45
Creating a custom table in SAP. . . . 48
Creating import jobs in Reference 360. . . . 49
Running the jobs. . . . 53

Index. . . . 55

Preface

Follow the instructions in *Material 360* to deploy the Material 360 extension.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the Informatica® Intelligent Data Management Cloud™ (IDMC) web site at http://www.informatica.com/cloud.

Intelligent Data Management Cloud Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

To access the IDMC Community, see Master Data Management SaaS Community.

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security policies and real-time system availability.

You can access the trust center at https://www.informatica.com/trust-center.html.

Subscribe to the IDMC Trust Center to receive upgrade, maintenance, and incident notifications. The Informatica Intelligent Data Management Cloud Status page displays the production status of all the Informatica cloud products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single component or all IDMC components. Subscribing to all components is the best way to be certain you never miss an update.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Introducing Material 360

An industry 360 application is a ready-to-use package that you can use as a template for implementing MDM SaaS. With an industry 360 application, you can customize solutions to meet specific requirements and business initiatives of your industry. Use an industry 360 application to reduce implementation time, enhance data quality, and achieve faster business outcomes.

You can use Material 360 to efficiently process both material data and material category data, employing processes such as matching, merging, consolidating, and enrichment.

Use Material 360 to achieve the following goals:

Centrally author and maintain material data

Centrally author and maintain material master data to ensure collaboration between business users from various departments. Use the workflow to control the maintenance of the material master data. For example, when you create a material record, you can streamline the business process by involving business users to approve the record data before the record creation.

You can maintain a material hierarchy for material analysis and price determination.

Integrate material master records with SAP ECC and SAP S/4HANA

Ingress SAP ECC and SAP S/4HANA records to MDM SaaS, process the data in batches, and egress the data to SAP S/4HANA.

Use the extension to migrate material data from SAP ECC to SAP S/4HANA. You can ingress material and material category data from SAP ECC to MDM SaaS. After you ingress, you can process the data and egress the data to SAP S/4HANA.

Track and trace material

Track and trace a material and its hierarchy across the supply chain. For example, you can quickly and accurately identify the impact of a product recall or a supply chain disruption.

Guidelines for importing assets

Consider the following guidelines before you import the industry 360 application assets:

- Set up the prerequisite MDM SaaS business application.
- Import the industry 360 application assets before you customize the business entities. You can safely import multiple industry 360 application assets that use different business entities and in different MDM SaaS business applications. When you import the assets in an environment that already has an industry 360 application with the same business entities, the import fails.
- After you import the assets, consider them as your custom assets.

- Once you deploy an industry 360 application, upgrading to a newer version of the industry 360 application isn't supported.

Guidelines for migrating assets

Consider the following guidelines before you migrate the industry 360 application assets to another environment:

- To migrate the industry 360 application assets to higher environments, such as QA and production, export the assets from the development environment. Then, import them into the QA and production environments. For more information about migrating assets, see *Migrating projects and assets*.
- Don't import the industry 360 application assets again into a higher environment.

Prerequisites

Before you deploy Material 360, perform the following prerequisites:

- Ensure that you have the license for the Integration Components for Business 360 and MDM SaaS edition. Ensure that you have the licenses required to manage connections, external data, and service rights.

  Note: The use of the extension doesn't confer any additional license or entitlement to license consumption beyond the terms specified in the applicable licensing agreements.
- Ensure that the version of the package matches the current MDM SaaS version where you import the extension assets.
  To view the MDM SaaS version, in Business 360 Console, click **About** in the IDMC Help menu and verify the build version.

  To view the MDM version of the extension, navigate to the readme text file in the extracted extension package and verify the platform version.

  If the version of the extension bundle doesn't match the current MDM SaaS version, contact Informatica Global Customer Support to use the current version of the extension.

Before you integrate MDM SaaS with SAP ECC, ensure that you complete the following prerequisites:

- Ensure that your organization uses the SAP ECC 6.0 EHP8 version of SAP
- Enable the following licenses:
  - SAP Table Connector
  - SAP Business Application Programming Interfaces (BAPI) Connector

Before you integrate MDM SaaS with SAP S/4HANA, ensure that you complete the following prerequisites:

- Ensure that your organization uses the SAP S/4HANA 2023 version of SAP
- Enable the following licenses:
  - SAP Table Connector
  - SAP Business Application Programming Interfaces (BAPI) Connector

CHAPTER 2

Material 360 and SAP integration

Use Material 360 to integrate MDM SaaS with SAP ECC or SAP S/4HANA and process the SAP material data in MDM SaaS.

Run ingress batch jobs to import SAP material records to MDM SaaS from SAP ECC or SAP S/4HANA. Run egress batch jobs to export MDM SaaS material records to SAP S/4HANA.

After exporting material records from MDM SaaS to SAP S/4HANA, you can write the status of the updated material record in SAP as either successful or failed, and reflect this status back in MDM SaaS.

Processing data in batches

Use Material 360 to process SAP ECC and SAP S/4HANA records in batches.

Run a batch job to ingress SAP ECC and SAP S/4HANA records to MDM SaaS. The job uses a taskflow to run mapping tasks. Each mapping task includes a mapping that maps the SAP fields with the Material business entity fields.

Ingress data


You can import material and product hierarchy records from SAP ECC or SAP S/4HANA into MDM SaaS using the predefined ingress jobs.

When you ingress material and product hierarchy records from SAP ECC or SAP S/4HANA into MDM SaaS, the ingress job creates master material records and material category records for these SAP records in MDM SaaS.

To read data from SAP, you require SAP Table Connector, and to write data to MDM SaaS, you require Business 360 FEP Connector. After you ingress SAP records, you can process the records in MDM SaaS.

For more details about ingress jobs, see “Predefined batch jobs” on page 18.

The following image shows how to ingress SAP records in batches:




Egress data

After you process records in MDM SaaS, you can export the records to SAP S/4HANA in batches. Use Cloud Data Integration assets and multiple Business Application Programming Interfaces (BAPIs) to export the processed material records.

You can export the following records to SAP S/4HANA in batches:

- Records imported from SAP ECC. After you import material and material category records from SAP ECC, you can process the records in MDM SaaS. You can export the processed records to SAP S/4HANA, and SAP S/4HANA assigns a new material number to the processed SAP ECC record.
- Records created or updated in MDM SaaS. After you create material records in MDM SaaS, you can export the processed records to SAP S/4HANA, and SAP S/4HANA assigns a new material number to the processed material record. If you update the material records integrated earlier with SAP S/4HANA in MDM SaaS, you can export the updated SAP S/4HANA records to SAP S/4HANA with the existing material numbers.
- Records imported from SAP S/4HANA. After you import material and material category records from SAP S/4HANA, you can update the records in MDM SaaS. You can export the updated records to SAP S/4HANA with the existing material numbers.

The following image shows how to egress material records to SAP S/4HANA in batches:



Note: After you delete a record that you already exported to SAP S/4HANA from MDM SaaS, you can't synchronize the deleted record in SAP S/4HANA.

CHAPTER 3

Material 360 assets

Material 360 is available as a package for installation on request.

The package includes the following predefined assets:


- Business entities
- Connections
- Custom reports
- Data quality rule associations
- Taskflows
- Mapping tasks
- Mappings
- Predefined jobs
- Hierarchies
- Predefined pages
- Processes
- Reference data assets
- Relationships
- Search components
- Source systems

Data model attributes

The Material 360 package includes the following business entities:

- Material. Stores information about materials that an organization uses, such as material plant, material description, and industry sector.
- Material Category. Stores information about the categories of materials, such as the category ID, description, and the level of a material category.

The following image shows the Material 360 business entities and their relationships:



Material business entity model

Material business entity stores information about materials that an organization uses, such as material plant, material description, and industry sector. This business entity contains some basic fields and some field groups.

General fields of the Material business entity

The general fields store basic information about a material, such as material type, material number, and basic constituents of a material.

The following table describes the general fields of the Material business entity:

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Authorization Group	infap360mm_authorizationGroup	Text	4	NA	Group of users with authorizations to control access to a material.
Base Unit of Measurement	infap360mm_baseUnitOfMeasure	Lookup	NA	infap360mm_UOM	Unit to measure the quantity of a material. For example, pound, each, and box of 12.
Basic Constituent of Material	infap360mm_basicConstituentOfMaterial	Text	50	NA	The basic constituents that the material is made of.
Bulk or Liquid Indicator	infap360mm_ind_isBulkLiquid	Boolean	NA	NA	Indicates whether a material is in bulk or a liquid form.
Configurable Material Indicator	infap360mm_ind_configurableMaterial	Text	1	NA	Indicates whether a material can be produced in different variants.
Cross Plant Material Status	infap360mm_xPlantMatStatus	Lookup	NA	infap360mm_XPlantMatStatus	Status to indicate the usability of a material for multiple plants. For example, for approval, or obsolete.
Division	infap360mm_division	Lookup	NA	infap360mm_Division	Division of the organization that a material belongs to.

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Environmentally Relevant Indicator	infap360mm_ind_environmentallyRelevant	Text	1	NA	Indicates whether a material is part of the environmental footprint of a company.
General Item Category Group	infap360mm_generalItemCategoryGroup	Lookup	NA	infap360mm_GeneralItemCatGrp	Group to determine a material category in a sales order.
Highly Viscous Indicator	infap360mm_ind_isHighlyViscous	Boolean	NA	NA	Indicates whether the material is highly viscous.
Industry Sector	infap360mm_industrySector	Lookup	NA	infap360mm_IndustrySector	Branch of an industry for the assignment of a material. For example, plant engineering and construction, chemical industry, mechanical engineering, and pharmaceuticals industry.
Material Group	infap360mm_materialGroup	Lookup	NA	infap360mm_MaterialGroup	Group of materials and services with the same attributes. For example, office supplies, beverages, and maintenance work.
Material Group - Packaging Materials	infap360mm_materialGroupPackagingMaterials	Lookup	NA	infap360mm_MaterialGroupPackagingMaterials	Grouping parameter to group materials that need similar packaging materials.
Material Number	infap360mm_materialNumber	Text	40	NA	Unique identifier for a material.
Material Number Type	infap360mm_matNumType	Lookup	NA	infap360mm_MaterialNumType	Source from which the material number is obtained.
Material Type	infap360mm_materialType	Lookup	NA	infap360mm_MaterialType	Type of material based on basic attributes.
Net Weight	infap360mm_netWeight	Decimal	13(3)	NA	Delivery of net weight of a material in a shipment.
Old Material Number	infap360mm_oldMaterialNumber	Text	40	NA	Old identifier for a material under which the material was managed so far.
Transportation Group	infap360mm_transportationGroup	Lookup	NA	infap360mm_TransportationGroup	Group of materials that have similar transportation requirements. For example, trucks, tankers, and trains.
Unit of Measurement for Weight	infap360mm_weightUnit	Lookup	NA	infap360mm_UOM	Unit of measurement for the weight of a material.
Valid From	infap360mm_validFrom	Date	NA	NA	The date from when the material details become valid.

Alternative Unit of Measurement field group of the Material business entity

The Alternative Unit of Measurement field group stores the detailed measurements of a material in addition to the base unit of measurement.

The following table describes the fields of the Alternative Unit of Measurement field group:

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Alternative Unit of Measurement	infap360mm_dimAlternativeUnitOfMeasureSKU	Lookup	NA	infap360mm_AlternateUOM	Unit of measurement in addition to the base unit of measurement to manage the stocks of a material.
Denominator of Conversion Factor	infap360mm_dimDenominatorToBaseUom	Decimal	5(0)	NA	Denominator of the quotient that specifies the ratio of the alternative unit of measurement to the base unit of measurement.
Gross Weight	infap360mm_dimGrossWeight	Decimal	13(3)	NA	Gross weight of a material.
Height	infap360mm_dimHeight	Decimal	13(3)	NA	Height of a material.
Length	infap360mm_dimLength	Decimal	13(3)	NA	Length of a material.
Numerator of Conversion Factor	infap360mm_dimNumeratorToBaseUom	Decimal	5(0)	NA	Numerator of the quotient that specifies the ratio of the alternative unit of measurement to the base unit of measurement.
Unit of Measurement for Dimensions	infap360mm_dimUnitOfDimensions	Lookup	NA	infap360mm_UOM	Unit of measurement for the dimensions of a material.

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Unit of Measurement for Volume	infap360mm_dimVolumeUnit	Lookup	NA	infap360mm_UOM	Unit of measurement for the volume of a material.
Unit of Measurement for Weight	infap360mm_dimWeightUnit	Lookup	NA	infap360mm_UOM	Unit of measurement for the weight of a material.
Volume	infap360mm_dimVolume	Decimal	13(3)	NA	Volume of a material.
Width	infap360mm_dimWidth	Decimal	13(3)	NA	Width of a material.

Identifier field group of the Material business entity

The Identifier field group stores the identifier related information of a material, such as identifier type and status of the identifier.

The following table describes the fields that the Identifier field group contains:

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Identifier Status	infap360mm_identifierStatus	Lookup	NA	infap360mm_IdentifierStatus	Status of the identifier. For example, active or inactive.
Identifier Type	infap360mm_idType	Lookup	NA	infap360mm_IdentifierType	Source of the identifier. For example, SAP ECC or SAP S/4HANA.
Identifier Value	infap360mm_altIdValue	Text	40	NA	Value of the identifier.

Material Description field group of the Material business entity

The Material Description field group stores the description of a material.

The following table describes the fields of the Material Description field group:

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Description	infap360mm_description	Text	40	NA	Description of a material.
Language	infap360mm_language	Lookup	NA	Crosswalk-Language	Language of a material description.

Material Plant field group of the Material business entity

The Material Plant field group stores the details of a material plant.

The following table describes the fields of the Material Plant field group:

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Commodity - Import Code Number for Foreign Trade	infap360mm_commodityCode	Lookup	NA	infap360mm_CommodityCode	Code from the Harmonized Commodity Description and Coding System to identify a commodity for import.
Country of Origin	infap360mm_countryOfOrigin	Lookup	NA	Country	Country where a material is manufactured.
Export and Import Material Group	infap360mm_exportImportMaterialGroup	Lookup	NA	infap360mm_expImpMaterialGrp	Group of materials with similar export and import attributes.
Loading Group	infap360mm_loadingGroup	Lookup	NA	infap360mm_LoadingGrp	Group of materials with similar loading requirements for transportation. For example, cranes, forklifts, and trolleys.
Plant	infap360mm_plant	Lookup	NA	infap360mm_Plant	Location that holds the stock of a material.
Profit Center	infap360mm_profitCenter	Text	10	NA	Profit center of a material.
Region of Origin of Material	infap360mm_regionOfOrigin	Lookup	NA	infap360mm_Region	Region from where a material is manufactured.

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Storage Location	infap360mm_storageLoc	Lookup	NA	infap360mm_StorLoc	Place where a material is stored.
Unit of Measurement for Commodity Code	infap360mm_unitOfMeasure	Lookup	NA	infap360mm_UOM	Unit of measurement for the commodity code of a material.

Record Status field group of the Material business entity

The Record Status field group stores the status of the Material business entity record.

The following table describes the fields of the Record Status field group:

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Status Type	infap360mm_statusType	Lookup	NA	infap360mm_ErrorStatusType	Type of the record status. For example, S4Hana Integration Status.
Description	infap360mm_errorDescription	Text	255	NA	A brief description about the record status.
Last Updated	infap360mm_date	Date and Time	NA	NA	The latest date and time when the status was updated.
Status	infap360mm_status	Lookup	NA	infap360mm_ErrStatus	Status of the record. For example, success or failure.

Material Category business entity model

Material Category business entity stores information about categories of materials, such as the category ID, description, and the level of a material category. This business entity contains some basic fields.

General fields of the Material Category business entity

The general fields store basic information about the category of materials with the same attributes or purpose.

The following table describes the general fields of the Material Category business entity:

Display Name	Internal ID	Field Type	Length	Reference Data	Description
Category ID	infap360mm_categoryID	Text	20	NA	Unique identifier for the category of a material.
Description	infap360mm_description	Text	50	infap360mm_UOM	Description of the category of a material.
Level Number	infap360mm_leveNo	Integer	NA	NA	Unique number for the level of a material category.

Predefined batch jobs

Use batch jobs to ingress the SAP ECC and S/4HANA material records to MDM SaaS and to export the processed records from MDM SaaS to SAP S/4HANA.

After you import the SAP ECC and SAP S/4HANA records to MDM SaaS, you can process the imported records in MDM SaaS. Export the processed records from MDM SaaS to SAP S/4HANA.

Each job uses a taskflow to run a mapping task. Each mapping task includes a mapping that maps the SAP fields with the Material business entity fields.

Batch jobs of the Material business entity for SAP ECC

The following table lists the predefined jobs for initial inbound and their related taskflow, mapping task, and mapping of the Material business entity for SAP ECC:

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_ingress_ecc_material_material_inbound_initial	infap360mm_tf_ecc_material_material_inbound_initial	- infap360mm_mt_ecc_material_material_inbound_plant_initial - infap360mm_mt_ecc_material_material_inbound_alternate_identifier_initial - infap360mm_mt_ecc_material_material_inbound_altUnitOfMeasurement_initial - infap360mm_mt_ecc_material_material_inbound_root_initial - infap360mm_mt_ecc_material_material_inbound_description_initial	- infap360mm_m_ecc_material_material_inbound_plant_initial - infap360mm_m_ecc_material_material_inbound_alternate_identifier_initial - infap360mm_m_ecc_material_material_inbound_altUnitOfMeasurement_initial - infap360mm_m_ecc_material_material_inbound_root_initial - infap360mm_m_ecc_material_material_inbound_description_initial	Imports the entire data from SAP ECC to the Material business entity.

The following table lists the predefined jobs for incremental inbound and their related taskflow, mapping task, and mapping of the Material business entity for SAP ECC:

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_ingress_ecc_material_material_inbound_delta	infap360mm_tf_ecc_material_material_inbound_delta	- infap360mm_mt_ecc_material_material_inbound_root_delta - infap360mm_mt_ecc_material_material_inbound_plant_delta - infap360mm_mt_ecc_material_material_inbound_alternate_identifier_delta - infap360mm_mt_ecc_material_material_inbound_description_delta - infap360mm_mt_ecc_material_material_inbound_altUnitOfMeasurement_delta	- infap360mm_m_ecc_material_material_inbound_root_delta - infap360mm_m_ecc_material_material_inbound_plant_delta - infap360mm_m_ecc_material_material_inbound_alternate_identifier_delta - infap360mm_m_ecc_material_material_inbound_description_delta - infap360mm_m_ecc_material_material_inbound_altUnitOfMeasurement_delta	Imports incremental data at the field groups level from SAP ECC and updates it in the Material business entity.

The following table lists the lookup assets with taskflows, mapping task, and mapping of the Material business entity for SAP ECC:

Taskflow	Mapping Task	Mapping	Description
- infap360mm_tf_ecc_enterprise_lkp_plant_inbound - infap360mm_tf_ecc_enterprise_lkp_material_group_inbound - infap360mm_tf_ecc_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_tf_ecc_enterprise_lkp_TransportationGroup_inbound - infap360mm_tf_ecc_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_tf_ecc_enterprise_lkp_region_inbound - infap360mm_tf_ecc_enterprise_lkp_storageloc_inbound - infap360mm_tf_ecc_enterprise_lkp_LoadingGrp_inbound - infap360mm_tf_ecc_enterprise_lkp_division_inbound - infap360mm_tf_ecc_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_tf_ecc_enterprise_lkp_GeneralItemCatGrp_inbound - infap360mm_tf_ecc_enterprise_lkp_CommodityCd_inbound - infap360mm_tf_ecc_ecc_lkp_region_inbound - infap360mm_tf_ecc_ecc_lkp_CommodityCd_inbound - infap360mm_tf_ecc_ecc_lkp_expImpMaterialGrp_inbound - infap360mm_tf_ecc_ecc_lkp_storageloc_inbound - infap360mm_tf_ecc_ecc_lkp_GeneralItemCatGrp_inbound - infap360mm_tf_ecc_ecc_lkp_material_group_inbound	- infap360mm_mt_ecc_enterprise_lkp_plant_inbound - infap360mm_mt_ecc_enterprise_lkp_material_group_inbound - infap360mm_mt_ecc_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_mt_ecc_enterprise_lkp_TransportationGroup_inbound - infap360mm_mt_ecc_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_mt_ecc_enterprise_lkp_region_inbound - infap360mm_mt_ecc_enterprise_lkp_storageloc_inbound - infap360mm_mt_ecc_enterprise_lkp_LoadingGrp_inbound - infap360mm_mt_ecc_enterprise_lkp_division_inbound - infap360mm_mt_ecc_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_mt_ecc_enterprise_lkp_GeneralItemCatGrp_inbound - infap360mm_mt_ecc_enterprise_lkp_CommodityCd_inbound - infap360mm_mt_ecc_ecc_lkp_region_inbound - infap360mm_mt_ecc_ecc_lkp_CommodityCd_inbound - infap360mm_mt_ecc_ecc_lkp_expl	- infap360mm_m_ecc_enterprise_lkp_plant_inbound - infap360mm_m_ecc_enterprise_lkp_material_group_inbound - infap360mm_m_ecc_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_m_ecc_enterprise_lkp_TransportationGroup_inbound - infap360mm_m_ecc_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_m_ecc_enterprise_lkp_region_inbound - infap360mm_m_ecc_enterprise_lkp_storageloc_inbound - infap360mm_m_ecc_enterprise_lkp_LoadingGrp_inbound - infap360mm_m_ecc_enterprise_lkp_division_inbound - infap360mm_m_ecc_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_m_ecc_enterprise_lkp_GeneralItemCatGrp_inbound - infap360mm_m_ecc_enterprise_lkp_CommodityCd_inbound - infap360mm_m_ecc_ecc_lkp_region_inbound - infap360mm_m_ecc_ecc_lkp_CommodityCd_inbound - infap360mm_m_ecc_ecc_lkp_expImpMaterialGrp_inbound - infap360mm_m_ecc_ecc_lkp_storageloc_inbound - infap360mm_m_ecc_ecc_lkp_GeneralItemCatGrp_inbound - infap360mm_m_ecc_ecc_lkp_material_group_inbound - infap360mm_m_ecc_ecc_lkp_loadingGrp_inbound - infap360mm_m_ecc_ecc_lkp_plant_inbound - infap360mm_m_ecc_ecc_lkp_division_inbound	Imports the material data from SAP ECC to Reference 360 reference data sets. **Note:** You must manually create an import job with the taskflow. For more information, see "Creating import jobs in Reference 360" on page 49.

Taskflow	Mapping Task	Mapping	Description
- infap360mm_tf_ecc_ecc_lkp_loadingGrp_inbound - infap360mm_tf_ecc_ecc_lkp_plant_inbound - infap360mm_tf_ecc_ecc_lkp_division_inbound - infap360mm_tf_ecc_ecc_lkp_transportationGroup_inbound - infap360mm_tf_ecc_ecc_lkp_BasicConstituentOfMaterial_inbound - infap360mm_tf_ecc_ecc_lkp_xPlantMatStatus_inbound	mpMaterialGrp_inbound - infap360mm_mt_ecc_ecc_lkp_storageloc_inbound - infap360mm_mt_ecc_ecc_lkp_GeneralItemCatGrp_inbound - infap360mm_mt_ecc_ecc_lkp_material_group_inbound - infap360mm_mt_ecc_ecc_lkp_loadingGrp_inbound - infap360mm_mt_ecc_ecc_lkp_plant_inbound - infap360mm_mt_ecc_ecc_lkp_division_inbound - infap360mm_mt_ecc_ecc_lkp_transportationGroup_inbound - infap360mm_mt_ecc_ecc_lkp_BasicConstituentOfMaterial_inbound - infap360mm_mt_ecc_ecc_lkp_xPlantMatStatus_inbound	- infap360mm_m_ecc_ecc_lkp_transportationGroup_inbound - infap360mm_m_ecc_ecc_lkp_BasicConstituentOfMaterial_inbound - infap360mm_m_ecc_ecc_lkp_xPlantMatStatus_inbound	

Batch jobs of the Material business entity for SAP S/4HANA

The following table lists the predefined jobs for initial inbound and their related taskflow, mapping task, and mapping of the Material business entity for SAP S/4HANA:

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_ingress_s4h_material_material_inbound_initial	infap360mm_tf_s4h_material_material_inbound_initial	- infap360mm_mt_s4h_material_material_inbound_altUnitofMeasurement_initial - infap360mm_mt_s4h_material_material_inbound_root_initial - infap360mm_mt_s4h_material_material_inbound_Plant_initial - infap360mm_mt_s4h_material_material_inbound_alternateIdentifier_initial - infap360mm_mt_s4h_material_material_inbound_description_initial	- infap360mm_m_s4h_material_material_inbound_altUnitofMeasurement_initial - infap360mm_m_s4h_material_material_inbound_root_initial - infap360mm_m_s4h_material_material_inbound_Plant_initial - infap360mm_m_s4h_material_material_inbound_alternateIdentifier_initial - infap360mm_m_s4h_material_material_inbound_description_initial	Imports entire material data from SAP S/4HANA to the Material business entity.

The following table lists the predefined jobs for incremental inbound and their related taskflow, mapping task, and mapping of the Material business entity for SAP S/4HANA:

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_ingress_s4h_material_material_inbound_delta	infap360mm_tf_s4h_material_material_inbound_delta	- infap360mm_mt_s4h_material_material_inbound_altUnitofMeasurement_delta - infap360mm_mt_s4h_material_material_inbound_root_delta - infap360mm_mt_s4h_material_material_inbound_description_delta - infap360mm_mt_s4h_material_material_inbound_Plant_delta - infap360mm_mt_s4h_material_material_inbound_alternateIdentifier_delta	- infap360mm_m_s4h_material_material_inbound_altUnitofMeasurement_delta - infap360mm_m_s4h_material_material_inbound_root_delta - infap360mm_m_s4h_material_material_inbound_description_delta - infap360mm_m_s4h_material_material_inbound_Plant_delta - infap360mm_m_s4h_material_material_inbound_alternateIdentifier_delta	Imports incremental data at the field groups level from SAP S/4HANA to the Material business entity.

The following table lists the lookup assets with taskflows, mapping task, and mapping of the Material business entity for SAP S/4HANA:

Taskflow	Mapping Task	Mapping	Description
- infap360mm_tf_s4h_s4h_lkp_plant_inbound - infap360mm_tf_s4h_s4h_lkp_CommodityCd_inbound - infap360mm_tf_s4h_s4h_lkp_region_inbound - infap360mm_tf_s4h_s4h_lkp_BasicConstituentOfMaterial_inbound - infap360mm_tf_s4h_s4h_lkp_storageloc_inbound - infap360mm_tf_s4h_s4h_lkp_transportationGroup_inbound - infap360mm_tf_s4h_s4h_lkp_xPlantMatStatus_inbound - infap360mm_tf_s4h_s4h_lkp_material_group_inbound - infap360mm_tf_s4h_s4h_lkp_division_inbound - infap360mm_tf_s4h_s4h_lkp_expImpMaterialGrp_inbound - infap360mm_tf_s4h_s4h_lkp_GeneralItemCatGrp_inbound - infap360mm_tf_s4h_s4h_lkp_loadingGrp_inbound - infap360mm_tf_s4h_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_tf_s4h_enterprise_lkp_plant_inbound - infap360mm_tf_s4h_enterprise_lkp_region_inbound - infap360mm_tf_s4h_enterprise_lkp_division_inbound - infap360mm_tf_s4h_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_tf_s4h_enterprise_lkp_storageloc_inbound	- infap360mm_mt_s4h_s4h_lkp_plant_inbound - infap360mm_mt_s4h_s4h_lkp_CommodityCd_inbound - infap360mm_mt_s4h_s4h_lkp_region_inbound - infap360mm_mt_s4h_s4h_lkp_BasicConstituentOfMaterial_inbound - infap360mm_mt_s4h_s4h_lkp_storageloc_inbound - infap360mm_mt_s4h_s4h_lkp_transportationGroup_inbound - infap360mm_mt_s4h_s4h_lkp_xPlantMatStatus_inbound - infap360mm_mt_s4h_s4h_lkp_material_group_inbound - infap360mm_mt_s4h_s4h_lkp_division_inbound - infap360mm_mt_s4h_s4h_lkp_expImpMaterialGrp_inbound - infap360mm_mt_s4h_s4h_lkp_GeneralItemCatGrp_inbound - infap360mm_mt_s4h_s4h_lkp_loadingGrp_inbound - infap360mm_mt_s4h_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_mt_s4h_enterprise_lkp_plant_inbound - infap360mm_mt_s4h_enterprise_lkp_region_inbound - infap360mm_mt_s4h_enterprise_lkp_division_inbound	- infap360mm_m_s4h_s4h_lkp_plant_inbound - infap360mm_m_s4h_s4h_lkp_CommodityCd_inbound - infap360mm_m_s4h_s4h_lkp_region_inbound - infap360mm_m_s4h_s4h_lkp_BasicConstituentOfMaterial_inbound - infap360mm_m_s4h_s4h_lkp_storageloc_inbound - infap360mm_m_s4h_s4h_lkp_transportationGroup_inbound - infap360mm_m_s4h_s4h_lkp_xPlantMatStatus_inbound - infap360mm_m_s4h_s4h_lkp_material_group_inbound - infap360mm_m_s4h_s4h_lkp_division_inbound - infap360mm_m_s4h_s4h_lkp_expImpMaterialGrp_inbound - infap360mm_m_s4h_s4h_lkp_GeneralItemCatGrp_inbound - infap360mm_m_s4h_s4h_lkp_loadingGrp_inbound - infap360mm_m_s4h_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_m_s4h_enterprise_lkp_plant_inbound - infap360mm_m_s4h_enterprise_lkp_region_inbound - infap360mm_m_s4h_enterprise_lkp_division_inbound - infap360mm_m_s4h_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_m_s4h_enterprise_lkp_storageloc_inbound - infap360mm_m_s4h_enterprise_lkp_TransportationGroup_inbound - infap360mm_m_s4h_enterprise_lkp_material_group_inbound - infap360mm_m_s4h_enterprise_lkp_xPlantMatStatus_inbound	Imports material data from the SAP S/4HANA object to the Reference 360 reference data sets. **Note:** You must manually create an import job with the taskflow. For more information, see "Creating import jobs in Reference 360" on page 49.

Taskflow	Mapping Task	Mapping	Description
- infap360mm_tf_s4h_enterprise_lkp_TransportationGroup_inbound - infap360mm_tf_s4h_enterprise_lkp_material_group_inbound - infap360mm_tf_s4h_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_tf_s4h_enterprise_lkp_GeneralItemCatGrp_inbound - infap360mm_tf_s4h_enterprise_lkp_CommodityCd_inbound - infap360mm_tf_s4h_enterprise_lkp_LoadingGrp_inbound	- infap360mm_mt_s4h_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_mt_s4h_enterprise_lkp_storageloc_inbound - infap360mm_mt_s4h_enterprise_lkp_TransportationGroup_inbound - infap360mm_mt_s4h_enterprise_lkp_material_group_inbound - infap360mm_mt_s4h_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_mt_s4h_enterprise_lkp_GeneralItemCatGrp_inbound - infap360mm_mt_s4h_enterprise_lkp_CommodityCd_inbound - infap360mm_mt_s4h_enterprise_lkp_LoadingGrp_inbound	- infap360mm_m_s4h_enterprise_lkp_GeneralItemCatGrp_inbound - infap360mm_m_s4h_enterprise_lkp_CommodityCd_inbound - infap360mm_m_s4h_enterprise_lkp_LoadingGrp_inbound	

The following table lists the predefined jobs for outbound and their related taskflow, mapping task, and mapping of the Material business entity for SAP S/4HANA:

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360sap_egress_s4h_material_material_outbound	iinfap360sap_tf_S4h_material_material_outbound	- infap360sap_mt_S4h_material_material_create_outbound - infap360sap_mt_S4h_material_material_update_outbound - infap360sap_mt_S4h_MaterialGetNum_material_outbound	- infap360sap_m_S4h_material_material_create_outbound - infap360sap_m_S4h_material_material_update_outbound - infap360sap_m_S4h_MaterialGetNum_material_outbound	Exports data from the Material business entity to SAP S/4HANA.

The following table lists the mapplets that the predefined mappings use:

Mapping	Mapplet	Description
- infap360sap_m_S4h_material_material_create_outbound - infap360sap_m_S4h_material_material_update_outbound	BAPI Save Data	Loads material data from MDM SaaS into SAP S/4HANA.
infap360sap_m_S4h_MaterialGetNum_material_outbound	BAPI Get Int Number	Generates a SAP S/4HANA material number.

Batch jobs of the Material Category business entity for SAP ECC

The following table lists the predefined jobs and their related taskflows, mapping tasks, and mappings of the Material Category business entity for SAP ECC:

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_ingress_ecc_producthierarchy_materialcategory_inbound	infap360mm_tf_ecc_producthierarchy_materialcategory_inbound	infap360mm_mt_ecc_producthierarchy_materialcategory_inbound	infap360mm_m_ecc_producthierarchy_materialcategory_inbound	Imports data from SAP ECC to the Material Category business entity.
infap360mm_ingress_ecc_producthierarchy_matcat_matcat_inbound	infap360mm_tf_ecc_producthierarchy_matcat_matcat_inbound	infap360mm_mt_ecc_producthierarchy_matcat_matcat_inbound	infap360mm_m_ecc_producthierarchy_matcat_matcat_inbound	Imports hierarchy relationships between the Material Category and Material Category business entity records.
infap360mm_ingress_ecc_producthierarchy_matcat_mat_inbound	infap360mm_tf_ecc_producthierarchy_matcat_mat_inbound	infap360mm_mt_ecc_producthierarchy_matcat_mat_inbound	infap360mm_m_ecc_producthierarchy_matcat_mat_inbound	Imports hierarchy relationships between the Material Category and Material business entity records.

Batch jobs of the Material Category business entity for SAP S/4HANA

The following table lists the predefined inbound jobs and their related taskflow, mapping task, and mapping of the Material Category business entity for SAP S/4HANA:

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_ingress_s4h_producthierarchy_materialcategory_inbound	infap360mm_tf_s4h_producthierarchy_materialcategory_inbound	infap360mm_mt_s4h_producthierarchy_materialcategory_inbound	infap360mm_m_s4h_producthierarchy_materialcategory_inbound	Imports data from SAP S/4HANA to the Material Category business entity.
infap360mm_ingress_s4h_producthierarchy_matcat_matcat_inbound	infap360mm_tf_s4h_producthierarchy_matcat_matcat_inbound	infap360mm_mt_s4h_producthierarchy_matcat_matcat_inbound	infap360mm_m_s4h_producthierarchy_matcat_matcat_inbound	Imports hierarchy relationships between the Material Category and Material Category business entity records.
infap360mm_ingress_s4h_producthierarchy_matcat_mat_inbound	infap360mm_tf_s4h_producthierarchy_matcat_mat_inbound	infap360mm_mt_s4h_producthierarchy_matcat_mat_inbound	infap360mm_m_s4h_producthierarchy_matcat_mat_inbound	Imports hierarchy relationships between the Material Category and Material business entity records.

The following table lists the predefined outbound job and its related taskflow, mapping task, and mapping of the Material Category business entity for SAP S/4HANA:

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_egress_S4h_materialproducthierarchy_update_outbound	infap360mm_tf_S4h_materialproducthierarchy_update_outbound	- infap360mm_mt_S4h_matcat_be_ff_outbound - infap360mm_mt_S4h_materialhierarchy_update_outbound	- infap360mm_m_S4h_matcat_be_ff_outbound - infap360mm_m_S4h_materialhierarchy_update_outbound	Exports data from the Material Category business entity to SAP S/4HANA.

Field mapping

The Cloud Data Integration mappings map the fields of MDM SaaS and SAP. MDM SaaS stores the SAP data based on the mappings.

General fields of the Material business entity

The following table lists the SAP material data fields that are mapped to the general fields of the Material business entity:

Material 360 Display Name	Material 360 Internal ID	SAP Table Name	SAP Column Name
Authorization Group	infap360mm_authorizationGroup	MARA	BEGRU
Base Unit of Measurement	infap360mm_baseUnitOfMeasure	MARA	MEINS
Basic Constituent of Material	infap360mm_basicConstituentOfMaterial	MARA	WRKST
Bulk or Liquid Indicator	infap360mm_ind_isBulkLiquid	MARA	ILOOS
Configurable Material Indicator	infap360mm_ind_configurableMaterial	MARA	KZKFG
Cross Plant Material Status	infap360mm_xPlantMatStatus	MARA	MSTAE
Division	infap360mm_division	MARA	SPART
Environmentally Relevant Indicator	infap360mm_ind_environmentallyRelevant	MARA	KZUMW
General Item Category Group	infap360mm_generalItemCategoryGroup	MARA	MTPOS
Highly Viscous Indicator	infap360mm_ind_isHighlyViscous	MARA	IHIVI
Industry Sector	infap360mm_industrySector	MARA	MBRSH
Material Group	infap360mm_materialGroup	MARA	MATKL
Material Group - Packaging Materials	infap360mm_materialGroupPackagingMaterials	MARA	MAGRV
Material Number	infap360mm_materialNumber	MARA	MATNR
Material Number Type	infap360mm_matNumType	NA	NA
Material Type	infap360mm_materialType	MARA	MTART
Net Weight	infap360mm_netWeight	MARA	NTGEW
Old Material Number	infap360mm_oldMaterialNumber	MARA	BISMT
Transportation Group	infap360mm_transportationGroup	MARA	TRAGR
Unit of Measurement for Weight	infap360mm_weightUnit	MARM	GEWEI
Valid From	infap360mm_validFrom	MARA	MSTDE

Note: By default, the MDM SaaS Material Number Type field displays the source of the material number.

Alternative Unit of Measurement field group of the Material business entity

The following table lists the SAP material data fields that are mapped to the Alternative Unit of Measurement field group of the Material business entity:

Material 360 Display Name	Material 360 Internal ID	SAP Table Name	SAP Column Name
Alternative Unit of Measurement	infap360mm_dimAlternativeUnitOfMeasureSKU	MARM	MEINH
Denominator of Conversion Factor	infap360mm_dimDenominatorToBaseUom	MARM	UMREN
Gross Weight	infap360mm_dimGrossWeight	MARM	BRGEW
Height	infap360mm_dimHeight	MARM	HOEHE
Length	infap360mm_dimLength	MARM	LAENG
Numerator of Conversion Factor	infap360mm_dimNumeratorToBaseUom	MARM	UMREZ
Unit of Measurement for Dimensions	infap360mm_dimUnitOfDimensions	MARM	MEABM
Unit of Measurement for Volume	infap360mm_dimVolumeUnit	MARM	VOLEH
Unit of Measurement for Weight	infap360mm_dimWeightUnit	MARM	GEWEI
Volume	infap360mm_dimVolume	MARM	VOLUM
Width	infap360mm_dimWidth	MARM	BREIT

Identifier field group of the Material business entity

The following table lists the SAP material data fields that are mapped to the Identifier field group of the Material business entity:

Material 360 Display Name	Material 360 Internal ID	SAP Table Name	SAP Column Name
Identifier Status	infap360mm_identifierStatus	NA	NA
Identifier Type	infap360mm_idType	NA	NA
Identifier Value	infap360mm_altIdValue	MARA	MATNR

Note: By default, the MDM SaaS Identifier Status field displays the status of the material number, and the MDM SaaS Identifier Type field displays the source of the material number.

Material Description field group of the Material business entity

The following table lists the SAP material data fields that are mapped to the Material Description field group of the Material business entity:

Material 360 Display Name	Material 360 Internal ID	SAP Table Name	SAP Column Name
Description	infap360mm_description	MAKT	MAKTX
Language	infap360mm_language	MAKT	SPARS

Material Plant field group of the Material business entity


The following table lists the SAP material data fields that are mapped to the Material Plant field group of the Material business entity:

Material 360 Display Name	Material 360 Internal ID	SAP Table Name	SAP Column Name
Commodity - Import Code Number for Foreign Trade	infap360mm_commodityCode	MARC	STAWN
Country of Origin	infap360mm_countryOfOrigin	MARC	HERKL
Export and Import Material Group	infap360mm_exportImportMaterialGroup	MARC	MTVER
Loading Group	infap360mm_loadingGroup	MARC	LADGR
Plant	infap360mm_plant	MARC	WERKS
Profit Center	infap360mm_profitCenter	MARC	PRCTR
Region of Origin of Material	infap360mm_regionOfOrigin	MARC	HERKR
Storage Location	infap360mm_storageLoc	MARD	LGORT
Unit of Measurement for Commodity Code	infap360mm_unitOfMeasure	MARC	EXPME

Relationships

You can use the predefined relationships between the Material and Material Category business entities that the Material 360 package includes.

The following image shows the predefined relationship types between the business entities and the direction of the relationships:



The following table describes the predefined relationships that the Material 360 package includes:

Relationship Name	Internal ID	Business Entity 1	Business Entity 2	Direction
Material Category to Material Category	infap360mm_material_cat_to_infap360mm_material_cat	Material Category	Material Category	Material Category > Material Category
Material Category to Material	infap360mm_material_to_infap360mm_material_categor	Material Category	Material	Material Category -> Material

Predefined pages

The Material 360 package contains predefined pages. You can use the predefined pages as a reference to create similar custom pages for business entities.

Use the Create page type to create records. Use the View and Edit page type to view and edit records.

The following table describes the predefined pages for the Material and Material Category business entities:

Page Name	Description	Assigned User Roles
Create Page Material Category	A page to create a Material Category record.	MDM Business User
Create Page for Requester	A page for a requester to create a Material record.	Material Requester
Edit Page Material Category	A page to view or edit a Material Category record.	MDM Business User

Page Name	Description	Assigned User Roles
Edit Page Material for Purchase Expert and Purchase Approver	A page for a purchase expert, purchase approver, and final reviewer to view or edit a Material record.	- MDM Business User - Material Purchase Expert - Material Purchase Approver
Edit Page Material for Requester and Final Reviewer	A page for a requester and final reviewer to view or edit a Material record.	- MDM Business User - Material Requester - Material Final Reviewer

For more information about creating pages, see *Designing user interface*.

Search result layout components

The Material 360 package contains predefined search result layout components.

The following table describes the search result layout components for the Material and Material Category business entities:

Search Result Layout Component Name	Description	Assigned User Roles
Search Layout Material	Search layout to display search results of the Material records.	- MDM Business User - <MDM SaaS business application> Manager
Search Layout Material Category	Search layout to display search results of the Material Category records.	- MDM Business User - <MDM SaaS business application> Manager

For more information about creating pages, see *Design the User Interface*.

Data quality rule associations

Add the predefined data quality rule associations to the business entity fields to cleanse, standardize, and validate the field values. When you import source records, the associated data quality rules validate and transform the records in MDM SaaS.

The following table describes the advanced rule association that the Material business entity uses:

Rule Association Name	Function Name	Applied Field	Description
infap360mm_rs_ValidFrom	Greater Than or Equal To	Valid From	Validates whether the date is the same as or later than the current date.

Reports

Use the predefined reports to visualize data in the form of charts and report tables in MDM SaaS.

The following table describes the predefined reports that the Material 360 package includes:

Report Name	Internal ID	Description
Material by Material Group	infap360mm_material_by_material_group	Displays the number of material records based on the material group.
Material by Source System	infap360mm_material_by_source_system	Displays the number of material records based on the source system identifier type.
Material by Type	infap360mm_material_by_type	Displays the number of material records based on the type of material.
Migration Status	infap360mm_migration_status	Displays the number of material records migrated to SAP S/4HANA from SAP ECC and the number of SAP ECC material records yet to be migrated to SAP S/4HANA.

Business process workflow

You can use the business process workflow to streamline processes that involve multiple predefined user roles.Material 360 includes a sample workflow that orchestrates the approval process to create and update material records.

The extension also includes predefined business events to trigger the sample workflow when users create or update a material record.

Based on your business requirements, use different workflows for different material properties. For example, you can create different workflows for semi-finished goods, finished goods, industry sector, and any material type.

Predefined user roles

Material 360 includes multiple predefined user roles to create, update, and review material records.

The following table describes the predefined user roles that the Material business entity includes:


Role Name	Description
Material Requester	Role for creating, editing, and deleting data in material records that go through the approval process.
Material Purchase Expert	Role for reviewing and editing purchase data in material records.
Material Purchase Approver	Role for editing and reviewing material records that the purchase expert approves.
Material Final Reviewer	Role for reviewing material records that the purchase approver approves.

Sample workflow to create material records

Material 360 includes a sample workflow to create a material record.

When a requester creates a material record, the record is sent to a purchase expert for reviewing the material purchase data. If the purchase expert finds that the record information is incorrect or inadequate, the purchase expert can send the record back to the requester. If the purchase expert approves the record, the record goes to the purchase approver. If the purchase approver approves the record, the record is sent to the final reviewer. After the final reviewer approves the record, the record is created and is active in MDM SaaS.

The following image shows the approval process that the sample workflow uses:




Sample workflow to update a material record

Material 360 includes a sample workflow to update a material record.

When a requester updates a material record, the record is sent to a purchase approver to review the material purchase data. If the purchase approver finds that the record information is incorrect or inadequate, the purchase approver can send the record back to the requester. If the purchase approver approves the record, the record is sent to the final reviewer. After the final reviewer approves the record, the record is created and is active in MDM SaaS.

The following image shows the approval process that the sample workflow uses:


Updates material record
Requester
Submit
Send back to Requester
Send back to Requester
Reviews purchase data in the material record
Purchase Approver
Send back to Purchase Approver
Approve
Reviews and updates data in the material record
Final Reviewer
Approve
Record gets updated in MDM SaaS

CHAPTER 4

Deploying Material 360 on MDM SaaS

To deploy Material 360 on MDM SaaS, configure the assets for the SAP ECC and SAP S/4HANA source systems. Download the extension package, import assets into MDM SaaS and update the predefined connections.

To deploy Material 360 on MDM SaaS, perform the following tasks:

1. Download and extract the extension package.
2. Importing the authorization assets.
3. Import the data model, the predefined custom pages, and the source systems.
4. Add predefined pages and search result layout components.
5. Import reference data code values into reference data assets.

When you import the extension assets, the predefined assets are configured to use Multidomain MDM SaaS as the business application. You can also configure other business applications to use the extension assets.

To import the authorization assets, ensure that you log in with the Admin user role.

To import the data model, pages, source system, Cloud Data Integration assets, jobs, and Cloud Application Integration assets, ensure that you log in with MDM Designer and Designer user roles.

Note: Before you log in with MDM Designer or Designer roles, ensure that you don't belong to the Admin user role.

After you deploy the extension, configure the extension to integrate the extension with SAP.

Downloading and extracting the Material 360 package

To get the link to download the Material 360 package, contact Informatica Global Customer Support.

After you download the Material 360 package, extract the package on your machine. The package contains data model attributes, relationships, Cloud Application Integration assets, Cloud Data Integration assets, reports, and predefined custom pages for MDM SaaS.

The extracted package contains the following files and folders:

File or Folder Name	Description
`0_Authorization_Assets(Admin Only).zip`	Contains the privileges configured for different user roles.
`1_MDM_Assets`	Contains the following folders: - `1_MDM_Assets.zip`. Contains the predefined assets such as, business entities, relationships, pages, and source systems. - `Reports`. Contains predefined reports for Product 360 SaaS and Multidomain MDM.
`2_DI_Assets.zip`	Contains the Cloud Data Integration assets and connections that you require to ingress and egress data.
`3_MDM_Job_Assets.zip`	Contains the job definitions to ingress and egress data in batches.
`4_CAI_Assets.zip`	Contains the Cloud Application Integration assets.
`Reference Data`	Contains files that store code lists and values that the business entities use.

Importing the authorization assets

Import the authorization assets that contain the privileges configured for different user roles.

To import the authorization assets, ensure that you belong to the Admin user role.

1. Log in with the Admin user role.
2. In Business 360 Console, click **Explore** > **Import**.
3. Navigate to the following file:

   `<Extracted extension package>/0_Authorization_Assets(Admin Only).zip`
4. Click **Open**.

   The **Import Assets** page lists the assets in the file.
5. Ensure that all the assets are selected.
6. In the **Review Locations** section, select the target project to which you want to import the assets.

   Product360 project is selected by default.
7. Click **Import**.
8. On the **My Import/Export Logs** page, verify whether the import job is successful.
9. In Administrator, select **User Roles**.
10. Verify whether the following user roles are available:
    - Material Requester
    - Material Purchase Expert
    - Material Purchase Approver
    - Material Final Reviewer

Importing data model, pages, source systems, and reports

After you import the authorization assets, import the data model assets, the predefined pages, the source systems, and predefined reports.

Note: Before you import the data model, pages, source systems, Cloud Data Integration assets, jobs, and Cloud Application Integration assets, ensure that you belong to the Designer user role, but not to the Admin user role.

1. In Business 360 Console, click **Explore** > **Import**.
2.
3. Navigate to the following file:

   `<Extracted extension package>/1_MDM_Assets`
4. Click **Open**.
5. Ensure that all the assets are selected.
6. In the **Review Locations** section, select the target project to which you want to import the assets.

   Product360 project is selected by default.
7. Click **Import**.
8. On the **My Import/Export Logs** page, verify whether the import job is successful.

Adding predefined pages and components

You can add the predefined pages and search result layout components of the Material and Material Category business entities to MDM SaaS. Ensure that you belong to the administrator user role.

1. In Business 360 Console, click **Explore** > **<Project>**.

   For example, if you use Product 360 SaaS, click **Product360**.
2. Click the business application.
3. On the **Pages** tab, select **Material**.

   Note: If you don't see Material, you can add the Material business entity.
4. On the **Create** tab, click **Add Page**.

   A blank row appears.
5. To select a page, click the asset picker.

   The **Select a page** window appears.
6. Select **Create Page Material**, and click **Select**.

   The selected page appears in the row.
7. To assign user roles to the page, from the list of user roles, select one or more user roles.

   For more information about the user roles assigned to pages, see “Predefined pages” on page 30.
8. On the **View and Edit** tab, click **Add Page**.

   A blank row appears.
9. To select a page, click the asset picker.

The **Select a page** window appears.

10. Select **Edit Page Material**, and assign the page to one or more user roles.

    For more information about the user roles assigned to pages, see "Predefined pages" on page 30.

11. In the left pane, select **Material Category**, and repeat steps 4 through 10.

    Note: Use **Create Page Material Category** and **Edit Page Material Category** as the pages for the Material Category business entity.

12. On the **Seach** tab, in the **Business Entities** section, select **Material**.

13. In the **Search Result Layouts: Material** section, click **Add Search Result Layout**.

    A blank row appears.

14. To select a component, click the asset picker.

    The **Select a Component** window appears.

15. Select **Search Layout Material**, and assign the component to one or more user roles.

    For more information about the user roles assigned to search result layout components, see "Search result layout components" on page 31.

16. In the **Business Entities** section, select **Material Category**, and repeat steps 13 through 15.

    Note: Use the **Search Layout Material Category** component for the Material Category business entity.

17. Click **Save**.

For more information about how to assign pages to user roles, see *Assign pages to user roles*.

Importing reference data assets

After you import data model assets, import reference data code values in bulk from CSV files into reference data assets.

The following table describes the files and folders in the extracted reference data directory:

File or Folder Name	Description
`_1`	Folder that contains the code values.
`Crosswalk`	Contains the reference data set crosswalks.
`LoadReferenceData.py`	Python script to import reference data.

The following table lists the reference data asset and the corresponding code list, crosswalk, and crosswalk location:

Reference Data Asset	Code List	Crosswalk	Crosswalk Location
Language	Language-Enterprise infap360mm_Language	Language-Enterprise infap360mm_Language to Enterprise Language	<Extracted extension package>/Reference Data/Crosswalk

For more information on crosswalks, see *Managing crosswalk*.

To import code values in bulk from CSV files that are available in the extracted reference data directory, run the LoadReferenceData.py Python script.

To import data from SAP ECC and SAP S/4HANA into Reference 360 reference data sets, create import jobs in Reference 360.

For more information about creating import jobs, see "Creating import jobs in Reference 360" on page 49.

To load data, Reference 360 uses the English language filter by default. To filter by a language other than English, you can configure the language from the query options in the source field.

For more information about configuring the source, see Configuring the source.

The following table lists the reference data assets and the corresponding code value location:

Reference Data Asset	Code Value File Location
infap360mm_IndustrySector	`<Extracted extension package>/Reference Data/_1/infap360mm_IndustrySector`
infap360mm_Language	`<Extracted extension package>/Reference Data/_1/infap360mm_Language`
infap360mm_MaterialGroupPackagingMaterials	`<Extracted extension package>/Reference Data/_1/infap360mm_MaterialGroupPackagingMaterials`
infap360mm_MaterialType	`<Extracted extension package>/Reference Data/_1/infap360mm_MaterialType`
infap360mm_UOM	`<Extracted extension package>/Reference Data/_1/infap360mm_UOM`
infap360mm_WeightUOM	`<Extracted extension package>/Reference Data/_1/infap360mm_WeightUOM`

Prerequisites

Before you import reference data into MDM SaaS, ensure that you complete the following prerequisite tasks:

- Ensure that you have permission to import reference data.
- Install Python version 3 or later on your machine.
- To verify whether the cURL library files are preinstalled and to check the cURL library version, run the following command from a command prompt:

  ```
  curl --version
  ```

  Note: If cURL isn't available in your operating system, ensure that you install it. You can download the cURL library for your operating system from the cURL website:

  ```
  http://curl.haxx.se/download.html
  ```

Importing the reference data

To import all the reference data in bulk, run the Python script.

1. Open a command prompt, and navigate to the following directory:

   ```
   <Extracted extension package>/Reference Data
   ```

2. Run the following command:

   - On Windows.
     ```
     python LoadReferenceData.py --podHostName <POD host name>.informaticacloud.com --
     userName <user name> --password <password> --region <POD region>
     ```
   - On Linux.
     ```
     python3 LoadReferenceData.py --podHostName <POD host name>.informaticacloud.com --
     userName <user name> --password <password> --region <POD region>
     ```

   The jobs to import reference data code values run.

3. To monitor the status of a job, click **My Jobs** in Reference 360.

   The My Jobs page lists the job instances that are currently running, failed, and successfully completed.

CHAPTER 5

Integrating Material 360 with SAP

Integrate Material 360 with SAP ECC or SAP S/4HANA to process SAP material data in batches. To integrate Material 360 with SAP, import and configure Material 360 assets.

Note: Import Material 360 assets before you customize your data model in MDM SaaS because the import process overwrites all your customization.

To configure Material 360 assets, perform the following tasks:

1. Import the Cloud Data Integration assets.
2. Import the predefined batch jobs.
3. Import the Cloud Application Integration assets.
4. Publish the Cloud Application Integration processes.
5. Set the Secure Agent parameters.
6. Configure the flat file connection.
7. Configure the Business 360 Connector.
8. Configure the SAP Table Connector.
9. Create custom tables in SAP.
10. Create import jobs.
11. Run the jobs.

Importing the Cloud Data Integration assets

Import the Cloud Data Integration assets, such as predefined taskflows, mapping tasks, and mappings, for each source system.

1. In Data Integration, click **Explore** > **Import**.
2. Navigate to the following file:

   `<Extracted extension package>/2_DI_Assets.zip`
3. Click **Open**.

   The **Import Assets** page lists the assets in the file.
4. Ensure that all the assets are selected, and then select **Publish Taskflow(s) after import**.
5. In the **Review Locations** section, select the target project to which you want to import the assets.

   Product360 project is selected by default.
6. Click **Import**.

7. On the **My Import/Export Logs** page, verify whether the import job is successful.

Importing the predefined batch jobs

After you import the Cloud Data Integration assets, import the predefined batch jobs. Use the batch jobs to ingress records from the source system and egress the processed records to SAP S/4HANA.

1. In Business 360 Console, click **Explore** > **Import**.
2. Navigate to the following file:

   `<Extracted extension package>/3_MDM_Job_Assets.zip`
3. Click **Open**.

   The **Import Assets** page lists the assets in the file.
4. Ensure that all the assets are selected.
5. In the **Review Locations** section, select the target project to which you want to import the assets.

   Product360 project is selected by default.
6. Click **Import**.
7. On the **My Import/Export Logs** page, verify whether the import job is successful.

Importing the Cloud Application Integration assets

After you import the batch jobs, import the Cloud Application Integration assets.

1. In Application Integration, click **Explore** > **Import**.
2. Navigate to the following file:

   `<Extracted extension package>/4_CAI_Assets.zip`
3. Click **Open**.

   The **Import Assets** page lists the assets in the file.
4. Ensure that all the assets are selected.
5. In the **Review Locations** section, select the target project to which you want to import the assets.

   Product360 project is selected by default.
6. Click **Import**.
7. On the **My Import/Export Logs** page, verify whether the import job is successful.

Publishing the Cloud Application Integration processes

To run a Cloud Application Integration process, publish the process.

1. In Application Integration, click **Explore** > **<Project>**.

   For example, if you use Product 360 SaaS, click **Product360**.
2. Click **Material 360**.
3. To publish the process, click the process, expand the **Actions** menu, and select **Publish**.

   Publish the following processes:

   - infap360mm_proc_MultiStepApprovalUpdateMaterial
   - infap360mm_proc_update_material_trigger_ingress
   - infap360mm_proc_MultiStepApprovalCreateMaterial

Adding a Secure Agent

After you publish the Cloud Application Integration processes, add a Secure Agent to the predefined Secure Agent group.

1. In Administrator, click **Runtime Environments**.
2. Expand the **Actions** menu for the `infa_extension_runtime` Secure Agent group, and select **Add or Remove Secure Agents**.
3. In the **Available Agents** list, select the Secure Agent that you want to add to the group, and click **Select**.
4. Expand the **Actions** menu for the `infa_extension_runtime` Secure Agent group, and select **Enable or Disable Services, Connectors**.
5. From the **Services** tab, select the services to enable for the Secure Agent group.
6. From the **Connectors** tab, select the connectors to enable for the Secure Agent group.
7. Click **Save**.

Importing parameter files

A parameter file is a list of user-defined parameters and their associated values. Import the parameter files for Cloud Data Integration mappings.

To import parameter files, save the parameter files in the Secure Agent Installation directory.

Copy the parameter files from the source directory to the target Secure Agent installation directory:

Source: `<Extracted extension package>\Secure Agent Files\Parameter Files`

Target: `<Secure Agent Installation Directory>\apps\Data_Integration_Server\data\userparameters`

Optionally, if you want to use a configured path for the target location, see *Parameter file location*.

Configuring the flat file connection

To access flat files from the Secure Agent, configure the flat file connection.

1. In Administrator, click **Connections**.
2. Click `infap360mm_conn_flatfile`.
3. Verify the directory to store the flat file.

   Default is `C:\ReferenceData`.
4. Test the connection, and ensure that the connection is successful.

Configuring Business 360 Connector

You can use Business 360 Connector to write data from SAP ECC and SAP S/4HANA into MDM SaaS. If the input values for source system integer fields are null, Business 360 Connector converts the null values to 0 in MDM SaaS.

1. In Administrator, click **Connections**.
2. Click `infap360mm_conn_product360`.
3. Test the connection.

   The connection might fail with the following error:
   ```
   The test connection for infap360mm_conn_product360 failed. Unable to fetch connector attributes, Ensure adapter ID is valid[com.infa.adapter.mdmflat].
   ```
4. If the connection fails, verify and ensure that the connection is successful.
   a. Ensure that you have a license for Business 360 Connector.
   b. Ensure that the connector is enabled for the Secure Agent group.
   c. Restart the Secure Agent.

Configuring the SAP connection

You can use a SAP Table connection to integrate SAP ECC and SAP S/4HANA with MDM SaaS and read SAP data.

1. To configure a SAP Table connection, perform the following steps:
   a. Verify whether the required licences are available for SAP Table Connector.
   b. If you host the Secure Agent on a Windows machine, download and install the Microsoft Visual C++ Redistributable package on the machine that hosts the Secure Agent.
   c. Download and configure the SAP libraries on the Secure Agent machine to read from and write to SAP tables.
   d. To enable the Secure Agent to connect to the SAP system as a Remote Function Call (RFC) client, create and configure the `sapnwrfc.ini` file on the machines that host the Secure Agent.
   e. Configure the SAP user account to access the SAP table data.

f. Install the SAP Table connection transport files on the SAP machines that you want to access.

g. To connect to SAP through HTTPS and read SAP table sources, configure the machine that hosts the Secure Agent and the machine that hosts the SAP system.

For more information about SAP Table Connector, see *Connections for SAP Table Connector*.

2. Configure the following connections:

- `infap360mm_conn_table_ecc`
- `infap360mm_conn_table_s4h`

The following table describes the SAP Table connection properties:

Connection Property	Description
Runtime Environment	The name of the runtime environment where you want to run tasks. Select a Secure Agent or serverless runtime environment.
Username	The user name with the appropriate user authorization to connect to the SAP account.
Password	The password to connect to the SAP account.
Client	The client number of the SAP application server.
Language	Language code that corresponds to the SAP language.
Saprfc.ini Path	Local directory to the `sapnwrfc.ini` file. To write to SAP tables, use the following directory: `<Informatica Secure Agent installation directory>/apps/Data_Integration_Server/ext/deploy_to_main/bin/rdtm`
Destination	DEST entry that you specified in the `sapnwrfc.ini` file for the SAP application server. Use all uppercase letters for the destination.If you enter the directory of the sapnwrfc.ini file in this field, you do not need to enter the host name or IP address, and system number of the SAP application server in the **Application Sever** and **System Number** fields.
Port Range	HTTP port range. The SAP Table connection uses the specified port numbers to connect to SAP tables using the HTTP protocol. Default range is 10000-65535. Enter a range in the default range, for example, 10000-20000. When a range is outside the default range, the connection uses the default range.
Test Streaming	Tests the connection. When selected, tests the connection using both RFC and HTTP protocol. When not selected, tests connection using RFC protocol.
Https Connection	When selected, connects to SAP through HTTPS protocol. To successfully connect to SAP through HTTPS, verify that an administrator has configured the machines that host the Secure Agent and the SAP system.
Keystore Location	Absolute path and file name of the keystore file to connect to SAP. Specify both the directory and file name in the following format: `<Directory>/< Keystore file name>.jks`

Connection Property	Description
Keystore Password	The destination password to access to the keystore file.
Private Key Password	The export password specified for the .P12 file.

3. Test the connections, and ensure that the connections are successful.

   For more information about the SAP Connector, see *SAP IDocs and RFCs/BAPI Connector administration*.

4. If the SAP instance and the Secure Agent are installed in the same Virtual Private Cloud (VPC) network, perform the following steps:

   a. Configure the Secure Agent host to use the private IP address to access the SAP instance.

      1. Open the following file on the Secure Agent:
         - On Windows. `\Windows\System32\drivers\etc\hosts`
         - On Linux. `/etc/hosts`
      2. Add an entry for the SAP instance in the following format:
         `<SAP Hostname> <Private IP address of SAP Host>`
      3. Repeat step 2 for all the SAP instances available in VPC as the Secure Agent host.

   b. For communication between the SAP instance and the Secure Agent, add a custom DTM configuration property to use the private IP address of the Secure Agent host.

      1. In Administrator, click **Runtime Environments**.
      2. Expand the **Actions** menu for the Secure Agent, and select **Edit Secure Agent**.
      3. In the **Custom Configuration Details** section, enter the following details:

Field Name	Value
Services	Data Integration Server
Type	DTM
Name	SapTableReaderNatIpAddress
Value	<Private IP address of Secure Agent host>

      4. Click **Save**.
         The Secure Agent restarts automatically within 10 minutes. To apply the properties immediately, you can restart manually. Ensure that no tasks run to avoid failure of any running task.

   c. Test the connection to verify the connectivity between the SAP instance and the Secure Agent.

      If the connection test is unsuccessful, disable the firewall to resolve the issue.

Creating a custom table in SAP

Create a custom table in SAP to store the MDM SaaS data in SAP S/4HANA. After you create a custom table in SAP, you can use the Cloud Data Integration assets to load MDM SaaS data to SAP S/4HANA.

1. Log in to SAP.
2. To use the ABAP dictionary, enter the transaction code value as `SE11` and press **Enter**.

   The **ABAP Dictionary: Initial Screen** page appears.
3. Enter the database table name you want to create as ZINFA_MM_EXTID.

   Note: The table name must start with `Y` or `Z` only.
4. Click **Create**.

   The **Dictionary: Change Table** page appears.
5. Enter a short description for the transparent table.
6. To create an application table that contains master data or transaction data, enter the delivery class value as `A`.
7. On the **Fields** tab, enter the following fields to the table:

Field Name	Data Type	Length	Description
BUSINESSID	CHAR	50	Unique identifier that MDM SaaS uses to identify records.
INTEGRATIONSTATUS	CHAR	10	Status of record integration. For example, success or failure.
MATERIALNUMBER	CHAR	18	Unique identifier for a material, generated by the Business Application Programming Interface (BAPI) named GET_MATERIAL_NUMBER.
SYNCDATE	DATS	8	Date of synchronizing MDM with S/4HANA.

   For more information about attributes, see "Data model attributes" on page 11.
8. Specify the primary key for each table. To set a field as a primary key for the table, select **Key**.
9. Click **Save**.
10. From the menu bar, click **More** > **Extras** > **Enhancement Category**.

    The **Maintain Enhancement Category for <database table name>** dialog box appears.
11. Select **Can Be Enhanced (Deep)**.
12. Click **Copy**.
13. From the menu bar, click the **Activate** icon.

Creating import jobs in Reference 360

Create import jobs in Reference 360 to import data from SAP ECC and SAP S/4HANA to Reference 360.

1. In Reference 360, click **New** .

   The **New Asset** dialog box appears.

2. Click **Jobs** > **Reference Data Import**, and click **Create**.

   The **Reference Data Import** dialog box appears.

3. Set the display name and internal ID of the job.

   To import the material storage location and material plant data from the SAP object to the Reference 360 SAP ECC or SAP S/4HANA Enterprise code list, create the following jobs:

   - infap360mm_import_ecc_lkp_p360_inbound
   - infap360mm_import_s4h_lkp_p360_inbound

4. Set the location as `<Business application>\Material 360`.

5. Add the taskflow associated with the job.

   Use a taskflow based on the source system from which you want to import data and the code list to which you want to load the reference data.
   For example, if you want to import region data from SAP ECC to Reference 360 SAP ECC code list, use the infap360mm_tf_ecc_ecc_lkp_region_inbound taskflow. If you want to import region data from SAP ECC to Reference 360 SAP ECC enterprise code list, use the infap360mm_tf_ecc_enterprise_lkp_region_inbound taskflow.

   Note: You can select multiple taskflows based on your business requirement.

   The following table lists the jobs and their related taskflow, mapping task, and mapping of the Material business entity:

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_import_lkp_p360_inbound	infap360mm_tf_ecc_lkp_p360_inbound	- infap360mm_mt_ecc_plant_plant_inbound - infap360mm_mt_ecc_storageloc_storageloc_inbound	- infap360mm_m_ecc_plant_plant_inbound - infap360mm_mt_ecc_storageloc_storageloc_inbound	Imports the material storage location and material plant data from the SAP ECC object to the Reference 360 SAP ECC Enterprise code list.
infap360mm_import_lkp_p360_inbound	infap360mm_tf_s4h_lkp_p360_inbound	- infap360mm_mt_s4h_storageloc_storageloc_inbound - infap360mm_mt_s4h_plant_plant_inbound	- infap360mm_m_s4h_storageloc_storageloc_inbound - infap360mm_m_s4h_plant_plant_inbound	Imports the material storage location and material plant data from SAP S/4HANA to the Reference 360 SAP S/4HANA Enterprise code list.

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_import_lkp_BasicConstituentOfMaterial_inbound	- infap360mm_tf_ecc_ecc_lkp_BasicConstituentOfMaterial_inbound - infap360mm_tf_s4h_s4h_lkp_BasicConstituentOfMaterial_inbound - infap360mm_tf_ecc_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_tf_s4h_enterprise_lkp_BasicConstituentOfMaterial_inbound	- infap360mm_mt_ecc_ecc_lkp_BasicConstituentOfMaterial_inbound - infap360mm_mt_s4h_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_mt_s4h_s4h_lkp_BasicConstituentOfMaterial_inbound - infap360mm_mt_ecc_enterprise_lkp_BasicConstituentOfMaterial_inbound	- infap360mm_m_s4h_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_m_s4h_s4h_lkp_BasicConstituentOfMaterial_inbound - infap360mm_m_ecc_enterprise_lkp_BasicConstituentOfMaterial_inbound - infap360mm_m_ecc_ecc_lkp_BasicConstituentOfMaterial_inbound	Imports the basic constituents of a material data from the SAP object to the Reference 360 code list.
infap360mm_import_lkp_CommodityCd_inbound	- infap360mm_tf_s4h_enterprise_lkp_CommodityCd_inbound - infap360mm_tf_s4h_s4h_lkp_CommodityCd_inbound - infap360mm_tf_ecc_enterprise_lkp_CommodityCd_inbound - infap360mm_tf_ecc_ecc_lkp_CommodityCd_inbound	- infap360mm_mt_s4h_s4h_lkp_CommodityCd_inbound - infap360mm_mt_ecc_ecc_lkp_CommodityCd_inbound - infap360mm_mt_s4h_enterprise_lkp_CommodityCd_inbound - infap360mm_mt_ecc_enterprise_lkp_CommodityCd_inbound	- infap360mm_m_s4h_s4h_lkp_CommodityCd_inbound - infap360mm_m_ecc_ecc_lkp_CommodityCd_inbound - infap360mm_m_s4h_enterprise_lkp_CommodityCd_inbound - infap360mm_m_ecc_enterprise_lkp_CommodityCd_inbound	
infap360mm_import_lkp_division_inbound	- infap360mm_tf_ecc_ecc_lkp_division_inbound - infap360mm_tf_ecc_enterprise_lkp_division_inbound - infap360mm_tf_s4h_s4h_lkp_division_inbound - infap360mm_tf_s4h_enterprise_lkp_division_inbound	- infap360mm_mt_ecc_ecc_lkp_division_inbound - infap360mm_mt_s4h_s4h_lkp_division_inbound - infap360mm_mt_s4h_enterprise_lkp_division_inbound - infap360mm_mt_ecc_enterprise_lkp_division_inbound	- infap360mm_m_s4h_enterprise_lkp_division_inbound - infap360mm_m_ecc_ecc_lkp_division_inbound - infap360mm_m_s4h_s4h_lkp_division_inbound - infap360mm_m_ecc_enterprise_lkp_division_inbound	

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_import_lkp_expImpMaterialGrp_inbound	- infap360mm_tf_s4h_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_tf_ecc_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_tf_s4h_s4h_lkp_expImpMaterialGrp_inbound - infap360mm_tf_ecc_ecc_lkp_expImpMaterialGrp_inbound	- infap360mm_mt_ecc_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_mt_s4h_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_mt_ecc_ecc_lkp_expImpMaterialGrp_inbound - infap360mm_mt_s4h_s4h_lkp_expImpMaterialGrp_inbound	- infap360mm_m_s4h_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_m_ecc_ecc_lkp_expImpMaterialGrp_inbound - infap360mm_m_ecc_enterprise_lkp_expImpMaterialGrp_inbound - infap360mm_m_s4h_s4h_lkp_expImpMaterialGrp_inbound	
infap360mm_import_lkp_GeneralItemCatGrp_inbound	- infap360mm_tf_s4h_enterprise_lkp_GeneralItemCatGrp_inbound - infap360mm_tf_ecc_ecc_lkp_GeneralItemCatGrp_inbound - infap360mm_tf_s4h_s4h_lkp_GeneralItemCatGrp_inbound - infap360mm_tf_ecc_enterprise_lkp_GeneralItemCatGrp_inbound	- infap360mm_mt_ecc_enterprise_lkp_GeneralItemCatGrp_inbound - infap360mm_mt_s4h_s4h_lkp_GeneralItemCatGrp_inbound - infap360mm_mt_ecc_ecc_lkp_GeneralItemCatGrp_inbound - infap360mm_mt_s4h_enterprise_lkp_GeneralItemCatGrp_inbound	- infap360mm_m_ecc_ecc_lkp_GeneralItemCatGrp_inbound - infap360mm_m_s4h_enterprise_lkp_GeneralItemCatGrp_inbound - infap360mm_m_s4h_s4h_lkp_GeneralItemCatGrp_inbound - infap360mm_m_ecc_enterprise_lkp_GeneralItemCatGrp_inbound	
infap360mm_import_lkp_loadingGrp_inbound	- infap360mm_tf_ecc_ecc_lkp_loadingGrp_inbound - infap360mm_tf_ecc_enterprise_lkp_loadingGrp_inbound - infap360mm_tf_s4h_enterprise_lkp_loadingGrp_inbound - infap360mm_tf_s4h_s4h_lkp_loadingGrp_inbound	- infap360mm_mt_ecc_ecc_lkp_loadingGrp_inbound - infap360mm_mt_ecc_enterprise_lkp_loadingGrp_inbound - infap360mm_mt_s4h_s4h_lkp_loadingGrp_inbound - infap360mm_mt_s4h_enterprise_lkp_loadingGrp_inbound	- infap360mm_m_ecc_ecc_lkp_loadingGrp_inbound - infap360mm_m_ecc_enterprise_lkp_LoadingGrp_inbound - infap360mm_m_s4h_enterprise_lkp_LoadingGrp_inbound - infap360mm_m_s4h_s4h_lkp_loadingGrp_inbound	

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_import_lkp_region_inbound	- infap360mm_tf_ecc_enterprise_lkp_region_inbound - infap360mm_tf_s4h_enterprise_lkp_region_inbound - infap360mm_tf_s4h_s4h_lkp_region_inbound - infap360mm_tf_ecc_ecc_lkp_region_inbound	- infap360mm_mt_s4h_s4h_lkp_region_inbound - infap360mm_mt_ecc_ecc_lkp_region_inbound - infap360mm_mt_s4h_enterprise_lkp_region_inbound - infap360mm_mt_ecc_enterprise_lkp_region_inbound	- infap360mm_m_s4h_enterprise_lkp_region_inbound - infap360mm_m_ecc_ecc_lkp_region_inbound - infap360mm_m_s4h_s4h_lkp_region_inbound - infap360mm_m_ecc_enterprise_lkp_region_inbound	
infap360mm_import_lkp_transportationGroup_inbound	- infap360mm_tf_ecc_enterprise_lkp_transportationGroup_inbound - infap360mm_tf_s4h_enterprise_lkp_transportationGroup_inbound - infap360mm_tf_ecc_ecc_lkp_transportationGroup_inbound - infap360mm_tf_s4h_s4h_lkp_transportationGroup_inbound	- infap360mm_mt_ecc_enterprise_lkp_transportationGroup_inbound - infap360mm_mt_s4h_enterprise_lkp_transportationGroup_inbound - infap360mm_mt_ecc_ecc_lkp_transportationGroup_inbound - infap360mm_mt_s4h_s4h_lkp_transportationGroup_inbound	- infap360mm_m_ecc_enterprise_lkp_TransportationGroup_inbound - infap360mm_m_s4h_enterprise_lkp_TransportationGroup_inbound - infap360mm_m_ecc_ecc_lkp_transportationGroup_inbound - infap360mm_m_s4h_s4h_lkp_transportationGroup_inbound	

Job Name	Taskflow	Mapping Task	Mapping	Description
infap360mm_import_lkp_xPlantMatStatus_inbound	- infap360mm_tf_ecc_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_tf_s4h_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_tf_ecc_ecc_lkp_xPlantMatStatus_inbound - infap360mm_tf_s4h_s4h_lkp_xPlantMatStatus_inbound	- infap360mm_mt_ecc_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_mt_s4h_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_mt_ecc_ecc_lkp_xPlantMatStatus_inbound - infap360mm_mt_s4h_s4h_lkp_xPlantMatStatus_inbound	- infap360mm_m_ecc_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_m_s4h_enterprise_lkp_xPlantMatStatus_inbound - infap360mm_m_ecc_ecc_lkp_xPlantMatStatus_inbound - infap360mm_m_s4h_s4h_lkp_xPlantMatStatus_inbound	
infap360mm_import_lkp_material_group_inbound	- infap360mm_tf_s4h_s4h_lkp_material_group_inbound - infap360mm_tf_ecc_ecc_lkp_material_group_inbound - infap360mm_tf_s4h_enterprise_lkp_material_group_inbound - infap360mm_tf_ecc_enterprise_lkp_material_group_inbound	- infap360mm_mt_s4h_s4h_lkp_material_group_inbound - infap360mm_mt_ecc_ecc_lkp_material_group_inbound - infap360mm_mt_s4h_enterprise_lkp_material_group_inbound - infap360mm_mt_ecc_enterprise_lkp_material_group_inbound	- infap360mm_m_s4h_s4h_lkp_material_group_inbound - infap360mm_m_ecc_ecc_lkp_material_group_inbound - infap360mm_m_s4h_enterprise_lkp_material_group_inbound - infap360mm_m_ecc_enterprise_lkp_material_group_inbound	

For more information about taskflows, see "Predefined batch jobs" on page 18 .

6. Save the job.

   For more information about import jobs, see *Import reference data*.

Running the jobs

After you integrate SAP ECC and SAP S/4HANA with MDM SaaS, you can run the predefined ingress and egress jobs.

To import hierarchy relationships for the Material Category business entity, run the jobs in the following order:

1. infap360mm_ingress_ecc_producthierarchy_materialcategory_inbound
2. infap360mm_ingress_s4h_producthierarchy_materialcategory_inbound
3. infap360mm_ingress_ecc_producthierarchy_matcat_matcat_inbound
4. infap360mm_ingress_s4h_producthierarchy_matcat_matcat_inbound

5. infap360mm_ingress_ecc_producthierarchy_matcat_mat_inbound
6. infap360mm_ingress_s4h_producthierarchy_matcat_mat_inbound

To import data from SAP ECC and SAP S/4HANA to Reference 360, run the following import jobs:

- infap360mm_import_ecc_lkp_p360_inbound
- infap360mm_import_s4h_lkp_p360_inbound

For more information about all the available jobs, see “Predefined batch jobs” on page 18.

INDEX

I

Informatica Global Customer Support
  contact information 6
Informatica Intelligent Data Management Cloud
  web site 5

M

maintenance outages 6

S

status
  IDMC 6
  system status 6

T

trust site
  description 6

U

upgrade notifications 6

W

web site 5