

Informatica MDM – Product 360

Desktop UI – User manual

Version 10.5 HotFix5 (English)

Informatica MDM - Product 360 - Desktop
Version 10.5 HotFix 5

© Copyright Informatica LLC 1993, 2025

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica and the Informatica logo are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be tradenames or trademarks of their respective owners.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Table of Contents

1 Informatica MDM - Product 360 - Desktop 16

1.1 Typographic conventions 16

2 Starting the 360 Desktop Client product 18

2.1 Program interface 19
2.2 Menus 20
2.3 Perspectives 21
2.3.1 Opening perspectives 24
2.3.2 Adapting perspectives 24
2.3.3 Adapting the perspectives menu 26
2.4 Windows and views 26
2.4.1 Opening a view 28
2.4.2 Blocking a view 29
2.4.3 Resizing windows 30
2.4.4 Changing the layout 30
2.5 Tables 31
2.5.1 Creating new data 33
2.5.2 Sorting a table 34
2.5.3 Selecting columns 35
2.5.4 Changing the order of columns 36
2.5.5 Changing the field qualification 36
2.5.6 Changing the column name 36
2.5.7 Changing the column width 37
2.5.8 Using field filters 37
2.5.9 Filtering a table 39
2.5.10 Grouping tables 39
2.5.11 Saving a grouping 41
2.5.12 Saving data 41
2.5.13 Saving settings 42

3 Data import 43

3.1 Preparation 44
3.1.1 Suppliers 44
3.1.2 Supplier catalogs 45
3.1.3 Customers 46
3.1.4 Mappings 47
3.1.5 Import projects 47
3.2 Import 48
3.2.1 Data source 49
3.2.2 Repository 51
3.2.3 Content 53
3.2.4 Frequency 54

3.2.5 Details....54
3.2.6 Functions....55
3.2.7 Creating subentities for deletion....56
3.2.7.1 Editing a subentity deletion configuration....57
3.2.7.2 Deleting a subentity deletion configuration....58
3.2.8 Field details....58
3.2.9 Log....59
3.3 Importing data in tables....60
3.3.1 Integrating the first data source....61
3.3.2 Integrating additional data sources....62
3.3.3 Filtering a view....62
3.3.4 Mapping the first worksheet....63
3.3.5 Mapping additional worksheets....63
3.3.6 Assigning attribute values....63
3.3.7 Performing an import....64
3.4 Importing structured data....65
3.4.1 Item data....66
3.4.2 Prices....67
3.4.3 Multimedia attachments....67
3.4.4 Structure assignments and attributes....68
3.4.5 Material group system....69
3.5 Automatic import....70
3.5.1 Import details....71
3.5.1.1 Hotfolder configuration....72
3.5.1.2 Hotfolder groups....75
3.5.2 Technical information....76
3.6 Importing user-defined structure systems....76
3.7 Adding multimedia data....77
3.8 Merge....78
3.8.1 Merge preview....79
3.8.2 Specifying merge settings....80
3.8.3 Scheduling a merge....81
3.8.4 Merge for characteristic values....82
3.9 Process overview....82
3.10 Importing characteristic values....83

4 Data maintenance....85

4.1 Spellchecking....85
4.1.1 Maintaining dictionaries....87
4.1.1.1 Managing spellchecking....88
4.1.2 Using the spellchecker....88
4.2 Finding items or products....90
4.2.1 Context selection....90
4.2.2 Search....93
4.2.2.1 Finding records....94

4.2.3 Navigation in structure systems....95
4.3 Editing items....97
4.3.1 General item data....98
4.3.2 Items....99
4.3.2.1 Creating items....101
4.3.2.2 Setting object rights....102
4.3.2.3 Clone items....102
4.3.2.4 Deleting items....102
4.3.3 Item details (form)....103
4.3.4 Maintaining item data....103
4.3.4.1 Item status....104
4.3.4.2 Maintaining descriptions....105
4.3.4.2.1 Find and Replace....106
4.3.4.3 Managing text features....107
4.3.5 Maintaining customer-specific data....108
4.3.6 Maintaining item attributes....109
4.3.6.1 Item attributes....109
4.3.6.2 Assigning item attributes to structure features....110
4.3.6.3 Preset values for attributes....111
4.3.6.4 Units of item attributes and structure features....111
4.3.6.5 Item attributes with multiple values....112
4.3.6.6 Item attributes (cumulative)....112
4.3.6.7 Transferring structure features as item attributes....113
4.3.6.8 Items with features....114
4.3.7 Item reference....115
4.3.7.1 Supplier relationships....115
4.3.7.2 Item comparison....116
4.3.8 References....117
4.3.9 Kits and components....119
4.4 Classifying....120
4.4.1 Preparation....121
4.4.1.1 Creating an overview....122
4.4.1.2 Finding the required data....122
4.4.2 Initial classification....123
4.4.2.1 Changing a structure assignment....124
4.4.2.2 Multiple assignment....124
4.4.2.3 Deleting a structure assignment....125
4.4.2.4 Classification and features....125
4.4.2.5 Item classification by import....126
4.4.2.6 Displaying structure groups....126
4.4.3 Multiple classification....127
4.4.3.1 Classifying items using the assignment recommendation....128
4.4.3.2 Multiple classification by import....129
4.4.3.3 Structure group assignments....130
4.5 Prices, surcharges and discount groups....132
4.5.1 Prices....133

4.5.1.1 Purchase prices....134
4.5.1.2 Selling prices....135
4.5.2 Price example....136
4.5.3 Checking price changes....137
4.5.4 Price surcharges....138
4.5.4.1 Packaging costs....138
4.5.4.2 Surcharge calculation based on metal content....139
4.5.4.3 Surcharge calculation based on jump....139
4.5.5 Discount groups....140
4.5.5.1 Purchasing and selling discount rates....140
4.5.5.2 Purchasing discount groups....141
4.5.5.3 Selling discount groups....141
4.6 Maintaining product data....141
4.6.1 Creating products....143
4.6.2 Editing products....143
4.6.2.1 Creating structure assignments....144
4.6.2.2 Assigning items to products....144
4.6.2.3 Creating product references....145
4.6.2.4 Creating a multimedia attachment....146
4.6.2.5 Maintaining product attributes....147
4.6.3 Product details (form)....147
4.7 Assortments....147
4.7.1 Creating assortments....148
4.7.2 Adding an item or product to an assortment....149
4.7.3 Working with assortment filters....150
4.7.4 Managing assortments....151
4.7.5 Views for assortments....152
4.8 Versioning....152
4.8.1 Creating a version....153
4.8.2 Working with versions....154
4.8.3 Versions and tables....155
4.8.4 Closing a version....156
4.8.5 Deleting a version....156
4.9 Compare....156
4.10 Preview function....157
4.11 Lookups....158

5 Data quality checks....161

5.1 Definitions....161
5.2 Quality rule overview....162
5.3 Creating quality rules....164
5.4 Maintaining reference data....167
5.5 Planning quality checks....170
5.6 Specifying quality checks for particular channels....172
5.7 Performing quality checks....175

5.8 Determining the status ... 176

6 Multimedia data maintenance ... 179

6.1 Multimedia data management systems ... 180
6.2 System settings ... 180
6.3 Multimedia overview ... 181
6.3.1 Document categories ... 183
6.3.2 Media asset file ... 185
6.3.2.1 Documents ... 187
6.3.3 Dependencies ... 188
6.3.4 Multimedia attachments ... 188
6.3.5 System multimedia attachments ... 189
6.3.6 Multimedia documents ... 189
6.3.7 Image preview ... 189
6.3.8 Miniature view ... 190
6.3.9 Miniature view (documents) ... 191
6.4 Searching multimedia data ... 192
6.4.1 Advanced multimedia data search ... 193
6.5 Linking multimedia data and items ... 194
6.5.1 Creating a new multimedia attachment ... 194
6.5.2 Assigning documents ... 195
6.5.3 Changing a multimedia document ... 195
6.5.4 Assigning external documents ... 196
6.5.5 Copying a multimedia assignment ... 196
6.5.6 Displaying changes ... 196
6.5.7 Updating changes ... 197
6.5.8 Linking multimedia files automatically ... 198
6.6 Deleting documents ... 199
6.7 Linking multimedia data and structure nodes ... 200

7 Structure systems ... 201

7.1 Maintenance structure ... 201
7.2 Primary structure tree ... 202
7.3 Class list ... 203
7.4 Creating a structure system ... 204
7.4.1 Deleting a structure system ... 205
7.4.2 Creating structure groups ... 205
7.4.2.1 Renaming structure groups ... 206
7.4.2.2 Deleting structure groups ... 206
7.4.3 Class details ... 206
7.4.4 Subordinate structure groups ... 207
7.4.5 Setting object rights for a structure system ... 208
7.5 Maintaining structure features ... 208
7.5.1 Creating a structure feature ... 209
7.5.2 Deleting a structure feature ... 209

7.5.3 Creating structure preset values....209
7.5.4 Preset values for structure features....210
7.6 Maintaining structure group features....210
7.6.1 Feature groups list....210
7.6.2 Preset values for structure groups....211
7.6.3 Group features with multiple values....212
7.6.4 Feature attribute match....212
7.7 Feature inheritance....214
7.8 Copying a structure or substructure....215
8 Tasks....217
8.1 Standard tasks....217
8.1.1 Creating tasks....217
8.1.2 Accepting tasks....219
8.1.3 Sorting tasks....220
8.1.4 Filtering tasks....220
8.1.5 Searching tasks....220
8.1.6 Creating a task group....220
8.1.6.1 Creating a task group for a task....221
8.1.6.2 Creating a new task in a task group....221
8.1.6.3 Assigning a task to a different task group....221
8.1.7 Executing a task....222
8.1.8 Marking tasks as completed....222
8.1.9 Assigning tasks to different users/user groups....222
8.1.10 Deleting a task....223
8.1.11 Configuring E-mail notification....223
8.1.11.1 Creating templates....224
8.1.11.2 Task notification....225
8.2 Workflow tasks....226
8.2.1 Accepting elements to be processed....227
8.2.2 Completing/releasing/rejecting processing of elements....227
8.2.3 Assigning processing of elements to different users/user groups....227
8.2.4 Canceling a workflow for an element....228
8.2.5 Showing information for an element in a workflow task....228
9 Business process management....229
9.1 Creating workflow trigger configurations....230
9.2 Start Conditions....231
10 Audit trail....234
10.1 Audit trail search pane....234
10.1.1 Finding modified objects....235
10.2 Modification history....235
10.2.1 Viewing modification history....237
10.2.2 Filtering modified records....237
10.2.3 Reverting new values to old values....237

11 Dashboard 239

11.1 Managing dashboards 239
11.2 Calling up dashboards 241

12 Administration 242

12.1 Organization 242
12.1.1 Managing user groups 243
12.1.2 Managing licenses 245
12.1.3 Assigning views and perspectives 245
12.1.4 Assigning action rights 246
12.1.5 Action rights 246
12.1.6 Managing field rights 246
12.1.7 Qualified field rights 247
12.1.8 Object rights 248
12.1.8.1 Inheriting object rights 249
12.1.8.2 System object rights 251
12.1.8.3 Managing object rights 251
12.2 Managing users 253
12.3 Preferences 255
12.3.1 Table settings 255
12.3.2 Item attributes 256
12.3.3 Item classification 257
12.3.4 Image preview 257
12.3.5 Import settings 257
12.3.6 Merge preview 257
12.3.7 Miniature view 258
12.3.8 Multimedia attachments 258
12.3.9 Product 258
12.3.10 Structure editor 258
12.3.11 Structures - Basic settings 259
12.4 The "Administrator" user 259
12.5 System messages 259
12.5.1 Creating system messages 260
12.5.2 Editing system messages 261
12.5.3 Deactivating system messages 261
12.6 Units 261
12.6.1 Unit systems 262
12.6.2 Unit system 262
12.6.3 Unit maintenance 262

13 Export 264

13.1 Export module 265
13.1.1 Export format templates and export profiles 266
13.1.2 Data sources, export parameters, and variables 266
13.1.3 Data fields, functions, and comments 267

13.1.4 Export files 267
13.1.5 One-off or repeated export 268
13.1.6 Export operation principle 268
13.2 Introductory examples 270
13.2.1 Creating a simple export format template using test export 270
13.2.1.1 Selecting a data source in the export format template 272
13.2.1.2 Creating a module 273
13.2.1.3 Editing a module 274
13.2.1.4 Test export 276
13.2.1.5 Formatting output files 277
13.2.2 Qualified data fields and export profile 278
13.2.2.1 Plan for output data 279
13.2.2.2 Creating an export format template 279
13.2.2.3 Creating a module with a header for the export file 279
13.2.2.4 Creating a module for data output 280
13.2.2.5 Using a qualified data field 280
13.2.2.6 Outputting item attributes 281
13.2.2.7 Creating a variable 282
13.2.2.8 Creating an export profile 284
13.2.2.8.1 Export 285
13.2.2.8.2 Checking results in export files 286
13.2.3 Using submodules and multiple export files 286
13.2.3.1 Using multiple export files 287
13.2.3.2 Creating multiple headers 287
13.2.3.3 Module for output of item data 288
13.2.3.4 Item attributes 288
13.2.3.5 Creating a sub-module 289
13.2.3.6 Referencing a sub-module 290
13.2.3.7 Performing an export 290
13.2.3.8 Export results 291
13.3 Creating export format templates 291
13.3.1 Properties of an export format template 293
13.3.1.1 Settings 294
13.3.1.2 Data sources 295
13.3.1.3 Variables 296
13.3.1.4 Data fields 296
13.3.1.5 Functions 299
13.3.1.6 File management 300
13.3.1.7 File attachments 301
13.3.1.8 Post-processing 302
13.3.2 Creating modules and sub-modules 304
13.3.2.1 Properties of a module 305
13.3.2.2 Module editor 307
13.3.2.3 Checking the export format template 308
13.3.3 Managing export format templates 309
13.3.4 Saving an export format template 310

13.3.5 Loading an export format template....311
13.3.6 Managing format mapping tables....312
13.3.7 Exporting characteristic values....312
13.4 Creating export profiles....313
13.4.1 Managing export profiles....315
13.4.2 Editing an export profile....316
13.4.3 Deleting an export profile....317
13.5 Export....317
13.5.1 Export immediately....319
13.5.2 Scheduling a one-off export....322
13.5.3 Repeated export....323
13.5.3.1 Repetition interval....324
13.5.3.2 Repetition pattern....325
13.5.4 Quality checks....328
13.5.5 Editing exports....330
14 Appendix....332
14.1 Rights groups for action rights....333
14.1.1 Rights group: General....334
14.1.2 Rights group: Item....334
14.1.3 Rights group: Item assortments....335
14.1.4 Rights group: Item search....335
14.1.5 Rights group: Audit Trail....336
14.1.6 Rights group: Tasks....336
14.1.7 Rights group: Task notifications....336
14.1.8 Rights group: Users....336
14.1.9 Rights group: Data quality....337
14.1.10 Rights group: Document management....337
14.1.11 Rights group: E-mail templates....337
14.1.12 Rights group: Units....338
14.1.13 Rights group: Export....338
14.1.14 Rights group: Import....339
14.1.15 Rights group: Channel....339
14.1.16 Rights group: Catalogs....339
14.1.17 Rights group: Customers....340
14.1.18 Rights group: Suppliers....340
14.1.19 Rights group: Merge....340
14.1.20 Rights group: Multimedia attachments....341
14.1.21 Rights group: Products....341
14.1.22 Rights group: Product assortments....341
14.1.23 Rights group: Product search....342
14.1.24 Rights group: Process planning....342
14.1.25 Rights group: Qualified field rights....342
14.1.26 Rights group: Discount groups....343
14.1.27 Rights group: Structures....343
14.1.28 Rights group: Structure groups....343

14.1.29 Rights group: Structure group search....344
14.1.30 Rights group: Structure features....344
14.1.31 Rights group: Structure preset values....345
14.1.32 Rights group: System messages....345
14.1.33 Rights group: Text features....345
14.1.34 Rights group: Company management....345
14.1.35 Rights group: Versions....346
14.1.36 Rights group: Predefined queries....346
14.1.37 Rights group: Workflow....347
14.1.38 Rights group: Dictionaries....347
14.1.39 Rights group: Lookups....347
14.1.40 Rights group: Characteristics....348
14.2 Rights groups for visibilities....348
14.2.1 Visibilities in PIM Desktop....348
14.2.2 Visibilities in PIM Web....354
14.3 Import function reference....356
14.3.1 concat....357
14.3.2 Date....358
14.3.3 defaultBoolean....358
14.3.4 defaultDate....358
14.3.5 defaultNumber....359
14.3.6 defaultString....359
14.3.7 delete....359
14.3.8 deleteIfEmpty....359
14.3.9 format....360
14.3.10 if....360
14.3.11 left....361
14.3.12 length....361
14.3.13 logError....361
14.3.14 logInfo....362
14.3.15 logWarning....362
14.3.16 lower....362
14.3.17 mid....363
14.3.18 replace....363
14.3.19 right....364
14.3.20 round....364
14.3.21 search....365
14.3.22 select....366
14.3.23 truncate....366
14.3.24 upper....367
14.4 Export function reference....367
14.4.1 BMEcatDataType....369
14.4.2 BMEcatMediaAssetQuality....370
14.4.3 BMEcatMediaAssetType....370
14.4.4 BMEcatPriceType....370
14.4.5 BMEcatReferenceType....371

14.4.6 Calculate....371
14.4.7 Compare....372
14.4.8 CompareBooleanValue....372
14.4.9 CompareDate....373
14.4.10 CompareIgnoreCase....373
14.4.11 CompareNumeric....374
14.4.12 Concat....374
14.4.13 CreateCDataSection....375
14.4.14 CreateXMLTagWithContent....375
14.4.15 CreateXMLTagWithValue....375
14.4.16 DatasetCounter....376
14.4.17 DatasetId....376
14.4.18 DatasetIdentifier....376
14.4.19 DateGetFirstDay....377
14.4.20 DateGetLastDay....377
14.4.21 EscapeValue....378
14.4.22 ExportMime....378
14.4.23 FillLeft....378
14.4.24 FillRight....380
14.4.25 FormatAttributeValueAsDecimal....380
14.4.26 FormatDate....382
14.4.27 FormatDecimal....383
14.4.28 FormatHierarchicalNumber....384
14.4.29 FormatSimplePattern....384
14.4.30 FormatTime....385
14.4.31 GetDate....385
14.4.32 GetDecimalSeparator....386
14.4.33 GetFirstValue....386
14.4.34 GetTime....387
14.4.35 GetValue....387
14.4.36 IfEmptyThen....388
14.4.37 IfEmptyThenNotEnc....388
14.4.38 IfNotEmptyThen....388
14.4.39 IfNotEmptyThenNotEnc....389
14.4.40 IsoCodeCurrency....389
14.4.41 IsoCodeLanguage....389
14.4.42 IsoCodeTerritory....390
14.4.43 LoopCounter....390
14.4.44 LowerCase....390
14.4.45 MimeDerivateGetUNCPath....391
14.4.46 MimeGetHtmlLink....391
14.4.47 MimeGetUNCPath....391
14.4.48 Modulo....391
14.4.49 NumberGet....392
14.4.50 NumberIncrement....392
14.4.51 NumberSet....393

14.4.52 RemoveBlanks....393
14.4.53 Replace....393
14.4.54 ReplaceUmlauts....394
14.4.55 SplitKeywords....394
14.4.56 SplitText....395
14.4.57 SplitTextGetLineCount....396
14.4.58 StringIndexOf....396
14.4.59 StringIndexOfIgnoreCase....397
14.4.60 StringLastIndexOf....397
14.4.61 StringLastIndexOfIgnoreCase....398
14.4.62 StringLeftBytes....398
14.4.63 StringLength....399
14.4.64 StringRemoveLinebreak....399
14.4.65 StringTruncateAtSpace....400
14.4.66 Substring....400
14.4.67 Trim....401
14.4.68 UpperCase....401
14.4.69 UpperCaseFirst....401
14.4.70 ValueGet....402
14.4.71 ValueSet....402
14.5 Data source reference....402
14.5.1 Data type: Item....403
14.5.1.1 Item list....403
14.5.1.2 Items by product assignments....406
14.5.1.3 Changed and new items....409
14.5.1.4 Structure group item....413
14.5.2 Data type: Units....417
14.5.2.1 All units in the unit system....417
14.5.3 Data type: Deleted relationships....417
14.5.3.1 Deleted item references....417
14.5.3.2 Deleted product references....418
14.5.3.3 Deleted assignments of items to Media Assets....419
14.5.3.4 Deleted assignments of items to products....419
14.5.3.5 Deleted assignments of items to structure groups....420
14.5.3.6 Deleted assignments of products to Media Assets....420
14.5.3.7 Deleted assignments of products to structure groups....421
14.5.3.8 Deleted assignments of structure groups to Media Assets....422
14.5.4 Data type: Deleted objects....422
14.5.4.1 Deleted items....422
14.5.4.2 Deleted Media Assets....423
14.5.4.3 Deleted products....423
14.5.4.4 Deleted structure groups....423
14.5.5 Data type: Customer....423
14.5.5.1 Customers....424
14.5.6 Data type: Supplier....424
14.5.6.1 Suppliers....424

14.5.7 Data type: Media Assets....424
14.5.7.1 Media Assets....424
14.5.8 Data type: Product....424
14.5.8.1 Changed and new products....424
14.5.8.2 Products by item assignment....428
14.5.8.3 Product list....431
14.5.8.4 Structure group products....434
14.5.9 Data type: Structure....437
14.5.9.1 Structure system....437
14.5.10 Data type: Structure group....438
14.5.10.1 All groups in structure system (with item filter)....438
14.5.10.2 All groups in structure system (with product filter)....440
14.5.10.3 Changed and new structure groups of a structure system....442
14.5.10.4 Structure group list....443
14.5.10.5 Structure sub-tree....444
14.5.11 Data type: Selling discount groups....445
14.5.11.1 All selling discount groups....445
14.6 Glossary....445
Index....452

1 Informatica MDM - Product 360 - Desktop

The Product Information Management (Informatica MDM - Product 360) suite aims at B2B dealers and manufacturers of technical products. The complete solution is geared towards medium-sized to large enterprises. This standard software solution covers the entire process chain, from data acquisition, through information management, to automated publication and distribution of printed and electronic catalog data.

User productivity when processing large amounts of data is the critical criterion for the success of a PIM solution. The added value that you as a supplier can offer your customers provides you with a competitive advantage. Global providers are increasingly recognizing the positive effects that an automated PIM solution can have on sales and costs. In a climate of fierce international competition, companies can only achieve their goals with structured, standardized processes for producing and distributing their product information.

1.1 Typographic conventions

The objective of this manual is not to describe every single variation of each and every command. As a rule, the description of the procedure and command calls is restricted to recommended variations for ease of reading. It does not differentiate between menu commands, dialog box calls, and changing categories within a dialog box. For example, if you read **Management > Preferences > Structures - Basic settings** in the instructions, this means that you call up the **Management** option in the program menu and then select **Preferences** in the submenu to open the relevant dialog box. Within this dialog box, special categories are available. Navigate to **Structures - Basic settings** and the dialog box will provide the corresponding configuration and selection options.

The names of views and perspectives are emphasized, e.g. the ***Context selection*** view in the ***Explorer (Items)*** perspective.

Step-by-step instructions are numbered.

1. Open the ***Explorer (Items)*** perspective.
2. In the ***Context selection*** view, select the "Master catalog" node.

Text markings at various points indicate special instructions, tips, or warnings, as the following examples show:

Tip: Tables like this contain useful tips.
Note: These tables contain important information:
Caution: This includes warnings about sources of errors and how to avoid them.
Information: Provides additional information about the current topic.

In addition, examples are provided from an imaginary company called "Erstein", which uses Product 360 Desktop and is involved in typical business transactions. A typical description of such a text is as follows:


> Every year in May, Erstein Handelsgesellschaft AG issues its annual main catalog with all the available items and the prices valid at that time. The item data including the image information must be perfectly maintained at that time. The sophisticated layout…

In conjunction with the description of a fact or object, an actual name is used, e.g. of a catalog, which may not exist in your system. To indicate that this is a system-specific name, <Catalog name> is written in the text instead of the actual name.

2 Starting the 360 Desktop Client product

Product 360 Desktop is based on the "client/server" concept. This means that in order to be able to use the client application that is installed on your computer, the computer must be constantly connected to the Product 360 Desktop server. All changes that you make to the data using the client are not saved on your computer but directly in the database. If several users are connected to the Product 360 Desktop server, they all have access to this data. You can access the data from any computer on which the Product 360 Desktop client is installed. However, settings that affect your own application, such as the arrangement of windows, are saved locally on the corresponding workstation computer.

When installing the client, only the name or IP address of the server has to be specified. However, if you want to connect to another server or even just to check the name entered after installation, press and hold the CTRL key during the startup operation. You will then see the following screen.



Server connection

When starting the application, this enables you to specify another server and also the port that the client and server use to communicate. No changes should generally be made here.

Depending on the settings in User management, you can log in with a name other than that of the operating system user:

1. Hold down the CTRL key in the above screen.
2. Click on **OK**.
   - Login continues but is then interrupted again. You can now log in explicitly with a name other than the name of the operating system user. Product 360 Desktop always displays the same screen if the client was able to connect to the server when starting the program but the operating system user name is not a valid Product 360 Desktop user. In this case, you must either log in using a different name or ask the administrator to create your user name as a valid account in Product 360 Desktop.

Note: From using other programs, you may be accustomed to receiving a prompt from the program to save any unsaved data when you click on "Close" or call up the corresponding function. In many cases, there is no such prompt in Product 360 Desktop since – except in a few rare situations – all data is always saved immediately in the server system.

2.1 Program interface


Der Product 360 Desktop provides all of the operating methods that are generally used. These include:

- Function calls from the program menu
- Function calls from view menus
- Function calls via context-sensitive menus that are called up by right-clicking (pop-up menu)
- Function calls by clicking on icons
- Function calls via key combinations (indicated as an alternative in the pop-up menu)

As a rule, the same function call is available using several access options.

Program interface

The program window (1) includes a menu area (2) at the top and a status bar divided into two (5) and (6) at the bottom. The menu area (2) is divided into the main menu, a toolbar and the context toolbar.The context toolbar can be used to obtain an overview of the current context settings. It also gives you quick access to the individual context elements (catalogs, assortments, and language). You can show or hide individual elements in the context toolbar under **Management > Preferences > General > Context toolbars**. The menu bar provides program functions, while the status bar provides feedback from the system. You can show or hide the status bar under **View > Status bar**.



Workstation

In the menu bar (2), a toolbar and the perspective line can be displayed if required. You can show or hide the toolbar under **View > Toolbar**. You can also show the perspective line separately below the toolbar:

1. If the toolbar is hidden: Select **View > Toolbar**.
2. Position the mouse on the perspective entry.
3. Select **Dock on > Top left** in the pop-up menu.
   - The perspective line is displayed as a separate line below the toolbar.
   - **Dock on > Left** displays the perspective line at the left edge of the window.
   - **Dock on > Top right** displays the perspective line in the toolbar.

Windows and views

The large area between the perspective line and the status bar normally contains windows (3) and (4). Every window has at least one "view". In the figure, the right window (4) has a single view. Additional views for each window are displayed by additional "tabs", which are shown in the left window (3) in the figure. A view always provides a very specific representation, e.g. the tree-like structure of a classification, a table of items or an image display. A view provides functions for editing the data using menus and icons.

Tip: Click on in the top right of a view to open the Product 360 Desktops online help. Alternatively, you can press F1.

Views can be linked to one another. For example, if you double-click on a catalog in the ***Context selection*** view, the ***Item #1*** view for all items in that catalog is displayed. Clicking on an item in this list displays additional data, e.g. the associated references in the ***References*** view. In order for this to work, both views must be placed in a logical relationship, i.e. a view must be able to "obey" changes in another view. This logical relationship is typically created automatically in the supplied perspectives.

Der Product 360 Desktop also provides you with unlimited display options in terms of the layout of the views in perspectives: Using the mouse, you can move a view from one window to another, you can position a window anywhere inside the program window, and it will be automatically anchored there. You can also "detach" a window from the program window entirely, perhaps to move it to a second screen.

2.2 Menus

Menus are displayed dynamically in Product 360 Desktop, i.e. the range of menu options displayed depends on the relevant program situation. If no perspective is open, only a few menu options are available. However, if a perspective is open, you have access to a much wider range of functions. The meanings of the menu options are explained in the corresponding context. At this point, you should note the following:

- The menus respond dynamically.

- Certain functions (but not all) can be accessed using program menus.
- Menu options either provide functions directly or they call up a perspective.
- Besides the program menus, there are also context-sensitive menus with special options, which you can call up either from the Views menu or using the pop-up menu for a specific option.
- There are functions that you cannot access from program menus or context-sensitive menus; these can only be executed using the drag and drop functionality.

Note: Because of the extensive rights assignment options, it is possible that not all of the functionalities or menus described below will be available. If necessary, contact your Product 360 Desktop Administration for an explanation of this issue.

In order to carry out a certain task, simply select the perspective provided for it.

In Product 360 Desktop the individual predefined perspectives are assigned to categories that represent typical task areas:

- Data transfer
  This category contains perspectives for importing supplier catalogs and transferring catalog data to the master catalog (in Product 360 Desktop the latter is referred to as a "merge").
- Data maintenance
  The Data maintenance category groups all perspectives that allow product data maintenance, classification of items and management of multimedia data and thus improve the data quality of your master catalog. This includes all functions that are indirectly required to maintain your master catalog and prepare for the output of the data. These are primarily the maintenance of user-defined structure systems, and the definition of assortments.
- Publications
  This category contains perspectives that can be used to export and publish items.
- Management
  This category includes perspectives that are used for managing customers, suppliers, units and Product 360 Desktop users.

2.3 Perspectives

In Product 360 Desktop a task is assigned to a group of windows and views. This window group is referred to as a "perspective". Product 360 Desktop is supplied with an entire series of preconfigured perspectives. You can use these perspectives immediately or you can adapt them to your own needs. In addition to these preset perspectives, Product 360 Desktop also provides the option of creating custom perspectives. In your work, you always require at least one perspective.

Category	Perspective	Description
Data transfer	Hotfolder	This perspective is used to manage the information and definitions necessary for an automatic import operation.


Category	Perspective	Description
	Import	In this perspective, you can load item, variant, product or structure data and read it in line with the rules you have defined.
	Merge	You can use this perspective to transfer selected items from the supplier catalogs into your master catalog in a precisely specified manner.
Data maintenance	Attribute assignment (items)	In this perspective, you maintain item attributes and their relationship with structure features.
	Initial classification (items)	This perspective provides the views required for item classification.
	Explorer (items)	This perspective is the simplest of all perspectives. It contains all important views needed to navigate and search in catalogs or in the master catalog.
	Explorer (products)	This perspective is used to maintain and manage product information.
	Multiple classification (items)	This perspective provides options that allow you to assign classified items to a different structure system.
	Multimedia attachments	This perspective is used to manage complex information such as image files, Microsoft Word documents or PDF documents. You can assign this information to items or products and you can change or delete assignments.
	Prices (items)	This perspective is used to maintain and monitor purchase prices and public or customer-specific selling prices.
	Discount groups	In this perspective, you can manage separate discounts and discount groups for purchasing and selling. You can assign discount groups to customers.
	References (items)	This perspective is used to monitor and maintain relationships between items. For example, such a relationship can exist between two items if one item is an accessory for another.
	Structures	You need this perspective to monitor the features and details of a standard structure system (e.g. eClass 8.0) or, in particular, to maintain a user-defined structure system.
	Structure group assignments	You use this perspective to create structure group assignments for multiple classifications of items.

Category	Perspective	Description
Publications	Export format templates	This perspective is used to create or edit the export format templates and export profiles that you require for an export.
Management	Task notification	In this perspective you can define and manage e-mail templates that are linked to different tasks and their phases. This is based on a specific role concept.
	Users	This perspective is used to manage users. Users with corresponding rights can create and manage users here, and assign them rights, in particular, by specifying their membership of rights groups.
	Documents	In this perspective, you analyze the dependencies between the multimedia documents stored on your Media Asset server, in other words, you can check where a certain document is used.
	Units	This perspective is used to manage the unit systems in Product 360 Desktops.
	Customers	This perspective is used to manage your customers, in other words, business partners for whom you create electronic catalogs, for example.
	Suppliers	This perspective lists all suppliers. You can create new suppliers or deactivate existing suppliers directly in this list.
	Supplier catalogs	This perspective is used to manage your supplier catalogs.
	Organization	This perspective is used to maintain data for your own company and also to manage rights groups.
	Process overview	This perspective provides you with an overview of planned, current, and past import and export operations and other operations.
	Versions	This perspective is used to create and manage your versions.
	Workflows	Here, you can manage all of the necessary workflow information.
	Dictionaries	This perspective is used to maintain imported dictionaries that are used for spellchecking.

2.3.1 Opening perspectives

When you start Product 360 Desktop for the first time, the default ***Explorer (items)*** perspective opens automatically. If several perspectives are open when you exit the program, all of these perspectives will reopen when you restart it later, and the perspective that was active last will be reactivated.

If you have not opened any perspective, the user interface will look like this:



No perspective open

1. Select **Perspectives > Open**.
   - The dialog box for selecting perspectives opens. The perspectives are divided into various categories. You will find your custom perspectives under "User-defined".
2. Open a category, e.g., **Default > Data maintenance**.
3. Select a perspective, e.g., ***References (items).***
4. Click on **OK**.
   - The perspective opens and is the perspective currently displayed.

2.3.2 Adapting perspectives


You can change perspectives by rearranging windows, closing windows, opening new windows, and creating, changing or deleting dependencies between windows. As a result, a perspective may look completely different from the one shown here. To reset a perspective to its delivery status, proceed as follows:

1. Open the perspective if it is not already open.
2. Select **Perspectives > Reset**.
   - The perspective is reset to the original delivery status.

Creating custom perspectives

You can create custom perspectives and design them according to your needs by opening certain views or changing their layout.

1. Change an existing perspective in such a way that it has the required appearance and composition.
2. Select **Perspectives > Save as…**.
   - The dialog box for saving perspectives opens.



Saving a perspective

3. Enter a descriptive name for your new perspective so that you can later identify the purpose of the perspective from its name.
4. Click on **OK**.
   - The modified perspective is saved under the new name. The existing perspective remains unchanged unless you have selected an existing name. You can also further adapt your custom perspective in this way.


If you have closed the perspective, you can open it again using the perspective selection dialog box.

Note: Information about perspectives you have created yourself is stored locally on your computer, specifically in a file in the "workspace" directory (in which many other settings are also saved). This directory can be fully deleted for administrative purposes. If this happens, all of your personal settings are lost. However, the directory can also be transferred to other computers.

2.3.3 Adapting the perspectives menu

In the menu, you can configure fast access to frequently required perspectives:

1. Select **Perspectives > Adapt...**.
   - The "Perspectives" dialog box opens. Existing perspectives are shown on the left-hand side while perspectives displayed in the perspective menu are shown on the right-hand side. The perspectives are organized into categories within a tree structure.



Adapting the perspectives menu

2. Open a category, e.g., **Default > Data maintenance**.
3. Select the relevant perspective, e.g. ***References (items).***
4. Click on **Add->**.
   - The perspective is displayed on the right.
5. Click on **OK**.
   - The dialog box is closed. You can now select **Perspectives > References (items)** to open the perspective.

Tip: If you transfer several perspectives to the menu, you can use and to change the sequence of the perspectives on the right-hand side of the menu.

2.4 Windows and views

A perspective in Product 360 Desktop contains at least one window, but usually contains several windows. Windows have the following properties in Product 360 Desktop:

- They contain at least one view.
- They are either embedded (anchored) in the application or they can be detached from it.
- Their size can be changed.

You can only change the size, detach or anchor windows using the mouse, not the keyboard.

Windows can have a context-sensitive menu, which you can open using ▽. This is known as the Views menu because it changes depending on which view is currently open. Additional icons for calling up the most important functions from the menu may also be displayed to the left. If the window is not wide enough for all icons or the view tabs to be displayed in the header, a new line is automatically inserted for the menu.

Views are provided in predefined categories to make targeted access easier. The table below shows a rough selection of the available views.

Category	Views
Administration	Action rights, Tasks, Task notification, Users, User details, User groups, E-mail templates, E-mail preview, Unit maintenance, Field rights, Customers, Suppliers, Licenses, Members, Object rights (system), Qualified field rights, System messages, Versions, Words, Dictionaries
Item views	Item, Item with features, Item attributes, Item details, Item assortments, Item search, Attribute assignments, Purchase prices, References, Selling prices
Item views (file attachments)	Image preview, Miniature view, Multimedia attachments
Item views (EKI)	Item comparison (supplier/master catalog), Supplier relationships
File attachments	Image preview, Miniature view, Multimedia attachments, Multimedia documents
Data transfer	Data source, Details, Field details, Functions, Hotfolder groups, Hotfolder configuration, Frequency, Content, Merge preview, Log, Repository
Documents	Dependencies, Documents, Document categories, Miniature view, System multimedia attachments
Export format templates	Properties, Export format templates
Background processes	Current and past processes, Overview
Catalog views	Context selection, Supplier catalogs
Classifications and material groups	Class details, Feature groups list, Primary and secondary structure tree, Source structure assignments, Structure group search, Structure systems, Preset values, Assignment recommendation
Product views	Product attributes, Product details, Products, Products with features, Product assortments, Product search, References, Variants, Selling prices
Discounts	Purchasing discount groups, Purchasing discount rates, Selling discount groups, Selling discount rates

Workflow	Profiles, Workflows
Other	Log, Quality check, Comparison view


In a structure tree such as the ***Context selection*** you normally select an entry for which you want to display the content in a view. If the content is represented in the form of a table, the first entry is displayed as selected. If several windows and views are open, Product 360 Desktop "remembers" the last content displayed when you set the focus to a different window. When you switch back, you will find the same content.

If you remain in the same window and deselect your selection, this results in the subordinate information unit being displayed. If you are at the lowest level or there is no underlying hierarchical structure, the views remain blank.

This general behavior of the views is disabled by a lock and no longer applies.

2.4.1 Opening a view

1. Select **Perspectives > Open view**.
   - The view selection dialog box opens. The views are displayed organized into categories.




Opening a view

2. Click on ▷ in front of a category, e.g. Item views.
   - The category opens up and shows the views available. Views shown in gray are already open in the current perspective.
3. Select a view, e.g., ***Item details (form).***
4. Click on **OK**.
   - The dialog box closes and the ***Item details (form)*** view opens in the current perspective.

Note: Alternatively, you can enter the view name as filter text if you know the name of the view.

2.4.2 Blocking a view

A view normally "monitors" every other view that you use, e.g. the ***Item #1*** view monitors the ***Context selection*** view, the ***Tasks*** view, etc. The ***Item #1*** view is then recompiled based on the selections you make in the other views. You can identify this dependency by virtue of the fact that, in the Views menu in the ***Item #1*** view, the "All views" option is selected under **Obtain content exclusively from**.



Obtain content exclusively from

Depending on the circumstances or the task, you can limit this "universal dependency" to a particular view, by selecting one of the currently open views under **Obtain content exclusively from** in the Views menu. The tab text for the ***Item #1*** view indicates which context (supplier catalog or master catalog) you have currently selected.

However, you can protect a view from being recompiled by clicking on or by selecting **Retain current content** in the Views menu. When is "pressed in", the "retain mode" is activated. Otherwise, it is deactivated. If the mode is activated, the view contents are unaffected by a change of context.

Note: This function is not available in all views.

If you want Product 360 Desktop to display the items from a particular context, an additional new ***Item #1*** view is automatically opened if no view is available to receive the data. The reasons for this could be:

- No ***Item #1*** view is open.
- The context of the available ***Item #1*** view is not based on the calling view.
- The ***Item #1*** view is in "retain mode".

2.4.3 Resizing windows

1. Move the mouse over the edge of the window until the pointer changes into a double arrow.
2. Hold down the left mouse button.
3. Move the mouse right/left or up/down in the direction of the arrow.
4. Release the mouse button when the desired size has been reached.

Two icons for minimizing and maximizing the window appear in the top right:  . The icon on the left minimizes the window to the size of the window's title bar. The icon on the right maximizes the window to the maximum size. The maximum size is defined by the program frame.

If the window has been maximized, the following icons are available:  . The left icon minimizes the window, while the right icon restores the window to its previous size. If the window has been minimized, appears on the nearest edge. Clicking on this restores the window to its previous size.

Note: If a window is so narrow that not all tab texts for the views it contains can be displayed, Product 360 Desktop automatically collapses these views to an appropriate width and represents the tab texts that cannot be displayed with double arrows:  . The number 2 indicates that two views are compressed in this way. Click on the double arrow to open one of the views arranged in this window from a drop-down list.

2.4.4 Changing the layout

You can change the layout of windows within the program window as required. However, you cannot overlay the individual windows as you may have seen in other Windows programs. The frame of a window always borders on other window frames. (Exception: the window has been detached from the program window). Changing the layout works in one of the following two ways:

- After changing the layout, a window is displayed at a different location within the program frame. This often involves changing the sizes of the adjacent windows.
- After the layout is changed, a window and its views are integrated into another existing window.

To change the layout:

1. Click on a free area in the relevant window title bar.
2. Hold down the left mouse button.
3. Drag the window to a different position in the program frame.
   - As long as the mouse button is held down, a black frame indicates where the window will be displayed when you release the left mouse button. The mouse pointer changes to indicate which of the two options you are using: An arrow symbol represents the first option and a folder symbol the second.

Tip: If you only want to move one individual view, you can can click on the view tab instead of the free gray area in the window title bar.

Since the Product 360 Desktops program window can incorporate several windows and you can arrange these as required, Product 360 Desktop must apply a certain system to arrange them. This layout can be either row-based or column-based.

For example, if four windows are tiled in a perspective, you can change the height of the top adjacent windows simultaneously in a row-based display. It does not matter whether you "grab" the border of the right or left window with the mouse pointer when changing the height of the two windows. In a column-based perspective, you can simultaneously change the width of the windows that are above and below one another. It does not matter whether you grab the border of the top or bottom window with the mouse pointer when changing the width of two windows positioned one above the other.

Tip: If you display three windows next to one another in columns, the width of the left window changes when you change the width of the (middle or) right window. To set optimum column widths for the three windows, first set the width of the window on the right and then work towards the left.

The same also occurs in the case of windows that are arranged one above the other.

You can change the orientation of a perspective created by Product 360 Desktop by "forcing" Product 360 Desktop to reconstruct it. To do this, you must first distribute the open views between just two windows and arrange these two windows according to the desired orientation. Then redistribute the views.

2.5 Tables

The ***Item #1*** view is the default display for items. Similar to a spreadsheet program (EXCEL, LOTUS etc.), the row and column logic is used to display the item. Entries are selected and deselected using standard Windows keyboard shortcuts combined with the mouse. The number of entries in this table is shown in brackets on the View tab after the description. In addition, you can use the Views menu to display a status bar showing the number of entries currently selected.





Table display

As you will know from other spreadsheet applications, it is very easy to sort by one or more columns in ascending or descending order. You can apply an additional filter to a table and, using a dialog box, add columns to a table or remove them, and change their sequence. You can save a "layout" of the table you have modified in this way under a separate name and reuse it again and again.

If you want to navigate in the view without a mouse, use the arrow and TAB keys. You can make a selected field editable by using the Enter or F2 key. A yellow arrow on the right edge of a field indicates that a drop-down list is available for that field.

Under **Management > Settings > Table settings** you can configure the number of data records you want Product 360 Desktop to display when you retrieve data from the server. If the number of data records called exceeds the value configured here, a message appears:



Confirmation prompt for loading large data

The following selection options are available:

- Load limited: Only the number of data records specified in the table settings is loaded.
- Load all: The number of data records specified in the table settings is ignored on this occasion and all data records are loaded.

Caution: In certain cases and depending on the data volume, this setting may result in long load times and in problems with the memory.

- Load all optimized: In this case also, the number of data records specified in the table settings is ignored and the data is loaded using a "virtual access", which enables optimized handling of the data.

Selecting one of the three options does not change the value in the table settings. To change the table settings, place a check mark next to the "Do no longer prompt for data type "x"" option.

Note: The dialog box may vary according to the data type. For example, optimized access to customer data is not currently possible. In this case, you can only choose between the "Load limited" and "Load all" options.


2.5.1 Creating new data

The procedure is always the same for creating new data in tables:

1. Clic on + or press CTRL and N on your keyboard.
   - A new row is created in the table.
2. Enter the data.
3. Click on or press CTRL and S on your keyboard to save the new data record.

Note: A new data record is also saved automatically if you select another existing row in the table or another view and when you press the tab key at the end of the row or press the down arrow key. A new blank row is inserted automatically when you press either of these keys.

Invalid entries are highlighted in red font. The system will display a response if you try to save invalid entries. You can then choose to correct the entries or reject the new data record completely.




Errors when creating data records


Caution: When you change an existing data record, the changes are applied immediately. This means that you do not need to explicitly click on .

2.5.2 Sorting a table

A table has column headers, which are freely configurable. Clicking on a column header will cause the table to be sorted in ascending or descending order based on the criterion in that column. This works as follows: If you click on the column header of an unsorted column, the table will be sorted in ascending order. Each subsequent click inverts the existing sort order. This is indicated by a triangular symbol.



Sort ascending



Sort descending


The row number column is always renumbered in ascending order after a sorting operation.

You can also sort by two or more columns at the same time by first clicking on the column header of the first column, pressing and holding the Shift key, and then clicking on the column header of another column. Hold down the Shift key if you want to change the sort order.

2.5.3 Selecting columns

The "Field selection" dialog box is used to select the table columns to be displayed.

1. Click on or select **Field selection** in the Views menu.
   - The "Field selection" dialog box opens.



Field selection dialog box (in the table view)

2. Select the relevant entry in the list on the left. The fields are divided into different categories, which you can expand and collapse. You can use the search field in the top left to perform a targeted search for fields. Use the asterisk (*) symbol as a placeholder for one or more characters in the search. All available fields in a view are shown by default.
3. Click on **Add ->**. (The button is inactive if no entry is selected.)
   - The entry now appears in the list on the right. This list shows, from top to bottom, the columns in the table, in the order they are displayed from left to right.

Tip: You can also transfer an entry to the other list simply by double clicking on the entry.

Remove column

1. Select an entry in the right-hand list.
2. Click on **<- Remove**.

Alternatively, you can use drag and drop to remove the columns from the table directly in the view, if you no longer want them to be displayed.

Tip: You can select several fields in the list at the same time and click on **<- Remove** or **Add ->** to move them.

Caution: The number of fields reflects the number of columns to be displayed in the tables. To improve the clarity, the number is limited to 50 static and 50 dynamic fields.

2.5.4 Changing the order of columns

1. Open the "Field selection" dialog box.
   - The list on the right shows, from top to bottom, the columns in the table, in the order they are displayed from left to right.
2. In the list on the right, select the entry you want to move.
3. Click on  or  to position the entry further to the right or further to the left in the table.

Note: You can only move a field in the top position "down" and a field in the lowest position "up". Other fields can be moved either up or down.

You can also select several fields at the same time and move them "up" or "down" together.

Alternatively, you can use drag & drop to drag a column to a different position in the table.

2.5.5 Changing the field qualification

Der Product 360 Desktop provides some fields that need to be "qualified" more in more detail. In other words, it is not enough just to indicate which column is to be displayed; you must also specify the version to be displayed. This is important, for example, for language-specific fields or for fields showing prices and attributes.

1. Open the "Field selection" dialog box.
2. Select an entry in the right-hand list.
3. Specify the field qualification in the bottom right section of the dialog box.

Tip: You can add a field several times if it is qualified with different values.

2.5.6 Changing the column name

If you display a field several times with different qualifications, it is useful to use descriptive column headers.

1. Open the "Field selection" dialog box.
2. Select an entry in the right-hand list.
3. Edit the column header in the "Field name" text field.

Tip: When you rename fields, make sure you do not assign a field name that already exists.

2.5.7 Changing the column width

The procedure for changing the width of the columns is as follows:

1. Move the mouse to the right edge of the column in the column header
2. Press the left mouse button
3. Drag the mouse to the right or left with the button held down.
4. When you have reached the width you want, release the mouse button.

Tip: A double click adjusts the column width so that the widest entry can still be displayed in this column.


2.5.8 Using field filters

You can define filters for a table, to hide some of the data. A filter definition consists of one or more filter conditions for one or more fields (columns in the table). Each table display manages its own filter. You can use to activate or deactivate the filter definition, i.e. filtering occurs when the filter is active. When you define a new filter, it is automatically activated.

Tip: The filter definition only applies to the entries listed in this table. In some table displays you have the option of restricting the scope qualitatively or quantitatively in other ways, e.g. in the ***Item #1*** view using the item search. Review these alternatives and select the best restriction method for your purposes.

To create a new filter condition:

1. Select **Field filter** in the Views menu.
   - The dialog box for filter definition opens. Existing filter definitions are displayed in the upper section, while the lower section is used to create new filters.



Field filter dialog box

2. In the "Column" drop-down list, select the field you want to assign a condition. This list shows only those fields that are currently displayed as columns in the table.

Tip: Add any missing fields to the table using the "Field selection" 35 dialog box.

3. In the center combo box, you can define the condition type. You can choose from the following:
   - "includes"
   - "does not include"
   - "begins with"
   - "does not begin with"
   - "equal to"
   - "not equal to"
   - "ends with"
   - "does not end with"
4. In the right field, enter one or more characters in plain text.
5. Then click on **Add** to transfer this condition to the filter definition list.
6. If you add more filter definitions in the same way, when the filter is activated only the data records that satisfy all the filter definitions will be displayed in the table.
7. Click on **OK** to apply the filter you have defined in this way.
8. To remove filter entries already defined, select the corresponding filter definition.
9. Click on **Remove**.
   - To remove all filter definitions from the list, click on **Remove all**.

Tip: You can remove a filter definition from the filter definition list and edit it by double clicking on the corresponding entry.

The table is only filtered using the current list; this means that data is hidden but no new data is added. It is important to bear this in mind if a search returns more hits than are displayed in the table due to restrictions in the preferences.

Quick filter function

You can also filter tables more quickly by using the quick filter option in the status bar. The quick filter is a simplified alternative to the field filter.

The difference is that the filter condition is automatically set to "contains".

To use the quick filter:


1. Click in the quick filter input field.
2. Enter the filter text.
3. By default, filtering is by the first column in the table. If you want to filter by other or additional fields, click on ▾ to the right of the input field and select the relevant fields.

Note: If you select multiple fields, the table shows those data records where the filter text entered occurs in at least one of the selected fields

2.5.9 Filtering a table

You can also create a field filter directly, i.e. using the pop-up menu for an entry in the table:

1. For example, in the ***Item #1*** view, select a word or the required text in the "Short description" column.
2. Select the filter you want to use in the pop-up menu:
   - You can always select the "Contains" or "Does not contain" filter.
   - If you have selected a character string at the beginning of the cell, you can select the "Begins with" or "Does not begin with" filter.
   - If you have selected a character string at the end of the cell, you can select the "Ends with" or "Does not end with" filter.
   - If you have selected the entire text in the cell, you can select the "Identical" or "Not identical" filter.



Set filter

3. You can define a series of filter criteria in turn. The second filter is applied to the result of the first filter and so on.

Note: You can delete all defined field filters by selecting **Delete all field filters** in the Views menu.

2.5.10 Grouping tables

The grouping function makes it easier to handle large data volumes, in a similar way to classification, assortments or filtering. You have a free choice of the information by which a table is to be grouped.

1. Click on to activate or deactivate the grouping mode.
   - When you activate the grouping mode, a separate area opens to the left of the table.
2. Using drag and drop, move one or a succession of columns shown in the table into this area. The column header acts as the "handle" for the relevant column.
   - Each column represents a kind of filter criterion that enables you to quickly gain an overview of the data. The different entries in the column are listed in the lower section of the grouping area. If you have moved several columns into the upper section of the grouping area, the lower section has a tree structure, in which you can navigate. Note that the grouping function is case-sensitive.

3. Click on the column header in the grouping column to sort grouped columns. You can reverse the sort order by clicking again. You can also change the sorting in the pop-up menu for the grouping column.





Table with grouping function activated

Alternatively, you can select **Group by this column** in the pop-up menu for a selected column header. Grouping mode is then automatically activated.

If a grouping criterion would contain more than 500 subnodes, Product 360 Desktop informs you that not all nodes can be displayed. For example, this would occur if there are more than 500 items in the ***Item #1*** view and you specify the GTIN as the first grouping criterion.




Limited display with a large number of nodes

Note: You can still sort by the grouped column. However, you will only see the first 500 entries or the maximum number of entries configured in the preferences 255.

2.5.11 Saving a grouping

You can save the grouping in a CSV file to evaluate it statistically.

1. Create the required grouping.
2. Select **Save grouping tree** in the Views menu or in the pop-up menu for the grouping tree.
   - The "Save grouping tree" dialog box opens.




Save grouping tree

3. Specify:
   - Where the table will be saved.
   - Which character set is used - this is particularly relevant for special characters
   - Which separator is used.
   - Additional options, e.g. saving the table columns as headers.
4. Click on **Finish**.

2.5.12 Saving data

Selecting **File > Save as...** in the program menu allows you to save the currently selected content of a table as a simple text file (CSV).



"Save as..." dialog box


In the "Save table" dialog box, you can specify:

- Which character set is used - this is particularly relevant for special characters
- Which separator is used.
- Additional options, e.g. saving the table columns as headers.

You can process the CSV files further with other programs. You can also specify that the CSV file is to be opened after saving.

2.5.13 Saving settings

If you require different table settings, you can save them as layouts and quickly call them up again later.



Copying a table layout

1. Compile a table with the required layout.
2. Select **Layout > Save as...** in the Views menu.
3. Enter a name for the layout in the "Save layout" dialog box.
4. Click on **OK** to save the layout.

The saved table layout is now active in the current perspective. Product 360 Desktop remembers the layout of views depending on the perspective, i.e. if you change the perspective, the same view may have a different layout.

You can switch between the individual layouts using **Layout** in the Views menu. To delete a layout:

1. Open the layout.
2. Select **Layout > Delete**.
   - The layout is deleted. If the layout is still used in another perspective, a warning message will appear.

Note: After deleting, the default layout is loaded automatically. The default layout cannot be deleted or renamed.

3 Data import

To edit data in Product 360 Desktop, you do not normally enter the data manually but import it into the system.

The data source is an external file. If you import data into a supplier catalog and then proceed to "merge" the items from the supplier catalog to the master catalog, there is an implicit relationship between a supplier catalog item and a master catalog item as the source for the master catalog item is a specific item in the supplier catalog. This relationship is useful when you are subsequently updating your source file.

- When you import data directly into the master catalog, the item numbers of the items to be imported can be used as the item numbers in Product 360 Desktop. This is particularly useful for example when you transfer the item numbers from your leading ERP system, for example (manufacturer scenario).
- If you are in a commercial enterprise, it is useful to transfer the data to the master catalog via the merge process and to maintain your own item numbers in the master catalog (dealer scenario).
- If the merge process cannot find an item in your master catalog, it automatically creates this item. However, it cannot use the item number from the supplier catalog as the item number in the master catalog. Instead, Product 360 Desktop uses an item number generator to automatically create a new item number.
- In addition, you can define a specific supplier of an item as the main supplier and maintain one or more other suppliers as "alternative suppliers" for this item.

When transferring data, make a distinction between the following areas:

- Item data import, including structure assignment
- Product data import, including structure assignment
- Structure data import, including structure mapping

Multimedia data is transferred in a special way since only item, product or structure group references are imported into Product 360 Desktop and not the data itself.

The three areas mentioned above are more or less complex entities in the Product 360 Desktop database. Depending on which data you want to import, the source information must be assigned to the Product 360 Desktopentities. This assignment is referred to as "mapping".

As both the Import and Merge dialog box enable you to define the time at which the function is to be carried out, it is possible to refer to a kind of automation. This is very useful for large commercial enterprises with an ERP interface, as these processes occur in the background, thus saving work and time.

Tip: When transferring data, make a distinction between "reading" and "importing". Data that you read into Product 360 Desktop from a file is not yet imported. When a file has been read, its data can only be displayed in Product 360 Desktop. It cannot be made available for other uses until the import is completed.

The procedure has been made more user-friendly in the new version of the program and no longer requires the use of import projects. Data import structures can be saved directly in the database as a mapping.

3.1 Preparation

Before you can import catalogs, you must first create the suppliers and customers and then the catalog itself. You can only import data once you have created a catalog, i.e. it exists in the data transfer area.

- First create the supplier and then the catalog, as you will need to specify the relevant supplier when creating the catalog.
- You will need the customer if the catalog contains customer-specific data that needs to be imported.

3.1.1 Suppliers

You maintain details of your suppliers in the ***Suppliers perspective.*** The supplier data is required for catalog imports to enable the supplier catalog to be assigned to the corresponding supplier. The data is also used to identify supplier catalogs.

The perspective comprises the ***Suppliers*** and ***Supplier*** views. While the ***Suppliers*** view lists all suppliers entered in the system, the ***Supplier*** view shows the details of a selected supplier in a form. You can update the data for a supplier both in the form and in the table.

Note: If you have selected several suppliers in the table, the fields in the form view are deactivated, i.e. they cannot be edited.

Creating new suppliers

1. Select **Management > Suppliers** to open the ***Suppliers*** perspective.
2. In the ***Suppliers*** view, click on ✚.
   - A new row is created in the table.
3. Enter the data for the new supplier.
4. Click on 💾 to save the data record.

Delete suppliers

1. Select the corresponding supplier in the ***Suppliers*** view.
2. Press DELETE or select **Delete** from the pop-up menu.
3. Confirm with **Yes**.
   - The supplier is deleted.

Tip: You can also deactivate a supplier without deleting it by clearing the check mark in the "Active" column.

3.1.2 Supplier catalogs

A catalog is a kind of container for items and information about them. The container itself also has a name, the catalog name, a sender and a recipient. The supplier is the catalog creator and the customer is the recipient. When you receive a catalog from a supplier to transfer to Product 360 Desktop, you are the customer in this sense.

Supplier catalogs are managed in the ***Supplier catalogs*** view, in the perspective of the same name, which is called up by selecting **Administration > Supplier catalogs.**

Create supplier catalogs

Tip: Create the supplier in the ***Suppliers*** perspective first and then create the supplier catalog.

1. Click on ✚ in the ***Supplier catalogs*** view.
   - A new row is created in the table.
2. Edit the new entry in the table by giving it a unique catalog identifier. At this point, it also makes sense to specify the supplier (and not to leave the optional field blank).
3. Click on 💾 to save the data record.
   - When you first create a catalog, you have defined the "catalog container" but the catalog itself is still empty.

Note: Each catalog identifier may only appear once and it is case-sensitive. The two catalog identifiers "Catalog1" and "CATALOG1" are therefore not considered identical. The language-specific catalog name is not a mandatory entry in Product 360 Desktop, and therefore does not need to be unique. However, you will find it easier to identify your catalogs if you enter descriptive names as far as possible.

Delete supplier catalogs

Caution: Remember that deleting a supplier catalog also deletes all items in that catalog.

1. Select the catalog in the ***Supplier catalogs*** view.
2. Select **Delete** in the pop-up menu.
3. Confirm with **Yes**.
   - The catalog and its items are deleted.

3.1.3 Customers

The ***Customers*** perspective is opened by selecting **Management > Customers**. Here you can create new customers and maintain existing customer data. The customer data is important for maintaining customer-specific product data and assigning customer catalogs to the appropriate customer.

The perspective consists of two views. While the ***Customers*** view lists all customers entered in the system, the ***Customer*** view shows the details of a selected customer in a form. Of course, you can update the data for a customer both in the form and in the table.

Note: If you have selected several customers in the table view, the fields in the form view are deactivated, i.e. they cannot be edited.

Creating new customers

1. In the ***Customers*** view, click on +.
   - A new row is created in the table.
2. Enter the data for the new customer.
3. Click on to save the data record.

Delete customers

1. Select the one or more customers in the ***Customers*** view.
2. Press DELETE or select **Delete** from the pop-up menu.
3. Confirm with **Yes**.
   - The customer(s) will be deleted.

Tip: You can also deactivate a customer without deleting it by clearing the check mark in the "Active" column.


3.1.4 Mappings

Mappings can be saved directly in the database or as an individual file.

To open the dialog box for managing mappings, click on in the Import perspective or select **File >Manage mappings...**.

Here, you can selectively access mappings by filtering the data by name or purpose. You can display all mappings or only those you have created. You can also use the creation and editing date as selection criteria. Individual task or role allocations are implemented by targeted rights assignment and change the appearance of the dialog box by disabling certain buttons.

Depending on your permissions, you can copy existing mappings to use them as a basis for creating new ones, or remove mappings you no longer require from the database by deleting them.



Managing mappings

Mappings can be managed in a structured way based on various features. Assignment to categories reflecting the different usage options or your purpose - manual import, link to Product 360 Supplier Portal, automatic import - helps you to maintain order and to ensure targeted provision for the system.

3.1.5 Import projects

Imports were previously saved in an import project. An import project consists of the data file (source file) and the associated mapping. In the latest version of Product 360 Desktop, mappings can be saved directly in the database, which means that they can be accessed independently of the user, if necessary.


By contrast, source files are mostly much larger and cannot therefore be saved in the database. By selecting **Management > Preferences > Import settings**, you can determine where you want the files to be saved.

Note: It is no longer necessary to maintain the project concept. However, integration of existing projects is still supported.

3.2 Import

The ***Import*** perspective can be used to import both structured data and data in tables.

For each import, you require a source file and the associated assignment file, referred to in Product 360 Desktop as the mapping.



Import

Data is imported based on the following pattern:

1. Open the ***Import*** perspective by calling up **Import** from the pop-up menu for a new, empty supplier catalog, an existing supplier catalog or the master catalog in the ***Context selection*** view.
2. Add a new file at the top left of the ***Data source*** view. The file is displayed in a tree structure in the view, allowing you to gain an idea of the structure, content and scope of the file, which may be completely unfamiliar to you. In the ***Data source*** view, you can scroll through the file gradually or view entire selected areas in the ***Content*** view at the bottom left. Also in the bottom left, the ***Frequency*** view for a field selected in the ***Data source*** view shows the contents plus the number of occurrences in the entire file. In the ***Details*** view, you can see longer texts, e.g. long description, for an item displayed in the ***Data source*** view.
3. Load an existing mapping or create a mapping by dragging the fields to be imported from the ***Data source*** view to the corresponding field in the ***Repository*** view in the top right. In the bottom right, you can use the ***Function*** view to specify functions to be applied to the data when importing.
4. Before the actual import, test the mapping created by performing a test import. The ***Log*** view in the bottom right shows information and any errors.

5. Start the import. Here, you can enter the catalog you want to import into and whether the import is to be performed immediately or at a set time. You can monitor the progress of the import and view the log in the ***Process overview*** perspective.


Tip: When you are scheduling an import, you can use the same dialog box to specify the import mode to be used. For example, you can specify that only existing elements are to be updated but no new elements are to be imported.

3.2.1 Data source

This section only explains the import of individual files. If you want to import multiple data sources, you will find the information in the Additional data source section.


The ***Data source*** view shows the data you want to import into Product 360 Desktop.

1. Click on or select **File > New import**.
2. Click on **Select** and then select the source file, which must be in one of the following formats: Excel (*.xls, *.xlsx, *.xlsm), CSV (*.csv, *.txt) or XML (*.xml).
   - The format settings for the source file are displayed.



Source file format settings in XML format

3. Click on **OK**.
   - The source file is opened. Here you have another opportunity to adapt the format settings.



Import dialog box


4. You can either select an existing mapping from the list box (a) or load it from a file (b).

   a. Various classification features (category, purpose) are available to you when selecting a mapping.

   b. Click on **Select** and then select the relevant mapping in the file manager that opens.

In order to support the widest possible range of data import scenarios, Product 360 Desktop redefines the existing mapping functionality. Different file formats are taken into account in terms of their characteristics and are checked for a match before the import. Three evaluation criteria are used:

- Does the total of the columns in the selected source file match the total in the mapping?
- Do the file format specific features match the definitions in the mapping?
- Verification at field level




Possible messages

A message about the match appears in the dialog box header,

---

   c. If no mapping exists yet, click on **New mapping**.

5. The file is opened in the ***Data source*** view.



XML file as data source

Note: You can also edit the settings later by opening the pop-up menu and clicking on **Format settings**.

6. You can use the filter function in the Views menu to define whether all fields from the file will be displayed in the view or only certain fields. Set or clear the check marks for the fields to show or hide them.
7. In the "Selection" column, you can use the arrows to scroll through the individual data records. Double-clicking on the field allows you to enter a specific row number.

Note: The ***Content*** view shows the complete content of the area selected in the ***Data source*** view.


8. You can either create a new assignment in the ***Repository*** view or select **File > Manage mappings...** to open an existing assignment file. The orange check mark before the entry in the ***Data source*** view indicates that an assignment has been created. A blue circle indicates that there are fields with and without assignments below the entry.
9. Once you have created an assignment, click on to perform a test import or on to start the import. You can see the results of the test import in the ***Log view.*** For the import, you can also see the results here or you can switch to the ***Process overview*** perspective.

3.2.2 Repository

The assignments for the import are created in the ***Repository*** view. This view contains a tree structure showing all available data fields for which you can create assignments. Here, you can specify which information is imported and which fields it will be assigned to in Product 360 Desktop. You can use the filter function in the Views menu to define whether all data areas will be displayed in the view or only certain areas.

This view is split into three columns:

- The "Structure" column displays the data fields to which you can assign the data to be imported.
- The "Assignment" column contains the assignment. You can edit this assignment here or in the ***Function*** 55 view.
- The "Content" column shows the result of the assignment, i.e., which values will be imported. This display depends on the data record selected in the ***Data source*** 49 view.



"Repository" view

Complex fields, e.g., language-specific text fields, prices or classification information, can be expanded in the "Structure" column. In these cases, assignments are specified for subordinate elements.

Once you have opened a file in the ***Data source*** view, you can create an assignment in various different ways:

- Select a row in the ***Data source*** view and use drag & drop to drag it to the corresponding data field in the ***Repository view,***
- After selecting the required data field in the ***Repository*** view, drag the row from the ***Data source*** view into the ***Function*** 55 view.
- You can use the same method to drag the columns from the ***Content*** 53 view into the ***Repository*** or ***Function*** view.

An orange check mark before the entry in the ***Data source*** view indicates that an assignment exists for a data field. Entries without a check mark are ignored during the import. Clicking on an assignment in the ***Repository*** view highlights the relevant entry in yellow in the ***Data source*** view. Conversely, you can also select an entry in the ***Data source*** view and the assignment will then be highlighted in yellow in the ***Repository*** view.

An incorrect assignment is highlighted in red in the ***Repository*** view and marked with an exclamation mark in the "Structure" column, e.g., if you have inadvertently assigned a text field to a price field that expects a numerical value. If there is an incorrect assignment for a subnode, the main node is also marked in red so that the incorrect assignment is still indicated when the fields are collapsed.

1. Select the incorrect assignment in the ***Repository view.***
2. Select **Delete assignment** in the pop-up menu.
   - The assignment is deleted and you can create a new assignment.

Note: Note that an assignment may be mandatory for the "Item no.", "Product number" or "Structure group identifier" data field, depending on the data to be imported. This is indicated by the key symbols preceding these fields. As soon as you create an assignment for a subnode of these fields, the node is highlighted in red to indicate the missing keys.

You can also transfer a fixed value to a data field in the ***Repository*** view instead of an import value. If you want to use a fixed value, do not create an assignment. Simply enter the value in the "Assignment" column in the ***Repository*** view. The use of functions in the ***Function*** view also enables you to combine fixed values with assignments.

If you require a node several times, e.g., because item attributes are spread across several columns in an Excel or CSV file:

1. Select the relevant node in the ***Repository view.***
2. Select **Duplicate node** in the pop-up menu.
   - The node is duplicated so that you can make another assignment to this data field.

Saving assignments


It is our experience that the files to be read often have the same internal structure. Alternatively, you may have agreed with the supplier that data will always be supplied in the same form. In such cases, you can save the assignments – some of which can be quite complex – for reuse. Select **File > Save mapping as file** to save the current assignment settings as a file.

Note: Product 360 Desktop Version 6.0 gives equal standing to items and products. This logic has been incorporated into the repository, making it necessary to update existing mappings.

3.2.3 Content

The ***Content*** view displays the contents of the file areas selected in the ***Data source*** view. In this view – as in the ***Item #1*** view – you can use the field selection dialog box to show or hide columns in the available context in each case), group by columns, or filter.

Note: With very large files, not all contents are displayed. To maintain performance, the display is limited to the first 250 entries.




Displayed contents

3.2.4 Frequency

The ***Frequency*** view shows the distributions of values in the data file. For example, if you select an area in the ***Data source*** view, the system determines which manufacturers are named and how often. In this view – as in the ***Item #1*** view – you can use the field selection dialog box to show or hide columns in the available context in each case), group by columns, or filter.


Note: With large data volumes, only the first 100 occurrences with the largest number are displayed to maintain performance.



Distribution within the file

3.2.5 Details

The ***Details*** view displays the complete text for an entry selected in the ***Data source*** view, which is particularly useful for longer texts such as long descriptions. You can copy texts in this view but you cannot edit them.



Detail view

3.2.6 Functions

In the ***Function*** view, you can specify functions for values to be imported, which are to be applied to the data when importing. First select a data field in the ***Repository*** 51 view to edit its assignment in the ***Function*** view.

A simple assignment is indicated by square brackets. For example, if you create an assignment for a BMEcat file, the assignment for the "Item no." field will appear as "[SUPPLIER_AID]" in the ***Function*** view. The "Content" column in the ***Repository*** view shows the result of applying the function to the data record currently selected in the ***Data source*** 49 view.

Note: Data fields are shown with square brackets in the ***Functions*** view. If a field name contains square brackets in the name, this must be masked using a backslash "\", e.g. [Name \[2\]].

Texts within functions must be written in double quotation marks. If the text itself contains double quotation marks, they must also be masked with "\", e.g. "20\" monitor" If the text contains "\", this must be masked with "\".

Figures are written with a point as the decimal separator, e.g. 1.75 or -0.5.

Date values are specified in the form YYYY-MM-DD, e.g. 2012-08-18.

True or false can be used as logical values.

A special value is "null". If a field is assigned this value, the content of the field remains unchanged.

Press CTRL and space bar to open the input wizard, which you can use to select the standard functions: You can find an overview here 356.

You can also use numerical values to perform simple mathematical functions such as addition, subtraction, multiplication, and division. The plus symbol has a special position, as it can also be used to combine several text sections (in a similar way to the **concat** 357 function).

Operators	Description
+	The plus symbol can have three meanings: • Sign for a positive number • Addition of numerical values • Linking of character strings (as in the **concat** function)
-	The minus symbol can have two meanings: • Sign for a negative number • Subtraction of numerical values
x	Multiplication of numerical values
/	Division of numerical values
%	Modulus; calculates the remainder from dividing two numbers

Operators	Description
<	Less than (comparison operator)
<=	Less than or equal to (comparison operator)
>	Greater than (comparison operator)
>=	Greater than or equal to (comparison operator)
= ==	Checks for equality and the result is a logical value. A blank character string and the value "null" are considered identical. ("=" and "==" can be used interchangeably.)
!	Negation (for logical values), i.e. "false" becomes "true" and vice versa
!=	Checks for inequality and the result is a logical value. A blank character string and the value "null" are considered identical.
&& and	Logical And; the result is a logical value. The second parameter is only evaluated if the first parameter has the value "true". The result is only "true" if both parameters have the value "true".
|| or	Logical Or; the result is a logical value. The second parameter is only evaluated if the first parameter has the value "false". The result has the value "true" if one of the two parameters is "true".
;	Sequence operator; the arguments are executed in succession, and only the last result is then used. This operator is useful if the first expression produces a side-effect, e.g. for output of a warning message in the import log.

You can also link functions, e.g.,

```
([NET PRICE]*0.19)+([NET PRICE])
```

This function calculates the sales tax on the net price and then determines the gross price.


Note: Click on to save changes in the ***Function*** view. After saving, you will see the effect of the function on the data to be imported in the ***Repository,*** view.

3.2.7 Creating subentities for deletion

When you define an import mapping, you can configure the subentities of an item, variant, or product for deletion from the database. You can configure subentities to delete for both manual import and hotfolder import.

You can also select specific records of the subentity to be deleted by specifying the corresponding qualifications. The records that match the specified qualifications, but are not available in the import file, are deleted from the database. The remaining records are either retained or updated by the import.

In the following example, the mapping is configured to delete the English and German short descriptions for the corresponding items in the import file.



Creating subentities for deletion

1. In the **Import** perspective, on the **Subentity deletion** tab, click the **Create subentity deletion configuration** icon.

   The **New configuration** dialog box opens.

2. Select the root entity that includes the specific subentity.
3. Select the subentity to delete.
4. In the **Qualifications panel**, perform one of the following tasks to specify the qualifications:
   - To delete all the records of the selected subentity, select the check box under the **All** column.
   - To delete specific records of the selected subentity, select the required qualification from the list under the **Value** column.
5. Click **OK**.
6. Click **Create**.

3.2.7.1 Editing a subentity deletion configuration

1. On the **Subentity deletion** view, right-click the configuration, and perform one of the following tasks:
   - Select **Edit configuration**.
   - Double-click the required configuration.

   ⇨ The **Edit configuration** dialog box appears.
2. Edit the configuration as required.

3.2.7.2 Deleting a subentity deletion configuration

1.On the **Subentity deletion** tab, perform one of the following tasks:


- Right-click the configuration, and select **Delete**.
- On the Edit menu, click **Delete**.
- Press the **Delete** key on your keyboard.

The **Deleting subentity deletion configuration** dialog box appears.

2.Click **OK**.

3.2.8 Field details

The ***Field details*** view shows information about an entry selected in the ***Repository*** view.



Field details


Depending on your selection, the following data is displayed:

- Type (numerical value, alphanumeric value, Boolean value or date value)
- Maximum length of field
- Rich text: Specifies whether the field can contain rich text
- Enumeration: Specifies which enumeration the field supports
- Default value: Set default value if no entry is made
- Decimal places: Number of decimal places
- Value range: Specifies the minimum and maximum values of a value range
- Example

3.2.9 Log

The ***Log*** view shows the logs for the test import or import. If necessary, press the F5 key to refresh the view. If an error occurs, you can select the corresponding line in the ***Log*** view – this highlights the corresponding entry in yellow in the ***Data source*** or ***Repository*** view. Double-clicking on a line opens the entire message in a separate dialog box.

If the icon in the ***Log*** view is pressed in, the complete log for the entire test import or import is displayed. If the icon is not pressed in, you will see only the log entry relating to the data record currently selected in the ***Data source*** view.



Log for a test import

When log entries are displayed, they are grouped according to status, so that you can quickly obtain an overview of the context in which errors or warnings have occurred. The log categories also help you to quickly obtain an overview of the entry type.

The following categories are available:

- Summary: General messages, e.g., the time at which the import or export started
- Unambiguity: Errors concerning data uniqueness, e.g., whether an item already has this item number
- System: General system errors
- Value range: Errors concerning data values, e.g., values that are too long for fields with length restrictions
- Data type: Errors when handling data types
- Mandatory value: Errors concerning mandatory values, e.g., if a mandatory field is not assigned a value
- Note: Notes concerning an import, e.g., user does not have write privileges for individual fields
- Consistency: Errors during a consistency check, e.g., as a result of using incorrect data fields in an export format template
- Security: Errors caused by problems concerning rights or security, e.g., an attempt to change a write-protected structure
- Various: There are several "various" errors.

3.3 Importing data in tables

When you are importing data in tables in CSV or Excel format, Excel files may contain several worksheets. For example, the Excel file can contain three worksheets with different data:

1. Worksheet with item information, e.g. item numbers, descriptions, classification, etc.
2. Worksheet with prices
3. Worksheet with item attributes

Item no.	Measuring range	Measuring tube length	Weight
ER 123-09-09	800	150	180
ER 123-09-10	200	60	140
ER 123-09-11	300	90	150
ER 123-09-12	1000	150	300
ER 123-09-13	500	150	120
ER 123-09-15	1500	200	160
ER 123-09-18	150	40	140
ER 123-09-19	2000	200	350
ER 123-09-20	1000	150	300

Item attributes


Note: If separators occur within texts in a CSV file, e.g. semicolon or line break, this text must be enclosed in quotation marks. If the text actually contains quotation marks, the quotation marks in the text must be doubled (see http://tools.ietf.org/html/rfc4180).

The first step is to integrate the data sources.

3.3.1 Integrating the first data source

The item number is used as a unique identifier on the worksheets. The first step is to load the file containing the different worksheets to the ***Data source view.***

1. Create a new catalog in the ***Supplier catalogs*** perspective.
2. In the ***Context selection*** view, select **Import** in the catalog pop-up menu.
   - The ***Import*** perspective opens.
3. Click on 🗋 in the ***Data source*** view to add the first worksheet from the file to be imported.
4. Select the file to be imported in the standard "Add" dialog box.
5. Click on **Open**.
   - A preview of the data is displayed in a dialog box.



Excel file with several worksheets

6. Specify:
   - Which worksheet is to be used.
   - Whether the first row contains column headers.
   - From which row the data is to be read.
   - How many data records are to be displayed in the preview, as not all data records are read in for the preview for performance reasons. Every change made in the dialog box is applied to the preview data immediately.
   - Whether blank cells overwrite any existing content, i.e. they are deleted by the import.

Note: For CSV files, you should also use this dialog box to specify which separators and format settings are to be used.

7. Click on **OK** to display the data in the ***Data source*** view.
   - The first worksheet from the file is displayed.

Now integrate the other worksheets in the same way.

3.3.2 Integrating additional data sources

Note: Note that you can only integrate multiple data sources if they are tabular data sources (Excel and CSV, but not XML).

Note: If you are using multiple data sources, they must be combined with one another. For example, you cannot import structure preset values and items that are unrelated in the same import operation.

Clicking on in the ***Data sources*** view allows you to integrate additional worksheets in the same way. However, you can also use the data source management:


Tip: You can change the format settings for the data sources later for the selected worksheet by opening the pop-up menu and clicking on **Format settings**.

The next step is to change the display in the ***Repository*** view.

3.3.3 Filtering a view

Before you create the mapping for importing the file, edit the display in the ***Repository view.*** As the file does not contain any product or structure group information, you can hide the corresponding fields in the ***Repository*** view:

1. Open the "Filter" drop-down list in the Views menu.
2. Clear the check marks after Structure group and Catalog group system.



Hiding mapping fields


3. Click on **OK**.
   - The ***Repository*** view now shows only the fields for the item mapping.

You can now start mapping the first worksheet.

3.3.4 Mapping the first worksheet

The mapping for the first worksheet is created as normal:

1. Use drag & drop to move the item number for the first data source from the ***Data source*** view to the ***Repository*** view.




Mapping the item number

2. Repeat this procedure for the other fields for the first data source.

Then carry out the mapping for the other worksheets.

3.3.5 Mapping additional worksheets

1. Drag the item number for the second data source to the "Item no." field using drag & drop.



Mapping the second item number


   - After mapping, the second data source is shown indented in the ***Data source*** view.
2. Now create the assignment for the additional fields for the second data source.
3. Drag the item number for the third data source to the "Item no." field using drag & drop.
   - After mapping, the third data source is shown indented in the ***Data source*** view.

To assign the attribute values, nodes need to be duplicated in the ***Repository*** view.

3.3.6 Assigning attribute values


The attribute values are listed in the third worksheet by columns for each item. For this assignment, you need to duplicate nodes.

1. Drag the first attribute value to the "Attribute value" field.
2. Enter the name of the attribute in the "Attribute name" field.



Assigning attribute values

3. Select the "Attributes" node in the ***Repository*** view.
4. Select **Duplicate node** in the pop-up menu.
5. Drag the second attribute value to the "Attribute value" field for the duplicated node.
6. Enter the name of the attribute in the "Attribute name" field.
7. Repeat this procedure for the other attribute values.




Duplicate node

[Start importing the file.](#)

3.3.7 Performing an import

1. Click on to run a test import to check the mapping created.




Import test run

➪ The results of the test import are displayed in the ***Log*** view. If the log contains any errors, resolve these before the import.

2. Click on to start the import.

➪ The dialog box for scheduling the import opens.



Scheduling the import

3. You can start the import immediately or specify a date and a time for the import. You can also specify:
   - The catalog into which catalog the data is to be imported.
   - Whether existing group assignments are to be supplemented or overwritten.
   - Which import mode is to be used.
   - Which error mode is to be used.
   - You have the option of performing a test import before the actual import.
4. Click on **OK** to start or schedule the import.

You can monitor the progress of the import in the ***Process overview*** perspective.

Note: If you start the test import directly using the pop-up menu, the settings from the last import are automatically adopted. For an initial test import, the default settings are used.

3.4 Importing structured data

If you want to import structured data, e.g. a catalog in BMEcat format, the process does not differ significantly from importing tabular data, except that only an XML data source is possible. The example below is just one possibility, as BMEcat catalogs can differ greatly due to the large number of optional details available.

Note: The example assumes that you are familiar with the general structure of the BMEcat format, i.e. which elements can occur where.

1. Create a new catalog in the ***Supplier catalogs*** perspective.
2. In the ***Context selection*** view, select **Import** in the catalog pop-up menu.

➪ The ***Import*** perspective opens.

3.Click on 🗋 to start a new import[48].

➪ The file is loaded in the ***Data source*** view.

4.Now create the assignments for the file:


- Item data[66]
- Prices[67]
- Multimedia attachments[67]
- Structure assignments and attributes[68]
- Material group system[69]

5.Carry out the import.[64]

3.4.1 Item data

The SUPPLIER_AID is used as a unique code in a BMEcat file. The assignment is made in the ***Repository*** view below the “Header data” node.


1.Use drag & drop to move the SUPPLIER_AID entry from the ***Data source*** view to the "Item no." field in the ***Repository*** view.



Assigning SUPPLIER_AID

2.Use drag & drop to move the DESCRIPTION_SHORT entry from the ***Data source*** view to the "Short description" field in the ***Repository*** view.

➪ In the ***Repository*** view, the value "English" is automatically displayed in the "Language" field. You can change this setting at any time using the drop-down list in the "Assignment" column.




Selecting the language

3.Create the assignments for the other fields in the ARTICLE_DETAILS area.

3.4.2 Prices

An item can have several prices, e.g. valid in different regions or for a different period. For assignment, use the "Prices" node in the ***Repository view.***

1. Use drag & drop to move the PRICE_AMOUNT entry from the ***Data source*** view to the "Price" field in the ***Repository*** view, below the “Price band” node. Enter the details under the "Purchase price" or "Selling price" node, depending on the specified price type.
   - Other details such as price type, currency, etc. are automatically added using default values in the ***Repository*** view. You can either change these using drop-down lists in the "Assignment" column or overwrite them with another assignment.
   - If you have items with multiple prices, the "Price" field in the ***Repository*** view is highlighted in red after this initial assignment to indicate that duplicate values are present. You can restore clarity by making further assignments.
2. Use drag & drop to move the PRICE_CURRENCY entry from the ***Data source*** view to the "Currency" field in the ***Repository*** view.
3. Create the assignments for the other fields in the ARTICLE_PRICE_DETAILS area.




Prices valid for different regions

3.4.3 Multimedia attachments

Under the "Multimedia attachments" node in the ***Repository*** view, you specify the assignments of multimedia attachments to items. The multimedia data itself is imported in another way.

Note: Make sure that the file path is complete. The complete path for all document categories must be included along with the file name, e.g. "hlr-system/images/small//55922.jpg".

1. Use drag & drop to move the MIME_SOURCE entry from the ***Data source*** view to the "Identifier" field in the ***Repository*** view, below the "Media Asset documents" node.
   - Other details such as type, quality, etc. are automatically added using default values in the ***Repository*** view. You can either change these using drop-down lists in the "Assignment" column or overwrite them with another assignment.
   - If you have items with multiple multimedia attachments, the "Identifier" field in the ***Repository*** view is highlighted in red after this initial assignment to indicate that duplicate values are present. You can restore clarity by making further assignments.
2. Use drag & drop to move the MIME_TYPE entry from the ***Data source*** view to the "Quality" field in the ***Repository*** view, below the "Media Asset documents" node.
3. Use drag & drop to move the MIME_PURPOSE entry from the ***Data source*** view to the "Type" field in the ***Repository*** view.
4. Create the assignments for the other fields in the MIME_INFO area.




Assigning multimedia attachments

Note: Note that a file attachment is identified by the combination of quality, language, and type, in other words, there can only be one assigned file for each combination of these three values. If there is already a file attachment with these properties, it may be overwritten with the new data.

3.4.4 Structure assignments and attributes

Under "Classification and properties" in the ***Repository*** view, you can create assignments for item attributes and the structure assignment to a structure system. Assignment to a catalog structure system is carried out separately.

1. Use drag & drop to move the REFERENCE_FEATURE_GROUP_ID entry from the ***Data source*** view to the "Structure assignments" field in the ***Repository*** view, below the "Structure assignments" node.
   - The default value is automatically entered in the "Structure system" field in the ***Repository*** view.
2. Use the drop-down list in the "Assignment" column to select the corresponding structure system.
3. For item attributes, drag the FNAME and FVALUE attributes from the ***Data source*** view to the "Attribute name" field below the "Attributes" node and the "Attribute value" field below the "Attributes > Attribute values" node respectively in the ***Repository*** view.



Assigning attributes

If you have features with multiple values, e.g. an efficiency of 5 to 8 %, the "Efficiency" attribute has two values. In order to import both values, you must use the **select** import function.

1. Drag the FNAME entry from the ***Data source*** view to the "Attribute name" field in the ***Repository*** view.

2.Select the "Attribute value" entry in the ***Repository*** view.

3.In the ***Function*** view, use CTRL and Space to select the **select function.**

4.Enter [FVALUE] in the function instead of the "value" placeholder.

5.Enter the value 1 in the function instead of the "position" placeholder.

6.Click on .

7.Select the "Attribute value (max)" entry in the ***Repository*** view.


8.In the ***Function*** view, use CTRL and Space to select the **select function.**

9.Enter [FVALUE] in the function instead of the "value" placeholder.

10.Enter the value 2 in the function instead of the "position" placeholder.

11.Click on .

⇨ When importing, the first value of FVALUE is imported to the "Attribute value" field and the second value to the "Attribute value (max)" field.



Using the "select" function

3.4.5 Material group system

Material group structures for the catalog are a special feature when importing BMEcat catalogs. The catalog itself contains a structure system by which the items are classified. Assignments are made in the following way:

1.Use drag & drop to move the GROUP_SYSTEM_ID entry from the ***Data source*** view to the “Identifier” field below the “Catalog group system” node in the ***Repository*** view.

2.Carry out the subsequent assignments under the "Structure group" node:

- Assign GROUP_ID to the "Structure group identifier" field.
- Assign PARENT_ID to the "Parent identifier" field.

Structure group		
Multimedia attachments		
Fields of structure groups		
Structure group identifier	GROUP_ID	1
Parent identifier	PARENT_ID	0
Sequence		
Language-specific data		
Language	"English"	English
Name	GROUP_NAME	Hydraulic tools
Description	GROUP_DESCRIPTION	Hydraulic tools
Comment		
Other remarks		
Keywords		
Additional identifiers		
Structure assignments		
Features of structure groups		
Catalog group system		
Identifier	"ErsteinClass"	ErsteinClass
Language-specific data		
Language		English
Name	"ErsteinClass"	ErsteinClass
Full name		
Description		

Assigning material groups

3. Duplicate the “Item” node in the ***Repository*** view by selecting **Duplicate node** in the pop-up menu.

   ➪ The node is displayed as "Item (2)" below the previous "Item" node, which is now called "Item (1)".

4. Use drag & drop to move the ART_ID entry from the ***Data source*** view to the "Item no." field in the ***Repository*** view, below the "Item (2)" node.
5. Use drag & drop to move the CATALOG_GROUP_ID from the ***Data source*** view to the “Catalog structure assignments” field below the “Item (2) . Classification and properties > Catalog group assignments” node in the ***Repository*** view.
6. Select the "Catalog structure system" field in the ***Repository view.***
7. In the ***Function*** view, specify the name of the catalog structure system in quotation marks, as listed under GROUP_SYSTEM_ID.

Item (2)		
Header data		
Item no.	ART_ID	11001005
GTIN		
Alternative item no.		
Manufacturer item number		
Manufacturer		
Supplier ERP group		
Status		
Last status change		
Language-specific data		
Texts		
Prices		
Surcharges		
References		
Multimedia attachments		
Classification and properties		
Structure assignments		
Catalog group assignments		
Catalog structure system	"ErsteinClass"	ErsteinClass
Catalog structure assignments	CATALOG_GROUP_ID	0101010101
Attributes		

Assigning a catalog structure system

3.5 Automatic import

Basic information

Product 360 Desktop provides a standard interface for automated data transfer from materials management, ERP, and other systems: the **hotfolder.** This allows integration into existing IT environments.


Recurring imports of large data volumes can be automated using a configurable storage folder. This folder is monitored for incoming data, the data found is checked for validity, and a new import process or a data update is then carried out.

These processes can import data into transfer catalogs or directly into the master catalog.

The file name scheme is used to identify the incoming file and link it with an appropriately prepared import mapping.

Administration of these links, the file name scheme and other settings, e.g., the catalog to import to, is carried out in the ***Hotfolder*** perspective in the Product 360 Desktop client and is protected by corresponding permissions.

Import mappings used for automated imports are created in the conventional way in Mapping Studio. They are stored on the server and provided according to their assigned purpose.




Possible purposes of

In the ***Process overview*** perspective, you can find information about the progress of the hotfolder processing and the import operation. A log shows you detailed information, any error messages, or warnings.

3.5.1 Import details

The **Hotfolder** perspective is used to manage the automatic import operations.



Hotfolder perspective

The **Hotfolder** perspective provides the following views:

1	***Hotfolder configurations***. Use Hotfolder configurations to manage all the automatic import operations.
2	***Hotfolder groups***. Use Hotfolder groups to view all the group definitions.

Within the hotfolder perspective, you can perform the following tasks:

1. **Create** new configurations and groups. Click on the ✚ icon in the relevant view to open the corresponding dialog box.
2. **Edit** existing configurations and groups. Double click the corresponding data record to open the associated dialog box.

3. **Search** for existing configuration groups, filter or use the familiar grouping functionality.
4. **Delete** existing configurations and groups.


For editing options, you can use both the **Edit** menu and the pop-up menu.

Note: Ensure that you do not modify the hotfolder configurations and hotfolder groups if the associated files are available in the hotfolder.

3.5.1.1 Hotfolder configuration

Several hot folder entries can be combined into groups. This enables various import scenarios to be performed in combination without files blocking one another. For executing a group referenced import, the sequence of the data configuration is an important criterion and should be checked before execution.

Double-click the relevant data record in the **Hotfolder configuration** view to open the **Hotfolder configuration** dialog box.



Hotfolder Configuration


Field	Description
Identifier	Enter a unique name for the configuration.
File pattern	Specify the file pattern. All the files that match the specified file pattern are considered for automatic import. You can use regular expressions or the following placeholders in the file pattern:

Field	Description
	• Asterisk (*). Searches for files with multiple characters in the position of the asterisk. For example, the file pattern *_1.csv considers the files such as, product_1.csv and item_1.csv. • Question mark (?). Searches for files with one character in the position of the question mark. For example, the file pattern item_?.csv considers the files such as, item_1.csv and item_2.csv. • Hash (#). Searches for files with one character in the position of the number sign. Use hash to group files that you want to process together. If there are multiple file patterns with a hash sign in a hotfolder, the files with the same values for the hash sign are processed together. For example, if the hotfolder contains files with file patterns item_#.csv and product_#.csv, the following files are processed together: • item_1.csv and product_1.csv • item_2.csv and product_2.csv • item_a.csv and product_a.csv You can process the grouped files together irrespective of the order in which they are placed in the hotfolder.
Import mapping	Specify the import mapping. Mappings are identified by their purpose. Click **Select** to display all the mappings with the purpose **Hotfolder**. Specifying a mapping is optional if the preparatory import steps have been defined.
hotfolder group	Select a hotfolder group from the list.
Catalog	Specify the catalog you want to import to.
Group assignment	Specify the group assignment. You can either retain or overwrite the existing assignments.
Structure	Select the relevant structure system for importing structure groups.
Lookup	Select a relevant lookup.
Import mode	Select the import mode. The following options are available: • Import or update all objects • Import new objects only • Update existing objects only
Error mode	Select the error mode. The following options are available: • Tolerant (object is imported as far as possible) • Restrictive (object is not imported in case of error)
Test run	Schedule an import test run. You have an option to perform the test run before import and cancel the import in case of an error.
Status	Clear the check box to temporarily deactivate the hotfolder configuration. By default, the check box is enabled.

Expert tip: A mapping does not have to be assigned to an entry in the hotfolder. To prepare files for the import, one or more preparatory import steps can be defined and carried out before the actual import process. The procedure is comparable with post-processing of exports. The steps are processed sequentially in the specified order. Preparatory import steps could include splitting files or unpacking ZIP files.

3.5.1.2 Hotfolder groups

Double-clicking on the relevant data record in the ***Hotfolder groups*** view opens the dialog box below.



Edit hotfolder group

Find our further details about this view:

Field	Description
Identifier	Enter a unique name for the group.
Description	You can insert a detailed description here.
Type	1.Sequential processing, no wait for files (multiple mappings, multiple files): Imports of a group are never carried out in parallel, i.e., sequentially one after the other regardless of any order. 2.Multi-file import, wait for all files (one mapping, multiple files): A multi file mapping waits until all required source files have been received before the import can be started **IMPORTANT:** The order of the files configured in the mapping is crucial for this group type. Make sure that the relevant settings have been made before the import. You can access the required information using the mapping selection dialog box for the relevant hotfolder configuration. Example: The mapping expects two files – prices and texts. To achieve this, the Price file must be created at the first position in the hotfolder configuration and the file containing the texts in the second position. 3.Sequential processing, wait for files (multiple mappings, multiple files): The group waits until all associated files have been received and then processes them in the specified order. 4.Multiple data extraction (multiple mappings, one file): An individual source file is imported multiple times in a specified order using several independent import mappings
File sorter	If the hotfolder contains identical files based on the file sample, they are sorted by the last change date by default. Alternative sorting mechanisms are possible.

Field	Description
Group entries	If hotfolder entries have already been assigned to the group, they are displayed in this table.
Time limit	If multiple files are provided for an import process, you can enter a maximum time period for the group's waiting time for remaining files here. To do this, you must deselect the **No time limit** option.

3.5.2 Technical information

The folder structures required for automatic import operations are created in the server during installation. By default, the installer creates the following folders:


1. **Hotfolder** folder. Contains files to be automatically imported.
2. **Processing** folder. Contains files that are detected in the Hotfolder for automatic import. The files include a timestamp indicating the time when they were detected by the hotfolder.
3. **Archive** folder. Contains files with completed import operation.
4. **Error handling** folder. Contains files that failed to import.

The system browses the Hotfolder for new files corresponding to the set file sample, assigns the relevant configuration mapping or group, and performs the import.

3.6 Importing user-defined structure systems

You can load user-defined structure systems in Product 360 Desktop by importing and edit them if required in the Structure editor. This option is particularly recommended if you have obtained the information from another system, such as a pre-processing system or a customer or supplier system.

1. First create a new, empty structure.
2. Select **Import** in the pop-up menu in the blank ***Primary structure tree*** view.
   - The ***Import*** perspective opens.
3. Create a new import project.
4. Integrate the data file into the ***Data source*** view.
5. Create an assignment as described under Import – the essential assignments are as follows:
   - Structure group identifier: Unique identifier of the group within the material group system; this is language independent.
   - Parent identifier: Identifier of the higher level group; if the group is located at the top level, this value must be "0".
   - Name: Name of the material group, which is also displayed in the ***Primary structure tree*** view; this can be entered in multiple languages.



Importing a multi-language structure system

You can also specify a description, the sequence within a level, and a hierarchical number for each material group.


Tip: If the server fails during a structure import, for example, due to a power failure, this may result in structure groups that do not have parent nodes and therefore cannot be displayed. To make these structure groups visible, in the ***Primary structure tree*** view select **Retrieve hidden groups in structure** from the pop-up menu.

After importing the user-defined structure system, you can use it to classify items and products.

3.7 Adding multimedia data

Along with a new catalog file, you import multimedia links, but not the multimedia files themselves. To add files to the system:

1. Open the ***Multimedia attachments perspective.***
2. Open the directory containing the files in your file browser.
3. Use drag & drop to move the required file(s) from your file browser to the desired category in the ***Document categories*** view.
   If you want to assign the new files to a new document category, you can drag the entire directory into the ***Document categories*** view and thus create a new document category with the same name as the directory.
   - Copies of the selected data are created in the Product 360 Desktop file system.
4. If a file of the same name already exists, you need to decide whether it will be replaced with the new file.



Overwriting a file

Note: If you have access to the "CatalogImages" directory on the Product 360 Desktop server, the multimedia files can be copied directly to subdirectories in "CatalogImages".

3.8 Merge

Note: Die Informatica Corporation bemüht sich, innerhalb von Product 360 Desktops vornehmlich deutsche Begriffe zu verwenden. Für den Merge ist es jedoch nicht gelungen, einen solchen zu finden. Deutsche Übersetzungen wie "Mischen", "Einmischen", "Vermischen", "Vermengen" oder dergleichen drücken nicht ausreichend aus, welcher Prozess sich hinter "Merge" verbirgt.


The merge process enables particular values from a large number of items to be transferred to the master catalog. The merge process is not merely a "Copy and Paste" process but enables you to make different settings for individual areas as required. The settings for the individual areas and data determine how these are transferred to the master catalog. Detailed distinctions can be made as to what the results should look like if a value is read. The settings are either made globally in the preferences 255 or for specific catalogs.

Tip: To familiarize yourself with the details of the merge settings, you can simulate the effects of individual settings in the ***Merge preview*** 79 view.

In every case, the number of items that are created or – if the items already exist in the master catalog – overwritten in the master catalog is equal to the number of items in the supplier catalog (or in an assortment in the supplier catalog). An item in the supplier catalog is identified as "identical" to an item in the master catalog if an "internal system reference" exists between the two objects. This internal system reference can only be created by a merge.

Information: A merge process can never be used to transfer item numbers from the supplier catalog to the master catalog.

1. Select the relevant supplier catalog in the ***Context selection*** 90 view. The merge process is executed in the context of the supplier catalog to be merged.
2. Select **Merge** in the pop-up menu.
   - The ***Merge*** perspective opens.



Calling up the "merge"

Tip: If you have inadvertently selected an incorrect catalog, you can change the merge context at any time by selecting the correct catalog in the ***Context selection*** view and then calling up **Set as default catalog** in from the pop-up menu.

The ***Merge*** perspective consists of three windows, which contain the following views:

- Top left ***Context selection***, ***Primary structure tree*** 202 and ***Item search*** 93
- Top right ***Item #1*** 99
- Bottom left ***Merge preview***

You can find an overview of all merge operations in the ***Process overview*** 82 perspective.

3.8.1 Merge preview

If the ***Merge preview*** view is still empty, select a particular supplier catalog in the ***Context selection*** view and display the items in the ***Items #1*** view. The ***Merge preview*** shows the results of a merge for a selected item.

The first column in the ***Merge preview*** view lists the available data types in a tree structure. The larger, right section of the view consists of three columns: "Current master catalog (basis)" "<Catalog name>", and "Simulated master catalog". The first of these three columns displays the values that Product 360 Desktop has found for this item in the master catalog, while the center column shows the values of the item currently selected in the ***Item #1*** view. Finally, the right column is created from the two preceding columns, depending on your merge settings. 80

Note: As the column name states, this is a simulation. You can experiment with different merge settings to familiarize yourself with them.

If you expand an area in the "Data type" column of the ***Merge preview*** view, differences between the supplier catalog and the master catalog are indicated by a red background. Moving the mouse over an entry displays a tooltip that shows the differences for the selected entry. You can enlarge this tooltip using the F2 key.

The following icons are available in the view:

- : Opens all nodes in the "Data type" column.
- : Closes all nodes in the "Data type" column.

- : You can specify the Merge settings here.
- : Opens a dialog box that you can use to schedule the merge process.
- : Here, you can select which nodes you want to display in the "Data type" column.
- : Reduces the display to those data records that have different content.

Tip: If you do not want to merge certain items, use an assortment including the specific items you actually want to transfer to your master catalog.

Multimedia attachments

If multimedia attachments are present, they are displayed as preview images in the merge preview. Moving the mouse over the preview image displays a tooltip that shows the differences for the selected entry. You can enlarge this tooltip with the mouse after pressing the F2 key.

3.8.2 Specifying merge settings


The merge settings allow you to specify the detailed options for the data to be transferred to the master catalog. In this context, it is important to know:

- What data is already contained in the master catalog?
- What new data is available?
- What effect will the transfer of this new data have on the existing data and under what circumstances should this occur?

Note: Bear in mind that due to your internal business processes, the quality of the information in your master catalog may be significantly better in some areas than the information you receive from your supplier.

You can define global merge settings in the preferences under **Management > Settings > Merge preview** or make them for specific catalogs by going to the ***Merge preview*** and calling up **Merge settings** from the Views menu. There are four different merge modes:

- Add: New content is added but existing content is not changed.
- Replace: All content in the master catalog is overwritten; content in the master catalog is also deleted if it is not included in the supplier catalog.
- Ignore: Content is not transferred.
- Overwrite: New content is added; existing content in the master catalog is overwritten if it is included in the supplier catalog, otherwise it remains unchanged.



Merge settings


Each of these modes can be set for a particular area, or for each field within that area. The various areas appear in bold in the "Data type" column. Clicking on the plus sign at the start of the row displays the individual fields within this area; these fields can then be set separately.

To set the mode, click in the "Settings" column to open the drop-down list and then set the required value. The effect of the settings is simulated in the ***Merge preview*** view using the currently selected item.

3.8.3 Scheduling a merge

To perform a merge based on defined options, you must first "schedule" it.

1. In the Views menu in the ***Merge preview*** view, select **Schedule merge...**.
   - The dialog box for scheduling a merge opens.



Scheduling a merge

2. Specify whether the entire catalog is to be merged, or just an assortment from the catalog.
3. Specify whether the merge is to be performed "As soon as possible" or at a particular time by specifying a date and time.
4. Click on **OK**.

- The merge is started or scheduled. You can monitor the merge process in the ***Process overview*** perspective.

3.8.4 Merge for characteristic values

Note: Characteristics are managed in Product 360 Web. You can find definitions of characteristics and characteristic values in the Product 360 Web user documentation.

Unlike other data types, in the merge settings for characteristic values only two merge modes are supported:

- Ignore
- Overwrite

In addition, you have the option of limiting the amount of characteristic values to be merged by only selecting certain basic characteristics. Only the characteristic values for these basic characteristics - including all subordinate characteristics (complete hierarchy) will then be merged.

3.9 Process overview

The ***Process overview*** perspective shows you all current and completed Product 360 Desktop processes. The ***Overview*** view on the left-hand side shows the process categories in a tree-like structure:

- Data transfer: Hotfolder data processing, import operations, merge operations
- Data quality: Data quality check (one-off), data quality check (repeated)
- Data maintenance: Quality check, Find and Replace, setting, versioning
- Publications: Export operations (one-off), export operations (repeated), test export operations
- System processes: Update item-structure group assignment, Update EGD structure group assignment, Update structure group features, Update image versions, Update modification date, Update tasks, Remove deleted objects, Remove obsolete query results, Remove obsolete processes, Remove obsolete workflows, Product item feature transfer, New derivative schema (when connected to Product 360 Media Manager), Check for escalated tasks, Preview image generation, Multimedia attachment assignment.

Note: The list of process categories may differ in your system, as they can be configured by your Product 360 Desktop consultant.

Old entries in system processes are automatically deleted at regular intervals, the duration of which can also be adjusted by your Product 360 Desktop consultant.

Here, you can select the category for which you want to view the processes in the ***Current and past processes*** view. In the ***Log*** view, you will see the log for a selected process, if one exists. Double-clicking on a line in the log opens a detailed view of the entry.

Tip: Since these processes mostly concern a considerable volume of data, the categories can be used to selectively access a particular data range from the pop-up menu. In the "Merge operations" process category, you can determine all of the items transferred to the master catalog in order to make them available for further editing (for example, as a task).

Clicking on the button lists only the processes you have scheduled yourself.

Note: The "Number" column in the ***Log*** view shows the number of affected objects for an entry. You can select **Show objects** from the pop-up menu for a particular row to display these in a new view.

Depending on the process selected, different options are available in the pop-up menu in the ***Current and past processes*** view.

Area	Option	Description
Import	Show in import perspective	Opens the associated import project in the Import perspective.
	Export import project as Zip file	Downloads the import project (data file and mapping file) to the directory you specify as a Zip archive.
	Show imported objects	Depending on the import, additional selection options are available in a submenu. For example, you can display items in the Item #1 view and structure groups in the Class list view.
	Performance analysis	Technical dialog box; Informatica Corporation consultants can use it to review improvement options for the import.
Export	Download export file(s)	Downloads the exported fields to a local directory. These include the data files and the multimedia archive (if one was generated). The files can be compressed.
	Repeat export	Opens the "Export export profile" dialog box. The selected export operation can be repeated with the parameters used.

3.10 Importing characteristic values

Note: The characteristic must first be defined.

Important for the import:

- The characteristic values must match the characteristics.

- You must define “root” as the higher-level characteristic ID for the basic characteristic.
- Existing characteristic values that are not included in the current import are deleted. This does not apply to basic characteristics not included.
- Only complete characteristic hierarchies can be imported. If there are incomplete hierarchies, the import is canceled for the entire item. This also applies in tolerant import mode.

The "Structure" column displays the data fields to which you can assign the data to be imported:

Structure	**Description**
Item no.	The item number
Data record identifier	The data record identifier of the characteristic value (“Data record ID”).
Parent data record identifier	The data record identifier of the higher-level characteristic value
Sequence	The sequence of the characteristic values below a parent data record.
Characteristic	The characteristic identifier
Language	The language for the imported value.
Value	The imported value

4 Data maintenance

The core of your stock of item data is what is known as the master catalog. As a minimum, the master catalog includes all items or products that are to be output, e.g. for an online store or print catalog. You use products maintain information about multiple items centrally. Differentiated branching is required for some catalog concepts in order to map an existing network of relationships. In this case, for example, variants of a product are required, which "precede" the items in the hierarchy.

Each item must be assigned the corresponding information depending on the output destination. Typical item data includes:

- Identifying information for the item, e.g. item number
- Ordering information
- Prices
- Image information
- Product features and product descriptions (which may be formatted differently for different target systems)
- Organization in a catalog structure
- References to other items

You also need data that is used for selecting and structuring the items in the catalogs to be output, and data that relates to the catalog header data itself. This relates not only to the maintenance of user-defined classification systems but also to the creation of assortments. At the same time, a customer and a supplier are required for each catalog to be created.

Data maintenance is of critical importance in Product 360 Desktop. There are several ways to accomplish most of the tasks that have to be completed. Which one you choose depends on the processes in your company. Below, you will find an overview of the available functions.

4.1 Spellchecking

As described earlier, a product information management system is a convenient way of managing all your product information centrally. To safeguard the benefits of such a system, this information must be handled consistently and saved correctly. If text is available in multiple languages, spellchecking becomes even more important because this data is usually published. But what does spellchecking mean?

Spellchecking can be regarded as the entirety of all writing conventions, expectations or standards within a language community. English spelling, in other words, orthography, comprises the words "ortho" and "graphy". These words stem from Greek meaning:

Ortho: "Correct" writing with regard to efforts not to make mistakes in order to follow the conventions.


Graphy: Correct "writing" with regard to the analysis and interpretation of the written language itself, in other words, with regard to the efforts to implement the system of written language.

Spellchecking is usually offered in two different modes:

- During input, also known as SCAYT (**S**pell **C**heck **A**s **Y**ou **T**ype) or
- by explicitly activating an icon specified for this purpose as a switch function.

An automatic spellchecker is integrated in nearly all modern text editors and is also referred to as a "*software-based method for correction of spelling or typing errors in electronic texts*". To do this, dictionaries are required for each language to be checked. You can find out in the next chapters how to manage the required settings, implement the required language support and ultimately how to use the spellchecker.

As a rule, you may only use the administrative functions if you have been assigned the necessary authorization by your administrator.



Dictionary action rights

To assign a user the rights to add a word to the dictionary from the dialog box or text field in Product 360 Desktop or Product 360 Web, the user only needs the 'Add words to the Dictionary' right and object rights for the dictionary in the required language.

It is also possible to assign users just the right to suggest words: In this case, words are added to the dictionary but are flagged as inactive. The words then become available once they have been activated by an authorized user.

Note: Product 360 Desktop enables you to install dictionaries that are freely available as the basis for spellchecking and to maintain your own words. Separate instructions describing how to install dictionaries are available and this can be carried out by your Product 360 Desktop consultant.

4.1.1 Maintaining dictionaries


There are two ways of adding dictionaries to Product 360 Desktop. One option is to store **existing dictionaries** in a special server directory.

The other option is to import dictionaries. These must be in UTF-8 format in order to also support special characters. The words must be arranged line by line and be separated by a line break.

Importing dictionaries

To import a dictionary, proceed as follows:


1. Open the ***Import*** perspective.
2. Click on 🗋 to open a new import project.
3. In the mapping dialog box that opens, select the "New mapping" option.
4. Add the required dictionary as the ***data source*** and confirm your settings.
5. The format settings dialog box shows you the layout of the fields. Accept these settings and close the dialog box by clicking on **OK**.
6. The dictionary is displayed in the ***Data source*** view in the perspective. Double-click on the dictionary entry to access the content.
7. Repeat this procedure in the ***Repository*** view with the "Word" structure. By dragging the entry to the "Word" value, you create a link, which is indicated by a blue check mark in front of it.
8. Now start the import by clicking on . Here, you can enter the dictionary you want to import into and whether the import is to be performed immediately or at a set time. You can monitor the progress of the import and view the log in the ***Process overview*** perspective. You can access the import results using the ***Dictionaries*** perspective.



Simple import of a dictionary

Maintaining your own word lists

When editing and spellchecking texts, you can also add words to these dictionaries. You can view and edit these words using the ***Dictionaries*** perspective.




Dictionaries perspective

Here, you can

- click on to show other fields that provide information about the creation or editing history.
- click on in the "Active" column to decide whether to add a word to the dictionary or exclude the word by clearing the check mark.

4.1.1.1 Managing spellchecking

Like all parameters, the spellchecker settings are also managed via the **User settings** menu.




User settings for spellchecking

You can activate or deactivate the spellchecker here by selecting or clearing the check mark. A list containing information about all the installed dictionaries is also displayed.

4.1.2 Using the spellchecker

To avoid interrupting the flow during editing, the spellchecker is implemented using a switch function. This means that you can click on to turn the spell checker on or off. **It is important to note that only read access is permitted when the spell checker is activated and that no other character string editing is possible.** This is only possible when the spellchecker has been explicitly ended.


Spellchecking is only carried out on language-specific fields. The check is based on the dictionary that matches the language assigned to a field. As fields are offered in different ways, the check is also executed in different ways.



A language assigned to a field

Spellchecking in single-line entries


All values in tables and dialog boxes are displayed on single lines. Spellchecking is activated here by default. You can deactivate this in the pop-up menu of the current field and edit the character strings in the usual way. You can also add individual terms to the dictionary.



Pop-up menu for field-related


Spellchecking in the text editor

To edit multi-line entries, you can click on to call up the text editor. This makes editing much more convenient. When the spellcheck is activated, the editor appears as shown in the following example:



Activated spellchecker in the text editor

All character strings displayed in red are not recognized by the dictionary or are misspelled. By clicking on a highlighted character string, you call up the pop-up menu. Using the menu you can add terms to the dictionary or select an alternative spelling from the suggestions available.



Pop-up menu of

You do not have to work your way through all highlighted character strings. You can return to editing mode at any time by clicking on .

Tip: The administrator can use the repository module to exclude fields from the spellchecker or explicitly include fields in the check. This procedure is described in a separate document.

4.2 Finding items or products

Extensive options are available to you for finding items, products or their variants in Product 360 Desktop. First, you must always select the "pool of data" in which you want to search. This may be a specific supplier catalog (items only) or your master catalog (items or products). To specify this, you can use the ***Context selection*** view.

In addition, you can use the item search or navigation in structure systems to find the required data.

4.2.1 Context selection

The ***Context selection*** view is a key view for finding your way around Product 360 Desktop. Actions, tasks and displays normally always relate to a particular context. All available context areas are shown in a tree view, and you can navigate through them and select the desired context. The main nodes are:

- Data transfer
  The data transfer area normally includes imported catalogs from your suppliers. (If the node is empty, you have not yet imported a catalog.) In the Data transfer area, you can manage the properties of the imported catalogs and check that they are complete. To import a new catalog, you must first create it.
- Master catalog
  The master catalog is "your" catalog, this is the "center point" of everything. This is where you maintain all the product information that is to be used later elsewhere.
- Export profiles
  You can use export profiles to export items from your master catalog and prepare them for a specific purpose. For example, you can create an assortment in English from your master catalog and export it. Further information can be found in the separate Product 360 Desktop export manual.

Selecting a particular entry in the ***Context selection*** view "focuses" Product 360 Desktop on a certain area, e.g. a supplier catalog. This "focusing" or "context setting" is achieved by displaying the pop-up menu for the desired entry. Here, you call up **Set as default catalog**. Other display elements now take this context as a basis for further actions. For example, if you want to search for an item, Product 360 Desktop searches in the set catalog.

Tip: You can see how the current focus is set at any time in the program title.

You can call up **Show items** or **Show products** from the pop-up menu for a catalog or your master catalog even if the corresponding context has a different focus. This function lists the available items or products in a table. In turn, the table provides a wide range of sorting and filtering options, which are often sufficient for finding the items or products you require.

Tip: Think of the ***Context selection*** and ***Item #1*** or ***Products #1*** views as a file explorer for your operating system – with the folders on the left and the files on the right.

Different functions are available in the pop-up menu depending on which context you have selected. On the one hand, these can be used to call up perspectives, e.g. the ***Explorer*** or ***Initial classification (items)*** perspective. They also provide you with access to functions that cannot be found in any other menu in the same form.


If you have selected a supplier catalog in the "Data transfer" area and then call up the pop-up menu, the following functions are available:

Function	Description
Show >	This opens a submenu in which you can define criteria to limit the data to be displayed, e.g. only display items that have not yet reached a particular maintenance status. This function retrieves the data directly from the database, i.e. it is not a filter applied to the current ***Items #1*** (or ***Products #1***) view, which may be restricted in some other way. You should view the list as a "current report", i.e. even when you edit an object, the list retains the same status until you call up the function again.
Explorer (items)...	Opens the ***Explorer (Items) perspective.***
Show items	Displays items from a supplier catalog or the master catalog in the ***Item #1*** view. Product 360 Desktop automatically opens the ***Item #1*** view if the perspective does not contain a view that "monitors" the ***Context selection*** view. Because **Show items** is highlighted in bold in the pop-up menu, you only need to double click on the corresponding catalog. **Show items** is the default function for double clicking on a catalog or the master catalog.
Edit items >	This submenu allows you to delete purchase or selling prices.
Set as default catalog	This function specifies a catalog you want to use as the context.
Delete	Deletes a supplier catalog. As the delete operation cannot be undone, a confirmation prompt appears before deleting. Answer the query with **Yes** if you definitely want to delete the catalog. **Note that the delete operation may take some time depending on the size of the catalog.**

Function	Description
	Use **View > Refresh** to regenerate the display in the ***Context selection*** view. Any catalogs that have been deleted by other users will then no longer appear.
Refresh	Causes Product 360 Desktop to redisplay the entries for the "Data transfer" node. This enables catalogs created by other users to be displayed. Catalogs that other users have deleted are not removed from the view until the **View > Refresh** function is called up. When you restart Product 360 Desktops, the view is always up to date.
Import	Opens the ***Import*** perspective.
Merge	Opens the ***Merge*** perspective.
Show material group structure	Displays the material group system in the ***Primary structure tree*** view, provided that the supplier catalog is assigned to a material group system.
Initial classification (items)...	Opens the ***Initial classification (Items)*** perspective.
Multiple classification (items)...	Opens the ***Multiple classification (Items)*** perspective.
Properties...	Opens the "Properties" dialog box. This dialog box displays general information about the catalog, its references, versions, and object rights.
Object rights...	Opens the dialog box for editing the object rights. Here, you can add users or user groups and assign them the following permissions: • Read: Objects can only be read. • Write: Objects can be read and edited. • Delete: Objects can be read, edited, and deleted. • Full access: Includes the read, write, and delete rights as well as permission to change object rights.

Not all of the functions listed above are available in the pop-up menu for the master catalog, as they can only be executed in the context of a supplier catalog. On the other hand, **Show products** is only available in the pop-up menu for the master catalog. It is used to display the products in the ***Products #1*** view.

Note: You can sort the display of supplier catalogs or export profiles in the tree. To do this, select **Sort > ...** in the pop-up menu for the "Data transfer" or "Export profiles" node.



Sort

4.2.2 Search

To search for items, products, or structure groups, use the ***Item search***, ***Product search***, or ***Structure group search*** view. The ***Item search*** is part of the ***Explorer (items)*** perspective, as is the ***Product search*** view.

Use **Perspectives > Open view** to call the ***Structure group search*** view. The procedure for searching is the same in all views.

Comparison operators

You can use the following comparison operators to find specific records.

- **equals**. Searches for the exact string.
- **starts with**. Searches for records that start with the specified string.
- **contains**. Searches for records that contain values specified in the string.
- **not equal to**. Searches for records that are not equal to the specified string.
- **wildcard search**. Supports the underscore (_) and percentage (%) wildcard characters, and searches for records that match the pattern of the search string.
- **negated wildcard search**. Supports the underscore (_) and percentage (%) wildcard characters, and searches for records that do not match the pattern of the search string.

If you use backslash (\) before the wildcard character, the wildcard character is considered as a regular character. For example, if you select the wildcard search operator and specify "battery_drill_" in the search string, you get battery_drill1, and other such matching entries.

Wildcard search

The wildcard search comparison operator returns results in the following pattern:

- Underscore (_). Returns results that contain any character in the position of the underscore. For example, if you specify "Article_234_", you get Article12345, Article612345, and other matching entries.
- Percentage (%). Returns results that match the pattern of the search string.

For example, if you specify "battery%drill", you get battery-powered drill, battery powered hammer drill, battery powered compact drill, and other matching entries.

Negated wildcard search

Use the negated wildcard search comparison operator to get the results that are reverse of the wildcard search operator.


The negated wildcard search comparison operator returns results in the following pattern:

- Underscore (_). Returns all other records except the ones that contain any character in the position of the underscore. For example, if you specify "Article_234_", you get all other records except Article12345, Article612345, and other matching entries.
- Percentage (%). Returns results that do not match the pattern of the search string.

For example, if you specify "battery%drill", you get all other records except battery-powered drill, battery powered hammer drill, battery powered compact drill, and other matching entries.

4.2.2.1 Finding records

Perform the following steps to find records:



Item search view


1. Click Field selection...

   The "Field selection" dialog box appears.
2. Select the field in which you wish to perform a search.
3. Click OK.
4. Select a comparison operator.
5. Enter the search term in the Comparison value field.
6. Click **Start search**.

   ➪ The ***Items #1*** or ***Class list*** view displays the search results.

If you specify more than one field as search criteria, the result set must meet both criteria. The criteria have an "AND" link. If you specify search criteria for text fields, it can be useful (when making your selection) to specify whether you want to perform a case-sensitive search. If the corresponding check mark is not set, you do not need to pay attention to the case when entering the search term.

You can save your search under a particular name and then call it up again at any time. You can edit saved searches, i.e. rename, delete and categorize them. You can perform these actions using the management dialog box.



Manage item search

Saving a search

1. In the views menu select
   ➪ The dialog box for managing search queries opens.
2. Enter a category and search name. A more detailed description makes it easier to find it again later.
3. Selecting Release/Object rights takes you to the dialog box that enables you to define the access rights for the search you have just created.
4. Click on **Save**.

The Views menu provides you with additional functions:

- The existing search settings are undone so that you can enter new search criteria.
- Opens the management dialog box for selecting saved searches. Here, you can search using categories, names, or descriptions, and by the person who created or modified the search.
- Saves the search under the existing name.

4.2.3 Navigation in structure systems

You can often find the items you are looking for more easily using targeted navigation – provided

your items have been classified or assigned to a product group structure. Using the corresponding view, you can quickly navigate to the item you are looking for in the structure system and then display it in the ***Item #1*** view.

First, select the catalog or master catalog you want to use as the context. Within the set context, you have the following options for finding the data you want:

- Select the relevant structure group in the ***Primary structure tree*** view.
- To find the structure group, you can use the search function within the view, which you activate using in the menu.
- Clicking on displays only those structure groups to which items are assigned.


To simultaneously edit the items from multiple structure groups in a common, higher level structure group:

1. Select the higher level structure group.
2. Select **Show all items below this group** in the pop-up menu.
   - The ***Item #1*** view shows all items in the subordinate structure groups.

Note


In the latest version, you can display the name of the structure group in addition to the identifier in table views of products and items.

1. Click on or select **Field selection** in the Views menu.
   - The "Field selection" dialog box opens.
2. Select the ***Group name*** option in the list on the left in the ***Classification and properties*** category.
3. Click on **Add ->**. (The button is inactive if no entry is selected.)
   - The entry now appears in the list on the right. This list shows, from top to bottom, the columns in the table, in the order they are displayed from left to right.
4. Specify the appropriate structure system for this entry.



Structure system selection

5. The structure group name display is language independent, i.e. the operating system language setting is ignored. The setting you specify here has priority.



Language selection

6. You can now determine the order of the fields by clicking on  and  to position the entry either further to the left or to the right in the table.

4.3 Editing items

Product information is normally transferred to your master catalog by importing 43 electronic supplier catalogs and then merging 78. If the items are not available in electronic form or if only a few items need to be created, you can also create new items manually. 99


The quality and completeness of the additional item data, such as descriptions, images, classifications and features, can vary widely. In addition, depending on the intended output form, you will probably have different requirements for the data in your master catalog. Whether you maintain the item data in the individual supplier catalogs or directly in the master catalog depends on the workflows you have defined for data maintenance. In theory, you can view, check and change or make additions to all the item data present in both the supplier catalogs and the master catalog.

Tip: Check and correct the new data each time you transfer data to a supplier catalog. If you immediately enhance the data with additional information in the master catalog, you will always have an up-to-date master catalog with no errors, which you can use immediately for forwarding item data for use in electronic or print catalogs.

First, compile the items to be maintained, e.g. using the item search 93 or by navigation in structure systems 99. Then determine the information to be displayed in the ***Item #1*** 99 view, or use special item views to selectively view or modify specific item data.

4.3.1 General item data

The starting point for selecting, displaying and modifying data is a perspective such as ***Explorer (items)***, which contains the ***Context selection***, ***Primary structure tree***, ***Item search***, ***Tasks***, and ***Item #1*** views. These views are available in many data maintenance perspectives.



Explorer (items)

To effectively use the functions of Product 360 Desktop, you should first configure your workstation for the corresponding tasks and working methods. You only need to make these settings once, as they will be saved as personal settings on your local computer. You can change these defaults at any time.

- Displayed structures

  Specify which structure system is to be displayed in the primary and secondary structure tree.

  If you require a second classification system for data maintenance, you can open the secondary structure tree under **Perspectives > Open view**.

- Item

  In the ***Item #1*** view, specify the columns to be displayed and their sequence. If you require different settings, you can save them as layouts and retrieve them later.

- Other views

  If you do not want to edit item data in the ***Item #1*** view and want to use the ***Item details (form)*** view instead, open it using **Perspectives > Open view**.

Note: You can only configure one version of the ***Item details (form)*** view. It is not possible to save different layouts here, as you can for the ***Item #1 view.***

- Arranging the individual views

  Set the arrangement and size of the individual views to meet your requirements.

4.3.2 Items

The ***Item #1*** view is one of the most important tables in Product 360 Desktop. In this table, you create new items or edit existing items.

If items are shown in the ***Item #1*** view, you can select them by clicking on the row header and then either execute functions that are provided in the pop-up menu or execute a drag & drop assignment function with the selected item(s), as you do during classification.

Function	Meaning
Copy	Copies the current values for the selected item(s) to the operating system clipboard. When you paste the contents of the clipboard into another program – for example, a text editor – the columns from the table are displayed, separated by tab stops.
Paste	Not possible within the view.
Delete	Deletes the selected item.
Select all	Selects all items in the table.
Refresh	Refreshes the table. The contents of a table can be changed by your own editing or through editing by other users, which may mean that the items displayed are no longer correct. Examples include: • You or another user has changed or deleted items. • The description of the list, e.g. the search query or the assortment definition, has changed.
Clone	Copies the selected item. You cannot use this function if more than one item is selected.
Find/Replace/Set…	Calls up the dialog box for finding and replacing entries in the current table. The dialog box contains the functions you will be familiar with from other standard products.
Tasks	Defines a new task or task group, either with the selected item(s) or using a dynamic query.
Compare	This function enables you to compare two different items or the different versions of an item. The ***Comparison view*** shows a comparison, with differences highlighted in red.
Versioning	The submenu allows you to add or remove the selected item to/from a version, but also to add all items to a version.
Arrangement by assortment	The submenu can be used to make the following selection for creating an assortment:

Function	Meaning
	• **Note selection in:** Creates an explicit link between the selected item(s) and an assortment. In the submenu, you can select the assortment to which the item(s) are to be added or create a new assortment. • **Note query in:** Creates an explicit link between the selected item (s) and a dynamic query. In the submenu, you can select the assortment to which the item(s) are to be added or create a new assortment. • **Remove selection from:** Removes the selected item(s) from an existing assignment to an assortment. In the submenu, you can select the assortment from which you want to remove the item(s). The item is deleted from the assortment, i.e. it can be added again using a new query or selection. • **Explicitly exclude selection from:** Explicitly excludes the selected item(s) from an assortment. This kind of explicit exclusion always takes precedence, i.e. if another rule specifies that the selected item(s) is/are part of the assortment, the explicit exclusion cancels this membership. • **Explicitly exclude query from:** Explicitly excludes the selected item(s) from a dynamic query (assortment). • **Manage assortments:** Calls up the dialog box for managing assortments.
Create product	This function enables you to create a new product based on the selected item. The item is automatically assigned to the product. This function is only available for an item that is not yet assigned to a product.
Show higher-level product	Opens the ***Products #1*** view and displays the product to which the selected item has been assigned.
Generate preview	Generates an HTML display in the default browser, as a detail or table view depending on the selected template.
Delete all structure assignments of the selected items to	If the selected item(s) is/are classified, calling up this function removes the assignment. Select the relevant structure system from the submenu that opens up.
Show list of assigned structure groups for	Displays the structure group for the selected item in the ***Class list*** view.

Function	Meaning
Show assigned structure groups in structure tree for	Displays the structure group to which the selected item is assigned in the ***Primary structure tree*** view. The submenu allows you to select the corresponding structure system.
Properties...	Opens the "Properties" dialog box. This dialog box displays general information about the item, its references, versions, and object rights.
Object rights...	Calls up the dialog box for editing object rights. Here, you can add users or user groups and assign them the following permissions: • Read: Objects can only be read. • Write: Objects can be read and edited. • Delete: Objects can be read, edited, and deleted. • Full access: Includes the read, write, and delete rights as well as permission to change object rights.

4.3.2.1 Creating items

An item that you create manually is no different to an item that you import. You can maintain or check its data and add it to an assortment. You can create items directly in the master catalog or in a supplier catalog. We recommend creating new items in a supplier catalog and then using the merge process to transfer the items to the master catalog. This enables these items to go through the same process that you have specified for imported item data.

Note: It is possible that your company operates as a supplier and maintains its own supplier catalog in Product 360 Desktop, in which items can be created.

If you want to create a supplier item, which you can later update using an import, you should create this in the relevant supplier catalog and not in the master catalog. In this way, Product 360 Desktop automatically creates a relationship between the supplier item and the master catalog item. Of course, this relationship can also be created afterwards but may require laborious and complex settings (supplier relationships).

Tip: Make sure that you have not activated a table filter. In that case, a new entry would be created but it would not be visible since it would be filtered out by the filter definition.

1. Double-click on the relevant catalog in the ***Context selection*** ***view.***
   - The ***Item #1*** view displays the items in the catalog.
2. Click on ✚ in the ***Item #1 view.***
   - This creates a new row in the table with a new, unique item number.

Note: You cannot create a new item without assigning it a unique item number.

3. Enter all of the required data directly in the new row.

4.Click on to save the new data record.

Tip: You can also press CTRL and S on your keyboard to save the new data record. The new data record is also saved if you create another new data record or switch to editing mode in another data record.

You can also use the ***Item details (form)*** view to maintain item data.

4.3.2.2 Setting object rights

You can use object rights to restrict or block access to specific items for individual users or user groups.

1.Select the item(s).

2.Select **Object rights...** in the pop-up menu.

- The "Object rights" dialog box opens. If you do not have any system presets all settings are blank.

3.Define your settings as described under Managing object rights.

4.3.2.3 Clone items

You can clone an item if you need to create several similar items. When you clone an item, it is copied and added to the table as a new data record.

Note: You require the corresponding action right to clone items.

1.Select the item you want to clone in the ***Item #1*** view.

2.Select **Clone** in the pop-up menu.

- A new data record with the copied item data is added to the table.

3.Edit the new item.

4.Click on to save the new data record.

4.3.2.4 Deleting items

If you have created an item incorrectly or if you want to remove an item from your master catalog or supplier catalog, you can delete it. If you only want to remove an item from an electronic catalog or print publication, change the assortment accordingly.

To delete one or more items:

1.Select the relevant item(s) in the ***Item #1 view.***

2.Press DELETE or select **Delete** from the pop-up menu.

3.Confirm the confirmation prompt for deleting the item by selecting **Yes**.

- The item is deleted.

Note: Note that an item that is deleted from the master catalog is recreated there by a merge process if it occurs in the merge assortment. In the master catalog, however, a new item number would be generated automatically for this item.

4.3.3 Item details (form)

The ***Item details (form)*** view can be used to display data for an individual item. By default, the view shows the following fields:

- Item no.
- GTIN
- Manufacturer item number
- Manufacturer
- Short description (German)

The form display of information for an item is ideally suited for using custom item displays for particular purposes. For example, this view allows you to compose a form consisting of the two fields "Short description (English)" and "Short description (French)", which you can use to translate the short descriptions of the item.

Open the "Field selection" dialog box as in the table display and configure the form as required. You can use the Views menu to set whether the fields shown are displayed with one or two columns.

Note: You cannot directly edit the long description in this view. Click on **Edit...** to open the Rich Text Editor.

4.3.4 Maintaining item data

As a rule, you use only a small selection of the item data that is actually available for data maintenance. Therefore, you should configure the item view(s) prior to actually maintaining the data. Select the desired items and display them in the required view.

You can change the existing item data directly in the ***Item #1*** (or ***Item details***) view.

1. To do this, click in the relevant field.
2. Enter the desired data.
3. If only certain specific values are allowed in a data field, you will see a drop-down list from which you can select a value. To open the drop-down list either use the arrow to the right of the field or press CTRL and the space bar.

Tip: If you want to make changes or additions to a large number of items, you can also perform an import, provided that the new item data is available in electronic format.

However, if you want to make the same change for all items, you can also use the "Find and Replace" dialog box.

Checking item descriptions

A typical application would be checking whether both the German and English short designations are maintained for all items. You may also want to enter the translation yourself immediately. You can quickly edit the texts by showing the two corresponding columns adjacent to one another in addition to the item number in the ***Item #1*** view. The ***Item details (form)*** and ***Text processing (items)*** views are better suited for long texts.

Checking item data

Use the various item search options to check the item data. Find items that have incomplete data or do not meet your quality requirements.

Tip: To check the classification of the item data, call up **Show > Items not classified by > <Structure system>** from the pop-up menu for the relevant catalog in the ***Context selection*** view.

4.3.4.1 Item status

In the ***Item #1*** view, you have the option of using the "Status" column to manage information about the update status of individual items. You can show the column by using the “Field selection” dialog box.


Tip: Save different layouts of the Item view depending on the task.

If you have edited item data, switch to the "Status" column. Simultaneously press CTRL and Space to display the drop-down list and change the status. The item status "01 New" is assigned to a manually created or imported item automatically. You can manually assign the following status information:

- 02 Purchase prices OK
- 03 Selling prices OK
- 04 Commercial data OK
- 05 Initial classification OK
- 06 Long description OK
- 07 Attributes OK
- 08 Internet image OK
- 09 Print image OK
- 10 Output released

This enables you to define a process for item maintenance by specifying that the status "04 Commercial data OK" can only be assigned if, in addition to "04 Commercial data OK", the statuses "02 Purchase prices OK" and "03 Selling prices OK" have also been attained.

The ***Context selection*** view allows you to to call up **Show > Items by status not reached > <Status>** and **Show > Items by status reached > <Status>** from the pop-up menu for the relevant catalog or the master catalog in order to perform a targeted search for items with a particular status.



Filtering by item status

Note: As well as the "Status" column, the table contains the "Last status change" column. Here, you can trace which user last changed the status of the item and when.

4.3.4.2 Maintaining descriptions

In the ***Text processing (items)*** and ***Text processing (structures)*** views, you can edit the texts in the "Long description" and "Additional comments" fields or you can edit the structure descriptions and assign text features to them. Various default functions are available in the view's menu bar. In addition, you have the option of using custom text features.

Here you can not only insert or delete text formatting using buttons; you can also use the integrated field selection function to edit the long descriptions of an item in different languages. Select an item in the ***Item #1*** view to display its long description in the ***Text processing (items)*** view.

Note: In the ***Item #1*** view, you can also use to open the “Edit text” dialog box in the Long description field. This provides the same functions for editing texts as the ***Text processing (items)*** view.

The view is divided into two areas. The text editor in which you work is on the left and the field selection is on the right. The buttons in the view have the following functions:

- : Switch function for activating/deactivating the spellchecker
- : Cut
- : Copy
- : Paste

- : Insert as text
- : Open "Find and Replace" dialog box
- : Open dialog box for inserting an icon
- : Undo last change
- : Redo last change
- : Delete formatting in selected text
- : Numbering
- : Bullet
- : Display selected text in bold
- : Display selected text in italics
- : Underline selected text
- : Make text subscript (custom text feature available)
- : Make text superscript (custom text feature available)
- There is also a drop-down list if you have created user-defined text features.

The procedure for showing a long description or the "Other remarks" field in additional languages is as follows:

1. Click on "Long description (German)" or "Additional remarks (German)" with the gray icon in the field selection on the right-hand side of the view.
   - A dialog box for qualifying the language opens.
2. Select the required language in the drop-down list at the bottom.
3. Click on **OK**.
   - A new entry with the selected language is added. It now has a colored icon.
4. Selecting this new entry displays the corresponding text in the text editor on the left.

4.3.4.2.1 Find and Replace

In the ***Item #1*** (or ***Products #1***) view, you can make the same changes to multiple items using "Find and Replace". If you use "Replace", this is automatically recorded in the change log. You can show the "Last change", "Last changed by" and "Most recent change by self" fields in the "Field selection" dialog box for details.

The “Find and Replace” dialog box is called up by selecting **Edit > Find/Replace** in the program menu or using the pop-up menu after previously selecting data records. You also have the option of executing the operation on the server. In the "Find and Replace" dialog box, you have an additional option called "Perform in the background", which means that you can continue working in Product 360 Desktop while the Find and Replace operation is executed on the server. You can view the progress of the operation, or view the error log if any errors occurred, in the ***Process overview*** perspective.

Tip: If you execute "Find and Replace" on the server, you can close the client without canceling the operation. As with server-side imports and exports, the server processes this operation independently.


You have additional configuration options relating to this feature:

- Cancel after first error
  The operation is automatically canceled the first time an error occurs. If you are executing Find and Replace at night, for example, a large number of errors may accumulate.
- Process all <n> data records of the query result
  You can use this option to edit those items that, as a result of the table settings in the preferences, are not displayed in the ***Item #1*** view.

Note: Since it is not useful to process a single item on the server using "Find and Replace", the **Replace** button is automatically deactivated as soon as you select the "Perform in the background" option.

Setting new values regardless of the previous values

In addition to the "Find" and "Replace" tabs, there is a third tab - "Set value". You can use the "Set value" tab for all set rows and columns to set a new value regardless of the original value. Otherwise, the same settings apply as with replacing.



Set new value


4.3.4.3 Managing text features

In the "Manage text features" dialog box, you can create predefined and custom text features, which you can use to maintain your descriptions and prepare them for output. You need these settings in both the ***Text processing (items)*** and ***Item details (form)***, views, as well as in the Product 360 Desktop and Product 360 Web text editor.

Note: Bear in mind that you can only use pure XHTML tags for user-defined text features.

1. Open the dialog box by selecting **Management > Text features**.
2. Click on **New text feature**.

3. Under "Template", select a template to use – for a user-defined tag this should be "User-defined (ud)". All other templates except for the "User-defined (ud)" template can only be used once.
4. Under "Identifier", enter a unique identifier for the text feature.
5. Under "Name", enter a name for the text feature.
6. For user-defined text features: Specify the start and end tag. For example, if you want to create your own text feature for writing texts in red font, enter `<font color="red">` as your start tag and `</font> as your end tag.`



Managing text features

Note: The output of text features in the export is described in the Export section.


4.3.5 Maintaining customer-specific data

You will need to maintain some customer-specific data in your master catalog. To do this, show the required columns in the ***Item #1*** view.

Tip: You can also identify whether a field is customer-specific by the fact that "(<Public>)" or "Customer selectable" is added onto the end of the field name in the list of available fields.

This is shown below, using the example of maintaining the buyer ERP group:

1. In the ***Item #1*** view, click on .
   - The "Field selection" dialog box opens.
2. Add the column you want to maintain for specific customers.



Maintaining customer-specific data

3. Open the drop-down list below the qualification options.
4. Select the relevant customer.

4.3.6 Maintaining item attributes

Item attributes are maintained in the ***Attribute assignment (items)*** perspective using the special ***Item attributes***[109], ***Item attributes (cumulative)***[112], and ***Items with features***[114] views.

4.3.6.1 Item attributes

The ***Item attributes*** view displays the existing attributes of a selected item in a table. In this view, you can create new item attributes and edit existing ones. In addition to the actual attribute and its value, you can also define the data type of the attribute or assign a purpose to it. Various purposes are available for selection here, depending on your system configuration.

Use the "Field selection" dialog box to display all required columns in the view.

1. Click on ✚.
   - A new row is created in the table.
2. Enter a unique name.
3. Enter the data types.

> Note: You can change the data type later, provided that you have not maintained a value for the attribute. If an attribute value is specified, you can only change the data type if the new data type matches the attribute value saved.

4.Enter the unit, if applicable.

5.Enter the attribute value.

6.Click on to save the data record.

You can edit item attributes:

- Define preset values
- Create item attributes with multiple values
- Create assignments to structure features

Tip: As well as language-specific attributes, you can also define language-independent attributes. The language-independent "Attribute value" field can also be shown for this purpose.

Deleting item attributes

1.Select one or more entries.

2.Select **Delete** in the pop-up menu.

A confirmation prompt is displayed.

3.Click on **Yes** to delete the item attributes.

4.3.6.2 Assigning item attributes to structure features

Note: You can configure your Product 360 Desktop system so that structure group features are automatically created as item attributes during classification. In case of doubt, contact your administrator for details of the settings.

When you first classify an item, it is often not enough to assign the item to a specific structure group. Often, the item includes additional information in its item attributes, which has no connection to features in the structure group.

To assign an item attribute to a structure feature:

1.Make sure that the ***Feature groups list*** view is displaying the structure features for the corresponding structure group.

2.Select the item i the ***Item #1 view.***

Its attributes are then displayed in the ***Item attributes*** view.

3.Select an item attribute in the ***Item attributes view.***

4.Drag the item attribute to the structure feature in the ***Feature groups list view.***

The assignment created to the structure feature is displayed in the "Assignments" column.

This assignment gives the item attribute a reference to the structure feature. If the attribute and the feature are different, the unit of the item attribute is exported. For example, an item may have the attribute "Weight", specified in kilograms. If this item has an assignment to a structure group with the feature "Weight" but the feature unit is grams, the weight is exported in "kilograms".

You can delete an assignment by selecting the item attribute in the ***Item attributes*** view and then selecting **Delete attribute assignments > <Structure system>** in the pop-up menu.

Note: You can only maintain the structure features themselves in non-standard classification systems. In standard structure systems, they are predefined and editing is not permitted.

4.3.6.3 Preset values for attributes

When assigning attributes, the feature to which you are assigning the attributes may have certain specifications in terms of the attribute value, e.g. the preset values for the "Color" attribute are "Red", "Green", or "Blue".

An item attribute that is assigned to a structure feature from a maintenance structure with default values is thus given a "suggestion list" in the ***Item attributes*** view, from which you can select a value. However, this suggestion list still allows users to enter their own values if required.

The following possibilities are covered:

- The attribute value is blank: A warning is displayed.
- The attribute value is one of the preset values: A suggestion list is provided for this attribute value, which is set to the attribute value.
- The attribute value is not one of the default values: The "incorrect" value is displayed on the left in red with an exclamation mark.

Note: If an item attribute is assigned to several structure features, the suggestion list is made up of the default values for the structure feature in the maintenance structure.

Tip: If a system contains a large number of attribute assignments, the overview in the ***Item attributes*** view ("Assignments" column) can become very unclear. For this reason, you can select **Perspectives > Open view** to open the ***Attribute assignments***, which displays all assignments of an attribute to structure features.

4.3.6.4 Units of item attributes and structure features

When assigning attributes to features, the units may differ. For example, if the unit of the item attribute is "Meters" and the unit for the assigned feature is "Millimeters", Product 360 Desktop checks whether the unit can be converted. If so, the attribute is displayed in the feature unit and the value is converted using the factors stored in the database. If not, the cell is highlighted in red in the ***Item attributes*** view, but the unit for the attribute continues to be used.

The assigned attributes must be maintained in the feature unit, but they are saved in the original unit in the background. If an item attribute has an assignment to a feature, the following applies:

- The attribute value changed using a conversion factor is displayed.
- The attribute is displayed in the feature unit.

Example: There are certain items (drills) that are assigned to the group "Drills". This group has particular features that have "Meters" as the unit, e.g. working length, diameter etc. By contrast, the item attributes are recorded in the more obvious unit "Millimeters".

The following Preferences can be used to control the conversion behavior and how the information is displayed:

- Show attribute values in feature unit (if assigned)
  If activated, the units of the assigned features are always displayed in the item attribute views if the unit can be converted.
- When assigning attributes, check that feature unit can be converted
  If activated, the system checks whether the unit can be converted. If not, a warning message is displayed for the user.

If a unit is to be converted in Product 360 Desktop but this is not possible, a message is displayed. Otherwise, the successful assignment is shown in the "Assignments" column.

4.3.6.5 Item attributes with multiple values

You can specify whether an attribute is to have multiple values. This means that the attribute will accept multiple values simultaneously. In contrast, attributes that have a single value can only ever have one value at a time.

Use the ***Item attribute values view to maintain attributes with multiple values.***

1. Open the ***Item attribute values*** view by selecting **Perspectives > Open view**.
2. Show the "Multiple values" column in the ***Item attributes*** view.
3. Create a new item attribute.
4. Place a check mark in the "Multiple values" column.
   - You can now enter more attribute values in the ***Item attribute values*** view.

Enter the language in addition to the identifier for attributes with multiple values, i.e. you can maintain values in multiple languages directly, just as you can for structure group features with multiple values in the ***Values for group features*** view.

Note: Single-value attributes have the identifier "DEFAULT" by default.

4.3.6.6 Item attributes (cumulative)

Note: For performance reasons, this view has some special restrictions:

- The "Name", "Attribute value" and "Assignment" fields can only be displayed in the leading attribute language defined in the repository.
- Adding more fields is not possible. Therefore, a "Field selection" dialog box is not available in this view.


If you have selected more than one item in the ***Item #1*** view, the ***Item attributes (cumulative)*** view shows all item attributes for the selected items. You can add a new item attribute to all selected items simultaneously.

1. Select the relevant items in the ***Item #1 view.***
   - The information line above the table header in the ***Item attributes (cumulative)*** view indicates the number of items selected.
2. Click on ✚.
   - A new row is created in the table.
3. Enter the name of the attribute.
   - Depending on your settings, when you switch fields you will be asked whether you want the new attribute to be created for all selected items.
4. Confirm with **Yes**.
   - The attribute is created for all selected items.

The number of times the respective attribute is used in the selected items is indicated in the "Number of attributes" column. If an attribute is not maintained for all selected items, the "Number of items" column is highlighted in yellow.

Tip: Unequal numbers are excellent indicators of discrepancies in attribute maintenance, which you may want to check out.

If a value is displayed in the "Attribute value" column, all selected items have the same attribute value. If they have different attribute values, only three dots are displayed in this column. If you want all selected items to have the same attribute value, you can change the "Cumulative" attribute value. Overwrite the three dots with the value you want to apply to all items.



Non-matching item attributes

You can only transfer structure features as item attributes in the ***Item attributes (cumulative) view.***

4.3.6.7 Transferring structure features as item attributes

Note: You can configure your Product 360 Desktop system so that structure group features are automatically created as item attributes during classification. In case of doubt, contact your administrator for details of the settings.

1. Make sure that the items are assigned to a structure group.
2. Select the items in the ***Item #1*** view to display their item attributes in the ***Item attributes (cumulative)*** view.
3. In the ***Feature groups list*** view, select the structure features that you want to transfer.

4.Click on in the ***Item attributes (cumulative)*** view.


➪ The features are transferred as item attributes (with assignment to the structure feature).

4.3.6.8 Items with features

The ***Items with features*** view allows you to maintain the attributes in the feature context in a table. Once you have selected a structure group in the ***Primary structure tree*** view, this view displays all items assigned to that structure group.

In addition to the item numbers and short descriptions, the item attributes are displayed in columns in accordance with the features of the structure group. You can edit and change the values in the table. Using a filter, you can sort the view by purpose and mandatory feature.

By default, the fields are displayed in the configured operating system language. If other language packs are available, the columns are then displayed in pairs. For some fields, you can also display the field label independently of existing translations. Use to open the dialog box for configuring the column display.



Maintaining items with features

Note the following points in relation to this view:

- Only features of the selected structure group are displayed in the view. If assignments to features are maintained for the corresponding assigned attributes, the entries in the table are highlighted.
- Attributes that are maintained for an item but do not exist as a feature of the structure group are not displayed.

- Item attributes that have the same name as an item structure feature are an exception to this rule. In this case, the values are displayed in the table but the entry is not highlighted. You can assign the value to the structure feature by clicking on the value in the table and pressing Enter to confirm. You can identify this change by the fact that this field will now also be highlighted.
- An item attribute is not displayed in the view if it has been assigned to a structure feature but has a different name. The view only takes account of feature names and not the existence of an assignment if the assigned structure feature has a different name.
- It is not possible to use the "Field selection" dialog box for this view because the contents and also the columns are defined automatically by the features of the selected structure group. For this reason, the layout of the view cannot be changed or saved.
- The layout of the features in columns means that the table increases in width and becomes less comprehensible as the number of features grows. Therefore, a maximum of 50 features can be displayed in the view.

4.3.7 Item reference

The ***Supplier relationships*** view represents the relationship(s) between an item in your master catalog and one or more suppliers. The view can only be displayed explicitly by selecting **Perspectives > Open view**.

This kind of supplier relationship is similar to the "purchasing info record" that may be familiar to you from a SAP system.

Note: Note that the relationship between a master catalog item and a supplier item exists even if the item appears in different catalogs from the same supplier.

Example: Supplier L1 has two catalogs K1 and K2 in the data transfer area. Both catalogs contain item A1 with the item number 123. As a result of the merge process, for example, this item has a supplier relationship with a master catalog item PA1, which has the item number 456. Both items A1 in K1 and K2 are handled in the same way.


When you transfer an item to your master catalog for the first time using the merge process, you also create an implicit relationship between the master catalog item and the supplier of the merged catalog. You have thus defined this supplier as the "main supplier". An item can only ever have one main supplier. All other suppliers are of the "Alternative supplier" type.

4.3.7.1 Supplier relationships

As usual in Product 360 Desktop, you can create additional supplier relationships using drag & drop.

1. Arrange two different item tables in such a way that you can simultaneously see both the supplier catalog item and the master catalog item.
2. If necessary, use to block a table.
3. Use drag & drop to drag the supplier catalog item to the master catalog item.

➪ The dialog box for the drag & drop action opens.



Creating a supplier relationship

4. Decide whether you want to create an item reference or a supplier relationship. In this case, you should choose a supplier relationship.

You can create any number of relationships between a master catalog item and items from supplier catalogs, but a supplier can only occur once. You can identify which of these is the main supplier from the "Main supplier" column.

Specifying a supplier relationship allows you to update ordering information as part of the merge process, e.g., purchase prices.

Note: Items from "alternative suppliers" can only supply information about purchasing conditions to the master catalog through the merge process, and then only if the settings in the merge process are different. Any additional transfer options are reserved for items from the main supplier. This enables you to "protect" the quality of your data against unintentional transfer.

To delete supplier relationships for one or more items:

1. Select the item(s) in the ***Item #1*** view.
2. Select the corresponding entry in the ***Supplier relationships*** view.
3. Select **Delete** in the pop-up menu.
   ➪ A confirmation prompt opens.
4. Click on **Yes**.
   ➪ The supplier relationship is permanently deleted.

4.3.7.2 Item comparison

The ***Item comparison*** view allows you to perform item comparisons between items in a supplier catalog and the associated items in your master catalog. It has all of the functions of a table.

1. In the ***Context selection*** view, select **Show > Item comparison (supplier/master catalog)** in the supplier catalog pop-up menu.
   ➪ The ***Item comparison*** view displays the items in the supplier catalog. A check mark in the first column, called "In master catalog", indicates that this item is also included in the master catalog, i.e., an internal item reference exists.
2. Use the "Field selection" dialog box to select the column(s) you want to view in more detail.

3.Select **Add corresponding master catalog field** in the pop-up menu for the column header of the relevant column.

- Product 360 Desktop shows an additional column to the right of this column, which has the same name but with the prefix "MC:". This indicates that the corresponding value comes from the master catalog.

Note: "MC" columns cannot be selected using the field filter dialog box. If you have displayed "MC" columns and want to add additional columns or change the order of the columns in the "Field selection" dialog box, Product 360 Desktop will then call up the default display repeatedly and position the "MC" column to the right of each selected column.

Delta column

To obtain a quick overview, you can display a delta column in addition to the "MC" column.

- Select **Compare with master catalog** in the column header pop-up menu.
  - An additional comparison column is shown. Texts are classified as "identical" or "not identical". In the case of monetary amounts, the difference appears as a percentage.
  - The corresponding column in the master catalog is automatically displayed too.


4.3.8 References

You need references if you want to create or manage relationships between two items, variants, or products. References are managed in the ***References (items)*** perspective, which contains the special ***References*** view. If you have selected an item in the ***Items #1*** view or a product in the ***Products #1*** view, you can check and maintain the relationships for this item or products in the ***References*** view.

Note: Product 360 Desktop enables you to set up multi-level references, i.e., item A can be a component of item B and item B a component of item C. Product 360 Desktop allows any reference and leaves it up to you to clarify whether the reference is actually coherent. Thus, C can be a component of A.

Creating item references using drag & drop

You can create a reference by linking one or more items with another in the ***Items #1*** view using drag & drop. This method works both within a table and across two tables. After the drop operation, a dialog box in which you specify the reference type opens automatically.



Creating a reference between items

You can choose from the following reference types:

- Similar item: Two items are so similar that they could be supplied as an alternative to one another.
- Alternative order unit: An item is identical to another item, but it is sold in different order units.
- Component: An item is a component of another item, as in a parts list.
- Cross-selling: Cross-selling of complementary items
- Spare part: An item is a spare part for another item.
- Successor item: An item is a successor item for another item.
- Essential spare part: An item is an essential spare part for another item.
- Optional spare part: An item is an optional spare part for another item.
- Other reference: An item has a relationship with another item that is not specified in more detail.
- Up-selling: Reference to a higher quality or value item
- Accessories: An item is an accessory for another item.
- Next level down: An item is part of a packing hierarchy that can consist of several individual items.

Note: You will usually want to create the reference using drag & drop. However, manual creation is fully justified if the referenced item is not maintained in your system, for example.

Creating references manually

1. Open the ***References (items) perspective.***
2. In the ***Item #1*** view, select the item to be assigned a reference.
3. In the ***References*** view, click on ✚.
   - A new row is created in the table.
4. Select the reference type from the drop-down list.
5. Enter the referenced catalog and the item number.
6. Click on 💾 to save the new data record.

The table provides the following fields.

Column name	Description
Item reference type	Type of relationship
Referenced item number	Item number of the item involved in the relationship You can also specify an item from a catalog that is not located in your system.
Referenced catalog	Name of the catalog in which the "referenced item" is located. If no catalog is specified, the same catalog as that in which the referencing item is located is assumed. When selecting the catalog, you can either enter the catalog identifier directly or use the shortcut CTRL + space bar to open a drop-down list and choose the catalog from this list. Your master catalog appears as a catalog in the list. Select this entry if you want to search your master catalog for the referenced item. You can also specify the name of a catalog that is not located in your system.
Number	Occasionally, it can be useful to specify not only whether and how an item has a relationship with another item, but also how often. Typically, you will require this information when managing a parts list. Enter the number here.
in system	Der Product 360 Desktop searches the specified catalog automatically for the referenced item. If the item is found, it is indicated by a check mark.

Information: By default, the "Referenced catalog" and "In system" fields in this perspective are not available. They must first be activated using the field selection. As both fields are logically linked, it is sufficient to activate the referenced catalog.

4.3.9 Kits and components

Dynamic or variable kit

A kit is a group of components that are displayed together as a unit. A component is an item that is a part of a kit.

Note:By default, a kit cannot be a component of another kit.

To allow a kit to be a component of another kit, contact your administrator.


Kits and components using drag & drop

You can create a kit by linking one or more items with another item in the ***Item #1*** view using drag & drop. This method works both within a table and across two tables.

➪When you drop the item, a dialog box opens automatically, in which you can specify the component type.

Note: Kits and components can only be created at item level.

A component can belong to several kits.



Drag & drop event

When you confirm your entries, a check mark appears in the ***Item #1*** view to visually indicate what is a kit and what is a component.

Creating kits and components manually

1. Open the ***Kits and components (items) perspective.***
2. In the ***Item #1*** view, select the item to be assigned to a component.
3. In the ***Kits and components*** view, click on ✚.
   - A new row is created in the table.
4. Select the type from the drop-down list.
5. Enter the item number.
6. Click on 🖫 to save the new data record.

Note: There are static and dynamic components, and only dynamic components can have the same sequence.

Sequence = Series of items as they are arranged in the kit

Additional function:

By right-clicking to open the ***"Kits and components"*** pop-up menu, you can select ***"Show assigned kits"*** to display the kits to which the component is assigned.

By right-clicking to open the ***"Catalog"*** pop-up menu, you can select ***Show items"*** and " ***Kits and components of catalog***" to display all kits and components statically or dynamically.

4.4 Classifying

To structure the master catalog and thus also the catalogs to be delivered, you can assign the items, variants and products in your master catalog to one or more classification systems. You

should also maintain the values of the predefined structure features so that the data is complete and comparable. It is also possible to maintain other item attributes or product attributes that are not stipulated by the structure systems used.

If an item is assigned to a product or a variant, the item "inherits" the product's or variant's structure assignments. This means that the item is assigned to the same structure groups as those to which the product is assigned. Any existing structure assignments of the item are changed. Likewise, the features of the structure groups are adopted as item attributes.


To classify and maintain the items and products, you can use the ***Initial classification (items)***, ***Multiple classification (items)***, and ***Attribute assignment (items)*** perspectives. You also have the option of creating and editing (including deleting) custom structure systems in the ***Structures*** perspective. To classify effectively, you should first set up Product 360 Desktop optimally and ensure that you completely understand the procedure.

Note: Product 360 Desktop uses the terms “Primary structure tree” and “Secondary structure tree”. As you become experienced as a product data manager, you will discover that you need to view two structure systems for certain tasks: For example, if you want to compare two structure systems with one another or to check the relationships between two structure systems. As a rule, however, one structure system per perspective is sufficient and you should use the ***Primary structure tree*** view.

4.4.1 Preparation

First you must ensure that the structure system(s) to be used are available in Product 360 Desktop. In addition, ensure that you have configured Product 360 Desktop optimally.

1. Open the preferences by selecting **Management > Preferences > Structures - Basic settings**.



Settings for structures

2. In the "Primary structure tree" area, select the structure system you will use most frequently. The drop-down list shows all structure systems available in Product 360 Desktop.
3. At this point, you can also select the secondary structure system shown in the second structure tree.

4.Close the dialog box by clicking on **OK**.

These settings specify which structure system will be loaded in the ***Primary structure tree*** and ***Secondary structure tree*** views when starting. While working, you can change the structure systems loaded in the two views without having to change the settings.

Note: "Loading" or "opening" a structure system means that Product 360 Desktop displays the structure system and you can use it. Therefore, you only require two structure views in Product 360 Desktop, even though you may actually use considerably more structure systems.

4.4.1.1 Creating an overview

Typical questions regarding classification include:

- Which structure systems are used to classify the items from a supplier catalog?
- Which items in a catalog are not (yet) classified using a specific structure system?
- Which structure system is to be used to classify the items and products in the master catalog?

First, you must decide whether you want to classify supplier catalog items or master catalog items and products. Depending on this decision, you then need to select the corresponding context to display the data to be classified. However, the classification procedure is the same in both cases.


Tip: When deciding whether to classify in the supplier catalog or in the master catalog, remember that with each new catalog import, the supplier catalog data that has already been maintained can be changed. If you classify in the master catalog, for each merge you can specify in detail whether and in what mode the classification information is transferred from the supplier catalog to the master catalog. This is how you can avoid the risk of data loss during a catalog import and can continue to enhance data.

4.4.1.2 Finding the required data

When you first view the supplier catalogs, click on the catalog to be viewed, which you assume has been classified according to eClass–8.0 and contains the items you want to classify, in the ***Context selection*** view.

1.Select the catalog in the ***Context selection*** view.

2.Select **Show > Items not classified by > ECLASS-8.0** in the pop-up menu.



Show items...

The ***Item #1*** view assigned to the ***Context selection*** view now displays all items in this catalog that are not classified according to the selected structure system. Ideally, the list is empty, or only shows very few entries, which may be classified afterwards if necessary. On the other hand, if the list displays all of the items, the catalog is not classified according to the selected structure system.


The same functionality is also available for the master catalog. Select the master catalog in the ***Context selection*** view and then select **Show > Items not classified by > ECLASS-8.0** in the pop-up menu. As a result, you will see all items that are not classified according to eClass- 8.0.

4.4.2 Initial classification

The term "initial classification" refers to the first assignment of an item to a structure group in a structure system.


Use the ***Initial classification (items)*** perspective for the initial classification. By default, the perspective includes:

- Top left: ***Context selection***[90] and ***Item search***[93]
- Top right: ***Items #1***[99]
- Bottom left: ***Primary structure tree***[202], ***Class list***[205], and ***Feature groups list***[210] (shows entries if an entry has been selected in the ***Primary structure tree*** view for which features are defined).
- Bottom right: ***Item #2*** (shows all items linked to the selected node in the ***Primary structure tree*** view)



Initial classification

While the ***Item #1*** view (top right) only "monitors" the ***Context selection*** view, the ***Item #2*** view obtains its content from the ***Primary structure tree*** view. The effects of this can be made apparent if you open **Obtain content exclusively from** in the pop-up menu for the corresponding view and check whether the check mark is in the desired location.



Checking the context of a table

1. In the ***Context selection*** view, navigate to the catalog or master catalog containing items you want to classify. To do this, use all of the options available in Product 360 Desktop, including item search 93, sorting in the table 34, field filters 37, and assortments 147. Items that are not classified according to a particular structure system can be directly displayed by calling up the corresponding function in the ***Context selection*** view.
2. Open the structure system to which you want to assign the items in ***Primary structure tree*** view (bottom left).
3. Use drag & drop to drop one or more items into the relevant structure groups in the ***Primary structure tree*** view (or the ***Class list*** view). Use the extensive search mechanisms in the tree view and the sort options in the list display to quickly locate the target node.
   - After the drag and drop operation, the number of items located in the relevant node is displayed in the ***Item #2*** view.


Note: If your system supports automatic creation of item attributes 109, the relevant item attributes are created automatically during classification in a maintenance structure and assigned to the structure features. 111

4.4.2.1 Changing a structure assignment

If you have mistakenly assigned an item to an incorrect node and it is displayed in the ***Item #2*** view, you can move it from there into the correct structure group. If you drag and drop the item from the ***Item #1*** view to another structure group, it is moved – unless you hold down the Ctrl key during this action and the classification system supports multiple assignments.

4.4.2.2 Multiple assignment

You can make multiple assignments by simply dragging and dropping the item on an additional structure group. Keeping the CTRL key pressed during drag and drop implies that the item is moved and not copied to the other structure group.




Note that multiple assignments are not allowed

Note: Do not confuse the terms "multiple assignment" and "multiple classification". Multiple assignments are created by assigning an item to more than one structure group within a structure system. A multiple classification is created by assigning an item to structure groups in two different structure systems.

4.4.2.3 Deleting a structure assignment

1. Select the relevant item in the ***Item #1*** view.
2. Select **Delete all structure assignments of the selected items to > <structure system>** from the pop-up menu.
3. A confirmation prompt appears. To confirm, click on **OK**.
   - The structure assignment for the item is deleted.



Delete assignment


4.4.2.4 Classification and features

Structure systems, e.g. eClass 8.0, may have features that can (or must) be maintained for items that are assigned to a structure group. You can or must assign these features values for the item after it has been classified.

Typical examples of these fields include "Manufacturer", "Product name" and "GTIN code". Some items already have this information, and their attributes may even have the same label.

You assign item attributes to structure group features in the ***Attribute assignment (items)*** perspective. The perspective comprises several views, the most important being the ***Item attributes***, ***Item attributes (cumulative)***, and ***Items with features (specialized)*** views.

Note: You can configure your Product 360 Desktop system so that structure group features are automatically created as item attributes during classification. Depending on the settings, existing item attributes are either deleted before classification or are retained as free attributes if they cannot be assigned to a structure group feature. In case of doubt, contact your administrator for details of the settings.



"Attribute assignment (items)" perspective


4.4.2.5 Item classification by import

You can also assign items using an import. In the simplest case, you need a two-column table containing the item number and the structure group identifier. You then perform the item import to your master catalog and assign the corresponding information in the mapping.

Tip: It is important to understand that the term "import" does not refer only to the creation of new items but also - and possibly more often - to the addition, i.e. enhancement, of data.

4.4.2.6 Displaying structure groups


1. Select the item in the ***Item #1*** view.
2. Select **Show assigned structure groups in structure tree for** in the pop-up menu. Product 360 Desktop displays a submenu containing only those structure systems to which this item is assigned.
   - The relevant structure system is automatically loaded in the ***Primary structure tree*** view and the node is opened. The ***Item #1*** view is then recreated and the originally selected item is displayed again, along with any additional items assigned to this structure group.



Show assigned structure groups

4.4.3 Multiple classification

You can assign an item to any number of structure systems using the initial classification procedure. The aim of this multiple classification is to assign an item that is already classified to another classification system. When two different classification systems are conceptually similar, it makes sense to use the assignment concepts for the first when making an additional classification. Use the ***Multiple classification (items) perspective for this purpose.***



Multiple classification (items)

The perspective consists of the following views:

- The ***Primary structure tree***202, ***Context selection***90, and ***Item search***93 views in the top left
- The ***Item #1***99 in the top right

- The ***Secondary structure tree*** and ***Secondary class list*** views in the bottom left
- The ***Assignment recommendation*** view in the bottom center
- The ***Item #2 view in the bottom right***

The top views are used to select items that have already been classified. The secondary classifications (bottom left) represent the "target system". Items from a selected node that already have multiple classifications are shown in the ***Item #2*** view. The ***Assignment suggestion*** view supports you in assigning items that are already classified to an additional structure system.

4.4.3.1 Classifying items using the assignment recommendation

Actual multiple classification essentially functions in the same way as initial classification. The ***Assignment suggestion*** view supports you in deciding which structure node in a second structure system an item is assigned to.

1. Open the ***Multiple classification (items)*** perspective by selecting **Perspectives > Open**.
2. In the ***Primary structure tree*** view, select **Show > Items not classified by > <Structure system>** in the pop-up menu to display only those items that are not classified using the second structure system.
   - The items are listed in the ***Items #1*** view.
3. Select an item so that you can then use the ***Assignment recommendation*** view to select the assignment to the second structure system.
   - From previous classification (mapping): If you have added group assignments to the system by importing a classification mapping, Product 360 Desktop can use it as a basis for recommending qualified assignments.
   - Wildcard search: Use a custom search to obtain an assignment recommendation. Enter a search term in the text box that contains the "*?" characters by default. When you press the Enter key, the ***Assignment suggestion*** view will list all structure groups that contain the search term in their name. The search is not case sensitive.
     The wildcards (placeholders) used are the question mark **?** for any single character and the asterisk ***** for any number (including zero) of characters. Example: Searching for "?ice" finds all the character strings that end in "ice", preceded by any other single letter: "rice", "dice", etc. By contrast, searching for "*ice" could return "ice" or "notice".
   - Similarity search: Returns the structure groups in the second structure system that have a similar name to the structure group you have selected in the ***Primary structure tree*** view.
   - From classified data: Product 360 Desktop uses information about items already assigned and classified. For example, if 10 items are assigned to the same node in the primary structure system and you successively assign these items to a node in the secondary structure system, once a certain number of items have already been assigned (e.g. 4), Product 360 Desktop can make a qualified suggestion of what you should do with the remaining 6 items.

4. Drag the item to the desired structure group in the ***Assignment suggestion*** or ***Secondary structure tree*** view. You can also classify multiple items simultaneously.

A single assignment and multiple assignments can be changed and deleted in a similar way to that used for the initial classification.

Tip: Select the structure group in the ***Assignment suggestion*** view and call up **Show group in tree** from the pop-up menu. The structure group is then displayed in the ***Secondary structure tree*** view.

4.4.3.2 Multiple classification by import

Using structure group assignments ("classification mapping"), the complete master catalog can be mapped from the source structure system to the target structure system by batch data processing. This procedure has two steps:

1. Import of an assignment table (the assignment table can be in CSV, XLS, or XML format)
2. Application of this assignment to the master catalog.

The first column of the import file contains the structure group identifier for the source structure groups – all other groups from other structure systems contained in the file are assigned to these source structure groups.


	A	B
1	Identifier_ECLASS	Identifier_UNSPSC
2	20010101	23151801
3	20010102	23151801
4	20020201	41101513

Assignment table

Tip: The table can include more columns, for example if you want to perform several assignments at the same time.

To import the above file as a classification mapping:

1. Switch to the ***Structures*** perspective.
2. Open the structure system to be used as the source structure system in the ***Primary structure tree*** view.
3. Select **Import** in the pop-up menu.
   - The ***Import*** perspective opens.
4. Create a new import project.
5. Click on ✚ in the ***Data source*** view to add the data file.
6. Use drag & drop to create a mapping for the "Structure group identifier" and "Structure assignment" fields.




Creating a structure mapping

7. Click on .

   - The assignments are imported into the system and any existing assignments are overwritten. However, the import is not applied to classified items. This is done in the second step.

8. In the Views menu for the ***Primary structure tree*** view, select **Apply classification mapping > to <Structure system>**.

   - The assignment is applied to the currently loaded structure (source structure). You will then see a dialog box showing how many items were affected by the mapping.



Applying a structure mapping


Tip: In the ***Item #1*** show the “Structure assignment” columns twice: once qualified by the first structure system (e.g. eClass 8.0) and once qualified by the second (e.g. UNSPSC-5.0301). This quickly shows you whether all items in your master catalog are classified according to one structure system or the other as a result of the mapping and whether your imported structure assignments were complete.

4.4.3.3 Structure group assignments

You can create an assignment to another structure for the structure groups within a structure in the ***Structure group assignments*** perspective. If you then assign an item to the first structure, it is also automatically assigned to the second structure, provided that your system has been configured accordingly.

You cannot assign one group in the source structure to several groups in the target structure. However, you can assign several groups in the source structure to the same target group structure. The two lower views in the perspective show you which source structure groups have been assigned to which target structure groups and vice versa.

Note: Circular references are not permitted, i.e. source structure group A has target structure group B. Conversely, however, structure group B cannot have structure group A as a target structure group.



Structure group assignments

In the ***Structure group assignment*** view, the source structure is displayed on the left and the target structure on the right. You can use the Views menu to select which structures are displayed in each case. The following icons are also available:

- : Only displays groups that have not yet been assigned to a target (for source structures only)
- : Only displays groups that contain items
- : Collapses all nodes in the structure tree

The two search bars in the ***Structure group assignments*** view allow you to search for entries in the source and target structure.

1. Enter the search term.
   - All entries that contain the search term are displayed in the tree structure.
2. To return to the unfiltered display of the structure, delete the search term from the search bar.

Note: If you search for keywords that are not contained in the structure, an empty view is displayed as the search result.

Creating a structure group assignment

1. In the Views menu for the ***Structure group assignment*** view, select **New source structure > <Source structure>**.
   - The selected structure is displayed in the left half of the view.
2. In the Views menu for the ***Structure group assignment*** view, select **New target structure > <Target structure>**.
   - The selected structure is displayed in the right half of the view.
3. In the source structure, open the group you want to assign.
4. In the target structure, open the group to which you want to assign the first group.
5. Use drag & drop to move the source structure group into the target structure group.
   - You can check the assignments in the ***Source structure assignments*** and ***Target structure assignments*** views.
6. Select the source structure group in the ***Structure group assignment*** view.
   - The assigned target structure group is displayed in the ***Source structure assignments*** view.
7. Select the target structure group in the ***Structure group assignment*** view.
   - The assigned source structure group is displayed in the ***Target structure assignments*** view.

Note: You can assign any number of source structure groups to the same target structure group but each source structure group may only have one target structure group.

Deleting structure group assignments

1. Select the source structure group whose assignment you want to delete.
2. Select **Delete structure group assignment** in the pop-up menu.
   - The assignment is deleted without a confirmation prompt.

4.5 Prices, surcharges and discount groups

You can check, correct, or add to the available prices as well as monitor price changes in the ***Prices (items)*** perspective.

Note: Note that your ERP system should retain price priority and continue to carry out essential, mostly customer-specific, price calculations.

You can also maintain price surcharges, e.g. metal surcharges. You can do this using the ***Explorer (items)*** or other data maintenance perspectives. Since surcharges represent price-relevant data, their maintenance is explained in association with price maintenance.

In the ***Discount groups*** perspective, you can specify price groups and their assignment to items.

4.5.1 Prices

You use the ***Prices (items) perspective to maintain item prices.*** An item price normally consists of a price type, a currency and an amount, which is valid for a certain time frame.

Often when large quantities are involved, volume discounts are granted, which results in price tiers. If items are offered in different countries, regional prices must be maintained, which may require the use of several different currencies. Frequently, there are special agreements with individual customers, which require customer-specific prices.


A distinction is made between purchase prices and selling prices. While a purchase price is specified for the Product 360 Desktop operator, selling prices are passed onto customers. Therefore, additional information about the customer is necessary, since an item can have different prices for different customers.

In general, prices must not be changed retroactively. Prices should also be unique, i.e. on any given date there must be only one price for each price type, customer and quantity interval. Your administrator can specify whether or not prices may be changed retroactively.

Product 360 Desktop ensures that prices are unique for you. It is not possible to enter prices with an overlapping validity period. When adding prices, Product 360 Desktop allows automatic adaptation of price periods. This is the case particularly when you want to maintain price promotions for a limited period. The principle of automatic time period adjustment is particularly effective in the case of manual data maintenance, import and merge. The existing and new prices to be added are "laid on top of one another", whereby the new price information added is considered more up-to-date than the existing prices. The resulting prices create a "chain of consecutive price periods" and are saved. The price maintenance settings are taken into account, which means that, in some cases, no retroactive price changes are carried out.


The ***Prices (items)*** perspective is used to maintain and monitor purchase prices and selling prices. The ***Purchase prices*** and ***Selling prices*** views are available for this purpose. These views display all existing purchase and selling prices for an item, regardless of when they are valid. Using the functions in these views, you can create new purchase and selling prices, insert additional price tiers or change existing data.

Note: Of course, the ***Item #1*** view is also available for price maintenance. However, only a properly configured table displays the required data. Therefore, select the fields carefully so that the selected fields are correctly assigned the required additional information, e.g. validity time.



Displaying price fields

Tip: If you want to display several columns with prices for different customers, it is helpful to rename the field.



	Item no.	Manufacturer	Short description (English)	Structure assignments (ECLASS-4.0)	Net customer price (from 1)	Net customer Erstein AG
1	000	A.Barcelò,Seguras ...	"Spain Olé" Gift Set	41-01-07-06	37.89	14.50
2	001	Le Contesse, Tre R...	"Dolce Vita" Gift Set	41-01-07-06	12.65	11.20
3	002	Selezione del Dotto...	"Cucina Italiana" Gift Set	41-01-07-06	14.28	
4	003	Viani,Giacchi	"Risotto e Funghi" Gift Set	41-01-07-06	19.40	
5	004	Viani,Giacchi,Selezi...	"Pasta, Pasta" Gift Set	41-01-07-06	26.31	
6	005	Viani,Giacchi,Fatto...	"Aromi di Toskana" Gift Set	41-01-07-06	26.18	
7	006	Viani,Giacchi,Coppo	"Tesori del Piemont" Gift Set	41-01-07-06	27.90	
8	008	Viani,Latini,Le Con...	"La Deliziosa" Gift Set	41-01-07-06	42.78	

View with two price columns

4.5.1.1 Purchase prices

You can insert new price tiers and new prices and make them visible using the pop-up menu for the ***Purchase prices*** and/or ***Selling prices*** views.

The ***Purchase prices*** view shows you all existing prices for the item selected in the ***Item #1*** view, regardless of when they are valid from. Using the functions in this view, you can create new prices, insert price tiers, or change existing data.

Note: Note that you always have to save new data records you have created by clicking on .

4.5.1.2 Selling prices

In the ***Selling prices*** view, you maintain all selling prices for the item selected in the ***Item #1*** view. Selling prices are always unique in terms of price type, time and customer. Product 360 Desktop monitors this uniqueness when:

- Creating a new price
- Editing a price

Creating a selling price

1. Click on + to create a new price.
   - A new row is created in the table.
2. Specify the price details in terms of price type, period, customer and area of validity.
3. Click on to save the data record.

The price is created if it is unique; otherwise Product 360 Desktop interprets the new price as an additional price for an existing price (or multiple prices) with the same price type, customer and price tier. The validity periods for the new price and the old price are compared and changed after you confirm a confirmation prompt. The following examples explain possible changes to the validity periods:

Old price	New price	Comment
Valid from 06/15/2013 to 08/15/2013	Valid from 6/1/2013 to 12/31/2013	The old price is completely replaced by the new price as its validity period is completely overlapped by the new price.
Valid from 06/15/2013 to 08/15/2013	Valid from 6/1/2013 to 6/15/2013	The new price overlaps the beginning of the old price's validity period. The validity period of the old price is reduced accordingly and the new price is inserted.
Valid from 6/15/2013 to 8/15/2013	Valid from 7/1/2013 to 7/31/2013	The new price's validity period lies within the validity period of the old price. The old price is split, i.e. the old price applies before and after the new price inserted.
Valid from 6/15/2013 to 8/15/2013	Valid from 8/1/2013 to 12/31/2013	The new price overlaps the end of the old price's validity period. The validity period of the old price is reduced accordingly and the new price is inserted.
Price 1: Valid from 6/15/2013 to 8/15/2013 Price 2: Valid from 8/16/2013 to 10/15/2013	Valid from 8/1/2013 to 9/30/2013	The new price partly overlaps the old prices 1 and 2. Both prices are changed and the new price is inserted.

Old price	New price	Comment
Valid from 6/15/2013 to 8/15/2013	Valid from 8/16/2013 to 12/31/2013	The old and new price do not overlap and there is no change to the old price when inserting the new price.

Changing a selling price

If you are changing an existing price, critical cases must be distinguished:


- Changing the price type or customer: A change is not possible if the changed price would no longer be unique.
- Change of validity period ("Valid from" and/or "Valid to"): Other prices whose validity periods are affected will also be changed.

If you set the date value for "Valid to" before the date value for "Valid from", the date value for "Valid from" is automatically set to the same value as "Valid to", so that no "negative periods" can result.

Tip: You can quickly check price tiers in the column view – the columns will automatically be displayed based on the existing price tiers. This enables anomalies to be identified quickly.

4.5.2 Price example

There is a net customer price of € 12.65 for an item, which is valid for the entire year 2009.



Selling prices (1)
ER-0008

	Price type	Valid from	Valid until	Customer	Price	Currency
1	Net customer price	1/1/2009	12/31/2009	<Public>	12.65	US Dollar

Price validity example (I)

A price promotion is to take place from December 1 through December 15, during which the item has a net customer price of just € 11.14. The price of € 11.14 is added either manually or by import for the validity period of 12/01/2009 to 12/15/2009.

For this period, there would now be two prices, so the current price data needs to be changed. A dialog box notifies you of this.



Automatic data record change when entering price information

The current price is terminated on the day before the period of the new price, and a new price with the old price amount must be inserted for a validity period, which begins one day after the promotion price period and is valid until the end of the original period. The promotion price applies in the resulting "gap" in the old price.

Selling prices (3)

ER-0008

	Price type	Valid from	Valid until	Customer	Price	Currency
1	Net customer price	1/1/2009	11/30/2009	<Public>	12.65	US Dollar
2	Net customer price	12/1/2009	12/15/2009	<Public>	11.14	US Dollar
3	Net customer price	12/16/2009	12/31/2009	<Public>	12.65	US Dollar


Saving the special price

4.5.3 Checking price changes

Price changes are frequently performed by import. If you want to check price changes, you should either do this outside of Product 360 Desktops or not immediately overwrite the existing prices with the import, but first import to another (unused) price column. You can then monitor the price changes very easily.

To check prices for different customers, a comparison view of the price columns is recommended.

1. Open the "Field selection" dialog box.
2. Add the fields you require to the table.
3. Select the columns with the customer prices in the list on the right.
4. Click on  .
   - A comparison column is shown for the two columns selected. This allows you to quickly see whether the prices are correct in the ***Item #1*** view.



Comparison function for two price columns

4.5.4 Price surcharges

Price surcharges are normally transferred into Product 360 Desktop via the supplier catalogs and passed onto your customers, which means that maintenance of these price surcharges is limited to checking the data. Only the base data for the price surcharges is captured. The actual surcharge calculation takes place in your ERP system, which also handles billing and has access to additional required information, such as current exchange rates.

Price surcharges may be metal surcharges, which are calculated according to the proportional item content and the applicable market price, or may be fixed or percentage surcharges such as insurance and material disposal costs.

Accordingly, you have the following options for entering price surcharges:

- The surcharge type and fixed or percentage amount for a surcharge that is not related to raw materials contained in an item, e.g. packaging costs. These surcharge types are located under "Other surcharge (type of surcharge)"
- Metal type, raw material base, percentage or absolute surcharge, and jump for surcharges depending on raw material listings.
- Metal type, raw material base and metal weight (metal content in the item) for surcharges that are calculated based on the proportional weight in the relevant item.

Note: Note that the values displayed depend on the relevant system configuration. In case of doubt, contact your administrator.

To maintain price surcharges, use the ***Explorer (items)*** perspective or one of the other perspectives that contain the ***Items #1*** view. Before you can begin, you must configure the ***Items #1*** and/or the ***Item details (form)*** view so that the relevant columns and fields are displayed. To do this, specify which columns and fields are to be displayed for each of the surcharge types in the “Field selection” dialog box.

Tip: For surcharge data maintenance, create a dedicated layout 42 for the ***Items #1*** view that you can use repeatedly for this purpose.


Examples:

- Packaging costs 138
- Surcharge calculation based on metal content 138
- Surcharge calculation based on jump 139

4.5.4.1 Packaging costs

Packaging costs are to be increased by 5 % for a packaging-intensive item. The following item data is known:

- Surcharge category: Packaging costs
- Surcharge: 5 %




Packaging costs

When the price is calculated, a surcharge of 5 % of the item price is charged as the packaging cost surcharge.

4.5.4.2 Surcharge calculation based on metal content

A cable contains 430 g copper per 10 m. It is sold in 10 m units. The price of the cable is calculated from the current copper listings. To obtain a suggested price for the item, a value of € 150 per 100 kg copper is assumed for the copper listing. The following item data is known:

- Order unit: 10 m
- Metal type: Copper
- Raw material content: 430 g (weight (in grams): 430)
- Raw material basis: € 150 per 100 kg copper (basis: 150, currency: Euro, base raw material quantity: 100 (default value), unit for base raw material quantity: Kilogram (default value))



Surcharge calculation based on metal content


At the time of the price calculation, copper is listed at 270 Euros per 100 kg. A price difference needs to be taken into account, amounting to: 270 Euros - 150 Euros = 120 Euros per 100 kilograms

For the 430 g of copper contained in the cable, the calculated copper surcharge is 120 Euros/100 kg x 430 g = 0.52 Euros

4.5.4.3 Surcharge calculation based on jump

The price of a zinc gutter depends on the zinc listing. A proportional cost for the zinc content is already included in the price. If the zinc listing is higher than the 250 Euro per 100 kg zinc already calculated, a surcharge is levied, defined by intervals in the zinc listing: Each time the zinc listing jumps by 20 Euro, a surcharge of 1.20 Euro is levied. The following item data is known:

- Metal type: Zinc
- Raw material basis: 250 Euro per 100 kg zinc (basis: 250, currency: Euro, base raw material quantity: 100 (default value), unit for base raw material quantity: Kilogram (default value))
- Jump: 20 Euro
- Surcharge: 1.20 Euro



Surcharge calculation based on jump

At the time of the price calculation, zinc is listed at 380 Euros. That is a price jump of 130 Euros compared to that calculated in the original price. The specified price jump of 20 Euros is exceeded 6 times, so a surcharge of 6 x 1.20 = 7.20 Euros is added to the item price.

4.5.5 Discount groups

Item prices are normally defined as net or gross prices with discount information. Discounts are specified by assigning items to discount groups. This applies to both purchase and selling prices, whereby the purchasing discount groups can be included in the data stock more for information purposes, as they are specified by the relevant supplier. The selling discount groups determine the customer prices, which are passed on to the customers as net prices or as gross prices with discount information. Your ERP system is responsible for managing this data. It is possible to transfer the price group information maintained in Product 360 Desktop into your ERP system, which should in any case be responsible for performing the necessary calculations. Your Product 360 Desktops consultant can provide you with more information about connecting Product 360 Desktop to your ERP system.

You can maintain purchasing and selling discount groups and the corresponding discount rates in the ***Discount groups*** perspective. In the default perspective display, the purchasing discount groups and their purchasing discount rates are situated on the left above one another and the corresponding views for the selling side are located on the right.

4.5.5.1 Purchasing and selling discount rates

Purchasing and selling discount groups contain discount rates that are valid for a limited time. Purchasing and selling discount rates are managed in tables in the ***Purchasing discount rates*** and ***Selling discount rates*** views, which are operated in exactly the same way. For each discount group, you can create one or more discount rates once you have selected a discount group. Discounts always have a fixed start time and a value.

1. For example, select a selling discount group in the ***Selling discount rates view.***
2. Click on ✚ in the ***Selling discount rates view.***
   - A new row is created in the table.
3. Specify the time from when the discount rate is valid.
4. Specify the discount rate.
5. Click on 💾 to save the data record.

To assign an item to a discount group:

1. Open the ***Context selection*** and ***Item #1*** views, e.g. in the ***Explorer (items)*** perspective.
2. Show the "Discount group (selling)" column using the "Field selection" dialog box – note that you must specify the customer for this field.
3. Select the relevant discount group from the drop-down list.

4.5.5.2 Purchasing discount groups

The ***Purchasing discount groups*** view is used to manage discounts that you have negotiated with your suppliers. As a consequence, you will normally maintain discounts for specific suppliers.

1. Click on ✚.
   - A new row is created in the table.
2. Assign a meaningful discount group number and a descriptive name. This information will help you to assign it to an item later.
3. Click on 💾 to save the data record.

Setting object rights for purchasing discount groups

1. Select the corresponding discount group.
2. Click on **Object rights**.
   - The dialog box for creating object rights opens.
3. Edit the object rights for the purchasing discount group.
4. Click on **OK**.

Once you have maintained one or more discount groups, you can assign the discount group to an item. Maintain the discounts for each discount group in the same way. If you have selected an entry in the ***Purchasing*** or ***Selling discount groups*** view, you can create new entries and edit or delete existing entries in the ***Purchasing and Selling discount rates*** view.

Tip: If you display the "Valid from" and "Discount rate" columns in the ***Purchasing discount groups*** view using the "Field selection" dialog box, Product 360 Desktop displays the discount rate that is valid on that date.

4.5.5.3 Selling discount groups

In the ***Selling discount groups*** view, you can create new discount groups for selling. A discount group must always be unique in terms of its discount group number. You must also specify whether the discount group applies to all customers or only to a specific customer. The view is operated in the same way as the ***Purchasing discount groups*** view.

4.6 Maintaining product data


In Product 360 Desktop, a product is a data record that is used as a container for items of the same type. You can think of a product of a kind of abstract general concept, which is turned into actual, specific items that can be ordered by adding properties, attributes, and features. For example, you cannot just buy a ticket - any ticket desk will ask you for at least the destination. However, you can buy a 2nd class train ticket for a single journey from Munich to Stuttgart. For this reason, you may

maintain different information for products than for items where required. Products are created and maintained exclusively in the master catalog.

Note: We would like to point out once again here that differentiated branching is required for some catalog concepts in order to map an existing network of relationships. In this case, for example, variants of a product are required, which "precede" the items in the hierarchy.

Note: Multiple items can be assigned to a product, but an item can only be assigned to one product. A product can reference another product, e.g. as a component of another product. You can classify products as items or maintain product attributes. Products and items are thus located at the same relationship level.

The ***Explorer (products)*** perspective is provided for maintaining products. The ***Explorer (products)*** perspective contains the ***Context selection*** view and also the ***Products #1*** view, which you can use in the same way as the familiar ***Items #1*** view.



Explorer (products)


In the ***Context selection*** view, you can display all products by selecting **Show products** in the master catalog pop-up menu. Alternatively, you can navigate in a structure system to display the products assigned to the structure groups.

By selecting a product, you refresh the ***All variants of product view.*** An item assignment or a product reference is created using drag & drop.

4.6.1 Creating products

To create products, you can either import them or create them manually. To import product data, use the procedure described under "Data import" 43.

Caution: When importing a product in the mapping, select the correct object type:



Object type for import mapping

You also have the option of creating products manually in the master catalog:

1. Switch to the ***Explorer (products)*** perspective.
2. In the ***Context selection*** 90 view, select **Show products** in the master catalog pop-up menu.
   - The products are displayed in the ***Products #1*** view.
3. Click on ✚.
   - This creates a new row in the table with a new, unique product number.
4. Enter the product data.
5. Click on 💾 to save the data record.

Tip: Make sure that you have not activated a table filter in this situation. If you have, a new entry will be created but may not be visible since it may be filtered out by the filter definition.

Creating a product via an item

You can create a new product by creating a product for an item. This is only possible with an item that has not yet been assigned to a product, as the item is automatically assigned to the new product.

1. Select the item.
2. Select **Generate product** in the pop-up menu.
   - A new product is created based on the item data and the item is assigned to the product.

4.6.2 Editing products

You work with products in the same way as with items. For example, you create a product assortment 147 in the same way as you create an item assortment.

You generally maintain products using the drag & drop method:

- Creating structure assignments 144
- Assigning items to products 144

- Creating product references
- Creating a multimedia attachment
- Maintaining product attributes

4.6.2.1 Creating structure assignments

To create a structure assignment for a product, either import the assignment or create an assignment manually. To create a structure assignment manually:

1. Open the relevant structure system in the ***Primary structure system*** view.
2. Display the products in the ***Products #1*** view.
3. Select a product.
4. Use drag & drop to drag the product to the structure groups to which you want to assign it.

You can check the result of your assignment by showing the "Structure assignments" column in the ***Products #1*** view. Make sure that you qualify the column correctly. You can also delete existing assignments here.

Note: An item automatically "inherits" the structure assignments of the product to which it is assigned.


4.6.2.2 Assigning items to products

An item can be assigned to just one product, while a product can have multiple items. The procedure for assigning one or more items to a product is as follows:

1. Open the ***Explorer (products)*** perspective.
2. Display the required products in the ***Products #1*** view, e.g., by navigating in the ***Primary structure tree view.***
3. Open the ***Items #1*** view, in which you can display the items you want to assign to a product.
4. Use drag & drop to drag an item from the ***Item #1*** view to a product in the ***Products #1 view.***

Note: An item automatically "inherits" the structure assignments of the product to which it is assigned.

You can check the result of your assignment in the ***Product variants*** view. This displays all assigned items for a product selected in the ***Products #1*** view. Alternatively, you can call up the pop-up menu for an item in the ***Items #1*** view and select **Show higher-level product**.



Product variants

The procedure for deleting an existing assignment of a an item to a product is as follows:

1. Select the item in the ***Referenced items of product view.***
2. Select **Delete product assignment** in the pop-up menu.
3. Confirm with **Yes**.
   - The assignment for the item is deleted.


Tip: If you have accidentally assigned an item to an incorrect product, you must first delete the product assignment for the item. You can then assign the item to a different product.

4.6.2.3 Creating product references

You need product references if you want to create or manage relationships between products. Typical examples of such relationships are as follows: One product is a spare part for another product, or two products are so similar that they can be supplied as alternatives to one another, etc. Various types of default relationships are provided in Product 360 Desktop.

The procedure for creating a product reference is as follows:

1. Open the ***Products #1*** view with the corresponding products.
2. Use drag & drop to drag the product to another product to which you want to assign the reference.
   - A dialog box opens, in which you can specify the reference type.



Product reference dialog box

3. Select the reference type:
   - Similar item: Two products are so similar that they could be supplied as an alternative to one another.

- Alternative order unit: A product is identical to another item, but it is sold in different order units.
- Component: A product is a component of another product.
- Cross-selling: Cross-selling of complementary products.
- Spare part: A product is a spare part for another product.
- Successor item: A product is a successor product for another product.
- Essential spare part: A product is an essential additional product for another product.
- Optional spare part: A product is an optional additional product for another product.
- Other reference: A product has a relationship with another product that is not specified in more detail.
- Up-selling: Reference to a higher quality or value product.
- Accessories: A product is an accessory for another product.

4. Click on **OK**.
   - The reference is created.

You can check the result of your assignment by selecting the product in the ***Products #1*** view. The product's references are then displayed in the ***References*** view. This view also includes the option of deleting product references.

4.6.2.4 Creating a multimedia attachment

To create a multimedia attachment, you can either use an import or create an assignment using drag & drop. To create the assignment manually:

1. Open the ***Explorer (products)*** perspective.
2. Display the required products in the ***Products #1*** view.
3. Also open the ***Documents*** view with the corresponding images.
4. If necessary, open the ***Document categories*** view to select the images for the ***Documents*** view.
5. Use drag & drop to drag an image to the corresponding product.
   - The dialog box for creating a new multimedia attachment is opened.

Then follow the same procedure as for maintaining multimedia attachments for items.

4.6.2.5 Maintaining product attributes

To maintain product attributes, you can use the ***Product attributes***, ***Product attributes (cumulative)*** and ***Products with features (specialized)*** views. The views are operated in the same way as the ***Item attributes***, ***Item attributes (cumulative)***, and ***Items with features (specialized)*** views.

The ***Product attributes*** view displays the existing attributes of a selected product in a table. In this view, you can create new product attributes and edit or delete existing attributes. As in the ***Item attributes*** view, you can use the "Field selection" dialog box to show the "Purpose" column. You use this column to assign a purpose to a product attribute.

The ***Product attributes (cumulative)*** view shows all shared features of the products selected in the ***Product #1*** view. You can add new product attributes to the selected products at once or transfer structure features as product attributes.

4.6.3 Product details (form)

The ***Product details (form)*** view can be used to display data for an individual product. By default, the view shows the following fields:

- Product no.
- Manufacturer product no.
- Manufacturer
- Short description (German)

The form display of information for a product is ideally suited for using custom product displays for particular purposes. For example, this view allows you to compose a form consisting of the two fields "Short description (English)" and "Short description (French)", which you can use to translate the short descriptions of the item.

Open the "Field selection" dialog box as in the table display and configure the form as required. You can use the Views menu to set whether the fields shown are displayed with one or two columns.

Note: You cannot directly edit the long description in this view. Click on **Edit...** to open the Rich Text Editor.

4.7 Assortments

Assortments are subsets of a catalog or master catalog, which you manage under a particular name. An assortment is made up of specific items, variants or products you have grouped for a particular purpose, e.g. for a publication. Think of an assortment as a view of your master catalog that includes or excludes certain items, variants or products. For this reason, assortments only specify which items, variants or products are to be included and which are not. Assortments are much more dynamic and flexible than structure systems and may be more temporary.

There are two different ways to define whether an item, variant or product is part of an assortment:

- Explicit: The selected item (variant or product) is saved in the assortment using its internal identifier.
- Dynamic as query: A query, on the other hand, saves the logic that serves to determine an item list, for example. This means that a query may change the set of items or products in the assortment if items that meet the conditions are added.

Both assortment rules can be used for inclusive and exclusive definitions. All inclusive rules are evaluated and added together first in the evaluation. The exclusive rules are then extracted. For example, you can define an assortment containing all items in structure group G1 (inclusive dynamic rule) but not items A1, A5 or A8 (exclusive explicit rule), even if these items are assigned to structure group G1.

Tip: Do not confuse assortments with your company's item groups. To structure your items or to divide them into item groups, use their classification.


Assortments are managed separately for each individual catalog or for the master catalog. Assortments exclusively contain references to products or items from the master catalog or an individual catalog. Therefore, an assortment can never be used to save an item or product from an area in which it is not managed. An item or product can be assigned to any number of assortments, or none at all. Assortments of the same name may exist, but not in the same catalog (or the master catalog).

Assortments must exist in advance of provision. For example, if you want to create a price list, you must first create the assortment before you can use it to output the price list. You can save assortments permanently and call them up repeatedly for later use.

4.7.1 Creating assortments

Note: You do not necessarily have to create an assortment first, i.e. you can create a new assortment during item or product assignment.

1. Select **Management > Item assortments**.
   - The dialog box for managing assortments opens.
2. Click on **New**.
   - A new blank assortment is created.




Creating a new assortment

3. Enter a descriptive, unique name. Bear in mind that you may want to manage a large number of assortments.
4. Enter a category. This makes it easier for you to manage assortments. When displayed, assortments are grouped into categories. Assortments that are managed without a category are automatically grouped together under the "<Not categorized>" node.
5. You can also specify a description that, e.g., identifies the purpose of the assortment.
6. Click on **Close**.

When you create an assortment, you have simply created a "container" in a catalog or master catalog, and given it a name that you can use to call up and use the assortment. This means that the assortment exists but it is still empty. This is indicated by the text "0 items", displayed on the right. You still have to add items or products to the assortment.

4.7.2 Adding an item or product to an assortment

1. Select the required items or products in the ***Item #1*** or ***Products #1*** view.
2. Select **Arrangement by assortment** in the pop-up menu. In the submenu, you can now add items or products to assortments or remove them from assortments.



Filling an assortment

3. Click on **Arrangement by assortment > Note selection in > More...** to open the selection dialog box for assortments and create an explicit assortment assignment.

4. Click on an existing assortment in this dialog to assign the selected items to the assortment. The last assortment used is displayed directly in the menu, allowing you to compile an assortment quickly.
5. You can also create a new assortment by clicking on **Manage**.

The following additional options are available for selection in the pop-up menu:

- Each ***Item #1*** (or ***Products #1***) view represents the result of a search (e.g., all items in a structure group). Regardless of the actual number of items (products), you can assign this query to a dynamic assortment by selecting **Arrangement by assortment > Note query in**. If items (products) are then deleted or their structure assignments change, the query result also changes. In this case, update the assortment to obtain the correct scope.

Note: When using search results in assortments, it is important to remember that the scope of the search results may exceed the number of items that can be displayed. However, all search items can be dynamically assigned to the assortment.

- Just as items (products) can be explicitly assigned to an assortment, they can also be excluded from an assortment.
- You can create a combination of an "explicit" and "dynamic" assignment, where the inclusive rules are evaluated first, followed by the exclusive rules. Any assortment can be described by a combination of inclusive and exclusive sets of items and individual items.

Tip: Check whether your requirements may already be met by your own saved searches.

4.7.3 Working with assortment filters


Der Product 360 Desktop remembers the setting for each individual catalog and for the master catalog, so that when you change contexts from one catalog to another or from a catalog to the master catalog, the last assortment filter used for the catalog or master catalog is applied in each case.

Activating the assortment filter

1. Select **View > Item assortments**.
   - The assortment selection dialog box opens.
2. Select the assortment to which you want to apply a restriction.
   - The dialog box is closed.
3. Reload the catalog or master catalog so that you can work with the activated assortment filter.
   - The assortment filter you selected is displayed in the status bar of the program window.

Deactivating the assortment filter

1. Select **View**.
   - The menu opens. The current assortment filter is shown below the "Item assortments" entry.



Deactivating assortment filtering

2. Click on the assortment filter entry to deactivate it.
3. Reload the catalog or master catalog to display it without an assortment filter.

4.7.4 Managing assortments

You can carry out other actions in the dialog box for managing assortments. The dialog box is opened by selecting **Management > Item assortments**.

Copying assortments

1. Select the relevant assortment.
2. Click on **Copy**.
   - A copy of the assortment is created. You can rename this copy or edit the assortment rules, for example.

Deleting assortment rules

1. Click on the arrow on the left of the assortment to expand it and display the assortment rules.
   - The inclusive and exclusive rules of the assortment are displayed, followed by the number of items to which these apply.
2. Select the rules you want to delete.
3. Click on **Delete**.
   - A confirmation prompt opens.
4. Click on **Yes** to delete the assortment rules.

Deleting an assortment

1. Select the relevant assortment.
2. Click on **Delete**.
   - A confirmation prompt opens.
3. Select **Yes** to confirm the confirmation prompt for permanently deleting the assortment.

Update assortment

1. Select the relevant assortment.
2. Click on **Update**.
   - The inclusive and exclusive assortment rules are evaluated and the assortment is updated.

Versioning an assortment

1. Select the relevant assortment.

2.Click on **Versioning**.

- The dialog box for version selection opens.

3.Select an existing version or create a new version.

4.Click on **OK**.

- The version is created and the objects that are to be assigned to this version are determined. A further dialog box informs you how many objects are affected.

5.Click on **OK**.

- The objects are assigned to the new version.

Setting object rights for assortments

1.Select the relevant assortment.

2.Click on **Object rights**.

- The dialog box for creating object rights opens.


3.Edit the object rights for the assortment.

4.Click on **OK**.

4.7.5 Views for assortments

The ***Item assortments*** view provides an overview of existing product assortments. Call up the view explicitly by selecting **Perspectives > Open view**.

You can use the "Source catalog" filter at the top of the view to determine whether only the assortments from the current catalog or all assortments are displayed. You can use the pop-up menu here to edit, update, duplicate, version or delete assortments, or to edit the object rights.



Item assortments

4.8 Versioning

Note: Versioning is only available to you if you have been assigned the necessary permissions by your administrator.

You can manage different versions of your data in the ***Versions*** perspective. Versions are used to "freeze" information at a particular point, so that you can continue to use the data in the working version. In a manner of speaking, the data in a version is "archived", e.g. for a print catalog, and the print catalog can be published unchanged at a later date. The following entities can be versioned:

- Item
- Products

- Structure groups and structures
- Price groups

If you version items, not only the items themselves are versioned but also their references, structure assignments and products. When versioning products or structure groups, however, these are versioned without the assigned items.

You do not work in versions themselves, you use the working version, i.e. you can only perform an import in the working version. You can release items or products in versions and thus edit the versions, provided they have not been closed. Once a version is closed, it cannot be modified.

The ***Versions*** view also shows you who created a version and when, and whether it is closed. You can use the pop-up menu for a version to:

- Close or re-open a version
- Create tasks
- Compare
- Specify object rights

4.8.1 Creating a version

There are two different ways to create a new version:

- Create a new empty version in the ***Versions*** perspective and then add data to it.
- First select the items or products and then create a new version in their context.


Creating a new empty version

1. Open the ***Versions*** perspective by selecting **Management > Versions**.
2. Click on ✚ in the ***Versions*** view.
   - A new row is created in the table.
3. In the new row, enter a unique identifier, a name and a description for the version.
4. Click on 🖫 to save the data record.
5. You can now add data to the version.

Creating a new version in context

You can create a new version by first selecting the items or products to be versioned.

1. For example, compile the required items in the ***Item #1*** view.
2. Select the items.
3. Select **Versioning > Add to selection to > More...** in the pop-up menu.
   - This opens the dialog box for selecting the version, which you can also use to create a new version.



Creating a new version

4. Select the "<Create new version>" entry from the drop-down list.
5. Enter an identifier, a name and a description for the version.
6. Click on **OK**.
   - The version is created and the objects that are to be assigned to this version are determined. A further dialog box informs you how many objects are affected.
7. Click on **OK**.
   - The objects are assigned to the new version.

4.8.2 Working with versions


The procedure for adding items to an existing version is as follows:

1. Select the required items, e.g., using an item search.
2. Select the items.
3. Select **Versioning > Add selection to > <Version>** in the pop-up menu.

Note: Similarly, you can use **Versioning > Remove selection from...** to remove items from a version.

If you want to add all items displayed to a version, you do not have to select all of these items. Use **Versioning > Add all objects to > More...** to version all of the items displayed.

You can switch between versions by calling up **View > Versions** from the program menu. You can then select the required version from a dialog box. The version that you are currently using is shown in the status bar of the program window.




Selecting a version

The fact that you are currently working in the context of an open version is indicated by the fields in the ***Item #1*** view, for example, being highlighted in yellow, while they are highlighted in gray for a closed version.

4.8.3 Versions and tables


You can use the "Field selection" dialog box to display columns with different versions by specifying the version as the field qualification:



Field qualification by version

However, you can also display or change the version in the context of individual columns. To do this, show the pop-up menu for the column header:

- **Versioning > Show > <Version>**: Shows an additional column with the corresponding version next to the selected column.
- **Versioning > Switch to > <Version>**: Switches the context from the currently selected column to the version selected.
- **Versioning > Compare with > <Version>**: Shows the corresponding version of the column next to the selected column, along with the comparison column.



Displaying a version

4.8.4 Closing a version

If you close a version, no new elements can be added to it and existing elements cannot be edited. The procedure for closing a version is as follows:

1. Under **Management > Versions**, open the ***Versions*** perspective.
2. Select the corresponding version.
3. Select **Close version** from the pop-up menu.
   - A query appears, asking whether you really want to close the version.
4. Confirm with **Yes**.
   - The version is closed. This is indicated by the key symbol in the “Status” column.

Note: If you subsequently want to make changes to a closed version, you must first explicitly open it again. You can open a version again by selecting **Open version** in the pop-up menu.

4.8.5 Deleting a version

Deleting a version means that you delete the version and all of the entities it contains. To do this:

1. Open the ***Versions*** perspective by selecting **Management > Versions**.
2. Select the relevant version.
3. Select **Delete** in the pop-up menu.
   - A confirmation prompt is opened to check that you really want to delete the version.
4. Confirm with **Yes**.
   - The version and all entities it contains are deleted.

4.9 Compare


In the ***Comparison view*** you can compare the different versions of items, products, structure groups, etc. with each other, but also different items, products, structure groups, etc. Differences are highlighted in red in the view and the first content column acts as a basis for the comparison.

Note: For performance reasons, only a maximum of 20 elements can be compared in the view.

The procedure for comparing different versions of an item with each another, for example, is as follows:

1. Select the item in the ***Item #1*** view.
2. Select **Compare > Different versions...** from the pop-up menu.
   - A dialog box opens, showing a drop-down list of versions.
3. Open the drop-down list.
4. Select the version by using a check mark to indicate which version you want.
5. Click on **OK** in the drop-down list.
6. Confirm the dialog box by clicking on **OK**.

➪ The ***Comparison view*** opens.



Comparison view

As is the case in the ***Merge preview***[79], you can open all nodes in the "Data type" column or only display the rows containing differences. The following icons are available in the view:

- : Opens all nodes in the "Data type" column.
- : Closes all nodes in the "Data type" column.
- : Select which nodes you want to display in the "Data type" column.
- : Reduces the display to those data records that have different content.

Tip: To change the reference basis, simply drag the column that you want to be the new reference basis to the left so that it is the first column after the "Data type" column.

Comparing different items

The procedure for comparing two different items with one another, for example, is as follows:

1. Select the two items in the ***Item #1*** view.
2. Select **Compare > With one another** from the pop-up menu.
   ➪ The ***Comparison view*** opens and shows the comparison of the two items.


4.10 Preview function

To make it easier for you to assess the completeness or quality of your data, the latest version of Product 360 Desktop includes a function that provides a visual representation other than tables or forms. Product 360 Desktop enables you to display **products**, their **variants**, **items**, and **structure groups** in a browser-based preview at a click of the mouse.


The previews are defined as[export format templates][291] and identified by the **Preview** purpose. Depending on the setting, they can either apply to individual selected objects or to a multiple selection. They can be accessed by selecting **Generate preview** from the pop-up menu in the object table corresponding to their data type, and can be executed directly. The operating system's default browser opens with the preview after a short delay.

As a preview always involves using a different amount of RAM, the system puts in place certain limitations. For example, the default **maximum number** of data records is defined as **100**. If more data records are selected, the preview is grayed out and is thus inactive. If it takes too much time to create the preview (currently a maximum of 20 seconds), the action is also canceled. An error message tells you the reason.

Preview examples



Preview as detail view



Preview for multiple selection

4.11 Lookups

Lookups define a particular set of permitted values for a specific data field. For example, a lookup “Countries of origin” contains all available countries that a business user can select when specifying

a value for a data field to which the lookup is assigned.

The Lookups perspective enables you to create and manage your own lookups.

1. Open the ***Lookups*** perspective by selecting **Perspectives > Open > Standard > Management > Lookups**.
2. Click on ✚ in the ***Lookups*** view.
   - A new row is created in the table.
3. Enter a unique identifier in the new row.
4. The following additional information can be specified:

Name	**Any text**	**Language-specific name**
Name scheme	Code Code name Name Name (code)	The display of the values changes when the list is opened depending on the selected setting.

5. Click on 🖫 to save the data record.

Adding values

6. Open the **Values - "Name of lookup"** view in the ***Lookups perspective.***
7. Click on ✚ in the ***Values*** view.
   - A new row is created in the table.
8. Enter a unique code in the new row.
9. The following additional information can be specified:

Active	Only active values are displayed in the rest of the application.
Code (system selectable)	Option for specifying a code for other systems
Name	Language-specific name
Sequence	Specifies the sequence within the list.

Editing values

You can edit the existing values directly in the Values “Name of lookup” view.

1. To do this, click in the relevant field.
2. Enter the desired data.
3. Saving is automatic when you click to exit the field.

Deleting values

You can delete existing values using the “Delete” option in the pop-up menu or by pressing the Delete key.

5 Data quality checks

To optimize your product data management, it is not just essential that you always know the latest processing status of all products and items and their relationships. The quality of the data is also extremely important. Since a product information management system brings together information from a variety of employees and from different suppliers from multiple sources, it is essential for commercial success to optimize the quality of the data at regular intervals.

What does data quality mean?

Criteria for the quality of data include the following:

- Correctness: The data must represent the actual situation.
- Consistency: A data record may not contain any contradictions within itself or with other data records.
- Reliability: The origin of the data must be traceable.
- Completeness: A data record must contain all the necessary attributes.
- Accuracy: The data must have the required degree of precision (example: number of decimal places).
- Up-to-datedness: All data records must represent the current situation of reality.
- Freedom from redundancy: There must not be any duplication within the data records.
- Relevance: The information provided by data records must correspond to the information required.
- Consistency: The information in a data record must have a uniform structure.
- Unambiguity: Every data record must allow unambiguous interpretation.
- Comprehensibility: The concept and structure of data records must meet the expectations of specialist departments.


The latest version of Product 360 Desktop has an integrated Informatica Data Quality component. This means:

- ✓You can now apply defined rules and adapt them to your requirements.
- ✓You can initiate quality checks on your data from different situations.
- ✓A status shows the resulting "condition" of your data and can be used as a criterion for a subsequent checking process or for creation of assortments and tasks.
- ✓It is also possible to optimize data for output in particular channels by configuring specific checking processes.

5.1 Definitions

Data quality criteria


Quality checks monitor compliance with particular standards relating to data quality management. Their relevance always relates to the specific purpose and only monitors compliance with all criteria in very rare cases.



The process is either completion, update, error resolution or standardization. Every analysis shows the variations and provides an opportunity to implement a targeted remedy.

Natural Language Processing

Because much of the information in PIM systems takes the form of unstructured text, the system must find a way to provide this data for the analyses. For some rules, an area of computer linguistics (NLP = Natural Language Processing) is used to prepare the data accordingly.



Levels of understanding in natural languages


As before, the steps in sequential preparation depends on the set rule, i.e. the purpose. Country-specific linguistic and cultural rules are taken into account at all stages.

5.2 Quality rule overview

Quality rules are saved as fixed, configured checking specifications and therefore can be used repeatedly. They are tailored to characteristic situations that can be used to maintain data quality. The following situations are possible:

- Incorrect values
- Invalid values
- Missing values
- Duplicates
- Incorrect assignment

All quality checks are managed using the ***Data quality*** perspective.



Perspective with all views for managing quality checks

This is called up by selecting **Perspective > Open > Management > Data quality**.

The output channels are created as an accordion in the left-hand section of the screen. This means that the tabs for the channels open horizontally when you click them. The right-hand section of the screen contains the "Data quality configuration" and "Data quality scheduling" tabs.

Below is an overview of the meaning of the individual icons:


Icon	Meaning
	Category for classification of rules
	Grouping of rules
	Individual rule with the set descriptions and parameters

The quality rules maintained in Product 360 Desktop can relate to all data objects. As a source and a target are always necessary for data cleansing, there is an input port and an output port. Both of these must refer to the same data type. However, rules for data output can relate to subordinate units of the same data type. For security, these are automatically referenced and provided for selection.

The following sections describe how to modify or create quality checks, adapt them for specific output channels, or schedule them.

5.3 Creating quality rules

All rules for quality checks are created and edited in the ***Data quality*** perspective. In this perspective, you can edit one or more rules. This is called up by selecting **Perspective > Open > Management > Data quality**. The "Data quality configuration" tab is active by default and provides the required environment.



View for creating and managing quality checks

Below is an overview of the meaning of the individual icons:

Icon	Meaning
	Opens the input area for creating a new category
	Opens the input area for creating a new rule group
	Opens the input area for creating a new rule
	Saves the modifications made
	Discards the modifications made or deletes the currently selected data record

Note the following:

- All fields ***followed by*** "*" are mandatory fields in which an entry must be made.
- Data records ***preceded*** by an "*" are currently being edited. Saving is carried out automatically when you exit the view but it can also be explicitly carried out manually at any time.

Caution: For a better overview, the rules are combined into groups and assigned to categories. When you create new rules and they cannot be incorporated into an existing category or group, it is necessary to create at least one new category.

Creating new check categories

To create a new category:


1. Click on .
2. Enter a descriptive name and a brief description in the corresponding fields.
3. Confirm your entries with or discard them .

Editing existing rules

Before creating new rules, you should check whether you can use any existing rules. You can also select and edit multiple rules.

To edit existing rules:


1. Select a category in the "Data quality configuration" view.
2. Right-click to open the pop-up menu.
3. In the pop-up menu, you can:



Create new rule groups

To create new rules:

1. Select a category in the "Data quality configuration" view.
2. Click on .
3. Enter a descriptive name and a brief description in the corresponding fields.



Creating a new rule group

4. Specify the data type and therefore the object for which the rule group will apply.
5. Confirm your entries with or discard them .


Creating new rules

To create new rules:

1. Select a group in the "Data quality configuration" view.
2. Click on .
3. Enter a descriptive name and a brief description in the corresponding fields.
4. Select to open the selection dialog box.
   - The dialog box provides you with the option of selecting from existing rules. All configured parameters are displayed. You can also add your own rules and any required reference files.

Caution: Creating your own rules requires knowledge of Informatica Data Quality.

5. Select the relevant entry and confirm with **OK**.
6. All settings for the selected rule are transferred.



Creating a new rule

7. The outputs themselves can be directly assigned to fields. You can do this by calling up the field selection dialog box.
8. Confirm your entries with or discard them .

Defining individual fields for the input port

Some application scenarios must not be implemented with preconfigured rules. Instead, individually defined data structures should be accessed. In Product 360 Desktop, you can define the field for the input port yourself. The following scenarios are possible:

1. You select a rule from the category "Unstructured Text". As in the above image, the "Field" column is blank and can be filled with any data (similar to using a text editor).
2. If you do not want a field entered by another user to apply to your situation, you can click on ... to open the selection dialog box.
   - Here, you can access and select predefined fields for your rule.
3. To make your own field entry, you must click on to remove this assignment. Then, access the rule again and make the relevant changes.

5.4 Maintaining reference data

Some quality rules reference data such as standardization dictionaries, for example, in order to standardize item colors, to remove disallowed words such as profanities from the item content, or to standardize the spelling of manufacturer names. After you create such rules, you must import the

reference data into the system. You can then maintain this data at a later time, if required.

Importing/updating reference data

The reference data or standardization dictionaries are imported via the configuration of the data quality rules being referenced. Imported reference data can also be updated in this way.

Note: The standardization dictionaries to be imported/updated must have the file format DIC and must contain a maximum of two columns. All of the standardization dictionaries to be imported/updated must be packed into a ZIP file.

Standardization dictionaries are imported or updated in the ***Data quality*** perspective, which you can call up by selecting **Perspective > Open > Management > Data quality**. The procedure there is as follows:

1. On the "Data quality configuration" tab, select the rule category and its rule group, which contains the rule in question.
2. Click on ... after the rule name.
3. Click on **Add reference data from file**.
4. Select the ZIP file that contains the standardization dictionaries to be imported.
   - The standardization dictionaries contained in the file are listed in the "Adding reference data" dialog box. Standardization dictionaries with more than two columns are marked with a preceding ⊗ icon.
5. In the "Action" column, select what you want to do with the relevant standardization dictionary. The following options are available:

Action	Description
"Import"	The standardization dictionary is imported. It is used to evaluate the rules being referenced, and it can be viewed and maintained in the Product 360 Desktop user interface.
"Copy"	The standardization dictionary is copied to the Product 360 Desktop server. It is used to evaluate the rules being referenced, but it cannot be viewed or maintained in the Product 360 Desktop user interface.
"Ignore"	The standardization dictionary is neither imported nor copied.

6. If you select the "Import" option, you must also select the relevant import mode in the "Import mode" column. The following import modes are available:


Import mode	Description
"Import or update all objects"	All dictionary entries are imported. If the standardization dictionary is already in the system, all existing dictionary entries are overwritten.
"Import new objects only"	If the standardization dictionary is already in the system, only the new dictionary entries are added. During the initial import, all entries are imported.

Import mode	Description
"Update existing objects only"	If the standardization dictionary is already in the system, only existing dictionary entries are overwritten. New entries are not added. During the initial import, all entries are imported.

7. If you select the "Import" option, you can use the "Synchronize" checkbox to determine whether the standardization dictionary is to be used in data quality checks performed immediately after the import. If you do not set a check mark, the standardization dictionary is imported but not yet used in the data quality check. You can then activate the standardization dictionary at a later time.
8. Click on **OK**.
   - The standardization dictionaries are imported into the system.

Maintaining standardization dictionaries

The standardization dictionaries imported into the system as described above can be viewed and maintained in the Product 360 Desktop user interface. They are maintained in the ***Dictionaries*** perspective, which you can call up by selecting **Perspective > Open > Management > Dictionaries**.



Standardization dictionaries

The ***"Standardization dictionaries"*** view lists the standardization dictionaries available in the system. In addition to the unique identifiers, the language-specific names and descriptions of the standardization dictionaries are also listed. The "Synchronized" column displays whether, in the event of changes to a dictionary, the changes have already been transferred to the system.

In this view, you can:

- **Create new standardization dictionaries**: To do this, click on ✚ and enter a unique identifier.
- **Delete standardization dictionaries**: To do this, select the standardization dictionary that you want to delete, select **Delete** in the pop-up menu, and confirm deletion.
- **Synchronizing/activating standardization dictionaries**: If you have made changes to a standardization dictionary, or if you want to activate a standardization dictionary after you have imported it, select the relevant dictionary and click on .

The ***Entries*** view lists the dictionary entries contained in the standardization dictionary selected in the ***Standardization dictionaries*** view. A dictionary entry comprises a unique value and a standardized value. The standardized value is the value that replaces the unique value by means of the quality rule referenced during a quality check. The above figure is an excerpt from a standardization dictionary for color standardization. In this example, the value "dark red" is replaced with the value "crimson" during a quality check. The standardized value does not have to be unique. In the above example, the value "scarlet" is also replaced with the value "crimson".


In this view, you can:

- **Create new dictionary entries**: To do this, click on + and enter a unique value and the standardized value.
- **Delete dictionary entries**: To do this, select the entry that you want to delete, select **Delete** in the pop-up menu, and confirm deletion.
- **Activate/deactivate dictionary entries**: You can set or remove the check mark in the "Active" column in order to decide whether or not an entry is to be taken into consideration during a quality check.

5.5 Planning quality checks

Note: You can perform quality checks when required by using the pop-up menu for a selected data record. This section explains how to define and configure particular dates or events that trigger a quality check.

You can create and edit all the triggers for quality checks by using the ***Data quality*** perspective. To open the ***Data quality*** perspective, click **Perspective > Open > Management > Data quality**. Switch from the Data quality configuration tab that is activated by default to the Data quality scheduling tab.



The following table describes the available triggers for planning quality checks:

Icon	Meaning

	Time controlled: Initiates a quality check at a particular date, as a one-off or at specified intervals.
	Entity changed: Initiates a quality check when an entity is changed.
	Entity created: Initiates a quality check when an entity is created.
	Export started: Initiates a quality check to filter the data before it is exported.
	Import completed: Initiates a quality check after an import operation has completed. If you completed the import operation automatically using a hotfolder configuration, ensure to specify the defined import profile.
	Merge completed and Merge started: Initiates a quality check before or after a merge operation.

Note the following:

- All fields ***followed by*** "*" are mandatory fields in which an entry must be made.
- Data records ***preceded*** by an "*" are currently being edited. Saving is carried out automatically when you exit the view but it can also be explicitly carried out manually at any time.
- Catalogs can be defined as ***fixed*** values by selecting one from the selection field.
- However, catalogs can also be defined as ***dynamic*** values by selecting your specified default catalog.

Creating a new trigger for quality checks

To create a new trigger for quality checks:


1. Select a category in the "Data quality scheduling" view.
2. Click on ✚.
3. Enter a descriptive name.
4. Select the relevant data type from the selection field.
5. Scheduling is carried out in the same way as export planning and can be one-off on a particular date, or repeated at a specified interval.
6. Now set the data to be checked by selecting an appropriate query that is automatically related to the specified data type.
7. As additional selection criteria for specifying the data to be checked
   A. you can specify a catalog for a particular query
   B. or optionally choose a channel with rules already assigned. To do this, you can select the channel from the selection window in the right-hand section of the window
   ⇨ and all assigned rule groups and rules are already activated.
8. Confirm your entries with 💾 or discard them ✖.

Differentiating import and merge as triggers for quality checks

Both importing and merging data require a destination. This can be the master catalog or any other catalog of your choice. The relevant referenced supplier can be specified as an additional condition.


5.6 Specifying quality checks for particular channels

A multi-channel distribution strategy supports the objective of being able to reach customers using different communication methods. It is possible to implement stationary multi-channel systems, which concentrate exclusively on management of multiple sales lines, or to allow output in various media formats, from which customers can select the most appropriate for them. In both cases, it is important for quality checks to take into account the characteristic differences.



Types of different output options for corresponding channels

You can do this using the "Data quality" perspective. This is called up by selecting **Perspective > Open > Management > Data quality**. All output channels are created as an accordion in the left-hand section of the screen. This means that the tabs for the channels open horizontally when you click them. An unsorted list of all channels appears at the top of the screen. Each of the tabs contains a subset assigned to a particular channel category. To give a user or a user group access to a channel, you can assign them object rights.



Channel view

Information: By default, the categories relate to the most frequently used sales channels. If you want to extend them, they can be edited using the "Repository module".


Below is an overview of the meaning of the individual icons:

Icon	Meaning
✚	Opens the input area for creating a new channel.
↩	Returns to the channel overview.
✖	Discards the modifications made or deletes the currently selected data record.

Creating new channels

To create new channels:

1. Select a category in the "Channels" view or remain in the directory if you do not want to make an assignment yet or no applicable assignment is currently available.
2. Click on ✚.
3. Enter a descriptive name and a brief description in the corresponding fields.




Creating an output channel

4. Add the required logo by clicking on **Browse...** to open the Windows file manager and then selecting the memory location of the image.
5. Confirm your entries with **OK** or discard them with **Cancel**.
   - The file manager dialog box is closed.
6. If you already know which category the channel is intended for, select it from the selection field. Otherwise, the channel remains uncategorized in the directory.
7. Confirm your entries with **Save** or discard them with **Cancel**.
   - The dialog box is closed.

Assigning rule categories, groups or individual rules

To assign rule categories, groups or individual rules:

1. Select the relevant entry in the "Channels" view.
2. Double-click on this entry.



Channel with assigned rules

3. You have the following options:

   A. Use the filter to search for a specific rule and then activate/deactivate it.

   B. Carry out the activation/deactivation directly in the relevant rule groups or rules

   C. Selecting a category
      - means that all assigned rule groups and rules are already activated.
4. Use to return to the channel overview, and all changes are automatically applied.

Note: The visibility of the rules is influenced by the channel's object rights. Specifically:

1. A user only sees all rules that are used in their channels.
2. A user sees all rules that are not assigned to any channels.

Below is an overview of the meaning of the individual icons:

Icon	Meaning
	A defined area of a category is selected.
	The relevant rule is active.
	The relevant rule is inactive.
	Category for classification of rules
	Grouping of rules
	Individual rule with the set descriptions and parameters

5.7 Performing quality checks

Quality checks can be initiated in different ways:


1. by a defined event or on a fixed date, or
2. by a direct request

We described the first case in a previous section. Here we will describe how you can perform a direct quality check.

Performing direct quality checks

1. Open a perspective containing the objects you want to perform a quality check on.
2. Select the data records you want to check.
3. Select **Execute data quality rules** in the pop-up menu.

   The following dialog box appears:



Setting parameters for quality rules

4. You have the following options:

A. Use the filter to search for a specific rule and then activate/deactivate it.

B. Carry out the activation/deactivation directly in the relevant categories or rule groups

C. Select one or more channels (

➪ means that all assigned rule groups and rules are already activated.)

5. Confirm your entries with **Execute** or discard them with **Cancel**

➪ The dialog box is closed.

5.8 Determining the status

You can open a complete overview of all quality checks by selecting **Management > Process overview**. This lists all checks based on your configuration and shows the current process status. The log displayed below provides you with an insight into messages and notifications listing precise information about the progress of the checks.

Status of the referenced object

You will primarily want to perform a quality check for items or products. Therefore, the specific views for items and products (e.g. ***Item#1***) include an option to display the current status of a check. For all other objects, the procedure is essentially the same.


You can use the field selection dialog box to display additional fields showing the following information:

<table>
<tr><th>Field</th><th>Meaning</th></tr>
<tr><td>Quality message (rule selectable)</td><td>Shows as a text message relating to the selected rule. It is also possible to specify reasons as to why a rule could not be applied or executed.</td></tr>
<tr><td>Quality status (rule selectable)
Quality overview (channel selectable)</td><td>Shows a symbol representing the status, relating to the selected rule or channel.
<table>
<tr><th>Icon</th><th>Meaning</th></tr>
<tr><td></td><td>The check has been performed with no errors.</td></tr>
<tr><td></td><td>The check has detected errors.</td></tr>
<tr><td></td><td>Object not fully checked, or object has been modified since last check.</td></tr>
</table></td></tr>
</table>

This enables you to selectively perform a direct quality check on particular data.

Status overview

To enable you to gain an overall impression of current quality checks, the ***Overview (items)*** perspective has been extended to include the "Quality status" view.



List of all statuses for data quality checks

Meaning of fields in detail:

Field	Meaning
Channel selection	All channels: All quality check results for the selected item are displayed. The results for all channels are displayed first, followed by all other results not assigned to a channel.
	Selection of a particular channel: All available quality check results for this channel for the selected item are displayed. In addition, an icon indicates that checks are still expected for particular rules. 
Rule	Specifies the name of the rule assigned in the definition.
Description	The description of the rule entered in the definition is displayed here.
Status	Symbol for the status of the executed rule
Message	Text output for the status and any error messages. For improved clarity, you can open this in a separate window by double-clicking.
Ignore	Under certain conditions, you can ignore the check results. Activating ☑ then logs the following information in the subsequent fields: who initiated this exclusion and when. Ignoring a rule has an effect on the quality overview. An ignored rule is assessed as a rule with the result "OK".
Score	For language identification rules, a match factor is specified here, which should be viewed as equivalent to a percentage correspondence.
Channels	All channels for which the relevant rule is to be applied are shown here.

Field	Meaning
Last execution	The date of the last execution enables you to assess whether and when a repeat check is necessary.


6 Multimedia data maintenance

Information: You can manage multimedia files using the **Media Asset Manager** or **Informatica MDM - Product 360 - Media Manager**. The basic differences are described here. If no explicit system is specified, the description applies to both systems.

You can maintain multimedia data without taking account of a reference to items. You can also link multimedia files directly to items, products, their variants or structure groups. Therefore, there are two different perspectives that provide you with the required views and data for each of these scenarios.

If you want to manage existing multimedia files, select the ***Documents perspective.*** In this perspective, you analyze the dependencies between the multimedia documents stored on the Media Asset server, in other words, you can check where a certain document is used. This perspective contains the following views:

- ***Document categories*** (top left)
- ***Documents*** and ***Miniature view (documents)*** (top center)
- ***Image preview*** (top right)
- ***Dependencies*** (bottom)




Documents

To assign multimedia attachments to items, use the ***Multimedia attachments*** perspective, which contains the following views:

- ***Context selection***, ***Item search***, ***Primary structure tree*** and ***Document categories*** (top left)
- ***Items #1*** (top right)
- ***Documents*** (bottom left)
- List of ***multimedia attachments*** for the selected item (bottom center, upper section)
- List of ***multimedia documents*** (bottom center, lower section)

- ***Image preview*** (bottom right)



Multimedia attachments

6.1 Multimedia data management systems

Media Asset Manager

Informatica MDM - Product 360 enables you to choose between two systems for maintaining and managing your multimedia documents. One option is the **Media Asset Manager**, which is based on the principles of a file management system. This means, for example, that deleting a document category always implies also physically removing the files it contains. Product 360 Desktop itself accesses multimedia attachments using this interface. Using the Media Asset Manager enables external software systems to be connected easily.

Product 360 Media Manager

As part of the Informatica MDM - Product 360 solution, Product 360 Media Manager enables you to consistently manage and edit all multimedia files that are required in a product information system. It has its own online help or user manual for the individual functions. Here, we are going to take a look at the interface functions in Product 360 Desktop.

⚠ Caution: For information on connecting software systems to the Media Asset Manager, contact Informatica Corporation or an authorized Product 360 Desktop partner.

6.2 System settings

Select **Management > Settings > Multimedia attachments** to access the screen on which you can change the settings for editing multimedia files or restore the default settings. The various

topics are grouped into corresponding subdirectories such as:

- Image preview:
  You can assign your own background color and select the image preview size here.
- Media portal connection:
  You can activate/deactivate whether you want confirmation prompts to be displayed for the following steps here: assigning documents to other categories, removing or moving category references. Here, you also set the maximum number of documents to be displayed per page in the ***Documents*** view. By setting this restriction, you lighten the load on the RAM, as only the specified number of documents needs to be made available and all the other documents are only activated when further pages are loaded through browsing.
  - The information for the Product 360 Media Manager server is saved in the subdirectory.
- Miniature view:
  The parameters for the miniature view relate to their maximum number and the number of columns per page.
- Multimedia attachments:
  Here, you determine which file types from Product 360 Desktop are to be recognized by their file extension and accepted as a multimedia attachment.

6.3 Multimedia overview

Catalog items contain not only raw data but also additional information, e.g. in the form of images or text documents. This information is referred to as MIME (MIME = Multipurpose Internet Mail Extensions, an Internet standard). The terms "MIME data", "MIME information" and "multimedia attachments" are often used synonymously.

You are normally provided with MIME data by the manufacturer in electronic form and assign this data to the items. If you are the manufacturer, you either create this MIME data yourself or have it created by an agency. In concrete terms, you must then carry out the following work steps:

- Copy MIME data to the system
  You must always import MIME data into the system if you want to transfer new or updated data to Product 360 Desktop.
- Compare existing and new MIME data supplied
  Once you have transferred new MIME data to Product 360 Desktop, you must check it against the existing data and replace as necessary.
- Create additional formats
  Depending on the output destination for the item data, the MIME data needs to be available in different formats. For electronic catalogs, the high quality large images suitable for printed catalogs need to be used to create smaller Internet-compatible image files. From an existing Word document, you can create Internet-compatible PDF documents (e.g. safety data sheet).



- Edit MIME data
  If the existing multimedia files do not meet your requirements, edit them as necessary. For example, correct the resolution of an image to optimize it for a specific purpose.
- Organize the MIME data in the system (category, file name)
  To facilitate clear management of the required information and to make it quicker to find what you need, the MIME data is stored in a hierarchical structure.
- Link MIME data to items
  In order to be able to use the multimedia information for electronic catalogs or publications, link it to the associated items or products.


Example: You want to provide a series of items in a French language online store with images. For this, you need image files that are optimized for display on the Internet and alternative French texts, which are to be displayed as a tooltip when the user moves the mouse pointer over the image. In contrast to this, you need entirely different image information if you want to output the same items for a printed English language catalog. Depending on the output destination, you therefore need different quality levels ("Internet" or "Print") and language versions (French or English) for the same image motif.

Multimedia attachments can be maintained independently of assignments to items. You can also assign the same multimedia attachment to several items, for example. In this way, you have the option of separating multimedia data maintenance on the one hand and item data maintenance on the other. It is also possible to use your own multimedia attachments for each item.

Note: If you want to use the multimedia attachments for several items, remember that changing a multimedia attachment affects all of the items linked to it.

6.3.1 Document categories

To structure multimedia documents, you can maintain document categories and assign documents to them. The available categories are displayed in a tree in the ***Document categories*** view. The green main node "hlr-system" corresponds to the document category that is assigned to the master catalog by default.



Document

Open the pop-up menu:



1. Select **Perspectives > Open view**.
2. Select Media asset file.
3. Right-click on a media asset file.
   - The pop-up menu opens.

Note: You cannot use names beginning with "hlr_" for custom categories. Likewise, you cannot use names that are invalid in your operating system,
e.g. those containing characters such as "/", "\" or "?" and "*". The length must not exceed the operating system's maximum length (e.g. 255 characters).

The document categories are maintained using functions, which you either call up using the pop-up menu for a particular category or in the free area of the view. For example, a category can include the multimedia data for a supplier catalog. There may be other subcategories below it for organizing the files, e.g. according to their purpose.

Note: Bear in mind that you must have corresponding rights for most of the functions in the file system.

Function	Meaning
Copy	Copies a selected category to the clipboard (to then paste under another category).
Paste	Pastes a category including any subcategories from the clipboard to the selected category as a subcategory. (This is not possible if a subcategory with the same name already exists there).
Delete	Deletes the selected category and all subcategories. **Note that this corresponds to deletion in the file system.**

Function	Meaning
	This confirmation prompt informs you about the use of the category you are about to delete. If documents in the document category are referenced, you can display the details. If you confirm the deletion, all existing references to the documents to be deleted will also be deleted.  **Deleting a referenced document category** Note: If you work with Product 360 Media Manager, this does not mean that there is any physical deletion as the categories are used primarily as reference containers. Any uncategorized multimedia attachments are filed automatically in a directory with the same name and are therefore also available via the tree view.
Refresh	Re-imports the directory from the Media Asset server and displays the structure in the view. **Remember that the directory structure could also have been edited by external programs.**
Rename	Renaming a category If the category is referenced, a dialog box is displayed showing how many items will be affected by renaming the category. If you confirm the renaming, all references will be updated.  **Renaming a referenced document category**
Create preview images	If you have selected a node, preview images are created for all (registered) data types below the selected node. Converters must be available to create these images. By default, preview images can be created for the following data types: GIF, JPG, TIF, PNG and BMP.

Function	Meaning
	Additional data types are possible by integrating the corresponding libraries. Any licensing issues may have to be clarified in order to be able to use such libraries. Preview images are created in four different sizes (default setting): • "Thumbnails": Very small images that can be displayed in tables, for example. • "Miniature images": Small images with a standard size of 100 x 100 pixels, which are used in the ***Miniature view*** 190. • "Large images": Cannot currently be viewed in the user interface, default setting is also 100 x 100 pixels (not currently used) • "Standard preview images": Standard size, same size as original image but with a lower color depth (72 dpi), used in the ***Image preview*** 185 view The settings for the sizes and color depths used for the calculations can be made by your Product 360 Desktop consultant.
Add category	Creates a new category at the highest level.
Add subcategory	Creates a new subcategory below the selected category.

If you want to change the structure of the document categories, drag and drop the category to be copied or moved to the desired location in the tree.


At the same time, you must decide whether the category is to be copied or moved together with all its subcategories and documents. A category is copied by default, which is indicated by the mouse pointer turning into a plus symbol. If you want to move the category, press the Shift key while dragging and the plus symbol will disappear.

If you move a document category, all existing references will be adjusted. When copying, all existing files are copied to the new category. The existing references are retained.

6.3.2 Media asset file

Note: The Media asset file view is only available if you are using Product 360 Media Manager.

The Media asset file view displays all media files in a document category. In the Media asset file view, you can search for particular attributes.



Media asset file

Opening a media asset file:

1. Select **Perspectives > Open view**.
2. Select Media asset file.
3. Double-click on the required media asset file.
   - The file is opened in an external program.

Which application is selected for which file format can be set in the preferences under "Multimedia attachments"258.

If you are looking for information, you will find more details about the advanced search function under Advanced multimedia data search193

Media asset details (form)


The Media asset details (form) view enables you to edit the meta data for a media asset.

Select **Perspectives > Open view**.

- The view selection dialog box opens. The views are displayed organized into categories.

Open the Media asset details (form) view in the "Documents" category.


- The view selection dialog box opens. Select Media asset details (form).



6.3.2.1 Documents

This table view shows you all the files in a document category, regardless of whether or not the files are actually used.

Note: Bear in mind that you will not see the overall list of all documents here, only those in the selected document category, i.e. if the category contains subcategories, the documents in the subcategory are not displayed.



Documents

In the Views menu, you can call up a filter that only shows the images that are actually used (**Show used**), or that only shows unused images (**Show unused**).

You can set the size of the preview images in the preferences under "Miniature view". As in other tables, you can use the "Field selection" dialog box to show or hide columns.

Note: The columns in the ***Documents*** view may vary depending on the Media Asset Manager used.

If you want to view a file that does not represent an image or if you want to open an image in a new window:

1. Select the entry in the ***Documents view.***

2.Select **Open** in the pop-up menu.

➪ The file is opened in an external program.

Which application is selected for which file format can be set in the preferences under "Multimedia attachments".


6.3.3 Dependencies

The ***Dependencies*** view shows the references for a multimedia document in the different areas.

1.Select a multimedia document in the ***Documents*** or ***Multimedia documents view.***

2.Select **Usage list** in the pop-up menu.

➪ The ***Dependencies*** view is opened and shows how many objects reference the selected multimedia document.




Dependencies for a multimedia attachment

Tip: If you call up the pop-up menu for an entry, you can use the relevant options, e.g. **Show items** to display the relevant items in the ***Item #1*** view.

6.3.4 Multimedia attachments

This list contains all multimedia attachments that have been assigned to the selected item or structure group.



Multimedia attachments (items)

Note: Note that multimedia attachments must be distinguishable by their type so that they can be uniquely identified.

In the "Category" column, you can enter text or keywords that describe the relevant multimedia attachment in more detail. This category can be useful if you want to find multimedia attachments later by filtering by this field.

To create a new multimedia attachment:

1.Click on ✚.

➪ A new row is created in the table.

2.Select the multimedia attachment type from the drop-down list in the "Type" column.

3.Enter additional data for the multimedia attachment.

4.Click on 🖫 to save the data record.


6.3.5 System multimedia attachments

This list shows all the multimedia attachments that are present in the system. In the "Category" column, you can enter text or keywords that will describe the respective multimedia attachment more fully. This category can be useful if you want to find multimedia attachments later because you can filter by this field.

Note: Note that multimedia attachments must be distinguishable by their type so that they can be uniquely identified.

6.3.6 Multimedia documents

This list displays all multimedia documents that exist for the entry selected in the ***Multimedia attachments*** view. As in the ***Documents*** view, you can show a preview of the image here.



Multimedia documents

The multimedia documents that belong to a multimedia attachment must be different in terms of their quality or their language.

6.3.7 Image preview

This view shows the image that has been selected using either the ***Multimedia documents*** or ***Documents*** view, i.e. the view monitors these two views.




Image preview

- Click on or to enlarge or reduce the image. You can obtain the same effect by right or left-clicking on the image.
- Click on to display the image in its original size.
- You can also use the Views menu to open the image in an external program, view its properties or download it.

A set enlargement retains the zoom factor - even when you click on another multimedia document. This enables you to compare the size of two similar images.

Tip: If you do not see an image, but you are sure that image material is hidden behind the multimedia document, check whether the zoom function has reduced that image to the point that it can no longer be displayed.

6.3.8 Miniature view

If you have selected one or more entries in the ***Items #1*** or ***Products #1*** view, the associated multimedia documents are displayed in the ***Miniature view*** view.



Miniature view

The Views menu contains filter functions, which you can use to view only standard images, for example. Calling up the pop-up menu for a multimedia document enables you to execute the following functions:

Function	Description
Open	Opens the selected object in an external application. For example, if it is an HTML file, your Internet browser will open. The application used can be set in the preferences under "Multimedia attachments".
Copy	Copies the entire identifier of the multimedia document to the clipboard. This can then be pasted, e.g. in the ***Multimedia documents*** view, by clicking in the empty area of the view and selecting **Paste** from the pop-up menu. The "New multimedia document" dialog box opens, in which you can enter additional information.
Download	Downloads the file from the Media Asset server, e.g. to a local data carrier.
Show structure groups	Lists the structure group that references this multimedia document in the ***Class list*** view. This function is only available if the ***Miniature view*** view shows multimedia documents for structure groups.
Show items	Lists all items that reference this multimedia document in the ***Items #1*** view. This function is only available if the ***Miniature view*** shows multimedia documents for an item.
Properties	Displays a dialog box containing the properties of the original object (not those of the miniature image). The information is provided by the Media Asset server. For example, for a JPEG compressed image:

Function	Description
	• Identifier: Unique identifier that the Media Asset system uses for a file name (this can be the file name or a sequential number). • Name • Last changed: Date on which the object was last changed • File size (in bytes) • Height (in pixels) • Width (in pixels) • Depth (color depth of the image in bits) • Levels (for most image formats this is 1, however TIFF formats can have more levels) • Format (compression type) • Size (width x height)

6.3.9 Miniature view (documents)

In this view, all documents in a category are shown in a miniature view format. You can open a document by double clicking on it or select particular subsets from the category using the Views menu.

- Create preview images
- Show all
- Show used
- Show unused

Calling up the pop-up menu for a multimedia document enables you to execute the following functions:

Function	Description
Open	Opens the selected object in an external application. For example, if it is an HTML file, your Internet browser will open. The application used can be set in the preferences under "Multimedia attachments".
Open with...	Opens the selected object with an alternative application, which you select in the submenu. This function is available if several entries have been made under "Multimedia attachments" in the preferences.
Copy	Copies the entire identifier of the multimedia document to the clipboard.
Usage list	Displays where the document is used in the ***Dependencies - Overview*** view.
Download	Downloads the file from the Media Asset server, e.g. to a local data carrier.
Delete	Deletes the document.

Function	Description
Rename…	Opens an input window for renaming the document.
Refresh	Updates the display in the view.
Properties	Displays the properties of the original object in a dialog box.

6.4 Searching multimedia data

The multimedia data search enables you to selectively search multimedia files. Two search methods are available:

- Simple multimedia data search
- Advanced multimedia data search

Simple multimedia data search

This section describes how you can use the simple search to find a multimedia file:

1. Open the "Documents" view.
2. Enter a search term in the "Search" field.
3. Click on .
   - The search result is displayed in the table.

Note: The multimedia data search is not case-sensitive.

Multiple terms

You can enter multiple search terms in the input box, separated by spaces. These are linked by "And", i.e. a hit must contain all of the words.

Tip: If you are searching for a term that could consist of composite words, break these down into their constituent words.

Example:

A search using multiple search terms returns results in the order of the hit rate. If all terms have been found in an item, the hit rate is higher than for an item in which only some of the search terms have been found. The hit rate is lowest where only one term is found or the search term only occurs as part of another word.

Phrase search

If you want a space to be part of the search term itself, enter the term in quotation marks (phrase search).

Example: Entering `Home Office` returns all items that contain the terms `Home` and `Office`. Use quotation marks - `"Home Office"` – if you want to search for this specific phrase.

Note: Note that characters such as slash (/), exclamation mark (!), semicolon (;) etc. are ignored when searching.

Wildcard search

Enter search terms in full or use the placeholder characters * (any number of characters) and ? (any single character) if you only want to enter part of the search term. If the search term begins or ends with *, the search is automatically carried out as a wildcard search.

Example: Entering the term `*ring` searches fr all items ending in "ring", such as `ring, rubber ring, Rotring, spring.`

Tip: The wildcard search enables you to enter parts of file names. The search term `123*` returns all multimedia files whose names begin with "123".

6.4.1 Advanced multimedia data search

The advanced multimedia data search enables you to perform a very specific search.

You search for media assets as follows:


- To display all media assets, click on in the menu bar.
- To selectively search for particular media assets, enter the file name, the ID, and the name or any part of the name in the input field in the menu bar and click on .
- To search in specific fields and/or using multiple search criteria that are logically linked:

1. Click on in the menu bar on the right next to .
   - The advanced search area is expanded:

In the drop-down lists, select

- the field in which you want to search and
- the relationship the result should have to the search criterion.

2. Enter the search criterion in the input field.
3. To link several search criteria together, click on .
   - A new row appears:



New row

4. Select how you want the search criteria to be linked.
5. Clicking on allows you to delete the last search row.
6. Click on to run your search.
   - The media assets found are displayed.

6.5 Linking multimedia data and items

To link items and multimedia files, use the ***Multimedia attachments*** perspective, which you can open under **Perspectives > Open**. This area provides you with a wide range of functions.

Tip: To assign a large number of multimedia documents at the same time, you can use an import. This involves importing not only the files themselves into the Product 360 Desktop system but also the links between the items or products and the files.


You can:

- Create a new multimedia attachment for an item.
- Add a document to an existing multimedia attachment.
- Modify existing multimedia attachments and multimedia documents.

6.5.1 Creating a new multimedia attachment

The procedure for creating a new multimedia attachment is as follows:


1. Drag the document from the ***Documents*** view into the ***Multimedia attachments*** view, which shows the list of multimedia attachments for the relevant item. Drag it to the empty area, not to an existing multimedia attachment.
   - The "New Media Asset" dialog box opens and the document appears by default in the "Source path" field.



New Media Asset

2. Enter a name and, if required, a description.
3. Select the type, the quality and the language.
4. Click on **OK**.
   - The multimedia attachment is created using the corresponding multimedia document.

If you assign a multimedia attachment to an item that already has an attachment, you will see a message. You can then decide whether you want to overwrite the existing attachment.




Confirmation prompt for overwriting a media asset

6.5.2 Assigning documents

To assign a document to an existing multimedia attachment:

1. Drag the document from the ***Documents*** view to the desired multimedia attachment for an item in the ***Multimedia attachments*** view.
   - The "New multimedia document" dialog box opens and the document appears by default in the "Source path" field.




New multimedia document

2. Select the quality and the language.
3. Assign the priority (this field is optional and must be enabled in the repository).
4. Click on **OK**.
   - The document is created as a new multimedia document.

6.5.3 Changing a multimedia document

1. Drag the document from the ***Documents*** view to the multimedia document to be changed in the ***Multimedia documents*** view.
   - The "New multimedia document" dialog box opens and the document appears by default in the "Source path" field.



New multimedia document

2. Check the data in the fields of the dialog box.

3.Click on **OK**.

➪ The multimedia document is changed.

6.5.4 Assigning external documents

If you want to assign a document that is not in the system to an item, you do not need to add it to Product 360 Desktop in advance. Simply assign the document to the item directly using drag & drop.

For example, a direct assignment can be made by dragging a multimedia file from Windows Explorer into Product 360 Desktop and dropping it on an item. The file is automatically transferred into the system and other data required is created automatically, such as the multimedia attachment and multimedia document. The procedure is the same as that for creating a new multimedia attachment.

6.5.5 Copying a multimedia assignment

You can use the multimedia attachment for an item for other items.

- Use drag & drop to move the multimedia document from the ***Multimedia documents*** view to another item in the ***Items #1 view.***


  ➪ The multimedia document is assigned to the item. If the item already has a multimedia document with the same name and type, it will be overwritten.

6.5.6 Displaying changes

To optimize your catalog management, it is essential that you always know the latest processing status of all products and items. However, you do not always need to access all data to do this. For a delta export, it is often sufficient to be able to filter out only the most recent changes.

In the latest version, all Informatica MDM - Product 360 objects whose referenced objects, e.g. images or document attachments, have been changed on the Media Portal side are flagged as having been changed.

Open the ***Process overview perspective.*** In the ***Overview*** view, select the process category **Update modification date**.



Process overview - Update modification date

The change is stored as a date/time stamp at PIM object level (product, item, structure group) and in the corresponding media asset on the Product 360 Desktop side. “System” is always displayed as they user that made the relevant change.


The prerequisite is a workflow created in the Media Portal. An event-monitored watch point is defined, which registers changes to media objects. An action point creates corresponding entries (specifying the ID of the relevant object) in the message queue. These are extracted right away by Product 360 Desktop and immediately updated in the process overview.

Note: More information about creating workflows can be found in the user manual for Product 360 Media Manager.

6.5.7 Updating changes

As you have already learned in the previous section, it is convenient to link to the media portal using workflows that are defined there. If you need to update the changed multimedia files outside the period defined in the media portal, you can trigger this in the "Document categories" view.

1. Select the corresponding entry in the "Document categories" view.



Document

2. Click on .
3. All multimedia data in the working version is checked (except versioned data) and replaced by newer versions available from the media portal. This action runs via a server-side job, which you can view in the Process overview.

Note: More information about creating workflows can be found in the user manual for Product 360 Media Manager.

6.5.8 Linking multimedia files automatically

Note: You can only access this functionality if you have also installed Product 360 Media Manager.

If you regularly integrate a large number of multimedia files into your master catalog and, as a result, have to create a lot of item links, automatic document assignment makes your life much easier.


In conjunction with Media Portal it is possible to identify files intended for automatic assignment by a naming convention you have defined. Based on the convention, the file name of the media document is broken down into individual components, thus ensuring unambiguous assignment.

The following information can be used as naming parameters: Object type (product or item), identifier (unique product or item number depending on the object type), multimedia type, data quality, language. Some of these parameters can also be assigned a fixed default value, i.e., in this case the parameter does not have to be part of the file name. The default configuration is stored on the server in a Properties file.

Tip: You can also use parameters in a Properties file to specify that automatic linking is available for structure groups. Your Product 360 Desktop consultant can set this up for you.

The prerequisite is a workflow created in the Media Portal. An event-monitored watch point is defined, which registers changes in a defined archive folder. This folder is used to store the multimedia files to be imported. An action point creates corresponding entries (specifying the ID of the relevant object) in the message queue. This is extracted right away by Product 360 Desktop and immediately listed as an assignment in the defined catalog (master catalog or supplier catalog) .

You can find out the current status in the ***Process overview*** perspective. To do this, in the ***Overview*** view, select the process category **Assignment of HMM document**.




Process overview – Assignment of HMM document

The assignment operations are listed in a table. For each scheduled operation, a log is created showing more detailed information, along with any warnings or errors. "System" is always shown as the user that carried out the automatic assignment.

Note: More information about creating workflows can be found in the user manual for Product 360 Media Manager.

6.6 Deleting documents


1. Select the document to be deleted in the ***Documents*** view.
2. Call up **Delete** from the pop-up menu or press the DEL key.
   - If the document is not used as a multimedia attachment, the following message is displayed:



Deleting unreferenced documents

3. Click on **Yes** to delete the document.

If the document is used in a multimedia attachment, you will see a dialog box in which the affected areas are listed.



Deleting referenced documents

You can use **Show details** to display all existing links. The operation is canceled and the ***Dependencies*** view is opened. When you confirm deletion with **OK**, all existing references are also deleted.

Note: If you want to delete multiple files at the same time, select the "***Apply to all***" checkbox and every multimedia document is then checked for possible assignments.

6.7 Linking multimedia data and structure nodes

It is not only item data that can be linked to images – structure systems can also be linked. The link between multimedia data and a structure group is essentially created using drag & drop. You can also display a structure system as a list in the table-based ***Class list*** view, which gives you alternative filter and search options.

Note: Bear in mind that you cannot assign multimedia files to structure groups from some standard structure systems, such as eClass 8.0.


1. In the ***Documents*** view, open the images to be assigned to structure groups.
2. Expand the relevant structure group in the ***Primary structure tree*** view.
3. Drag a multimedia document to the structure group and drop it there.
   - The "New Media Asset" dialog box opens.
4. Enter the data for the multimedia attachment.
5. Click on **OK**.
   - The multimedia document is assigned to the structure group.

7 Structure systems

Standard structure systems and user-defined structure systems are powerful and versatile tools for organization, navigation and display in Product 360 Desktop. Structure systems have a hierarchical layout and make it easier for you to maintain an overview, even with very large data volumes.

Because structure systems play such a central role, there are numerous functions for managing them. Editing structures plays a prominent role and allows you to create new structures and to edit or import existing, non-standard structure systems. You can do this using the ***Structures*** perspective, in which you can create and edit user-defined structure systems. You also use this perspective to monitor and edit features and details of structure systems.

Note: You can monitor but not edit standard structure systems, e.g. eClass-8.0.



Structures

The ***Structures*** perspective comprises several views, including the ***Primary structure tree*** view. This view is available in various perspectives, but has some additional functions in the ***Structures*** perspective.

7.1 Maintenance structure

The purpose of maintenance structures is to uniquely classify products based on their properties. All features are defined in this structure and separated by their purpose. They are used as a basis for creating the attributes. The mandatory fields for the attributes are specified and permitted values are defined.

The following rules apply for maintenance structures:

1. Multiple assignments are not allowed.
2. Assignment is only possible at the lowest levels.
3. There is always one single primary maintenance structure. It is also possible to create one or more secondary maintenance structures.

7.2 Primary structure tree

The ***Primary structure tree*** view displays the selected structure system in the form of a tree hierarchy. In addition to the hierarchical ***Primary structure tree*** view, there is also a view that displays the structure system in a table; this is the ***class list.*** In the two views, you can display different structure systems independently of one another.

Note: The ***Secondary structure tree*** view displays the structure system you have defined as "secondary" in the preferences. You can also display a different structure system in this view at any time. Otherwise the same information applies as for the ***Primary structure tree view.***

To navigate in the structure system, expand and collapse the "branches".

- Click on to open a branch.
- Click on to close an open branch.
- Click on to collapse all expanded branches. Alternatively, you can select **Reduce all groups** in the Views menu.
- Select **Expand all groups** in the Views menu to open all branches.

Caution: In powerful structure systems such as eClass 8.0, it takes slightly longer to expand the entire tree.

- Click on if you only want to display structure groups to which items or products are assigned in the structure tree. Alternatively, select **Show only groups containing items** in the Views menu.
- Click on to display only those structure groups whose items or products are intended for multiple classification in the structure tree. These items are already assigned to a structure system and are now available for further assignment.
- Select **Open structure in new view** in the Views menu to open the selected structure in a second view. (This function is not available in the ***Structures*** perspective.)

Note: You can only delete user-defined structure systems in the ***Structures*** perspective. To do this, call up the ***Primary structure tree*** **view and select Delete structure**.

Searching structures

1. Click on to browse the structure.
   - The input box opens.

2. Enter the search term in the search field. As soon you start to enter the search term, the system starts to restrict the results, i.e. the target node may be located after you enter just a few letters.
3. If you also click on , the search is limited to the branch that is currently selected. The search mode is activated when the symbol appears depressed.

Tip: You do not need to press Enter to search in the structure tree.


Changing the structure displayed

1. In the ***Primary structure tree*** view, select **Open structure** in the Views menu.
2. In the subsequent submenu, select the desired structure system.
   - You can open any structure system that is available in the system in this way.

In the same way, you can select **Different structure language** to open the current structure system in another language. If you select a language that is not maintained in the system, all of the structure groups are displayed with the name "Unnamed structure group".

7.3 Class list

Structure systems can be displayed hierarchically, as in the ***Primary structure tree*** view or in a table, as in the ***Class list*** view. The "Group type" column specifies whether a structure group is a node or a leaf. A structure group is classified as a node if other, subordinate structure groups are assigned to it. A structure group at the lowest level is referred to as a leaf. Certain structure systems allow certain functions and properties for nodes only and others for leaves only.



	Name (English)	Hierarchical nu...	Group type
1	Packing material	20-00-00-00	node
2	Ampoule (packing materi...	20-01-00-00	node
3	Ampoule (glass, packing ...	20-01-01-00	node
4	OPC ampoule (glass, pack...	20-01-01-01	leaf
5	Ampoule (glass, packing ...	20-01-01-02	leaf
6	Beaker (packing material)	20-02-00-00	node
7	Beaker (plastic, packing m...	20-02-01-00	node
8	Beaker (plastic, packing m...	20-02-01-xx	leaf
9	Beaker (paper, packing m...	20-02-02-00	node
10	Beaker (wrapping paper, p...	20-02-02-01	leaf
11	Bag (packing material)	20-03-00-00	node
12	Bag (plastic, packing mat...	20-03-01-00	node
13	Flat bag (plastic, packing ...	20-03-01-01	leaf
14	Satchel bag (plastic)	20-03-01-02	leaf
15	Block bottom bag (plastic)	20-03-01-03	leaf
16	Cross bottom bag (plastic)	20-03-01-04	leaf

Class list

If the hierarchical numbers are also maintained in the structure system, you can use these to derive the association of a structure group with a higher-level structure group.

If you open a different structure in the ***Primary structure tree*** view, the structure displayed in the ***Class list*** view does not automatically change. This allows a comparison between different structures. If you want to display the same new structure in the ***Class list*** view, open it in the Views menu using **Open structure**.

Note: The ***Secondary class list*** view displays the classification you have defined as "secondary". You can also display a different structure system in this view at any time. Otherwise, the view behaves in the same way as the ***Class list view.***

Moving structure groups

Caution: You will lose the sort order of the moved structure group.

In the ***Class list*** view, you can select more than one structure group. You can use Drag & Drop to change the hierarchy of the selected nodes.

Caution: You cannot use this method if you have loaded a different structure system in the ***Class list*** view than in the ***Primary structure tree*** view.

7.4 Creating a structure system

If you want to create structure systems:

1. Switch to the ***Structures*** perspective.
2. Select **New structure** from the Views menu in the ***Primary structure tree*** view.
   - A wizard opens, which you can use to enter a name and a description for the new structure system.
3. Enter the name and identifier of the structure system.
4. Select the desired structure type under Structure type.
5. Go to the **Details tab.**
6. On the **Details** tab, specify whether depth of the structure system is limited and, if necessary, the maximum number of levels the structure system is to have.
7. Specify:
   - whether multiple assignment of items is allowed
   - whether assignment at all levels is possible
   - which numbering system is to be used to identify the structure system
   - whether free attributes are to be deleted (For more information on deleting free attributes, refer to Feature groups list.
8. Click on **OK**.
   - The structure system is created and is loaded in the ***Primary structure tree*** view.
9. Now start setting up the structure groups or import a structure system.

Tip: You call up ***Edit structure/View details*** in the ***Primary structure tree*** view in the **Structures** perspective. This opens the above dialog box, in which you can edit the structure system later.

Note: Deleting free attributes is only possible in the primary and secondary maintenance structure.

7.4.1 Deleting a structure system

If you want to delete structure systems:

1. Switch to the ***Structures*** perspective.
2. In the ***Primary structure tree*** view, select **Delete structure** in the Views menu.
   - A confirmation prompt containing the number of assigned items, structure groups, and structure features is displayed.
3. Confirm with **Yes**.
   - The structure system is deleted along with its structure groups and structure features, and the structure assignments to the items and item attributes are removed.

Note: If "**Delete free attributes**" is set for the structure, all item attributes assigned to this structure group are also deleted, provided they have no other assignments.


7.4.2 Creating structure groups

In user-defined structure systems, you can create new structure groups or edit or delete existing ones.

1. In the ***Primary structure tree*** view, click on ✚ to create a new structure group within the currently selected group level.
2. Enter a name for the new structure group.
3. Press the ENTER key to confirm.
4. You can maintain additional details for the structure group in the ***Class details*** view.

To create a subordinate structure group for an existing node:

1. Select the node.
2. Select **New subordinate structure group** from the pop-up menu.
   - A new structure group is created within the selected group. When you create the first new subordinate structure group, the existing structure group, which was previously a "leaf", now becomes a "node". This is indicated by a change to the icon next to it.



Structure group with a

3.You can maintain additional details for the subordinate structure group in the ***Subordinate structure groups*** view.

Changing the order of structure groups

You can use drag & drop to change the order of the structure groups and to rearrange the hierarchies. It can take some time to recalculate very large structures.

You can also rename or delete structure groups once they have been created.

7.4.2.1 Renaming structure groups

If you want to rename a structure group:

1.Select the structure group.

2.Double-click on the name or press the **F2** key.

3.Change the name.

4.Press the ENTER key to confirm.

➪The structure group is renamed.

7.4.2.2 Deleting structure groups

If you want to delete structure groups:

1.Select the structure group to be deleted.

2.Select **Delete structure group** in the pop-up menu or press the DEL key.

➪ A confirmation prompt containing the number of assigned items is displayed.

3.Confirm with **Yes**.

➪ The structure group is deleted and the structure assignments for the items and item attributes are removed.


Note: If "**Delete free attributes**" is checked for the structure, all item attributes assigned to this structure group are also deleted, provided they have no other assignments.

7.4.3 Class details

The ***Class details*** view contains a form representing the structure group that you selected in the ***Primary structure tree*** view.


You use the "Field selection" dialog box to show or hide additional fields. The "Hierarchical number" field is displayed by default. Based on your settings, Product 360 Desktop can evaluate the hierarchical number and map it in the ***Primary structure tree*** view.

If you enter a hierarchical number Product 360 Desktop checks whether the input corresponds to the predefined template of the structure system. If this is not the case, a corresponding message is output:



Message indicating an incorrect hierarchical number

Example: The proposed term "##-##-##-##" was accepted when setting the format. The Erstein structure group includes three structure groups and has two levels. The numbers 10-00-00-00 (threaded bolts), 20-00-00-00 (screws) and 30-00-00-00 (nuts) are assigned for the first level. Subordinate structure groups start with the first two numbers of the respective higher-level structure group. Thus, the subordinate structure group "Machine screws" is assigned the number 20-10-00-00. In the structure tree, nodes are only displayed with those numbers that are significant at their level:




You can also change the description of a structure group in the "Edit text" dialog box, which you can call up in the view by selecting **Edit...** when the “Description (English)” field is displayed. Alternatively, you can use the ***Text processing (structure group)*** view, which you operate in the same way as the ***Text processing (items)*** view.

7.4.4 Subordinate structure groups

You use the ***Subordinate structure groups*** view when editing a user-defined hierarchical structure system. You can also use this display option to display a standard structure system. However, you cannot edit a structure system.

You can use the "Field selection" dialog box in the view to show additional columns, e.g. "the "Hierarchical number" column. In this way, you can quickly tell whether all subordinate structure groups have a hierarchical number because fields with a hierarchical number are highlighted in yellow.



Editing hierarchical numbers

You can also create new structure groups in this view:

1. Click on ✚ in the view.
   - A new row is created in the table.
2. Enter the name and hierarchical number.
3. Click on 💾 to save the new data record.

7.4.5 Setting object rights for a structure system

You can use object rights to restrict or block access to a structure system for individual users or user groups.

1. In the ***Primary structure tree*** view, select **Object rights...** in the Views menu.
   - The "Object rights" dialog box opens. If you do not have any system presets, all settings are blank.
2. Edit the object rights.
3. If you enable the "Rights passed down to child objects (structure group)" option, all structure groups in the structure inherit the settings.

7.5 Maintaining structure features

The items or products assigned to a structure group are normally so similar that they have similar properties. In some structure systems, structure groups are therefore assigned fixed "features" to make it easier to compare the items or products in a structure group. The features consist not only of a name and data type, but also allow you to specify units or a purpose.

You can create features globally in the structure and then use them in individual structure groups. You can also define new features for individual structure groups, which are then created globally. All features are displayed and managed in the ***Structure features*** view. In most cases, you will create a structure feature globally first, and then use it in individual structure groups.

In addition to its identifier and name, you can specify other settings for a structure feature, e.g.:

- Unit: Specify the unit in which values are entered for the feature.
- Data type: Define the data type of the feature. The data type allows you to force certain entries, e.g. the user must enter a date rather than a figure.
- Attribute type: Specify whether a feature will apply to item attributes only, product attributes only, or to both. For example, depending on the definition when assigning an item only the structure features that either have the attribute "Item attribute" or "All" are created as item attributes.
- Purpose: Use a drop-down list to specify one or more purposes for the structure feature.
- Multiple values: Specify whether the feature can accept multiple values simultaneously or can only have one value at any one time.

7.5.1 Creating a structure feature

You create new features in the ***Structure features*** view, which shows all features of a structure. By contrast, the ***Feature groups list*** view shows only the features of the selected structure group.

1. In the ***Structure features*** view, click on ✚.
   - A new row is created in the table.
2. Enter an identifier and a name for the structure feature.
3. Enter the data type, unit, attribute type, and purpose for the structure feature, as required.
4. Place a check mark in the "Multiple values" column if you want to create a structure feature that has multiple values.
5. Click on to save the data record.

Tip: If you use multiple languages, use the "Field selection" dialog box to add the "Name" column in other languages.

You manage preset values for structure features in the ***Structure preset values*** view, independently of the relevant structure feature. To edit the preset values of a specific structure feature, use the ***Preset values for structure feature*** view.

7.5.2 Deleting a structure feature

If you want to delete structure features:

1. Select the structure group feature you want to delete.
2. Right-click on the selected structure group feature
3. Select **Delete**.

Note: If "**Delete free attributes**" is checked for the structure, the item attributes assigned to the structure feature are also deleted, provided they have no other feature assignments.

7.5.3 Creating structure preset values

The ***Structure preset values*** view lists all available preset values for all structure features in a structure system. In this view, you can create, edit and delete preset values.

1. Click on ✚.
   - This creates a new row in the table with an automatically generated identifier.
2. Change the identifier if necessary.
3. As a minimum requirement, enter a name for the preset value. You can also maintain preset values in multiple languages.
4. Click on to save the data record.

Note: If you want to delete a preset value, select it and then select **Delete** in the pop-up menu. Confirm the confirmation prompt to delete the preset value.

7.5.4 Preset values for structure features

You maintain the preset values for a specific structure feature in the ***Preset values for structure features*** view. In this view, you also specify the sequence of the preset values that you require, e.g. for output in print publications.

1. Click on ✚.
   - A new row is created in the table.
2. Select an existing structure preset value from the drop-down list.
3. Enter the sequence for the preset value.
4. Click on to save the new data record.

7.6 Maintaining structure group features

You can maintain structure group features for structure groups in the same way you maintain structure features. You use the ***Feature groups list*** view to create new structure group features. The preset values for an individual structure feature are maintained in the ***Preset values for group features*** view. In this view you can either access existing structure features or define new features for the structure group.

If you want to use structure group features with multiple values, you must maintain these in the ***Values for group features*** view.

7.6.1 Feature groups list

The ***Feature groups list*** view shows the features of the selected structure group, regardless of whether you select this structure group in the ***Primary structure tree*** or in the ***Class list*** view. Entries are only displayed if the selected structure group in the ***Primary structure tree*** or ***Class list*** view actually has features.

Two factors must be taken into consideration:

- Not all structure systems have features.
- Features are only allowed and maintained at the lowest level of many structure systems.

Creating a structure group feature

In non-standard structure systems, especially custom structure systems, you can create your own group features or edit or delete existing ones in the ***Feature groups list*** view.

1. First use the "Field selection" dialog box to show all required columns.
2. Click on ✚.
   - A new row is created in the table.

3. Enter a unique name or select a structure feature from the drop-down list.
4. Select the data type for the feature.
5. Enter a feature unit, if required.
6. Select one or more purposes.
7. Specify the attribute type, whether the feature will apply to items or products, or to both.
8. Specify whether the structure group feature has multiple values.
9. Enter the feature value. For structure group features with multiple values, use the ***Values for group feature view to do this.*** Single-value features have the identifier "DEFAULT" by default.
10. Click on to save the data record.

Note: You can change data type at any time until you enter a value for a feature. If a value has already been entered, the system checks whether the new data type matches the value. If not, the data type cannot be changed.

If you want to maintain all features of a structure, e.g. for a translation, you can use the ***Structure features*** and ***Structure preset values*** views. In contrast to the ***Feature groups list*** view, this view shows all features in a structure. You can use the "Field selection" dialog box to show the columns in multiple languages.

You can also define alternative preset values for the structure group feature in the ***Preset values for group feature*** view.

Delete a structure group feature

1. Select the structure group feature you want to delete.
2. Right-click on the selected structure group feature
3. Select **Delete**.

Note: If "**Delete free attributes**" is set for the structure, the item attributes assigned to the structure group feature are also deleted, provided they have no other feature assignments.

7.6.2 Preset values for structure groups

The ***Preset values for group feature*** view lists all preset values of a structure group feature. In this view, you can create, edit and delete preset values.

1. Click on .
   - A new row is created in the table.
2. Select a structure preset value from the drop-down list.
3. Enter the sequence for the preset value.
4. Click on to save the data record.

Note: The sequence of the preset value is required for output in print publications, for example.


If you want to delete a preset value for a structure group:

1. Select the preset value in the ***Preset values for group feature view.***
2. Select **Delete** in the pop-up menu.
   - A confirmation prompt opens.
3. Confirm with **Yes**.
   - The preset value is deleted for the structure group.

7.6.3 Group features with multiple values

With structure group features with multiple values, a feature can have more than one value. For example, a "Color" group feature may have the feature values "Blue", "Red", "Green" and "Yellow". You maintain the preset values for a structure group feature with multiple values in the ***Values for group features*** view. You can also create these values in multiple languages here directly. To do this, you need to use the "Field selection" dialog box to show the "Language for value" column.

1. Click on ✚.
   - A new row is created in the table.
2. Enter the identifier for the feature value.
3. Enter the feature value.
4. Enter the feature value sequence, which you require for print publications, for example.
5. If you use multiple languages, select the relevant language in the "Language for value" column.
6. Click on 💾 to save the new data record.



Group feature with multiple values

7.6.4 Feature attribute match

If new features have been added to a structure group in a maintenance structure, or if existing features have been deleted or modified, you can use "Feature attribute match" to apply these changes to the items already classified. The feature attribute match can be carried out in three different ways:

1. For a specific structure group in the **Feature groups list view**
2. For multiple structure groups in the **Class list view**
3. As a one-off or recurring operation for all structure groups in a structure system.

Feature attribute match for a specific structure group

Select the button (icon) in the Feature groups list view. All features of the structure group are applied to the relevant items.



Feature attribute match

Feature attribute match for multiple structure groups

1.Open the Class list view.

2.Open your structure system using the Views menu.

3.In the Class list view, select the structure groups whose features you want to match.

4.Select **Execute feature attribute match** in the pop-up menu.

Feature attribute match for all structure groups in a structure system


The feature attribute match can also be performed for all structure groups in a structure system by scheduling it as a one-off or recurring operation.

To do this, follow the steps below:

1.Open the "Primary structure tree" view.


2.Select "Open structure" in the Views menu to open the relevant maintenance structure.

3.Select "Schedule feature attribute match" in the Views menu.



Schedule feature

➪The "Schedule feature attribute match" dialog box opens. The "Repetition interval" and "Repetition pattern" options are available for scheduling repeated matches.




Schedule feature attribute match

When scheduling, you can decide whether the series is to be ended automatically and when this is to occur. However, you also have the option of canceling a series later in the **Process overview** view, by deleting the operation in the Data maintenance_Feature attribute match category.

Note: You can only perform the feature attribute match for maintenance structures and their groups.

7.7 Feature inheritance

New features of structure groups are created in the ***Feature groups list*** view. When you create a feature for a structure group, you can use the ***Primary structure tree*** view to specify whether the features of this structure group are to be passed on to the subordinate structure groups.



Inheritance of features

- Replace. Passes all the features of the higher-level structure group to all the subordinate structure groups. It removes the existing features of the subordinate structure group.
- Overwrite. Passes all the features of the higher-level structure group to all the subordinate structure groups. If both the higher-level and the subordinate structure group have the same features, the features of the higher-level structure group overwrite the features of the subordinate structure group. It retains all other features.
- Add. Passes all the features of the higher-level structure group to all the subordinate structure groups. It does not affect the existing features.

You also have the option of only passing on specific features of a structure groups to their subordinate structure groups.

1. Select the structure group in the ***Primary structure tree*** view.
   - The ***Feature groups list*** view displays all group features of the structure group.
2. Select the group features you want to pass on to the subordinate structure groups in the ***Feature groups list*** view.
3. Select **Feature inheritance** in the pop-up menu.
4. Select the type of inheritance in the submenu.
   - The features are transferred to the subordinate structure groups.

7.8 Copying a structure or substructure

You can copy an entire user-defined structure system or just a subsection (subtree) within it. You copy the structure features, preset values, and language information, as well as (depending on the settings) the item and product assignments.


Copying a structure system

1. Select **Copy structure** in the Views menu of the ***Primary structure tree*** view.
   - A dialog box opens, in which you can specify a new name for the structure system.
2. Click on **Finish**.

Note: During copying, the structure system is locked for other users. Copying may take several minutes, depending on the size of the structure system.

Copying a subtree within the structure system

1. Select the subtree you want to copy.
2. Hold down the CTRL key and use drag & drop to move the subtree.
   - The following dialog box is then displayed:



Copy structure ...

3.Click on **OK** to copy the subtree within the same structure system.

Note: When copying a maintenance structure, it is not possible to include the object assignments in the copy operation.

Copying a subtree to a different structure system

1.Select **Copy to another structure system > <Structure system>** in the pop-up menu for the subtree, or hold down the Ctrl key and use drag & drop to move the subtree.

If you use the second option, the "Copy of structure group" dialog box is displayed.

2.Activate the "Copy this group to another structure system" option in the dialog box.

3.Select the relevant structure system from the drop-down list.

4.Click on **OK** to copy the subtree to the specified structure system.

8 Tasks

The ***Tasks*** view displays tasks created manually or by a workflow in a tree structure. The tree is divided into three main nodes. These are:

- My tasks
  Lists all the tasks you have accepted.
- Tasks not accepted
  Tasks that have been assigned to you or your user group but have not yet been accepted
- My responsibilities
  Tasks for which you are responsible but are being processed by other users

Depending on user rights, there are two other main nodes in the tree:

- Tasks assigned to other users
  Tasks that have been assigned to or accepted by other users from other user groups.
- Users in my user groups
  Tasks that have been assigned to or accepted by other users in your user groups.

There are two different task types:

1. Standard tasks
2. Workflow tasks

8.1 Standard tasks

Standard tasks can be:

- Create
- accepted
- sorted, and
- filtered.

You can also create task groups. For more details, refer to: Creating task groups


8.1.1 Creating tasks

You can create a new task in two ways: Create a new blank task in the ***Tasks*** view and then use drag & drop to assign items and products to this task, or first select the relevant items or products and then create the task or task group within their context. The second option is the more frequently used and is described in detail below.

1. Perform a search, e.g. to find items that have not yet reached the status "03 Selling prices OK".
2. Select the items in the ***Item #1 view***.

3.Select **Tasks > Note selection in** or **Tasks > Note query in** in the pop-up menu.

Note: There are both dynamic and static task types. You use the "Note query in" submenu to create a dynamic task because the result set for the query may change, for example, due to an import. You use the "Note selection in" submenu to create a static task, as you specify the exact number of items.




Creating a new task

4.In this submenu, specify whether you want to create a new task or task group, or select an existing task group.

5.In the dialog box that opens up, enter a name and a description and specify the assigned user, a deputy for that person and the person responsible for the task. The processor is the user to whom you assign the task. Alternatively, you can assign the task to a user group.
For a new task group, specify the name and description.

Note: Give the tasks unambiguous and descriptive names. This makes it easier for you to manage the tasks.



Properties of a task

6.Select the setting required for this task from the notification levels.

7. Specify a deadline and an escalation date for tasks.
   If an escalation date is less than 24 hours in the future, the task is highlighted in orange in the view. If the task is not yet completed when the escalation date is reached, it is assigned to the specified deputy. Tasks for which both the escalation date and the deadline have passed are assigned to the person responsible and shown in red in the view.

Note: The dates in the "Time expires on", "Escalation on" and "Forecast completion on" fields are set using a calendar. In addition, you can specify a time after the date. For example, your entry would then be: “31.10.2011 14:00".

8. If necessary, in the selection field select the template that is to be used in the 360 Web product to represent the task.
9. Click on **OK**.
   - The new task created is displayed to the assigned user under the "Tasks not accepted" node and to the person responsible under the "Responsibility" node.
     For a task group, a new task group is created containing the associated task.

The procedure for creating a new empty task is as follows:

1. Select the "My tasks" node in the ***Tasks view.***
2. Click on + in the Views menu.
   - The dialog box for editing a new task opens.
3. Give the task a name.
4. Specify the assigned user, the assigned user's delegate and the person responsible.
5. Enter an escalation date and an expiry date.
6. Specify the priority of the task.
7. Set the notification level.
8. Click on **OK** to save the task.

You can now use drag & drop to assign items to the task, for example.

8.1.2 Accepting tasks

If you have been assigned a task, it is initially located under the "Tasks not accepted" node. To accept the task:

1. Select the task.
2. Select **Accept** in the pop-up menu or click on .
   - The task is displayed under the "My tasks" node.

Once you have accepted a task, you can execute it.

Every task you create for yourself is automatically viewed as accepted and is stored in the "My tasks" node.

Note: If you have been assigned a task group, you can accept the entire group by selecting the node for the task group rather than the individual tasks.

8.1.3 Sorting tasks

You can change the sequence of tasks:

1. Select a task in the ***Tasks view.***
2. Click on to move the task up, or on to move the task down.
   - The task's position in the group moves up or down by one.

Note: You can use these steps to move tasks within a task group but not between task groups. To move a task into a (different) task group, you must use drag & drop.

8.1.4 Filtering tasks

You also have the option of assigning filters to tasks.

To assign a filter function:

1. Click on
2. In the extended window, select the filter function you want to activate.
3. You can choose between **Hide completed tasks** or **Hide tasks without escalation time**.
4. Click on next to the name to activate or deactivate the filter function

You can use on the **Tasks** tab to activate or deactivate the general filter function.

8.1.5 Searching tasks

You can search for tasks by specifying the task name in the Search box.

To search for tasks, perform the following steps:

1. In the ***Tasks*** view, click .
2. In the **Search** box, enter the partial or full task name.

   The tasks that match the search term appear in the navigation tree.

8.1.6 Creating a task group

If tasks are very extensive and need to be split up, assignment to a task group is recommended. This enables particular work steps to be coordinated and the processing time to be reduced.

You can create a new task group when you create a new task:

1. Open the ***Item #1 view.***
2. Select the relevant items.
3. Select **Tasks > Note selection in > New task group** in the pop-up menu.
   - The "Properties of task (in group)" window opens.

4.Enter the name of the task group.

5.Enter the data for the task.

6.Confirm with **OK**.

- The task group, together with the new task, is added to the task list of the assigned user.

8.1.6.1 Creating a task group for a task

The procedure for creating a task group for an existing task is as follows:

1.Select the relevant task in the ***Tasks view.***

2.Select **As task group** in the pop-up menu.

- The "Properties of task group" window opens.

3.Enter the name of the task group.

4.Confirm with **OK**.

- The selected task is assigned to the new task group.

Tip: You can also select several tasks simultaneously and create a task group for them.

8.1.6.2 Creating a new task in a task group

You can create new tasks in an existing task group:

1.Open the ***Item #1 view.***

2.Select the relevant items.

3.Select **Tasks > Note selection in > New task group...** in the pop-up menu.

- The dialog box for selecting task groups opens.

4.Select a task group.

5.Confirm with **OK**.

- The "Properties of task" window opens.

6.Enter the data for the task.

7.Confirm with **OK**.

- The task is created in the selected task group.

8.1.6.3 Assigning a task to a different task group

You can use drag & drop to assign a task to a different task group:

1.Select the relevant task in the ***Tasks view.***

2.Use drag & drop to drag the task to the relevant task group.

- The task is assigned to another task group.

8.1.7 Executing a task

The procedure for executing a task is as follows:

1. Select the task in the ***Tasks view.***
2. Select **Open** in the pop-up menu or double click on the task.
   - The items are displayed in the ***Item #1*** view.
3. Edit the items or products as specified in the task.

After completion of the task, you can mark it as completed.

> Note: If you want to edit the task itself, e.g. because a deadline has changed, select **Edit…** in the pop-up menu to open the dialog box containing the settings for the task.

8.1.8 Marking tasks as completed

You can mark an accepted task as completed after processing.

1. Select the task in the ***Tasks view.***
2. Click on or select **Mark as completed** in the pop-up menu.
   - The task is given the symbol instead of .

If necessary, you can mark a completed task as "not completed" again.

1. If necessary, click on to disable any filters applied to the ***Tasks*** view.
2. Select the task.
3. Click on or select **Mark as completed** in the pop-up menu.
   - The task is once again displayed as "not completed".

8.1.9 Assigning tasks to different users/user groups

You can assign tasks or task groups to different users or user groups. To do this:

1. Select the relevant task or task group.
2. Select **Assign task** in the pop-up menu or click on .
   - A selection dialog box containing the users and user groups opens.
3. Select the relevant user or user group.
4. Click on **OK**.
   - The task or task group is assigned to the user or user group.

8.1.10 Deleting a task

To delete a task:

1. Select the relevant task in the ***Tasks*** view.
2. Select **Delete** from the pop-up menu or press the DEL key.
   - A confirmation prompt appears, asking whether you really want to delete the task.
3. Confirm with **OK**.
   - The task is deleted.

8.1.11 Configuring E-mail notification

Different roles are involved with a task. In addition to the person assigned to perform the task, there is the person who created the task and a person responsible for monitoring performance and a delegate, who will step in to perform the task if a specified time limit has been exceeded.


A task passes through a life cycle and can have different statuses during this process. Certain people and roles, which may not regularly or continuously use Product 360 Desktop, must be notified promptly, e.g., if new tasks are set up or a task is completed.

Note: In Product 360 Desktop it is possible to notify the people involved by e-mail according to their role in relation to the relevant task depending on the current status and when a particular event occurs during a task. The prerequisite for this is that a valid e-mail address for these users has been created in the system.

Any e-mail templates can be stored in the system. These are manage independently of the language, i.e., if people who use different languages need to be notified, the information in the e-mail either has to be in a defined corporate language that everyone can understand or entered in multiple languages within a template.

These templates can then be assigned to the relevant e-mail status or events. Three different notification levels are available. One of these levels is set as the default. Targeted selection of a level for specific tasks can be controlled using corresponding authorizations.

The ***Task notification*** perspective is used to manage the templates for the different scenarios in your company.



Task notification perspective

It provides the following views:

1	This area contains predefined e-mail templates for a wide variety of tasks, which you can customize as required. Click on ✚ to create a new template. You can use the pop-up menu to rename or delete templates.
2	The source code for the template is located here. This is pure HTML code, which is freely configurable. How you can customize it is described in a separate section.
3	The e-mail preview shows what your template will actually look like.
	The "Task notification" view is set up in the form of a matrix and provides a wide range of configuration options.

Note: The editing options depend on the permissions your administrator has assigned you and may therefore differ from this description.


8.1.11.1 Creating templates

All templates supplied are based on a standardized layout. Here, you can adapt the existing templates or define new ones. This requires knowledge of HTML.

For a new template, specify the text that will appear in the e-mail subject line in the **Subject line**.

The HTML source code below this is provided for editing in a simple editor.

The lower section (marked) contains variables that you can insert in the relevant template. To do this, position the cursor at the appropriate position in the source text or subject line and click on the relevant variable.



E-mail template editor

The variables are not language-specific, which means that the content needs to be entered according to the language set on the recipient's mail server.

Note: For change notifications, variables can reflect the original value. For example, if the deputy has changed, the variable {&substitute} for the original value is copied and the ending "_old" is added. This enables you to compare the two values and make the modification transparent.

You can check the appearance of the template created in the preview. It also includes a button that you can use to send a test mail.

8.1.11.2 Task notification


Use the task notification perspective to set the notification levels. The notification level manages the number of people who get the notifications when a task changes its status. To set the default notification level and the default email ID to use to send mails, contact your system administrator. The **Sender** field displays the default email ID configured by the system administrator.

Note: If the default notification level is set to ***None***, the **Task notification** dialog box does not display the **Notification Level** field.

The following table describes the different notification levels:


Notification Level	Description
None	Notifies none.
Low	Notifies only the assigned user and the person responsible.
Regular	Notifies the changes in task status and assignments to all the people directly affected.
Detail	Notifies the changes in task status and assignments to all the people directly and indirectly affected.

For each event and each notification level you can specify who is notified by e-mail.



Configuring a notification level

To do this, click on the Select button next to the relevant field.



Template selection

The window that opens contains all existing templates. This provides maximum flexibility in representing individual situations.

Select the relevant entry. Each entry in this matrix is saved automatically.

Essentially, the notification levels represent the priority of a task. However, it is sometimes necessary to be able to re-assign the level regardless of the default value. This permission must be explicitly set up by the administrator. This applies to both users and user groups.

8.2 Workflow tasks

Workflow tasks are tasks generated by a workflow process.

To differentiate them from conventional tasks, they are preceded by a symbol. Workflow tasks are initially created by the relevant process for the relevant user or user group in the "Tasks not accepted" folder. They contain one or more elements to be processed (items, products, or variants), which have a particular process status (e.g. "Translation of short description into French") and are to be processed by the relevant user. The user must first accept the elements to be processed.

An additional workflow task containing the accepted elements is then created in the user's "My tasks" folder. The user processes these elements in line with the relevant task (e.g. Translation into French") and then completes processing.

8.2.1 Accepting elements to be processed

To accept an element:

1. Double-click on the task to open it
2. Select the elements you want to accept.
3. In the pop-up menu, either select **Accept** directly, or **Comment and ... > Accept**, if you also want to enter a comment.
   - A workflow task containing the accepted elements is created under the ***My tasks*** node.

Note: You can also assign elements to be processed to another user by selecting ***Assign*** or **Comment and ... > Assign** in the pop-up menu. In this case, a workflow task is created for the relevant user in their ***My tasks*** folder.

8.2.2 Completing/releasing/rejecting processing of elements

Depending on the workflow task, you can either complete, release, or reject elements.

To complete processing of elements:

1. Double-click on the task to open it
2. Select the relevant elements.
3. In the pop-up menu, either select **Processing completed** directly or **Comment and... > Processing completed** if you also want to enter a comment.
4. Confirm with **OK**.
   - Processing of the selected elements is completed and the elements are removed from the workflow task.

To check processed elements and then release or reject them:

1. Double-click on the task to open it
2. Select the relevant elements.
3. In the pop-up menu, select either Release or Reject, or alternatively select **Comment and ... > Release or Comment and ... > Reject.**
   - If rejecting, depending on the workflow structure the **Reject** dialog box opens, in which you can specify which workflow tasks have to be revised.
   - The task is marked as released or rejected.

Note: Processing of elements in workflow tasks can also be canceled by selecting **Cancel processing** in the pop-up menu.

8.2.3 Assigning processing of elements to different users/user groups

To assign an element to a different user or user group:

1. Double-click on the task to open it.
2. Select the elements you want to assign.
3. In the pop-up menu, either select Assign directly, or select **Comment and... > Assign** if you also want to enter a comment.

- The ***Assignment*** dialog box opens

4. Select the user or user group to which you want to assign the elements.
3. Confirm with **OK**.
   - The workflow task is assigned to the user or user group.

8.2.4 Canceling a workflow for an element

To cancel the workflow for an element:

1. Double-click on the task to open it.
2. Select the elements for which you want to cancel the workflow.
3. Select **Cancel workflow** in the pop-up menu.
4. Confirm with **OK**
   - The workflow for the elements is canceled.

8.2.5 Showing information for an element in a workflow task

As described in the previous sections, you can enter additional comments for the individual actions on elements of workflow tasks. These comments can then be displayed as information for the relevant subsequent workflow tasks:

1. Double-click on the relevant workflow task to open it.
2. Click on **Field selection** in the Item #1, Products #1, or Variants #1 view.
   - The "Field selection" dialog box opens.
3. Select Information in the list on the left under Workflows.
4. Click on Add.
   - The Information entry now appears in the list on the left.
5. In the lower right section of the dialog box, enter the name of the opened workflow task as the Status value.
6. Select the workflow from which the workflow task was generated.

Tip: You can take the name of the workflow and of the workflow task from the designation of the workflow task in the Tasks view. By default, the designations of workflow tasks have the following structure: <Workflow_Name> - <Name_Workflow_Task> - <Catalog_Name>.

7. Click on **OK**.
   - The Information column is added to the Item #1, Products #1, or Variants #1 view.


9 Business process management

Use the ***Business process management*** perspective to configure triggers for particular events, which initiate workflows when those events occur. The **Workflow trigger configurations** view displays a list of events for which you can configure trigger conditions.

The **Workflow trigger configurations** view includes the following sections:

- **Start conditions**. Displays the conditions, such as users, user groups, data types, modification fields, catalogs, and suppliers that determine when to trigger a workflow. Use the **Modification fields** section to specify channels and fields that can determine when to trigger a workflow.
  - **Channel**. The workflow initiates only if the field values that are a part of the specified channel are impacted.
  - **Fields**. The workflow initiates only if the values of the specified fields are impacted.
- **Communication**. Displays the mode to communicate the event details to the business process.
- **Parameters**. Displays the type of event detail that you can send to the business process. The Payload field displays the following options:
  - **Object and Change Meta**. Includes the names of changed fields.
  - **Object and Change Summary**. Includes the names of changed fields and the details of changes.

Note: To deactivate triggers for any event, select **Inactive**.



Workflow trigger configuration view

Events

You can configure triggers for the following events:

- Entity created. Occurs when an item, product, or variant is created.

- Entity changed. Occurs when changes are made to an item, product, or variant.
- Export started. Occurs after the start of an export before data is output to the relevant export channel.
- Import completed. Occurs after completion of an import, regardless of whether it was successful.
- Merge completed. Occurs after completion of a merge, regardless of whether it was successful.
- Merge started. Occurs after the start of a merge.

9.1 Creating workflow trigger configurations

You can create and manage workflow triggers from the **Business process management** perspective.

1. From the **Management** menu, click **Business process management**.
   - The ***Business process management*** perspective opens.
2. In the ***Workflow trigger configurations*** view, select the event in the tree structure for which you want to configure triggers.
3. Click ✚ .
   - A new workflow trigger configuration is created under the selected event node.
4. Specify a name for the trigger.
5. In the **Start conditions** section, specify the conditions to trigger the workflow based on the following objects:
   - Users
   - User groups
   - Data types
   - Modification fields
   - Catalogs
   - Suppliers
   - Initiators
6. To select the fields that can trigger the workflow, perform the following steps:
   a. Select **Modification** fields.
   b. To specify channels, from the **Channels** list, select the required channels.
      The workflow initiates when the values of fields in the selected channel are impacted.
   c. To specify fields, ensure that the data type is specified, and then click **Field Selection**.
      The **Relevant fields for rule condition** dialog box appears.
   d. Select the required fields, click **Add**, and click **OK**.
      The selected fields appear in the **Fields** field.

7. In the **Communication** section, perform the following tasks:
   a. From the **Communication** list, select the required communication mode.
   b. From the **Queue** list, select the message queue.
   c. In the **Service endpoint** list, select the service end point that determines the workflow to initiate.
8. In the **Parameters** section, in the **Payload** list, select the required payload.
9. Click .

Note: You can restrict the activation of triggers of the "Entity changed" type to changes in certain fields. To do this, enter the names of the relevant fields in the "Changed field" field, as specified in the PIM Service API, including their qualifications.

Examples:

Simple fields: GTIN: Article.EAN

Qualified field: Short description (German): ArticleLang.DescriptionShort(deu)

Attribute field: An item attribute with the name Color in English: ArticleAttributeValue.Value (Color,eng,DEFAULT)

Attribute field: An item attribute with the name Color in any language: ArticleAttributeValue.Value(Color,$[Empty],DEFAULT). All item attributes: ArticleAttributeValue.Value($[Empty],$[Empty],DEFAULT).

9.2 Start Conditions

The following table lists the events for which you can configure triggers:

Event	Start Condition	Description
Entity changed	**User**	The specified user changes the entity.
Entity changed	**User group**	The specified user group changes the entity.
Entity changed	**Data type**	The changed entity is of the specified data type.
Entity changed	**Modification fields**	The fields specified in the modification fields and the fields that belong to the specified channel change.
Entity changed	**Catalog**	The specified catalog contains the changed entity.
Entity changed	**Supplier**	The changed entity belongs to a catalog of the specified supplier.
Entity changed	**Initiator**	The specified initiator is responsible for the entity change. The list of initiators include, environment transfer, import, merge, revision, service API, and user. For example, if you select the Import initiator, the worklflow triggers if an import function is responsible for the entity change.

Event	Start Condition	Description
Entity created	User	The specified user creates the entity.
Entity created	User group	The specified user group creates the entity.
Entity created	Data type	The created entity is of the specified data type.
Entity created	Modification fields	The fields specified in the modification fields and the fields that belong to the specified channel are updated during entity creation.
Entity created	Catalog	The specified catalog contains the entity created.
Entity created	Supplier	The created entity belongs to a catalog of the specified supplier.
Entity created	Initiator	The specified initiator is responsible for the entity creation. The list of initiators include, environment transfer, import, merge, revision, service API, and user. For example, if you select the Import initiator, the worklflow triggers if an import function is responsible for the entity creation.
Export started	Catalog	The specified catalog contains the items exported.
Export started	Export format template	The specified export format template is used for the export.
Export started	Export profile	The specified export profile is used for the export.
Export started	Export variable	The export profile contains the specified variables.
Export started	User	The specified user starts the export.
Export started	User group	The specified user group starts the export.
Import completed	Import mapping	The specified import mapping is used for the import.
Import completed	Purpose of import mapping	The specified purpose of import is used.
Import completed	Supplier	The imported entity belongs to a catalog of the specified supplier.
Import completed	Supplier catalog	The imported entity belongs to the specified supplier catalog.
Import completed	User	The specified user imports the entity.
Import completed	User group	The specified user group imports the entity.
Merge completed	Supplier	The merged entity belongs to a catalog of the specified supplier.
Merge completed	Supplier catalog	The merged entity belongs to the specified supplier catalog.
Merge completed	User	The specified user completes the merge.

Event	Start Condition	Description
Merge completed	**User group**	The specified user group completes the merge.
Merge started	**Merge user group**	The specified user group starts the merge.
Merge started	**Supplier**	The entity being merged belongs to a catalog of the specified supplier.
Merge started	**Supplier catalog**	The entity being merged belongs to the specified supplier catalog.
Merge started	**User**	The specified user group starts the merge.

10 Audit trail

An audit trail records the history of all the modifications that an object undergoes. For example, a user might modify an item by updating the price. Also, an item might undergo modifications because of system operations, such as merge. The audit trail records the details of modifications that the users make and the modifications that occur because of system operations.

You can use audit trail to view the modification history of objects and track all the modifications. You can find any modified object, and view the history of its modifications.

To find modified objects, use the **Audit Trail** perspective. Use the search pane to specify search conditions and view the modified records based on the conditions you apply.

Use the **Change history** view to see the history of all the modifications of the selected objects. The **Change history** view displays the date and time of the modification, the user who made the modification, and the initiator of the modification for every modified field.

You can see if a section of data was created, deleted, or changed. You can also see the old and new values for each field, compare these values, and revert new values to old values if required.

10.1 Audit trail search pane


Use the **Audit Trail** perspective to find modified objects. Use the available filters in the search pane to specify your search conditions.

You can specify search conditions, such as an identifier, the type of change, the time period of the modification, the initiator of the modification, and the user who made the modification. For example, if you specify a specific user, such as administrator, all the modifications that the administrator made appear in the **List** view. To search across all the modified objects, you can leave the filters blank. However, the **Change types** filter is mandatory.

Product 360 Desktop retains the search conditions that you specify across sessions. Use the **Refresh** icon to reset the search conditions.

The **List** view displays details, such as the data type, identifier, container, event type, user who made the modification, and initiator of the modification.

The following image displays a list of objects that the administrator modified.



Audit Trail Search Results

10.1.1 Finding modified objects

Use the search pane in the **Audit Trail** perspective to find modified records. You can search for modified objects from products, variants, items, structure groups, lookup values, and characteristics.

1. From the **Perspectives** menu, click **Open**.

   The **Open Perspective** dialog box appears.

2. Expand the **Management** node, and click **Audit Trail**.
3. Click **OK**.

   The search pane appears.

4. Use the following search fields to specify your search conditions:

Field	Description
Identifier	Searches for the modified objects based on the specified identifier. For example, the item number is an identifier of an item.
Data type	Searches for the modified objects that belong to the specified data type, such as structure group or supplier catalog. To add a data type, click ⊕.
Field Selection	Searches for specific fields modified for the objects that belong to the respective data type.
Change types	Searches for objects based on the type of modification, such as created, changed, or deleted.
Timeframe	Searches for objects modified during the specified time duration.
Initiator(s)	Searches for objects modified by the specified initiator. For example, if you select import, the objects modified by the import appear.
Users(s)	Searches for objects modified by the specified user.

5. Click **Search**.

   The modified objects appear in the **List** view based on the conditions you specify.

10.2 Modification history


To see the details of the modifications, you must open the required **Change history** view. The **Change history** view displays details, such as the date and time of the modification, the user who made the modification, the initiator of the modification, the modified fields, and the modified values. You can view the modification history of multiple objects at once. When you select multiple objects, the object identifier for each change history event appears.

Each change history event appears as a node, and each node includes multiple child nodes. To view the details of the modifications, you must expand the child nodes.

For example, when you view the modifications made to the short and long descriptions of an object, you might see Texts as the primary node and Language-specific data as the child node.

When you expand the child node, you can see the modified values. You can see if a value was added, deleted, or changed. Both old and new values appear, and you can compare and revert the new values or old values.

The following image shows the modifications of an object on the **Change history** view:



History Tab

The following table describes the user interface elements of the **History** tab:

Legend	Description
1	Filters the records according to the specified user who made the change.
2	Filters the modification history based on the selected fields.
3	Filters the modifications made until a specific date.
4	Expands or collapses all the nodes.
5	User who made the modification. To view the user who made the modification, you must have the appropriate rights.
6	Date and time of the modification.
7	Initiator of the modification.
8	Field that the user modified.
9	Old value of the modified field.
10	New value of the modified field.
11	Icon to indicate that the field value was changed.
12	Icon to indicate that a new value was added.
13	Reverts the selected value to another historic value.
14	Status that indicates that the object was created.

10.2.1 Viewing modification history

To view the modification history of objects, you must first open the required **Change History** view, and then select the objects.

Open the Change history view

To view the modification details, you must first open the corresponding **Change History** view. For example, to view the change history of items, you must open the **Change history (Item)** view.

1. From the **Perspectives** menu, click **Open view**.

   The **Display view** dialog box appears.

2. Expand the **Audit Trail** node, and select the required **Change history** view.

   The **Change history** view opens.

View modification details in the Change history view

After you open a **Change history** view, you can see the modification history for the selected objects.

1. Navigate to the required catalog, and select the object.
2. The modification history of the selected object appears as nodes in the corresponding **Change history** view.
3. To view the modification details, expand the nodes. To expand all the nodes at once, click the **Expand all** icon.

10.2.2 Filtering modified records

After the modification history appears, you can choose to display modifications made to specific fields, modifications made by specific users, and modifications made until a specific date.

On the **Change history** view, perform one or more of the following tasks:

- To display modifications made by specific users, in the **Filter by user name** list, select the users.
- To display modifications made to specific fields, click the **Field selection** icon, and select the required fields. You can add fields without adding any qualifications.
- To display the modifications made until the specified date, click the **Calendar** icon, and select a date.

10.2.3 Reverting new values to old values

When you expand the field nodes, you see the old and new values of the modified fields. You can revert a current field value to another historic value.

1. On the **Change history** view, navigate to the field value by expanding the nodes.

The old value and the new value appear.

2. Hover over the new value or old value, and click **Revert**.

   The **Revert the field value** dialog box appears.


3. Click **Apply**. By default, the **Apply** button is disabled if the currently active value of the object is identical to the selected historic value.

11 Dashboard

The dashboard provides quick access to an aggregated view of the data quality, different workflows, task information, and KPI information.

These are visualized using individual components known as widgets.

Dashboards can differ for each user as required.



Business Dashboard

11.1 Managing dashboards

Note: To manage dashboards, you require the "Manage dashboard templates" action right. For more information about action rights, refer to Organization 242

There are two ways to create dashboards:

1.Create the data for the dashboard in the dialog box

2.Load the data for the dashboard from a file

Creating dashboard templates

1. In the ***Management*** menu, click on ***Manage dashboard templates.***
   - The ***Manage dashboard templates*** dialog box opens.
2. Click on **New** and select the new document created without a name in the view.
3. Enter a unique name and description.
4. To group your templates, select a category or enter a new one.
5. In the Template area, specify an XML description for the relevant user interface.
6. Click on **Apply** to save the data record.

➪You can see the dashboard you have created in the list in the left-hand window.

Uploading a dashboard template


1. Click on ***Load dashboard template from file...*** in the **Manage dashboard templates dialog box**

2. Select the XML file you want to upload. Make sure that this file contains the template's name and category.

Note: For more information about Dashboard Widgets and a detailed description of the used xml structure to define them, please have a look at chapter 'Task UI and Dashboard Configuration' in the Configuration Manual.

Note: If this template already exists with the same name, you will be asked whether you want to overwrite the template.

➪The uploaded dashboard template can now be seen in the window on the left.



➪You will find the new template created under the category contained in the file.

Note: New dashboards added are not initially assigned to a user group.

Copying existing templates

To copy and modify an existing template:

Click on the template you want to copy and then click on **Copy**.

➪ A copy of the template is created. You can rename or edit this template if required.

Adding object rights

You can use the **Release/Object rights** button to change, assign, or display object rights.

1.Select the dashboard you want to modify or assign to an object.

2.Click on "Release/Object rights".

➪ The view for changing object rights opens.

For more information about action rights, refer to Object rights


Assigning dashboards to user groups

In the pop-up menu for ***Management*** open the ***Organization*** perspective to manage user groups.

1. In the User groups view, click in the **Dashboards field.**

2.Select the dashboards you want to assign to the group from the drop-down list.

Note: If the Dashboards field is not available, add it in the field selection dialog box.



Note: You can only see dashboards if you have the corresponding interface visibility rights.

11.2 Calling up dashboards

Note: To call up dashboards, you require the "Business dashboards" interface visibility rights. For more information about interface visibility rights, refer to Organization

You can open the **Dashboard**view by selecting **Perspectives_Open view**.

For more information about calling up views, refer to Views.

Note:As for items or structure groups, you can also manage object rights for dashboards.


12 Administration

User management is generally carried out as part of the administration. A permission concept is based on the following principles:

- Users are only assigned the permissions required to perform their work with no problems.
- Permissions are assigned to protect users from any incorrect entries (by locking invalid entry screens or fields).
- The data and the system itself need to be protected against external access.
- Only the most necessary checks are carried out, so that the system maintains a good performance at all times.

The primary objective is to enable employees to work effectively without obstructing or slowing down processes with too much bureaucracy.

In Product 360 Desktop the combination of targeted interlinking of user groups with role-specific profiles allows appropriate permission packages to be provided for particular users. The profile design is very comprehensive and allows different types of rights to be linked, which will be explained in more detail in this section.



Furthermore, you can use administration to optimize the clarity of Product 360 Desktop by disabling particular perspectives or views for individual user groups.

This section deals with the following topics:


- Managing the organization 242
- Creating and managing users 253
- Managing visibilities 245
- Assigning user rights 243
- Editing object rights 248
- Client settings 255
- Managing units 261

Note: Note that all permissions for Product 360 Web are also maintained here. Because a web-based interface is used, the terminology used for the permissions differs.

12.1 Organization

Organizations are viewed as administration units. Because it is possible to link them in any kind of hierarchical structure, you can map very detailed company topologies. Depending on the

company's size, branches can also be viewed as an organization, as can individual business units or simply different departments.



Example of a typical organizational structure

Your company can act as both a supplier and a customer. Therefore, you can maintain the data for your company in the ***Organization*** perspective, which you call up using **Management > Organization**. The view used for this purpose contains a detailed view of your company data. You cannot maintain any other companies in this perspective.

The perspective includes:

- the ***Company data*** view, in which you can specify settings for your own company
- the ***User groups*** and ***Members*** views, in which you can manage user groups and their members
- the ***Action rights***, ***Interface visibilities***, ***Object rights (system)***, ***Field rights***, ***Qualified field rights***, and ***Licenses*** views

12.1.1 Managing user groups

Every user has certain rights within the application, which specify which parts of the application he or she can use. These settings are made with regard to a particular action right, e.g. "Create items", and a particular field right, e.g. "Short description (English)".

An action right or field right can never be directly assigned to an individual user. Assignments are always made using the user group. User groups are managed in the ***organization perspective.*** Users are assigned to a user group in the ***Users perspective.*** If a user belongs to several user groups, he or she has all of the rights assigned to these user groups.

Tip: First specify the permission structure in the ***Organization*** perspective, before you subsequently apply it in the ***Users*** perspective.

Although you create users in Product 360 Desktops, no user can create or manage his or her "own" objects. Every object created by an authorized user belongs to "everybody" or to "nobody". You can use object rights to change this behavior for individual objects.

Create user groups

1.Click on + *in the* User groups view.

⇨ A new row is created in the table.

2.Enter a unique name and a description of the user group.

3.Check whether the status of the user group is set to "Active".

4.Click on to save the data record.

Note: You can set the status of user groups to "Active" or "Inactive". In this way, you can temporarily modify the permissions for a large number of users at the same time by activating or deactivating a user group.

Sometimes, you may want to create a user group that only differs very slightly from an existing group. In this case, it is possible to clone the group. All permissions are then retained.

Cloning a user group

1.Select the entry to be cloned in the ***User groups*** view.

2.Duplicate it by selecting **Clone** in the pop-up menu.

⇨ This creates a new row in the table with the set information.

3.Modify the details.

4.Click on to save the data record.

Note: In order to be able to clone user groups, this field must be adapted accordingly by your Informatica consultant using the Repository module.

Members of a user group

To obtain an overview of which users are assigned to which user groups:

- Select the user group in the ***User groups view.***

⇨ The ***Members*** view shows all users from a selected user group.

Users are assigned to a user group in the ***Users*** perspective.

External group assignment

If you have configured an LDAP server, you can map the external LDAP groups to PIM groups here.

This means that users from the LDAP group are automatically created at login and assigned to the PIM group.

The users must use their LDAP access data to log into Product 360 Desktop.

Note: This works for both Product 360 Desktop and forProduct 360 Web

12.1.2 Managing licenses

The ***Licenses*** view lists all Informatica Corporation add-on modules for which you currently have licenses. Like action rights, you can assign or withdraw licenses to or from a user group.

1. Select the user group in the ***User groups*** view.
2. Activate a software module in the ***Licenses*** view by placing a check mark in the "Usage" column.

To simultaneously assign or withdraw one or more permissions to or from the selected user group:

1. Select the user group in the ***User groups view.***
2. Select the software module in the ***Licenses view.***
3. Select **Allow usage** in the Views menu or click on ☑.
4. Select **Withdraw usage right** in the Views menu or click on ⛔.

12.1.3 Assigning views and perspectives

Assigning views and perspectives to particular user groups makes the scope of Product 360 Desktop clearer, and thus simplifies the requirements for operation. You can find basic information about perspectives and views in the introductory sections.

Rights for interface visibilities are combined into rights groups for organizational reasons. A rights group combines individual rights so that you, as the user administrator, can find an individual right more quickly.

⚠ Caution: New users or user groups automatically have all interface visibility rights. New views and perspectives added are available to all users by default.

The ***Interface visibilities*** view depends on the ***User groups*** view. If you select a user group, the rights for the group are displayed in the ***Interface visibilities*** view.

1. Select the user group in the ***User groups*** view.
2. Set a permission in the ***Interface visibilities*** view by placing a check mark in the "Allowed" column.

To simultaneously assign or withdraw one or more permissions to or from a user group:

1. Select the user group in the ***User groups*** view.
2. Select the corresponding rights in the ***Interface visibilities*** view.
3. Select **Assign permission** in the Views menu or click on ☑.
4. Select **Withdraw permission** in the Views menu or click on ⛔.

You can find a list of all available interface visibilities, arranged by the relevant rights group, in the appendix.

⇨ Note: Note that the permissions for Product 360 Web differ in terms of visibility, as a Web-based interface is used here

12.1.4 Assigning action rights

The right to execute a particular function is referred to as an "action right". You can assign these to or withdraw them from a user group. Rights are combined into rights groups. You can use a filter to select rights groups.

The ***Action rights*** view is dependent on the ***User groups*** view. If you select a user group, the rights for the group are displayed in the ***Action rights*** view.

1. Select the user group in the ***User groups*** view.
2. Set a permission in the ***Action rights***, view by placing a check mark in the "Allowed" column.

To simultaneously assign or withdraw one or more permissions to or from a user group:

1. Select the user group in the ***User groups*** view.
2. Select the corresponding rights in the ***Action rights*** view.
3. Select **Assign permission** in the Views menu or click on ☑.
4. Select **Withdraw permission** in the Views menu or click on ⛔.

12.1.5 Action rights

Action rights are assigned to rights groups for the purposes of clarity. A rights group combines individual rights so that you, as the user administrator, can find an individual right more quickly.

> Note: There are similarities between a perspective and a "general access" permission but they are not the same thing. Remember that "general access" to a rights group may correspond to several perspectives.

Certain rights lend themselves well to assignment in combinations, others less so. For example, it is useful to assign the "Create users" right along with the "Edit users" right.

> Note: To classify an item or to delete its classification assignment, the user must have the "Edit items" right. On the other hand, any user who has the right to edit items also has the right to classify them.

You can find a list of all available interface visibilities, arranged by the relevant rights group, in the appendix.

12.1.6 Managing field rights

The right to view or edit a particular value is referred to as a "field right". In the ***Field rights*** view, you manage the permissions for the individual fields in Product 360 Desktop in the same way. The distinctive feature of the field rights concept lies in the fact that each individual field for which you set a permission status for a user group is an element in the repository. This means that, if you add more fields to the repository, you can automatically make use of the same control options in the rights concept as are available for all the other fields.

All existing field rights are divided into data ranges and field groups. A drop-down list allows you to select the range you require. You can define which rights are to be assigned to a selected user group either directly in the table or by using the menu icons.

A distinction must be made between fields that do not have to be qualified and those that do before they can be displayed. Here, you can specify a uniform field right for any field qualification. In other words, the field right for the "Short description (German)" field is always exactly the same as the field right for the "Short description (English)" field. If you want to restrict user groups' rights at qualified field level, use the ***Qualified field rights*** view, for example, to specify that a user group can edit the German short description but not the English.

Managing field rights

Field rights can be set to allow users to view a specific field or change the value stored for the field or to prevent them from doing so. You can assign these two rights entirely independently of one another. However, it is normally more logical to also assign the "Visible" right whenever the field is set to "Editable". This results in the following useful combinations:

- Not visible – Not editable
- Visible – Not editable
- Visible – Editable

All fields are divided into data ranges and field groups. The filter can be used to quickly identify the relevant fields. You have three options for assigning or withdrawing rights:

1. Clicking on the corresponding check mark.
2. Selecting the corresponding function in the Views menu.
3. Clicking on the corresponding icon in the Views menu:
   - Click on to make the selected fields visible or on to make them invisible
   - Click on to make the fields editable or on to make them not editable

If you choose to set the right by calling up the function or using the icons in the toolbar, you can select several or all fields in a data range and set the permission for them at the same time.

Note: If you select several user groups with different field rights, the icons are grayed out. First select a user group and the field for which you want to set the field rights.

The system automatically maintains the values for a small number of fields, e.g. time stamp. Therefore, you can never assign permission to edit these.

12.1.7 Qualified field rights

In the ***Qualified field rights*** view, you can further restrict the rights of user groups at qualified field level, e.g., to allow a user group to edit the German short description but not the English. These "qualified field rights" represent a further refinement of the assigned field rights. As is the case for field rights, a setting can be made to allow users to view a given field or change the value stored for the field or to prevent them from doing so.

The fields are divided by qualification key, e.g., for languages depending on the languages maintained in your system. In this view, you can define additional restrictions for user groups using qualification keys:

- Item identifier types
- Item reference types
- Valid in regions
- Customers
- Countries
- Suppliers
- Price types
- Product reference types
- Languages
- Structure systems
- Currencies
- Surcharges

Managing qualified field rights

You have three options for assigning or withdrawing rights:

1. Clicking on the corresponding check mark.
2. Selecting the corresponding function in the Views menu.
3. Clicking on the corresponding icon in the Views menu:
   - Click on to make the selected fields visible or on to make them invisible
   - Click on to make the fields editable or on to make them not editable

If you choose to set the right by calling up the function or using the icons in the toolbar, you can select several or all fields in a data range and set the permission for them at the same time.

12.1.8 Object rights

You can use object rights to restrict or block access to specific objects for individual users or user groups. You can set object rights for the following objects:

- Items and products
- Assortments
- Search
- Users and user groups
- Purchasing and selling discount groups
- Import mappings
- Export format templates and export profiles

- Supplier catalogs and master catalog
- Structures and structure groups
- Versions
- Dictionaries

You can choose between the following access levels:

- Read: Users have read-only access to the objects. They are not allowed to make any changes.
- Write: Users have read and write access to the objects. For an item, this means that you can also change and delete prices and attributes. However, they cannot delete the item itself.
- Delete: Users are allowed to delete objects.
- Full access: In addition to having Read, Write, and Delete rights, users can also edit the object rights themselves.

As long as you do not set any object rights, each user who has the corresponding user rights has full access to the object, provided that the object has not inherited any object rights and no system-specific object rights have been set. You set object rights in the object itself.

12.1.8.1 Inheriting object rights

A special feature of object rights is that - in the case of catalogs, structure systems, and structure groups - child objects can inherit them. For example, a catalog can pass on its object rights to its items. Note the following special features of inheritance:

- A catalog passes on its object rights to its child objects, that is, to its items.
- A structure system passes on its object rights to its structure groups.
- Structure groups pass on their object rights to their subordinate structure groups.
- For a specific structure system in the master catalog, you can specify that its structure groups also pass on their object rights to items. In order to do this, the structure system must not permit multiple assignments. Furthermore, the structure system cannot be changed. Your Product 360 Desktopconsultant can define this "inheritance" structure system for you.
- If both the master catalog and structure system were to pass on their object rights to an item, the structure system would "win", i.e., its object rights would be passed on to the item.
- If an item has inherited object rights from the parent object (supplier catalog), they are not transferred during a merge because, as a result of the merge, a copy of the item is created in the master catalog and, on top of that, the master catalog may have its own object rights, which it passes on to its child objects.

Note: Inheritance does not take products into account.

Various object right types are managed for objects. A distinction is made between:

- "Blank": No object rights set, i.e., any user who has the corresponding user rights can access the object


- System: System-specific object rights are set
- Inherited: Object has inherited object rights from the parent object, e.g., catalog or structure group.
- Individual: Individual object rights have been set for the object.

If an item has the object right type "Inherited", the object rights of the item automatically change when the parent object is changed. However, if the item has the object right type "Individual", changes to the parent object are only passed on if the "Force overwrite" option is enabled.



Inheriting object rights

You can cancel the inheritance of object rights in the "Object rights" dialog box by removing the check mark next to the "Rights inherited from parent object" option. You can then define individual object rights for the object.




Inherited object rights

Object rights and versions

Object rights are not versioned, i.e, the object rights in the working version are the same as the object rights for objects in other versions. When you create a version, all of the necessary objects are versioned, even if the user cannot see them as a result of his or her restricted object rights. This ensures that a version is complete at all times.

12.1.8.2 System object rights

In the ***Organization*** perspective, you define the rights for creating new system objects in the ***Object rights (system)*** view for different objects.



Object rights

1. Select the data type from the drop-down list in the ***Object rights (system)*** view.
2. Click on ✚.
   - The selection dialog box for users and user groups opens. In this dialog box, you first see the organization itself with all of its users, and then the individual user groups with their respective users.
3. Select the relevant user(s) or user group(s).
4. Click on **OK**.
   - The users or user groups are added.
5. Set the check mark for the corresponding rights.
6. Click on 💾 to save the settings.


Note: Here, you can also add the "current user group" or "current user" and assign it object rights. Usually, at this time, you do not yet know which user will create an object.

If the "current user" is a member of a user group that has several object rights, these object rights replace those of the "current user".

12.1.8.3 Managing object rights

The general procedure for setting object rights is outlined using the example of a structure group.


1. Select the structure group whose object rights you want to restrict in the ***Primary structure tree view.***
2. Select **Object rights...** in the pop-up menu.
   - A dialog box for setting the object rights opens.
3. If the structure group has inherited object rights, you must first remove the check mark next to the "Rights inherited from parent object" option so that you can edit the settings.



Setting the object rights

4. To add object rights for a new user or user group, click on **Add**.
   - The dialog box for selecting groups or users opens. Here, the user groups and their assigned users are displayed in a tree structure.
5. Click on the arrow next to the user group in order to display its users.
6. Select an individual user or user group. To select several entries, hold down the CTRL key.
7. Click on **OK**.
   - The user or user group is displayed in the "Object rights" dialog box.
8. Set the check mark for the corresponding rights.
9. If you also want the object rights to be passed down to child objects, set a check mark next to the "Rights passed down to child objects" option. You can also use the "Force overwrite" option to specify whether you want the program to overwrite individual object rights for child objects.
10. Click on **OK**.

You can also select several objects whose object rights you want to change. If different object rights are specified, a corresponding message will be displayed. In this case, you cannot change the object rights for all selected objects simultaneously.



Different object rights

Tip: In the "Field selection" dialog box, display the "Object rights" and "Object right type" columns so that you can group objects by these columns. They enable you to quickly obtain an overview of which objects have different object rights.


If you only want to find out which object rights have been set for a particular object, you can call up the properties of that object:

1. For example, select an item in the ***Item #1 view.***
2. Select **Properties...** in the pop-up menu.
   - The properties window opens.

3.Switch to the "Object rights" tab.

⇨ On the "Object rights" tab, you can view the object rights that have been set, but you cannot edit them.

If you want an object to be visible to all users again with no restrictions, delete all object rights for this object.



Removing all object rights

12.2 Managing users

To open the ***Users*** perspective, select **Management > Users**. It consists of two views:

- ***Users:*** A list of users in a table format
- ***Membership:*** A table in which the selected user's membership is managed

As for items or structure groups, you can also manage object rights for users.

Information: The "Logged in" column shows which users are currently logged in. Moving the mouse over the green symbol displays additional information in a tooltip.

Creating users

All users that have been entered in the system to date are displayed in the ***Users*** view.

1.In the ***Users*** view, click on ✚.

⇨ A new row is created in the table.

2.Enter the data for the user. After entering the password, a dialog box prompts you to repeat the entry.

3.Click on 🖫 to save the data record.

Note: You specify which form of authentication is to be used for user identification in the "Authentication mode" column.

Select one of the following options from the drop-down list:

- Internal: Only th Product 360 Desktop identifier is used, i.e. the user is authenticated using the user name and password defined in Product 360 Desktop user management.
- External: User authentication is based on the user ID of the operating system user, i.e. the operating system user must be created as an Product 360 Desktop user. User authentication is based on login to the operating system. In this case, the internal Product 360 Desktop password is irrelevant.

Assigning users to user groups

A user that you have selected in the ***Users*** view is assigned permissions by virtue of the fact that he or she belongs to certain user groups.

1. Select the user in the ***Users*** view.
2. The ***Membership*** view shows which user groups the user is assigned to.
3. Place a check mark in the "Member" column to assign the user to a particular group or clear the check mark to remove the user from that user group.

Note: Assignment to an inactive group has no effect on the scope of the user rights. User groups and the associated rights are managed in the ***Organization*** perspective.

Changing the password

Passwords are reset in the same way as when they are assigned for the first time.

1. Change the password in the "Password" column in the ***Users*** view.
2. A dialog box prompts you to confirm the changed password by entering it again. You can only close the dialog box with **OK** once you have correctly repeated the password.
3. Click on **OK**.

Note: Product 360 Desktop does not manage a runtime or password history, so in theory the same password can be used indefinitely. However, you can use internal processes to ensure that passwords are changed regularly.

"Normal" users cannot change their own passwords unless they themselves have the User administration right. Product 360 Desktop does not require initial passwords to be changed. You must set up your own internal workflows or guidelines as required.

Deleting users

Tip: If you only want to change the status of a user, clear the check mark in the "Active" column to deactivate the user.

1. Select the user in the ***Users*** view.
2. Select **Delete** from the pop-up menu or press the DEL key.
   - The selected user will be deleted immediately without a confirmation prompt.

Note: Since users do not have their "own objects", e.g. assortments, deletion presents no difficulties.

The user is only checked once, at login. If the user you have just deleted is still logged in, he/she can continue working. After the user closes the application, he/she will be unable to log in again.

12.3 Preferences

The client's user-specific settings are managed in the "Preferences" dialog box. Select **Management > Preferences** to open the dialog box.

The left side of the dialog box allows you to select particular topics from a tree structure, while the right side displays the associated settings.

If you are not yet fully accustomed to using Product 360 Desktop, seek advice on the best settings for your requirements.

Tip: Some pages of the dialog box require more space in order to be displayed fully. For this reason, you can change the size of this dialog box. You can also set the width of the left and right sections.


For all settings, you can restore the default values by clicking on **Restore default values**. This function affects all values on a page. Default values cannot be changed.

Changes on one page of the dialog box can be saved by clicking on **Apply**. Changes are also saved when you click on **OK** to close the dialog box.

12.3.1 Table settings

Under "Table settings", you can specify the maximum number of data records to be displayed in a table. Enter a higher or lower value depending on the capacity of your system. The number zero (0) means that all items found will be listed.

If the number of items found is greater than the number specified here, a corresponding message will be displayed when listing the items.



Message when loading items

You can choose from the "Load limited", "Load all" or "Load all optimized" options. The number 10,000 has been specified in the settings in the example above.

Note: The number set here can be viewed as a "protective mechanism". If the number selected is too high, excessive amounts of data may be loaded into the computer's main memory over the network. This would require so much of your computer's memory that in the worst case the operability of your system may be compromised.

You can decide in individual cases whether all of the data is to be loaded or specify the settings for the different data types.

Additional settings

- Restrict the number of grouping nodes per grouping level. The number zero (0) means that Product 360 Desktop will list all grouping nodes at each level. The number set here can be viewed as a "protective mechanism". This also applies to the note above relating to the size of the number.
- Activating or deactivating region-specific sorting for texts, and case sensitivity

Note: Using region-specific sorting may impair performance under some circumstances.

12.3.2 Item attributes

Under "Item attributes" you can specify:

- Whether a confirmation prompt is to be displayed before saving cumulative attributes.
- Whether attribute values for a classified item are to be displayed in the same unit as the features,
- Whether a check is made as to whether the item attribute can be converted to a structure feature. If this is the case and this option is activated, the converted value is displayed. If conversion is not possible, a warning to that effect is displayed.
  The value of the item attribute itself is never changed, because a multiple classification would inevitably lead to a (contradictory) multiple conversion depending on the conversion factors that were available for use.
- Whether assignment of default feature values to attribute values is to be enabled.
  Here, you can specify:
  1. Whether attributes that do not yet exist are automatically created in the ***Item attributes (cumulative)*** view.
  2. Whether the feature values are also transferred as part of the cumulated feature transfer.
  3. Whether the item attribute values are overwritten if the feature value transfer is enabled.
  4. Whether data types are also transferred as part of the cumulated feature transfer.
  5. Whether purposes are also transferred as part of the cumulated feature transfer.
  6. Whether customer-specific fields are also transferred as part of the cumulated feature transfer.

Caution: Note that, in "Completely overwrite attribute values" mode, attributes of the inheriting group that may have taken a long time to maintain may be reset by the inherited values and you may lose several days' work as a result.

- If necessary, you can specify that only selected features are to be transferred.

- Restrict the maximum number of items that are to be included in the cumulative feature transfer.

12.3.3 Item classification

Under "Item classification", you can specify whether the master catalog or the supplier catalogs will be used as the data basis for a classification analysis. You can also specify whether an information message is to be displayed during classification.

In addition, you can make a setting to determine whether the drag and drop action moves or copies the item assignment during multiple classification within a structure system. In the standard configuration, the item assignment is moved, while you must hold down the CTRL key at the same time if you want to copy it.

You can also set whether a warning message is to be displayed when classifying.

12.3.4 Image preview

Under "Image preview", you can specify the background color used for the display in the ***Image preview*** view. White is set as the default color.

12.3.5 Import settings

By default, import projects are stored in the client workspace. Here, you can specify a different directory for import projects, allowing a directory outside the workspace to be used.

12.3.6 Merge preview

The defaults can be used to maintain the values that will be set as the default settings when merging a new supplier catalog into the master catalog. The fields are divided into different areas, which can be opened or closed. When opened, the individual fields in the areas can be seen.

The merge mode can either be set for an entire area or directly at field level. For example, this enables all fields in an area to be dealt with in the same way while a different setting is made for specific individual fields.

The various ways in which the merge works are explained using the example of the "Short description" field:

Merge setting	Example
Add	German and English short descriptions exist. The new supplier catalog contains German, English and French short descriptions. The merge adds the French short descriptions, with no change to the German and English short descriptions.

Merge setting	Example
Replace	German, English and French short descriptions exist. The new supplier catalog contains English and French short descriptions but no German short descriptions. The merge replaces the English and French short descriptions and deletes the German short descriptions.
Ignore	New data is ignored, i.e. essentially no merge is carried out for these fields.
Overwrite	German and English short descriptions exist. The new supplier catalog contains German and French short descriptions. The merge overwrites the German short descriptions, adds the French short descriptions, and leaves the English short descriptions unchanged.

12.3.7 Miniature view

The "Number of columns" and "Page size" settings determine the display in the ***Miniature view*** 190 and ***Miniature view (documents)*** 191 view.

You can also specify whether the preview images in the ***Documents*** 187 view are to be displayed as small, medium or large images.

12.3.8 Multimedia attachments

Specify the applications to be started if you want to view or edit a particular MIME type.

All file types found on your computer by Product 360 Desktop are listed on the left. On the right, you can indicate the programs to which a selected file type is to be linked. You typically use the default setting, which you can also control using operating system mechanisms. However, you can also assign additional programs to the file types here. The specified program is used to open and display a multimedia document in Product 360 Desktops.

12.3.9 Product

Under "Product" you set whether a confirmation prompt will be displayed with creating product references.

12.3.10 Structure editor

Specify:

- Whether the features of the parent group are to be transferred when structure groups are created.
- Whether the (inheriting) subgroups are also to be updated when features are changed.
- Whether the items and item assignments are also to be copied when structures are copied.

12.3.11 Structures - Basic settings

In the "Structures – Basic settings" settings, you specify the default language in which structures are to be displayed. Of course, you can only select a language that is actually available in the system. You can also specify:

- Whether the standard classification system will be cached on the client.
- Which structure systems will be loaded by default on launch.

12.4 The "Administrator" user

As a newly installed ("empty") Product 360 Desktop system does not yet contain any users or user groups (except the "Administrator"), there must be a user that has all-encompassing rights without belonging to a user group. Of all the users, the “Administrator” user account therefore has a very special role.

- It cannot be deleted.
- Administration rights cannot be withdrawn from this user account, e.g. by assigning it to a group that only has restricted rights.
- However, it can be renamed just like any other user account.


Note: You can assign the Administrator user to a user group but this assignment has no effect.

These special features of the "Administrator" user account cannot be transferred to any other administrator account.

12.5 System messages

The administrator can use system messages to send notifications to Product 360 Desktops users, e.g. when updates need to be performed. A message informs users of this when the start their client. A special option enables the administrator to show the messages to users who are already logged in.

You can also open system messages by selecting **Help > Show system messages** in the menu.




System message s

In the ***System messages*** view, you can use the "Status" column to identify whether or not a system message is active. There are four different statuses:

- Green: The system message is active and is being displayed.
- Yellow: The system message is active but the start date is in the future. The system message is not yet displayed.
- Black: The system message has expired and is no longer displayed.
- Red: The system message has been deactivated.

12.5.1 Creating system messages

1. Open the ***System messages*** view.
2. Click on ✚.
   ⇨ The "New system message" dialog box opens.



Create new system message

3. Enter a title and a text for the message.
4. Specify the start time for the system message. The message will be visible from this time.
5. Specify the end date. After this date, the system message will no longer be visible.
6. Specify the event date, on which the event mentioned in the text will occur. This is displayed next to the title.
7. If you select the "Send message immediately" option, logged in users will see the message immediately.
8. Click on **Save**.

Note: You can clone an existing system message by selecting it and then calling up **Clone system message** in the pop-up menu.

12.5.2 Editing system messages

The procedure for editing an existing system message is as follows:

1. Open the ***System messages*** view.
2. Double click on the message you want to modify.
   - The "Edit system message" dialog box opens.
3. Edit the title, the text, or the start/end date, as when creating a system message.
4. Click on **Save** to save the changes.
5. Click on **Close**.

> Note: Expired system messages can no longer be edited. However, you can clone them and specify new start and end dates.

12.5.3 Deactivating system messages

You can deactivate a system message, i.e. make it invisible, even if the specified start date has been reached.

1. Select the message in the ***System messages*** view.
2. Select **Deactivate system message** in the pop-up menu.
   - The system message is deactivated. To reactivate it, select **Activate system message** in the pop-up menu.

12.6 Units

A unit system is used to manage all possible units you may require to specify a size. Product 360 Desktop is supplied with its own unit system, which is based on the UNECE code table. Units are managed in the ***Units*** perspective, which is called up by selecting **Management > Units**. This perspective contains the ***Unit systems***, ***Unit system***, and ***Unit maintenance*** views. This perspective tends to be used very infrequently.

> Note: The unit system used in your system may differ significantly from the unit system that is part of the package supplied. The unit system is normally specified by specialist departments before starting productive operation and is then changed very infrequently during operation.

Every size consists of a value and a unit. Typical examples of sizes include:

- 1 kg
- € 15.40
- 220 V
- 4 m/s
- 12 units

The units used in this example – "kg", "€", "V", "m/s" and "units" – must be managed in the unit system so that they will be available in drop-down lists. Maintained units are used at the following points:

- Purchase and selling prices
- Order information (order unit, package sizes, etc.)
- Purchasing info records
- Features

12.6.1 Unit systems

You can use the ***Unit systems*** view to manage your unit systems. A distinction is made between two different groups:

- **User-defined unit systems**
  You can edit user-defined unit systems, i.e. rename or delete them. Every unit system you create is always of the type "user-defined".
- **Default unit systems**
  One or more default unit systems are created automatically during installation. The default unit systems should be viewed as copies, issued by specialist organizations (ELDANORM, United Nations etc.) for example.
  Under some circumstances, your system may not contain any default unit systems.

12.6.2 Unit system

In the ***Unit system*** view you can display details of the unit system that you selected in the ***Unit systems*** view. If the selected unit system is a default unit system, you cannot edit the corresponding entries.

12.6.3 Unit maintenance

The individual units are managed in the ***Unit maintenance*** view.

1. Click on ✚ to create a new unit.
   ⇨ This creates a new row in the table with a unique code.
2. Enter the data for the unit.
3. Click on 🖫 to save the data record.

You can also assign the unit to a specific category and maintain it as language-specific, or assign a code or acronym to the unit. In addition to the Product 360 Desktop unit system, the codes for the maintained units can also be assigned to other unit systems by showing the corresponding columns using the field filter dialog box. (Unless otherwise specified in the setup, only codes created with the Product 360 Desktop code qualification can be used). Particularly when exporting items, maintaining alternatively qualified unit systems can be useful.

If you have specified a base unit for a unit, you can define how to convert between the two units.

Example: If you create the unit kilograms and specify grams as the base unit, you can define a conversion factor of 0.001 (0.001 kilogram = 1 gram).

13 Export

The export module in Product 360 Desktops is primarily used to export your product data to electronic catalogs. This concerns a "physical" export whereby data is transferred from one storage location to another. In contrast, you can use a browser to display the data in a preview schema. This type of "export" only transfers the data temporarily and simulates how the data is displayed for a particular output channel. This differentiation is governed by the purpose configured in the format template.

Furthermore, the main features of the export module are targeted data selection options and flexible conversion of e-commerce data. based on various export format templates. An export format template is similar to a whole package of agreements, which contains all the information about which item and product data is to be exported and how.

An export format template contains data fields, which access the data content in a particular data source when exported. The data fields can be arranged flexibly and positioned in any order. Existing export format templates can be copied and easily adapted to suit the specific requirements of your customers. You can also develop your own export format templates. You can supply the exact data requested by your customer in the required data format. There is no need for time-consuming data conversion.

To gain an overview of the settings made, you can define format templates exclusively for a preview. These apply to the "Item", "Product" and "Structure group" object types and can be provided for a single selection or multiple selection.

Specific properties of your data can be qualified, allowing country-specific settings to be made for price information, for example. The export module can be connected to ERP, publishing and printing systems to extend their functionality.

The data content to be output is converted to a particular format using various formatting functions and languages. The export format template also defines the file types of the export files. The options available range from comma-separated, tabular export files, e.g.:

- simple text files
- CSV files

through Web-based output media such as:

- online catalogs in HTML, CSS and XML format
- media files such as CIF

to industry-specific, predominantly XML-based data interchange formats including:

- cXML (Ariba)
- xCBL (CommerceOne)
- eCX (Ariba)
- BMEcat (Bundesverband Materialwirtschaft, Einkauf und Logistik e.V. -– Association of Materials Management, Purchasing and Logistics),
- Datanorm
- EldaNorm

13.1 Export module


Before the preparation, configuration and execution of export operations are discussed in detail, this section provides an overview of the general procedures and options for exporting data. This includes:

- Export format templates and export profiles
- Data sources, export parameters, and variables
- Data fields, functions, and comments
- Export files
- One-off or repeated export
- Export operation principle

You create and edit export format templates in the ***Export format templates perspective.*** It consists of the following views:

- ***Export format template***
- ***Properties*** of the export format template (and its modules)
- ***Export module editor***
- ***Log***

The most important editing options can easily be selected by clicking on the corresponding icon in the toolbar. Alternatively, the Views menu in the ***Export format template*** view provides a list of all export functions.



Export format template

13.1.1 Export format templates and export profiles

An export profile is a central element for a data export. An export profile contains all instructions for retrieving, formatting, checking and outputting data. An export profile must always be selected before you can start an export operation.

Each export profile is based on a single export format template and, depending on the export format template, may also contain additional settings. You can create several export profiles for performing data exports of the same type, for example, generation of a catalog in accordance with the BMEcat standard. These use the same export format template but contain specific settings, for example, the item assortment to be output or the language for language-dependent data.

The structure of the data to be output is defined in export format templates. For example, you can have an export format template for generating a BMEcat file, which generates a valid BMEcat catalog in each case. Additional configuration settings (such as the item assortment or language) can be made in the export format template itself with a fixed value (which cannot be changed) or a default value (which can be changed) or can be left blank. The value set here determines whether these settings can be changed in the export profile.

Export format templates are normally created and tested in accordance with the requirements for the export files. The relevant export profiles are then created and used to perform the data exports. This means that there are two ways of working in this area:

- Creating and testing export format templates
- Using the export profiles in a live export

13.1.2 Data sources, export parameters, and variables

The structure of the data to be output is defined in the export format template. The data source determines which type of data is to be exported. One or more data sources can be registered in the export format template for this purpose. These data sources supply information about the available data fields and may need to be configured. For example, a data source that provides item data must normally be assigned an assortment. A data source that supplies structure groups, meanwhile, must be assigned a structure group system.

In addition to the mandatory parameters mentioned above, many data sources also have optional parameters, such as the additional filtering of an item assortment using a product group system or structure system.

Default or preset values for parameters are useful in many cases. These are generated when a parameter can be changed and is assigned a value in the format template, for example, the output language that is to be used by default. If parameter values have not yet been filled in the export format template, you can do this by setting them as "editable", which means that they are displayed in the export profile and can be changed there. To hide parameters in the export profile, set them as "not editable" in the export format template. As a result, they are not visible in the export profile. Note that mandatory parameters must always be assigned a value.

Of course, the complexity of the export format templates and your specific requirements will always determine which combination of preset values and fixed parameter values you use in your export format templates.

An important option for simplifying export format templates and export profiles is the use of variables. Like data sources, these are registered in the export format template and are assigned a name and a data type. Variables can themselves be used as values to configure data sources. This is particularly useful if several data sources of the same type are to have identical parameters.

Example: Three item data sources are used in an export format template and all of these are to use the same item assortment. Three parameters with the same value must be configured in the export profile. If a variable is used instead, only one parameter value needs to be entered in the profile.

13.1.3 Data fields, functions, and comments

Once the data source has been registered in the format template, the contents of the data modules can be edited. This normally consists of a combination of text and placeholders, which are replaced by actual content during the export operation. These placeholders may be data fields, functions, comments, variables or submodules.

The data fields that can be used depend on the assigned data source: An item data source provides item data fields, e.g. item number, item name, etc., a structure group data source supplies structure group data fields, e.g. structure group name, etc. Data fields can be qualified, which is indicated by the field selection when configuring the item tables.

You can use variables to qualify the data fields. For example, you can use a "Language" variable to define the language for the language-specific data fields for outputting an item list. You use this variable to qualify all language-specific data fields. You can now export this item list in any language without having to make any changes to the export format template. You can create the language in the export profile or when starting the export operation.

The values of variables can also be output in the same way as the contents of data fields.

Functions or, more specifically, export functions, allow you to format, evaluate or edit the data to be output. There are numerous special functions to support you in creating particular output formats.

Comments help you to clearly organize and define the contents of the export format template modules. The comments are ignored during the actual export operation.

If you use submodules in your export format template, use this placeholder to mark the logical location where the contents of the submodule are to be output. Processing of submodules is described under Export operation principle.

13.1.4 Export files

An export operation normally creates a data file. If file attachments are exported, a multimedia archive is also generated. The multimedia archive contains all file attachments. This section only

deals with the export file or data file.

One or more export files may be generated, depending on the structure of the data to be output. You can define the name, the format and the coding of each data file.

You do not need to make any additional settings to output the data in a single file. To generate several files, register each file with its name, format and coding in the export format template and then assign the relevant export file to each format template module. A third option is to generate an export file for each data record. In this case, instead of the name you only specify a file naming convention to be used to generate the file name during the export operation.

13.1.5 One-off or repeated export

Export operations are always performed on the server side. When you perform an export you can decide whether the export operation is to be executed immediately, at a particular time or repeatedly. For an immediate export, you can also save the export file locally. The settings and output files are archived and the export log can be viewed in the ***Process overview*** perspective. The export file can also be downloaded to a local directory in the ***Process overview*** perspective.

To repeat server-side export operations, specify the number of times they are to be repeated and the time interval between each repetition, for example, "every week". Alternatively, you can use a repetition pattern, such as "Every second week on Monday".

13.1.6 Export operation principle

The principle according to which each export operation is executed is explained below. It is irrelevant whether the export is performed once or repeatedly and whether one or more output files are generated.

The format template modules at the top level of an export format template – known as main modules – are always processed in order.

If a data source has been assigned to the main module, this first retrieves the data in accordance with the configuration settings. The module contents are then processed once for each data record. A module without a data source is output only once.

During processing of a module, the placeholders (data fields, variables) within the module text are replaced with actual content, functions are evaluated and comments are removed. The resulting text is written to the file assigned to the module, whereby the format and coding are taken into account. Sub-module references are also used as placeholders here. The sequence of sub-modules in the format template is not relevant for processing. A sub-module is only processed if a main module contains a reference to that sub-module. A sub-module is output in the same way as a main module: The sub-module is processed once for each data record found. If no sub-data type was assigned, the module is output once.

After the actual export operation is completed, post-export steps can be executed. These not only complete the export of file attachments, but also enable additional operations in relation to the output file, including copying or moving to another directory or validation against a DTD.

The export of file attachments plays a special role. This comprises three steps, which must be taken into account in the export format template. The file name query for the multimedia server must be activated. Calling up the **ExportMime** export function selects a file attachment for the export; its path and name is the return value for this function and is output in the export file. Finally, the relevant post-export step must be assigned to the export format template to enable the generation of the multimedia archive.

13.2 Introductory examples

The following examples are intended to provide an initial overview of how export format templates are used. You will learn how to:

- Create export format templates.
- Connect and configure data sources.
- Use variables and export functions.
- Define the type, name and format of the output files.
- Export and test the data.

13.2.1 Creating a simple export format template using test export

What is an export format template?

An export format template is a reusable template that contains modules specifying all of the required information for the export.

You can select data fields. If you only want to export part of the data from the master catalog, you can choose an assortment. For each output file, the file format, character set, file name and path are specified.


You can create an export format template either by creating a brand new template or by copying an existing template.

The following example of a data export into a comma-separated CSV file will guide you systematically through the creation of an export format, to the selection of data and definition of the export contents, and finally the execution of the export.

The example will show you how to:

- create an export format template
- connect a data source
- create a module
- use the module editor
- use a simple function for formatting the output data
- perform a test export


You want to export a list of item numbers and manufacturers for stocktaking. For each item, the stocktaking list should contain a row with the item number, manufacturer name, and the text "Number:" During stocktaking, the number of items counted is then added manually at the end of the row. A semicolon is used as the separator between the data. This will be a pure text file with the file extension "txt".



Item list for stocktaking

To do this, you need to create an export format template.

2. Open the ***Export format templates*** perspective by selecting **Perspectives > Open**.
3. Click on in the menu bar for the ***Export format template view.***



Edit export format templates

4. In the ***Properties*** view, give the export format template the name "Item list".
5. In the "Format" drop-down list, select the entry "TXT (any text)".
6. In the "Encoding" drop-down list, leave the default entry "ISO-8859-1" unchanged.
7. In the "Description" field, enter a short definition of the export format template.
8. In this case, the preset purpose “Export (standard)” is sufficient.
9. Click on in the ***Export format template*** view to save the new export format template.
   - The "Save export format template as..." dialog box opens. If necessary, you can reenter the name and description of the export format template here.
10. Click on **OK**.
    - The export format template is saved.

13.2.1.1 Selecting a data source in the export format template

First, you must select a data source to supply the item data that is to be output.


What is a data source?

A data source provides particular data fields in an export format template. The data fields that can be selected depend on the data source's data type and sub-data types. When the export is performed, the data source provides the data to be exported.

The data source can be specified more precisely using parameters.


Example: The "Item list" data source provides the "Item number" data field and the "Attributes" sub-data type. For the "Item assortment" parameter, assign an entry from the list of available assortments.

1. Select the root node in the ***Export format template*** view.
2. Select **Properties** in the pop-up menu.
   - The "Export format template properties" dialog box opens.



Export format template properties

3. Click on the "Data sources" tab.
4. Click on **New...** at the bottom.
   - The "Select new data source" dialog box opens.
5. Select the required data source from the drop-down list. In this example, "Item list" is selected.



Select new data source

6. Confirm with **OK**.
   - A data source is now assigned to the format template and can be used in modules.
7. Edit the parameters of the data source.
8. Click on **OK** to close the Properties dialog box.

Note: Complex export format templates may require more than one data source. However, you should only add the number of data sources you actually need to use an export format template.

13.2.1.2 Creating a module

To use a data source, you first require a module. In a module, you can specify data content, text, the display method, and the file format for your export file.

What is a module?

The data content to be exported is split between one or more modules in the export format template. A module contains code that is used to create the export files during an export. You can use a module editor to edit the module code. You can insert text, data fields, and function calls. The content of data fields can be edited using functions, for example date and character format functions.


If you do not have a module, you must create one. (A new export format template is always created with a module by default.)

1. Select **New module** in the pop-up menu.
   - A module with the name "New module" is added below the root node.
2. In the ***Properties*** view, assign the module the name "Data module".
3. Click on in the ***Export format template*** view to save the changes.

4.You now need to select a data source for the module. Select the "Data module" module node.

Note: Only data sources that have already been provided on the "Data sources" tab in the "Export format template properties" dialog box can be selected in the module.

5.Select your data source in the ***Properties*** view. Here in the example, "Item list" is selected as the data source.



Selecting a data source

Note: The data type is also selected automatically, as each data source is associated with one specific data type. In this example, the data type is "Item". (There may be several sub-data types.)

13.2.1.3 Editing a module

To edit the code for the module, you need to open the module editor. Each module has its own module editor, which in turn has its own view.


1.Double-click on the module node.

The module editor opens.

2.Switch to the module editor or the ***Data module*** view.

3.Press CTRL and the space bar.

The input wizard opens.



Input wizard

4.Use the mouse or the (up/down) cursor keys to select the **& data field** entry.

5.Press the ENTER key to confirm.

- A **{&** is inserted, which is the prefix for a data field.


What is a data field?

Your master catalog contains data objects (data records) of a particular data type, for example the "Item" data type. A data type provides data fields for data content,
e.g. the "Item" data type has the data fields "Item number", "Manufacturer" etc.

6.Press CTRL and the space bar again.

- The input wizard opens to help you select a data field.

7.To select from the drop-down list, use the mouse or arrow keys to navigate to the data field that you want. You can also enter the first few letters of the name of the data field to find it more quickly.



Input wizard for selecting data fields


8.Click on the field or press Enter to insert it. In this example, the **Item no.** field is used.

9.Type a semicolon ";". This is used as the data field separator.

10.Select a second data field - in this case "Manufacturer" - in the same way.

11.Enter a further semicolon ";" as a separator.

12.Finally, you enter a text. In our example, this text is "Number:". In the stocktaking list, the stock taker can manually enter the number of items after this text.



Two data fields and a column containing

13.Insert a line break by pressing the Enter key.

14.Click on in the ***Export format template*** view to save the changes.

Note: A line break is necessary after a line in a module with data fields to ensure that each data record will appear in a new line in the export file. Otherwise, the data records would appear in a single long line in the export file.

13.2.1.4 Test export

You will now perform an export. The quickest and easiest way to do this is using a test export.

What is the difference between a test export and a normal export?

In a test export, a temporary export profile is automatically generated for the duration of the export. This profile uses the export format template that is currently being edited. If you execute the **Export...** command in the pop-up menu, a permanently saved export profile must be used.

While you are in the process of creating or correcting an export format template, the benefit of using a test export is that you do not need to switch to another view to perform the export. If the export format template has been completed, it can be used as part of an export profile without having to be explicitly opened.

1. Click on in the ***Export format template*** view.
   - The "Export export profile" wizard opens, with the first step "Configuration of export parameters".


What is an export parameter?

Export parameters are variables or parameters for the export format template. The predefined values for these export parameters can be changed both in the export profile and when exporting.

Parameters – or, more specifically, data source parameters – specify the data sources used in more detail and are defined in the export format template properties.

Variables are placeholders for the values of a defined data type, such as a language or character string. Like the parameters, they are defined in the export format template properties.

2. Select an item assortment. This is an export parameter that is created in the data source properties for the export format template.




Parameters in export profile

3.Click on **Next**.

⇨ This takes you to the "Select output destination" step.

4.Leave the execution option as "Export immediately".

5.The "Save export file(s) locally" option can be used for this export. However, you can also download the export file using the ***Process overview*** perspective.



Name and path of output file


6.To save the export files locally, check whether the correct path and file name have been selected.

- To change these, click on ....
- Select a different path or file name.

7.Click on **Finish**.

⇨ Your data is then exported.

You can monitor the export in the ***Process overview*** view. The result of this example is shown in the figure below.



Output file

13.2.1.5 Formatting output files

The data in the output text file is now complete but the formatting is not optimal. To improve readability, the manufacturer names should each have the same number of characters: Spaces are added to shorter names. In our example, none of the manufacturer names is longer than 25 characters.

1.Switch to the module editor.

2.Position the cursor in front of the data field containing the manufacturer name.

3.Open the input wizard by pressing CTRL and the space bar.

4.Select **? Function**.

⇨ In the module editor, **{?** appears to indicate a function.

5.To insert the required function, press CTRL and the space bar to re-open the input wizard.


⇨ The list of available functions is displayed. You can restrict the list displayed by entering the first letters of the relevant function.

6.Select the **FillRight** function.

7.Add the parameters of the function:


- Character string: This is the manufacturer name, i.e. the data field **{&Item.Manufacturer}**.
- Length: Enter the number **25** here to ensure that all manufacturer names will have a length of 25 characters.
- Characters: A blank space is to be added to the manufacturer name, therefore " " is specified as the third parameter.

The content of the module now appears as follows:



Function for formatting the manufacturer name

After saving the export format template, perform another test export. The generated file then contains the manufacturer names with the desired formatting.



Output with formatting

13.2.2 Qualified data fields and export profile

In this example, you will learn how to do the following in the export format template:

- Create a module for a header
- Create a module for outputting data
- Use data fields requiring qualification
- Use a variable

Note: Only data sources that have already been provided on the "Data sources" tab in the "Export format template properties" dialog box can be selected in the module.

13.2.2.1 Plan for output data

You are planning to export particular item data and attributes. To do this, you require the item number, the short descriptions in German and English, the weight (or, more specifically, the value of the "Weight" attribute) and the user who is exporting the data. The desired result is shown in the figure below. The first line in the export file contains the column headings, while the remaining lines represent the item data (the data records). Semicolons are used to separate the columns. The output format should be CSV because you want a comma-separated file.

Tip: When planning a CSV output file, you should bear in mind that the files are often very large and will be used in automated systems, for example because you use the CSV file to define an interface that is used to exchange data with another system. To define the common general conditions for CSV definition, it may be useful for you to read up on CSV standards (http://tools.ietf.org/html/rfc4180).

13.2.2.2 Creating an export format template

1. Create a new export format template
2. Give it the name “Descriptions”.
3. Select the format CSV in the ***Properties*** view. The extension CSV identifies your file as a comma-separated file.
4. Select the required data source in the "Export format template properties". The data source "Item list" is selected here.


13.2.2.3 Creating a module with a header for the export file

You want your output file to contain a header with column headings. A separate module is required for this purpose. This must also appear at the very top as the modules are processed from top to bottom when exported.

Note: Do not select a data source in a header module.

If a module accesses a data source during the export, the module is processed the same number of times as the number of data records. This would produce the same number of headers and data records in the output file. However, a header with column headings should only be output once.

1. Create a new module.
2. Give it the name “Header”.
3. Double-click on the module to open the module editor.
4. Enter the column headings for the item number, short description (German), short description (English), weight and user, separated by semicolons.
5. A line break is required after the last column heading. Press the Enter key to insert it.



Module for the header

Caution: Make sure that the actual column headings used do not contain separators – a semicolon in this example. This would restrict the further options for using the file.

This module only contains static text and therefore does not require a data connection, in other words, a data source.

13.2.2.4 Creating a module for data output

Next, you must create a module for outputting the item data in your export file.

1. Create a second module under the root node.
2. Assign it the name "Item description".
3. Select the "Item list" data source for the module. The "Item" data type is selected automatically.
4. Select the data fields. First, select the "Item no." data field.
5. Then enter a semicolon ";" after it.
6. Next, you will select a data field that can be qualified.

13.2.2.5 Using a qualified data field


Next, you will use a qualified data field. A qualified data field requires you to define at least one specifying feature. A typical example is the "Short description" field, for which the specifying feature is the language because the short description may be stored in various languages.

What is a qualified data field?

A qualified data field has one or more properties, each of which can be freely assigned a value from a list of values. The data field name is made up of the field name and the selected value, for example "Short description (German)". In this case, the value of the property is "German".

Since a qualified data field can be qualified in several different ways, for example "Short description (German)" and "Short description (English)", simple language comparisons can be prepared (for translators for example).

1. Select the data field to be qualified, i.e. "Short description (German)". This normally has a value in brackets in the name, for example "(German)".
   - A dialog box containing properties and the possible property values opens. The "Language" property is qualified with the default value "German". If you are using versions, you should also specify the required version.



Qualified data field

2. Define an alternative language in case no matching entry is available in the required language.
3. Click on **OK** to accept the preset value.
   - The "Short description (German)" data field is inserted into the editor line.
4. Enter a semicolon ";" after it as a data field separator.
5. Select the "Short description" data field again.
6. Assign the value "English" to the "Language" property by selecting it in the drop-down list.
7. Confirm by clicking on **OK**.
8. Enter a semicolon ";" after it as a data field separator.


13.2.2.6 Outputting item attributes

The next step involves using a data field that contains the value of an item attribute.

Other item attributes may exist in addition to the item data fields mentioned above, such as item number, short description etc. Each of these properties has a name, a value, a description and additional data.

In contrast to the data fields already used, to output item attributes you must select the attribute for which the information is to be exported.

1. Use the input wizard to select the "Attribute value (Name selectable, German, DEFAULT)" data field.
   - The corresponding properties window then opens.



Data field with selectable property

2.In the example, leave the "Language for value" property as German.

3.Define English as an alternative language in case no matching entry is available in German.

4.In the "Property" field, select the "Property name (key)" entry.

5.Place the cursor in the "Value" box.


6.Press CTRL and the space bar or the F3 key.

⇨A list of the freely selectable attributes is displayed. The list contains all attribute codes stored in the system.

7.Click on the "Weight" attribute to select it.

8.Confirm with **OK**.

9.In the editor, insert a semicolon ";" after the data field entry. In the example this is **{&Item.Attribute value for weight (German, DEFAULT)}**.



"Header" and "Item description" modules

13.2.2.7 Creating a variable

Finally, you need to use a variable. This will have the name "User".

What is a variable in the export module?

A variable is of a particular data type, which determines the possible values. For example, if you select the data type "String", you will have a variable in which you can enter any text or, to be more precise, any characters.

For a variable with the "Language" data type, the value can be selected from a list, e.g. "German", "English", "French", "Portuguese (Brazil)" or "Spanish", depending on which languages are configured in your system. These values are predefined. You can only select from the specified list of values and cannot define a different value yourself, for example "Greek". If a variable does not have an entry for the set language, you can define a default alternative language, whose value is then used in the field.

In order to be able to use a variable in a module, you must first create the variable in the export format template.

1.In the "Export format template properties" dialog box, open the "Variables" tab.


2.Select **New...** to create a variable.

3.In the "New variable" dialog box, give the variable the name "User".

4.Click on **OK**.

5.Leave the preset data type "Character string" unchanged.

6. Similarly, leave the check marks next to the "Mandatory value" and "Editable" options unchanged. The first of these means that a name must be entered when the export is performed, while the second allows the value to be changed for individual exports.
7. Click on **OK** to close the Export format template properties" dialog box.



Creating a variable in the export format template

Note: You should also specify a description in the "Information" field. By doing so, you can, on the one hand, meet minimum documentation obligations and, on the other, ensure that the text is displayed as a tooltip during the export. This helps the user to understand the purpose of the value to be entered.

If you have already entered a text in the "Value" field, this is used as the preset value.

In the example below, the variable is selected and used in the module.

1. Go back to the "Item description" module.
2. Position the cursor after the last data field or the last semicolon.
3. Press CTRL and the space bar.
   - The input wizard opens.
4. Select **%Variable**.
   - The prefix **{%** for variables is inserted.
5. Press CTRL and the space bar again.
   - Your variable is inserted. There is no need to explicitly select the variable at this point as so far there is only one variable in the export format template.
6. Press Enter to insert a line break after the last data field, so that each data record starts on a new line.
7. Click on in the ***Export format template*** view to save the export format template.

13.2.2.8 Creating an export profile


You want to perform the export using an export profile (i.e. not a test import). An export profile is always required to run an export. In the first example, a test export was used, which involves a temporary export profile being generated automatically. You now want to create an export profile that is saved and can be re-used.

What is an export profile?

An export profile is the overall object to be exported. An export profile uses an export format template and has an interface to its export parameters.

You can change the values preset for the export parameters in the export format template both when creating the export profile and during the export using the export profile, provided that this is permitted in the export format template.

1. In the Views menu select **New export profile**.
   - The "New export profile" wizard is opened. As an export profile is always based on an export format template, this template must first be selected.




Export format template selection

2. If the format template previously created is still open, this is automatically transferred to the corresponding field.

   Otherwise, click on ... after the “Format template” input field.
   - This opens a dialog box, where you can select an export format template.
3. Select the "Descriptions" export format template you have just edited.
4. The profile is automatically given the same name as the export format template. You can change this in the "Profile name" field if necessary. In this example, the export profile name is "Descriptions", i.e. the same as the name of the export format template.

5. Below this is the “Profile description” field. A descriptive text is entered here automatically. You can change or add to this as required.
6. Click on **Next**. In the next step, you can select the values for the export parameters.

Note: If your format template has errors or warnings, an additional dialog box appears at this point to inform you of this. You can then choose from two alternatives. You can either ignore errors and warnings and proceed to the next step, However, you can also cancel toeliminate the causes of the problems first.




Selecting or entering the export parameters

7. Select the required parameter values from the drop-down lists or enter values in the relevant fields. In our example, the "Export assortment" item assortment is selected for the "Item assortment" parameter. Enter your name in the "User" variable.
8. Click on **Finish**.
   - An info dialog box tells you that the export profile has been created successfully.

13.2.2.8.1 Export

Once you have created an export format template and an export profile, the preparations for exporting your data are complete.

1. In the Views menu select **Export...**.
   - This opens a dialog box, where you can select an export profile.
2. Select the export profile you have just created. In the example, this is the "Descriptions" export profile.
3. The "Export parameter configuration" dialog step is opened. You have already set the values for the export parameters in the export profile. Here, you have the option of changing the settings again.
4. Click on **Next**.
   - The "Select output destination" dialog step opens.
5. Retain the option "Export immediately".



Selecting the output destination

6.Click on **Finish**.

➪ The export is performed. You can monitor the operation in the ***Process overview*** perspective and download the export file there.

13.2.2.8.2 Checking results in export files

Open your export files and check whether you have achieved the desired results.

In our example, you have created a comma-separated file with the extension ".csv". You can open this in a text editor or a spreadsheet, or import it into a database.

Note: Minor errors can have a major impact.

For example, a missing line break can mean that data will appear consecutively on a single line rather than on the next line.

Exported texts can contain special characters, semicolons, or inverted commas, e.g. diameter A 3/8"; Ø B ¼". This can impair correct processing of a CSV file. You should consider appropriate methods for dealing with special cases like this (see also http://tools.ietf.org/html/rfc4180).

13.2.3 Using submodules and multiple export files

You will learn how to output multiple export files and how to create and use sub-modules. You want to export item data. The item data to be output can be exported to a single output file as only one data record is created for each item number. You also want to output attributes for the item data. However, there are several items of attribute data for each item number. For clarity, these should be output in a second file.

1.Create the export format template "Item index".

2.Create the "Item list" data source for your export format template on the "Data sources" tab in the export format template properties.

13.2.3.1 Using multiple export files

To generate several export files, this option must first be activated and defined in the properties of the export format template:

1.Open the properties of the export format template.

2.Open the "File management" tab.

3.Set a check mark next to "Extended options" to activate this option.

4.Click on **New file**.

5.Name the file "Item data".


6.Select the format "CSV".

7.Click on **New file** again.

8.Name the second export file "Item attributes".

9.Select the format "CSV".

10.Confirm with **OK**.



Defining multiple output files

13.2.3.2 Creating multiple headers

1.Create the "Item data header" module.

2.In the ***Properties*** view, select "Item data" as the export file.

3.Enter the column headings, separated by semicolons. The header in the example is "Item number; Manufacturer; Short description (English); Last change".

4.Press the Enter key to insert a line break.

5.Create the "Item attributes header" module.

6.In the ***Properties*** view, select "Item attributes" as the export file.

7.Enter the column headings. The header in the example is "Item number", "Attribute name" and "Attribute value".

8.Press the Enter key to insert a line break.

13.2.3.3 Module for output of item data

The module for outputting item data is essentially created in exactly the same way as the preceding examples. As there are two output files in the export format template, the output file must be explicitly selected.

1.Create the "Item data" module.

2.In the ***Properties*** view, select "Item data" as the export file.

3.Select the data source, "Item list" in the example. The data type is selected automatically, in this case "Item".

4.Open the module editor.

5.Set the data fields. In the example, these are the "Item no.", "Manufacturer", "Short description (English)" and "Last change" fields.


6.Press the Enter key to insert a line break.

13.2.3.4 Item attributes

In Product 360 Desktop there are structure group features and item attributes. Items belonging to the same structure group are generally so similar that they also have similar properties. Therefore, fixed features are assigned to the structure groups in some classification systems. The list of features assigned to a certain group can facilitate item comparison.

In addition, items can have "free" attributes, which are maintained for the relevant item directly. An item attribute may also be assigned to a structure group feature. More information about this topic can be found in the Product 360 Desktop manual.

To output attribute data, between zero and several data records with different attributes must be output for each item. It makes sense to write these attribute data records to a separate file. The reference to the item data record is created by the item number. For example, for the item "ER-129-09-19" the item attributes “Measurement range”, “Measurement tube length”, and “Weight” are output.



Item number	Manufacturer	Short description (English)	Last Change
ER 123-09-19	Erstein AG	Factory caliper 800 mm, measuring tube 150 mm with knife point	8/28/2007 10:38 AM
ER 123-22-41	Erstein AG	Caliper 300 mm, in box, measuring area with titan coating	8/28/2007 10:38 AM

Item number	Attribute name	Attribute value
ER 123-09-19	Weight	2,3
ER 123-09-19	Measurement range	800
ER 123-09-19	Measurement tube length	150
ER 123-22-41	Measurement range	300
ER 123-22-41	Measurement tube length	60
ER 123-22-41	Weight	140
ER 123-22-41	Diameter	0,8

Attributes referenced by the item number

13.2.3.5 Creating a sub-module


A sub-module is created for outputting the item attributes.

1. Switch to the "Item data" module.
2. Select **New sub-module** in the pop-up menu.
   - A submodule is created within the module.
3. Give this sub-module the name "Item attributes".
4. In the module properties, select the "Item attributes" export file.

Note: The data fields in a sub-module obtain their data from the same data source as the module under which they are located. For this reason, the data source is pre-entered in the sub-module properties - in the example, the data source is "Item list".

The data type or, more specifically, the sub-data type, must be selected in the submodule. A data source has a single data type that can be used in a module and from zero to several sub-data types that can be used in a sub-module. In the module, the data type is preset as the data source has a fixed data type. In the submodule, both data types and sub-data types can be used.

5. Select the "Attributes" data type for the "Item attributes" sub-module.
6. Switch to the module editor.
7. Select a data field to create the relationship between the submodule and the module. In our example, this is the "Item number" data field or, to give its full designation "Item.Item no.", i.e. a data field of the "Item" data type. This data field is also used in the module.
8. Select the corresponding data fields for the attributes. In the example, these are the "Name (German)" and "Attribute value (German, DEFAULT)" data fields. The language property in brackets indicates that it is a qualified data field. (When you select the field, the corresponding dialog box opens.) For language-specific data fields, you can define an alternative language that is used if no value exists for the preset language.



Property value selection

Note: Do not leave the sequence of the modules to chance!


The sequence of the modules has an impact on the output. When exporting, the modules are processed from top to bottom. Accordingly, the module for a "header" in an output file must always be above the modules for the output data. However, it does not have to be directly above them. There can be other modules in between. In the following example, the modules are processed in steps 1 to 4:

Module_1: Header in export file A

Module_2: Header in export file B

Module_3: Data line in export file A

Sub-module_3a: Data line in export file B




Sequence of individual modules

13.2.3.6 Referencing a sub-module

Modules must contain references to their sub-modules in the form **{$[sub-module name]}**.

Note: If a sub-module is not referenced, you will receive warnings when exporting.

1. Switch to the "Item data" module.
2. Position the cursor in the second line.
3. Press CTRL and the space bar.
   - The input wizard opens.
4. Select **$ Sub-module**.
5. Press CTRL and the space bar again.
   - The sub-module name is inserted. In the example, the "Item attributes" sub-module is referenced.



Reference to "Item attributes" sub-module in line 2

13.2.3.7 Performing an export

Once the header modules, the module and the submodule have been completed, you can perform the export.

1. Select **New export profile...** in the Views menu to create a new export profile.
2. Select the "Item index" export format template.
3. Give the export profile a name. The name of the export format template is preset as "Item index" in the example. You can change the default profile description if required.
4. Click on **Next**.

- This takes you to the "Export parameter configuration" dialog step.

5. Select the values for the export parameters. In the example, the "Item assortment" called "Online catalog" is selected.
6. Click on **Finish**.
   - You will see a message confirming that the export profile has been completed successfully. This export profile can now be used to perform the export.
7. Select **Export...** in the Views menu to open the Export Wizard.
8. Select the "Item index" export profile.
9. Check whether the export parameters have been set correctly and assign different values if necessary.
10. Click on **Next**.
    - The "Select output destination" dialog step opens. You do not need to change anything here.
11. Click on **Finish**.
    - The export is performed. You can monitor the operation in the ***Process overview*** perspective.

13.2.3.8 Export results

Two output files have been generated: A file “Item data.csv” containing one data record per item; by contrast, the second export file “Item attributes.csv” has multiple data records for each item. The data records in both files contain item numbers. The item numbers in "Item attributes.csv" are used to assign the attribute data records to the corresponding data records in "Item data.csv". For example, three attribute data records from the "Item attributes.csv" file belong to the data record with the item number "ER 123-09-19".

13.3 Creating export format templates

In a similar way to creating a form letter in a text editing program, you can use an export format template to create and manage the basic appearance of your export file. First of all, you define some "modules" and, in a second phase, you specify the contents of each individual module.

The first time you create a format template, you should first of all identify typical properties of your desired export file. For example, a simple comma-separated table may have a header with the individual entries below it. To realize this structure, you need two modules that are processed in the correct order.

If you want to export your data as an XML structure, you will normally need at least three modules:

- one module for the header area (e.g. opening tags)
- one module for the repeating area (e.g. for items)
- one module for the final footer area (closing tags)

You can map nested structures using sub-modules, which are executed by calling them up within a module.

In the new version, the purpose of format templates goes beyond merely exporting. They can now also be defined for an HTML preview to get a better idea of the visual implementation of the set rules and validations. If you have selected the **Preview** check box, you can specify whether this format template is valid for displaying individually selected objects. In this case, click on **Detail view only**. If the format template is also to be applied to a multiple selection, leave this check box unselected. You do not have to select the preview data type. Product 360 Desktop checks the selected object type and provides an appropriate format template from those available.


For this reason, a direct export has also been integrated, which can be called via the pop-up menu of an object table.

As a preview always involves additional RAM usage, two limitations are set by the system.

1. Number of objects to be displayed: Maximum 100.
2. Amount of time required to generate the preview: Maximum 20 seconds

Creating an export format template

1. Select **Perspectives > Open** to open the ***Export format templates*** perspective.
2. Click on to create a new export format template.
   - A new export format template is created with a module.



"Create export format template" perspective

A detailed description of how to work with modules is provided under Creating modules and sub-modules.

Saving export format templates

Export format templates can either be stored in the database under an individual name or as an external file (file extension .ext). If you save a format template in the database, you have the additional option of categorizing your objects. The advantage of an external file is that you can make it available to users of other Product 360 Desktop systems. This is done by importing the export format template into the other system.

1. Click on to save a new export format template within the database.
   - The dialog box for saving an export format template opens.
2. Enter a name and description.
3. Click on **OK**.
   - The export format template is saved.

You can click on to save an existing export format template under a new name. Saved export format templates are managed in a special dialog box.

> Caution: The current Informatica MDM - Product 360 release also contains the Product 360 Media Manager, Product 360 Web and Product 360 Supplier Portal components. If these need to be accessed by Product 360 Desktop, certain settings must be made to activate them. Your Product 360 Desktop consultant normally takes care of this.

13.3.1 Properties of an export format template

When you click on the root node in the ***Export format template*** view, you can use the pop-up menu to display the properties of the entire export format template. If you select a module, its properties are displayed.

In the ***Properties*** view, you can specify both the name of the template and the format. You specify not only the correct file extension but also convert any special characters for HTML browser compatibility. Select the desired coding for your file in the "Encoding" field.

Clicking on the "Configure advanced settings" link opens a dialog box containing numerous setting options organized on various tabs. This dialog box can also be opened in the ***Export format template*** view by clicking on **Properties** in the pop-up menu for the root node.

- Settings
  Contains the same settings as on the first page
- Data sources
  Here, register all of the data sources that you want to use in the modules. At module level, you can select the appropriate data sources from the list or return to this area to register additional data sources.
- Variables
  You can define additional variables here. These variables occur again when using the export profile in the User dialog box.


- Data fields
  A summary of the data fields already used is displayed here. If you have created data fields and then removed them from a module again, these fields will be shown with a gray symbol.
- File management
  The handling of export files is defined here. You can choose between default and advanced settings.
- File attachments
  To export multimedia attachments, you can specify the corresponding settings here.
- Post-processing
  If you want to provide additional activities after the export, you can define the necessary export steps here. For example, this is the case when exporting multimedia files.

13.3.1.1 Settings

Enter the format of the export format template on the "Settings" tab (or in the ***Properties*** view). Selecting a particular format automatically gives the specified file the corresponding extension. If, for example, you select HTML as a format, the variable content of your export file is converted so that it is browser-compatible. It is therefore important to correctly "mask" German umlauts in texts, e.g., each "ä" is output as "ä".

Note: Only the variable contents can be converted in accordance with the specified format. Static contents must be output with the relevant formatting in the export format template.

Property	Possible values
Name	Name of export format template
Format	TXT, HTML, XML, CSV
Encoding	Character set selection: UTF-16, UTF-8, ISO-8859-1, 1252 Windows (ANSI – Latin 1), ASCII, CP850 (DOS-Latin 1)
Format mapping table	When exported, existing text features, e.g. in the long description, are replaced in line with the specified table. Format mapping tables are maintained in the "Format mapping" dialog box, which you can access under **Management > Format mapping tables**.
Description	Entering a description

Property	Possible values
Purpose	Since export format templates are used not only for the actual export but also for creating previews, you must select the corresponding option here. If the preview function is active, additional parameters are displayed, which concern the data type (reference to a selected data source). It is also possible to only allow the preview function for the detail view or for a maximum number of records. Specific program components within a template can identify a "writable preview". This happens automatically in the system, which also sets the corresponding "check mark". 
Logging in the export log	Errors, warnings, header information: Checked boxes are active. Unchecked means no output. Choosing not to output warnings can significantly speed up the export.
Logging directly in the export file	Errors, warnings Enabling these settings can assist you in tracing the causes of errors during the development of complex export format templates.

13.3.1.2 Data sources

The "Data sources" tab is used to select and configure data sources. You can also register a data source multiple times when you want to use several blocks with similar data types but different restrictions within one file.

Property	Possible values
Data sources	The list of data sources assigned to the export format template is displayed here. When you select a data source, its name and parameters are displayed on the right of the tab. Any number of data sources (none, one, several) can be added to the list.
Name	There is usually no reason to change the name of a data source. However, it could be necessary if you are including a data source several times and want to assign special names rather than using an enumeration of the same data source.
Parameters	All parameters of the selected data source are displayed here. The values can be selected using drop-down lists or input fields.

Property	Possible values
	The parameters may be flagged as mandatory parameters. A value must be set for these parameters at the latest when scheduling the export. The "Editable" option means that a parameter is displayed and can be changed in the export profile.

1. Click on **New...** to create a new data source.
   - A selection dialog box appears, showing all data sources.
2. Select the relevant data source.
3. Click on **OK**.
   - The data source is added.
4. Edit the parameters of the data source. The parameters of the various data sources are described in the data source reference.

13.3.1.3 Variables

Variables are export elements you specify as editable content as part of the export profile. On the "Variables" tab, you define variables that will appear as additional export parameters in the User dialog box for the export profile. For example, you can define the name of the author as an optional input parameter.

1. Click on **New...** to create a new variable.
2. Assign a unique name to the variable. The same name cannot be assigned to two different variables.
3. Enter a short description for your variable in the "Information" field. This is then displayed as a tooltip in the "Export parameter configuration" dialog step when editing or exporting an export profile.
4. In the "Data type" drop-down list, define the data type of the variable, i.e., specify whether it is a date, a structure system, a character string, etc.
5. You can leave the "Value" drop-down list blank or you can specify a preset value. The variable may be flagged as a mandatory variable. At the very latest, this mandatory variable must be assigned a value during export scheduling. The "Editable" option means that a parameter is displayed and can be changed in the export profile.


Some data types permit the use of default values or updating of variable values. For example, you can click on to specify that the current value is always used for a variable of the "Date" data type. In this case, the value would always be today's date. A variable of the "Language" data type can be reset to the default value using .

13.3.1.4 Data fields

The "Data fields" tab shows you all of the data fields used in the export format template, along with their properties. You can rename data fields or change their properties.

1.Select the relevant data field.

2.If you only want to find out information about the properties of the data field, click on the arrow next to the entry and a hierarchical display containing the property entries is shown.



Sample view

3.To edit the data field, click on **Properties...**.

➪ The window containing the properties of the data field opens.

4.Make the relevant changes.

5.Click on **OK**.


➪ The window is closed.

6.Click on  to rename the data field.

➪ The dialog box for renaming data fields opens.

7.Enter a new, unique name. If the name already exists, a corresponding message will be shown in the dialog box.

8.Click on **OK**.



Format template properties (data fields)

Data fields you have created and subsequently removed from a module are shown in gray. Delete these fields if you do not intend to use them again.

1.Select the data field to be deleted.

2.Click on **Delete**.

➪ The data field is removed.


3.You can delete all data fields no longer in use by clicking on  .

Note: You cannot delete any data fields that are still in use in the export format template.

Validation rules for data fields

You can define additional validation rules for each data field. For each validation rule, specify the response in case of errors. This allows you to control whether there is an output in the export log or whether, for example, the export will be aborted in case of errors.

1. Select the data field.
2. Click on **Add validation rule...**.
   - The dialog box for selecting validation rules opens.



Defining validation rules

3. Select a validation rule on the left by double-clicking on it, or highlight the rule and click on  .
   The following rules are available, depending on the data type:
   - In value range: Checks whether a numerical value is within the specified range (including the limit values).
   - May not be blank: Checks that an entry has been made for a value.
   - Insert if blank: Specifies a default value to be used instead of blank values.
   - Truncate: Shortens a character string if its length exceeds the specified number of characters
   - Cut: Returns a section of a character string. To do this, you specify the position at which the section begins and how long it will be.
   - Replace: Searches a character string for the search term and replaces it with the specified expression.
   - Convert to upper case: Converts the character string to upper case.
   - Convert to lower case: Converts the character string to lower case.
   - Max. character length: Checks the maximum length of a character string.
   - Right: Returns the specified number of characters from the character string, starting on the right.


4. Specify the relevant entries for the validation rule.
5. On the right, specify the response in case of errors: None (no action), Remove data record, or Cancel export.
6. Also set which error classification is to be applied: Information, Warning or Error.
7. Click on **OK** to add the validation rule to the data field.

Note: You can edit existing validation rules by double-clicking to open them.

13.3.1.5 Functions

For the Functions tab, all export functions used in the export format template are listed.

They are shown in the following example:




Export format template

Functions used

The Functions tab shows all functions used in the current export format template on the left. The name, the description and any


additional error classification are listed (shown) on the right.



Function properties without error classification

In the example below, you can see a function with the error classification option.

This includes special cases, which can be defined for an export format template.




Function properties with error classification

The severity for each error output can be defined in the error classification.

13.3.1.6 File management

On the "File management" tab, you can specify the file name for the export file. If no settings are made, the name of the format template is used. Alternatively, you can assign a custom name for the default output file. To configure an export format template so that several data files are generated, activate the "Extended options" option.

Here, you can register the export files with their name, format, and coding. If you want file names to be generated automatically, create the naming convention for the export file template. In addition to a fixed part of the file name, a file naming convention always contains a placeholder, which is replaced with the current data during the export operation, for example the item number of the current item. You will assign the export files registered here to the relevant modules of the export format template at a later stage.



Managing export files

1. Set a check mark next to "Extended options".

2.Click on **New file**.

⇨ A new file is created in the "Output files" field.


3.Assign a name to the file.

4.Alternatively, click on  to create a file naming convention.

⇨ The dialog box for file naming conventions opens.

- Enter a data type and, in the "Pattern" field, enter the required file naming convention.
- If you want to select one data record for each file, check "One data record per file". You can choose from three preset values in the convention field:

ID for the internal numerical data record identification, IDENT for alphanumeric data identification, and NO for consecutive numbers.



File naming convention

- Click on **OK** to close the dialog box.

5.Specify additional settings for the file format and encoding.

13.3.1.7 File attachments

If you want to export multimedia attachments, you can store them as a zip file in the same directory as the export file. This involves three steps, which are explained below.

In the export format template modules, use the **ExportMime** export function to select the file attachments to be output. The "Document identifier" data field for the file attachment is used as a parameter for this function.

On the "File attachments" tab, enable the "Query file name with multimedia server" option and specify the required settings. The file attachments can be output in a directory structure that corresponds to the structure of the document categories, or in a single directory without any sub-directories. With the "All files excluding sub-directories" option in particular, duplicated file names may occur. You can also specify how these are to be handled on the "File attachments" tab. You can choose between the two options "Ignore" and "Create a new name (with sequential numbering)". You also have the option of outputting the occurrences of duplicate file names in the export log.


You must also assign the "File attachment export" post-export step to the export format template. This step executes the output of the file attachments to the multimedia archive.

13.3.1.8 Post-processing

If you want to provide additional activities after the export, you can define the necessary export steps on the "Post-processing" tab. For example, this is the case when exporting multimedia files.

Property	Possible values
Export steps	Selected post-export steps. The post-export steps are processed from top to bottom. You can change the order using and . An export step can also be assigned more than once
Name	Name of export step
Parameter	All parameters of the selected post-export step are displayed here. The parameters may be flagged as mandatory parameters. At the very latest, all mandatory parameters must obtain a value during export scheduling. The "Editable" option means that a parameter is displayed and can be changed in the export profile.

1. Click on **New...** to create a new post-export step.
   - The selection dialog box for post-export steps opens.



Post-processing an export

2. Select an export step.
   - File attachment export: Exports the multimedia attachments.
   - Copy export file: Copies the export file generated to another directory. Specify the destination directory as a parameter.
   - Execute command file: Executes the commands from the specified command file. Since the command file must be located on the export server, you can upload it using **Manage files** and view which files are available.

> ⚠ Caution: Complete each command line with the command `">NUL"`. This prevents output relating to the system. As a result, a command line could look like this: `"copy c:\file1 d:\file2 >NUL"`

- Validate XML file(s): Checks the XML file generated against the specified DTD or XSD schema. Since the schema file must be located on the export server, you can upload it using **Manage files** and view which files are available.
- XML Pretty Print:Formats the exported Xml files and removes blank lines.


> ⚠ Coution: Please do not use the XML Pretty Print export for large XML files.Â This export step is meant to assist you in creating new export formats and to make it easier for you to read the output file. Â This format is not necessary for further use beyond read-only activities.

3.Click on **OK**.

A post-export step is configured for the ***Supplier Exchange*** purpose that can create the direct link to Product 360 Supplier Portal.

1.Select the ***sent to Supplier Exchange*** export step.

➪ The following dialog box is displayed:




2.Give the post-export step a meaningful name. It is important to select the correct recipient suppliers and a corresponding message that will be displayed directly in the Product 360 Supplier Portal timeline after the export.

> 💡 Tip: You can find a modification option for these parameters when you click on the "Variables" tab. There, you can define the height of the display window for the message ("Message" variable), as well as the drop-down list to be offered for the recipient suppliers ("Supplier" variable).

3.Click on **OK** to complete the configuration.

When you perform the export with the ***Supplier Exchange*** purpose, the values you just configured in the **Export parameter configuration** dialog box are shown.



Caution: In the file `preferences.ini` in the Product 360 Supplier Portal plug-in you can set a parameter to specify how supplier catalog links are handled. The value "true" ignores existing references and allows an export to other catalogs. The value "false" is set if you want to prevent this and only allow export to your own supplier catalogs.

13.3.2 Creating modules and sub-modules

An export format template module (module for short) can be seen as an individual component of your export file. You use modules to define the contents that are to be output. All calls for data fields within a module are processed and output once for each data record. An export format template may comprise several modules. For example, you require at least three modules to output an XML file:

- In the first module, you define the header area of the XML file (opening tags).
- In the second module, you output the data (tags output multiple times).
- The third module closes the XML file (closing tags).

A module can, in turn, contain sub-modules. You can use these, for example, to output item attributes. To do this, call up the submodule for each data set in order to output all item attributes.


Creating modules and sub-modules

1. In the ***Export format template*** view, select a module below which you want to create another module or sub-module.
2. Select **New module** or **New sub-module** in the pop-up menu.
3. You can use drag & drop to change the sequence of the modules.
4. To delete modules that have been created incorrectly, select **Delete** from the pop-up menu.
5. Specify the relevant module settings in the ***Properties*** 305 view.

After creating a new module, you must fill it with content in such a way that Product 360 Desktop knows which information is actually to be written. This specification is made in the ***Export module editor*** 307 view.

13.3.2.1 Properties of a module

If you select a module or sub-module in the ***Export format template*** view, the ***Properties*** view displays its properties.



Properties of a module

Name and data connection

- Name: Assign the module a unique, meaningful name that clearly distinguishes it from other modules.
- Higher-level module: This entry cannot be changed. This shows the name of the parent module of a submodule.
- Data source for module: Here, you can assign the module a data source that you have already created in the export format template. A sub-module always uses the same data source as its parent module. If you only want to output static text with a module, no data source is required. You can use **Edit...** to define additional data sources for the export format template.
- Data type: For a module, this is defined by the data source used. In addition to the data type of the parent module, you can select other available sub-data types for the sub-module. If necessary, you can click on **Change...** to define additional filters for the export. For example, you can specify that item attributes are only to be output if they have been assigned a specific purpose.

Export file

This entry is active if you have made a setting in the export format template to specify that the data is to be output in several files. Use the drop-down list to select the export file to which the module is to write the data.

You can use the "Create a new file for each data record" option to specify that a separate export file is created for each data record. To do this, go to **Edit...** and enter a file naming convention.

Sorting

Caution: Depending on the volume of data and the sort criteria, an export operation with sorting may take a long time.

You can sort the data in such a way that, for example, it is exported and sorted according to manufacturer.

1. Set a check mark next to "Sort".
2. Click on **Add**.
   - The dialog box for a new sort criterion opens.
3. Under "Data field", select the data field according to which you want to sort the data. Data fields used in the module appear at the very top of the drop-down list, so that you can quickly access them, if required.
4. If necessary, change the qualification of the data field.
5. Specify whether the data should be sorted in ascending or descending order.
6. If necessary, select the sort algorithm.
7. Click on **OK**.
   - The sort criterion is displayed in the view. An arrow pointing upwards indicates sorting in ascending order while an arrow pointing downwards indicates sorting in descending order.

If there are several sort criteria, you can select **Up** and **Down** to change their sequence or you can select **Delete** to delete a sort criterion again.

Consistency check

If the selected module has a sub-module, the "Consistency check" option is also available. For a consistency check you specify whether sub-module has to provide data. In addition, you specify the response in case of errors. This allows you to control whether there is an output in the export log or whether, for example, the export will be aborted in case of errors.


1. Select the "Mandatory" option immediately to the right of the sub-module name.
2. Under "Action on error", select the response in case of errors: None (no action), Remove data record, or Cancel export.
3. Also set which error classification is to be applied: Information, Warning or Error.

Note: If you do not want to perform consistency checks for a sub-module, deselect the "Mandatory" option.

13.3.2.2 Module editor

You edit the contents of a module using the module editor, which you call up by double-clicking on the relevant module in the ***Export format template*** view. Alternatively, you can select the module and press F3 or Enter.

In the module editor, you can also enter normal text as in any other text editor. To enter placeholders, you can press CTRL + space bar on your keyboard to call up the input wizard.



Input wizard in the module

First of all, you must select one of the placeholder types and then press CTRL + space bar again to specify which element within a type you want to select.

Variables

Used to call up variables you have defined in the export format template. Call up the input wizard again to display a list of all available variables. (If you have only created a single variable, this is inserted automatically.)

Comments/Tasks

Use this placeholder to define comments within your module or to define comments for processing. The keyword "TODO" in a comment indicates a task, which is displayed, together with errors, at the left and right borders of the module editor. Comments and tasks are not output in the export.

Data field

You use data fields to access the available product information. Your master catalog contains data objects (data records) of a particular data type, for example the "Item" data type. A data type provides data fields for data content, e.g., the "Item" data type has the data fields "Item number", "Manufacturer", etc. An input wizard supports you in selecting data fields.

There are both simple data fields and data fields that can be qualified. A qualified data field must be specified in more detail with additional settings. This is the case, for example, with language-specific data fields. For example, a short description may exist for an item in either German or English.

Note: For your data fields to be available for selection, you must first specify the data source.

Sub-modules

Sub-modules are specified subordinate areas that you call up below a module. Call up the input wizard again to display a list of all available sub-modules. (If you have only created a single submodule, this is inserted automatically.)

To use a sub-module, i.e., to select it here, you must first have created it. Sub-modules cannot, in turn, contain own sub-modules.

Functions

Functions allow you to edit the data in different ways. Open the input wizard again to display a list of all available functions. The function reference provides you with an overview of which default functions are available.

13.3.2.3 Checking the export format template

Der Product 360 Desktop checks your export format template immediately. An incorrect module is identified accordingly in the tree view in the ***Export format template*** view. Any incorrect syntax in the module content is indicated in the ***Module editor***.

If the module contains errors, you cannot export any data. If warnings occur, the export can still be performed. However, you should make sure that these warnings do not cause any content errors in your export files. The following checks are performed:

- Are all of the data fields, variables, sub-modules, and functions used recognized?
- Do the functions have the correct syntax?
- Do the data fields used match the assigned data source and data type?
- Are all non-editable mandatory parameters and variables assigned a valid value?
- Does the template contain registered but unused data fields or variables?
- Are there modules or sub-modules without content?
- Are there unused sub-modules?

Warnings and notes can be viewed in the ***Log*** view. Three statuses are displayed in the view:

- **Errors**
  Data cannot be exported due to one or more errors, e.g., if an export function has been used with incorrect syntax or a mandatory variable with a blank default value has been defined as not editable.
- **Warnings**
  A sub-module, for example, has been created and written but is not used in the higher-level module.
- **Notes**
  Displayed, for example, if you have registered or created a variable but have not used it.

Tip: The "ID" column specifies the module in which something was found. Double-clicking on the entry in the ***Log*** view allows you to open the entry in a separate window.


You can also run a check on the export format template directly:

1. Select the export format template in the ***Export format template*** view.
2. Select **Run check** in the pop-up menu.

- The results of the check are displayed in the ***Log*** view. If the view is blank, no inconsistencies have been found.


13.3.3 Managing export format templates

The management dialog box for format templates is used to find, sort, open and save export format templates. Depending on the configuration of the application, part of the dialog box may be grayed out, i.e. no changes can be made to certain fields. For the search operation, a tree-type view with the filter options "Purpose" or "Creator" is provided.



Open export format template

The management dialog box also enables you to classify export format templates using categories. This makes it much easier for you to find them again as you can use the categories for selection. The same applies to the purpose. Format templates with the purpose **Export** are used for both the preview function and for the actual export operation. The purpose **Preview** cannot be used for the latter. You can also delete any centrally stored export format templates that are no longer required.



Managing export format templates

Managing export format templates

1. Click on in the ***Export format template view.***
   - The management dialog box opens.
2. Select an export format template.
3. Enter the name of a new or existing category in order to assign the export format template to this category.
   - To save your changes, click on **Apply** or select the next export format template you want to manage.
4. Click on Object rights to restrict access to the export format template.
   - The dialog box for editing the object rights opens.
5. Edit the object rights.
6. Click on **OK** to save your changes to the object rights and close the dialog box.

Note: You can store a uncategorized export format template in a new category, but you cannot create an empty category. Deleting the last export format template assigned to a particular category also deletes the category itself.

Deleting an export format template

1. Click on in the ***Export format template view.***
   - The management dialog box opens.
2. Select the corresponding export format template.
3. Click on **Delete**.
4. A confirmation prompt appears, asking whether you really want to delete the export format template.
5. Click on **Yes** to delete the export format template.

13.3.4 Saving an export format template

Export format templates are normally saved in the Product 360 Desktop database. However, if you want to transfer an export format template from one system to another, it can be saved as a file. This file contains all necessary information about the export format template, has the file extension ".ext", and is a text file in XML format. You can simply transport this file or send it by e-mail.

Note: When preparing an export format template for the target system, delete all system-specific parameter values to ensure that the format template can be loaded into the target system without any problems. System-specific parameter values include item assortments or static item lists.

1. In the Views menu in the ***Export format template*** view, select **Save format template as file...**.

- The standard "Save as" dialog box opens, with the "Export format template (*.ext)" file type selected by default.

2. Assign the file a name.
3. Select the storage location for the file.
4. Click on **Save**.


13.3.5 Loading an export format template

You can import an export format template from another Product 360 Desktop system:

1. In the Views menu for the ***Export format template*** view, select **Load format template from file…**.
   - The standard "Export format template" dialog box opens.
2. Select the export format template to be imported.
3. Click on **Open**.
   - The export format template is opened in the ***Export format templates*** perspective.

> Note: You can now use the export format template directly for an express export, but it is not yet known to other users of this system. You should therefore save the export format template centrally.

4. Click on .
   - The "Save export format template as…" dialog box opens.



Save export format template as

5. Enter a name and description for the export format template.
6. Click on **Save**.
   - The export format template is saved centrally.

13.3.6 Managing format mapping tables

When exporting field contents, the contents can be analyzed using a format mapping table, and certain features can be mapped automatically, based on the entries in the format mapping table.

This function is particularly useful if you want to standardize the way in which you manage your product information but nevertheless present it in different forms.

Example: You have entered the following text in the long description (English):

```
<heading1>First aid kit</heading1><CRLF><CRLF>Des. no. 010 ABS plastic
vehicle first aid kit<CRLF>Gray with contents DIN
13164<CRLF>Dimensions approx 250x170x80 mm<CRLF> <CRLF>Des. no.
020 Small ABS plastic industrial first aid kit<CRLF>Gray with contents
DIN 13157<CRLF>Dimensions approx. 250x170x80 mm<CRLF><CRLF>Des. no.
030 Large sheet steel industrial first aid kit<CRLF>Green with
contents DIN 13169<CRLF>Dimensions approx. 350x260x100
mm<CRLF><CRLF><bold>Large industrial first aid kit design</bold>
```

Subsequent processes should ensure that the features used here are mapped as follows:

Original description	Map to:
<CRLF>	
<bold>Any text</bold>	Any text
<heading1>Any text</heading1>	<H1>Any text</H1>

To perform these mappings, you must maintain a format mapping table.

1. Select **Management > Format mapping tables**.
   - The format mapping tables dialog box opens.
2. Click on **New format mapping table**.
   - The dialog box for creating a new format mapping table opens.
3. Enter a unique name.
4. Click on **OK**.
   - The format mapping table is created.
5. You can now specify mappings for the text features.

Under the properties of an export format template, you specify the format mapping table that you want to use in an export format template.

13.3.7 Exporting characteristic values

Note: Characteristics are managed in Product 360 Web. You can find definitions of characteristics and characteristic values in the Product 360 Web user documentation.

The export supports file-based export of characteristic values for items. The following must be noted:

Characteristic values for items can only be exported in a flat form or as a table, as is the case for attributes. You can use the sub-data types “Characteristic values” and “Characteristic values (in all languages)” for this purpose. Lookups are output in the “Preset value” data field, while all other values are output using the “Value” data field.

These values are output formatted according to their data type. If you want the formatting to follow the format pattern, use the export function “CharacteristicValueFormatByPattern”.

The output of characteristic values can be restricted using the following filters:

a. Output mode:

Only available: Only characteristic values of the item that belong to an available characteristic are exported

(A characteristic is available if the category is assigned to a structure group to which the item is also assigned).

Available/Not available: All characteristic values for the item that are visible in the user interface are exported.

b. Characteristic categories: Only the values for the item for characteristics whose categories have been specified in the filter are exported.

c. Characteristic purposes: Only values for the item for characteristics whose purpose corresponds to one of the purposes selected in the filter are exported.


d. Target markets: Only characteristic values for the item that have been maintained for one of the selected target markets are exported.

e. Basic characteristic: Only values for the item for characteristics that are located in the subordinate hierarchy of the selected basic characteristics are exported.

13.4 Creating export profiles

Note: You can only create an export profile if an export format template has already been saved.

1. Select **New export profile...** in the Views menu to create a new export profile.
   - The export profile wizard opens.



New export profile

2. Click on ... to select an export format template for the export profile.
   - A selection dialog box opens, containing all export format templates that have been created.

   If an export format template is already loaded, it is automatically transferred to the corresponding field.
3. Select the required export format template.
4. Assign a suitable profile name or use the suggested profile name. The suggested name is always based on the name of the export format template used, e.g, <Export format template name>.

Note: The export profile name must be unique, i.e., two different export profiles cannot have the same name. A warning message appears if you choose a name that is already in use.


5. If necessary, modify or extend the profile description.
6. Click on **Next**.
7. In the second dialog step, edit the export parameters for the export format template in input fields or in drop-down lists.
   The export profile does not need to contain a value for all parameters because these can be changed during export scheduling. All mandatory parameters must obtain a value at the latest when scheduling the export. These mandatory parameters have an asterisk “*” after their name. Other parameters may be assigned a value. If this is not the case, the relevant default values are used. The values of some parameters can be set to the current default value. For example, the value for a date can be set to the current date. You can also update the value of these parameters in the export profile immediately before or after an export.
8. Click on **Finish**.
   - You will see a message confirming that the export profile has been created.

13.4.1 Managing export profiles

You can also use the **Manage export profile...** option in the Views menu to manage export profiles that are saved centrally. You can delete them, organize them into categories, reorganize them, and create new categories.

After you create an export profile, it is classified under the "<Not categorized>" node, i.e., it does not belong to any category. The procedure for adding the export format template to an existing category is as follows:

1. Select **File > Manage export profile...**.
   - The selection dialog box opens.
2. Select the relevant export profile.
3. Enter a new or existing category in the "Category" field.
   - To save your changes, click on **Apply** or select the next profile you want to manage.
4. Click on Object rights to restrict access to the export profile.
   - The dialog box for editing the object rights opens.
5. Edit the object rights.
6. Click on **OK** to save your changes to the object rights and close the dialog box.




Manage export profiles

Note: The use of categories does not mean that the names of export profiles in different categories no longer need to be unique. Categories are merely intended to make navigation easier.

13.4.2 Editing an export profile

You can edit all of the settings that you made when creating an export profile.

1. In the Views menu 27 select **Edit export profile...**.
   - The management dialog box opens.
2. Select the required export profile.
3. Click on **Apply**.
   - The dialog box for editing an export profile opens. As described in Creating an export profile 313, you now specify the settings for the export profile.




Selecting the export profile

4. If necessary, change the export format template.

Note: If a different format template is selected, all previous settings need to be reset.

5. If necessary, change the profile name and description.
6. Click on **Next**.
7. If necessary, edit the export parameter values.
8. Click on **Finish**.
   - If you have retained the previous profile name, you will see a confirmation that the export profile has been saved successfully.
   - If you have assigned the export profile a new name, you will see a prompt asking you whether you want to rename the profile or create a new profile.



Renaming or copying an export profile

9. If you want to create a new export profile, click on **New export profile**.
10. If you want to rename an existing export profile, click on **Rename**.
    - You will see a message confirming that the export profile has been saved successfully.

13.4.3 Deleting an export profile

> Note: Note that deleting an export profile not only deletes the entry in the menu tree, but also the entire export profile.

The procedure for deleting an export profile is as follows:

1. Select **Manage export profiles...** in the Views menu.
    - The selection dialog box opens.
2. Select the relevant export profile.
3. Click on **Delete**.
    - A confirmation prompt appears, asking whether you really want to delete the export profile.
4. Click on **Yes** to permanently delete the export profile.

13.5 Export

To export files, use the export profiles that you created. When you export files, you can update the parameters of the export profile, specify execution time of the export, and specify the output destination of the exported files.


If the export profile includes a variable, you can choose to update the value of the variable either before the export operation or after. For example, if the export profile includes a Date variable, you can choose to update the date and time before the export execution begins.

You can select the execution time of the export. For more information about execution time, see the following topics:

- Export immediately
- Schedule export (once)
- Schedule export (repeating)

For export operations, the server creates a unique sub-directory in a preset directory to store the exported files. You can choose to export the files locally to a specified path.


1. In the **Context selection** view, right-click the export profile, and select **Export…**.
   - The **Export export profile** dialog box appears.
2. Click **Next**.
   - The Export parameter configuration dialog box appears that displays the set parameters.
3. Update the parameters if required.



Export Parameter Configuration

4. Click **Next**.

   The **Select output destination** dialog box appears.



Output Destination

5.Specify the execution time of the export. You can select one of the following options:

- Export immediately
- Schedule export (once)
- Schedule export (repeating)

6.To save the exported files locally, perform the following steps:

i. Select **Save export file(s) locally**.

ii.Select the required options, and specify the path to store the exported files.

7.Click **Finish**.

13.5.1 Export immediately

The procedure for executing the export immediately is as follows:


1.Select the relevant data records in an object overview (item, variant, product or structure group table).

2.Select **Generate immediate export** in the pop-up menu.

⇨ All existing export format templates– corresponding to their data type and respective object table – are offered and can be executed directly.

3.Select the relevant entry.

➪ The underlying export profile is displayed.



Export profile


4. If there are conflicts in terms of the data selection and the export profile not matching, corresponding warnings are displayed. Depending on the type of error, you can use radio buttons to determine whether you want to cancel the operation or continue with it.

   ➪ The description in the top graphic gives a “green light”, therefore click on **Next**.

Note: The export format template for the immediate export must contain the value "Editable" for the “Catalog” and “Assortment” parameters in the data sources. If one of these settings is missing, a warning to that effect is output, which you can view by clicking on in the log.

5. The **Export parameter configuration** dialog box is displayed.


- The selection field for the assortment is filled automatically and displays the selection to be exported. .



Export parameter configuration

6. If you would prefer to perform the export at another time or want to save the exported data locally in a specific location, click on **Next**.


- The **Select output destination** dialog box is displayed.



Select output destination


7. If all entries are correct or complete, click on **Finish**.

A system message informs you of the status of the export operation.



8. Close the window by clicking on **OK**.

You can view a log for the export operation in the ***Process overview*** perspective.



Process overview for one-off export operations

13.5.2 Scheduling a one-off export


The procedure for scheduling a one-off export at a predefined time is as follows:

1. Schedule the export.

2. In the "Execution" drop-down list, select the "Schedule export (once)" method.

Note: In this case, the export files cannot be saved locally.

3. Enter the required times in the "Start date" and "Start time" fields.



Executing the export once at a defined time

4. Click on **Finish**.

A message appears confirming that the export has been scheduled successfully.

5.Confirm with **OK**.

- You can monitor the progress of the export operations in the ***Process overview*** perspective and download the export files when complete.

13.5.3 Repeated export

The "Schedule export (repeating)" method is used to execute repeated exports at equal intervals or on regular dates. A repeated export (also called an export series) saves you having to remember to schedule regular exports yourself. For example, you always update an online catalog for your customers on the first of each month (date) or your Controlling department requires the new selling prices for their calculations every two days (time interval). In this case, the crucial factor is up to date data rather than the day of the month.

When you are scheduling a repeated export, you can use the variables in your export profile to specify the value to use for the export operation.

For example, you can use a Date variable in your export profile and choose to update the Date variable either before or after the export.

If you choose to update the date variable before the export, the start date and time of the export is updated. Use this option to set the start date and time of the export as value of the variable in the exported file.

If you choose to update the date after the export, the start date and time of the current export is available in the next export execution. Use this option to determine the updated data since the last export.

When scheduling an export series, you can decide whether the series is to be ended automatically and when this is to occur. Use this option to determine the updated data since the last export. However, you can also cancel an export series at any stage in the ***Process overview*** view.

To schedule a repeated export, follow the steps below:


1.Schedule the export.

2.In the "Execution" drop-down list, select the "Schedule export (repeating)" method.

- The information "(not configured)" is displayed in parentheses next to the list field. This indicates that a schedule for the repeated export has not yet been specified.

3.Click on  on the right.

- The "Export planning" dialog box opens. The Repetition interval and Repetition pattern options are available for scheduling repeated exports.



Export scheduling dialog box

Repetition interval and repetition pattern

The repetition interval represents a repeated export at equal intervals and an end date. The first export is performed in accordance with the date and time details in the "First execution" section. Subsequent exports are performed at the exact intervals specified. The number of repetitions can also be specified.

A repetition pattern enables you to make your export times even more flexible than is possible with a repetition interval. You can schedule your exports for particular days of the week, weeks, and months of the year or hours and minutes of the day. The pattern starts from the date of the first execution. For example, you may want to execute an export daily on working days but not at the weekend.

13.5.3.1 Repetition interval

The "Repetition interval" option enables you to schedule repeated exports using the following formula:


- Date and time of first export
- Interval between two exports
- Maximum number of repetitions

The repetition interval is the preferred option if exporting regularly is the key factor rather than exporting on particular dates.

The procedure for scheduling a repetition interval is as follows:

1. Schedule a repeated export. 323
2. Select the "Repetition interval" option.

3. Under "First execution", specify the date and time for the first execution of the export. If you do not make an entry here, the export series will start immediately.
4. Under "Last execution", you can specify the date and time for the last execution of the export.
5. Under "Repetition interval", define the interval between exports. This is made up of the number in the first drop-down list and the unit of time in the second drop-down list, e.g., "Every 2 days".




Specifying the repetition

6. If necessary, you can enter the maximum number of repetitions using the "limit to" option. If you do not specify the date of the last execution or the number of times the export is to be repeated, the export series will not end automatically.

Note: No more exports are started after the date and time of the last execution.

Therefore, you must ensure that the date and time of the last execution match the settings in the repetition interval. Alternatively, make only one of these settings.

7. Click on **OK**.
   - The "Export scheduling" dialog box closes.
8. Use the information under "Execution" to check that you have scheduled your export correctly.




Scheduled repetition interval

9. Click on **Finish**.
   - The export is scheduled and displayed in the ***Process overview*** perspective.

13.5.3.2 Repetition pattern

The "Repetition pattern" option extends the possibilities offered by the "Repetition interval" option. For example, you may want to execute regular exports only on certain days of the week or in particular months.


1. Schedule a repeated export.
2. Select the "Repetition pattern" option.
   - The five options "every minute", hourly", "daily", "weekly", and "monthly" are now available in the first drop-down list.



Options for setting a repetition pattern


The "monthly" option

The "monthly" option allows you to specify an export on a particular day of the month, e.g. the 20th of the month, at1 to 12 month intervals. The time is always the time of the first execution. The monthly export is ended at the date and time of the last execution.



Lowest possible values for the "monthly" option

Here, the export is performed monthly on the first day of the month from the time of the first execution to the time of the last execution.




Maximum possible values for the "monthly" option

Here, the export that is performed every 12 months on the 31st day of the month, starting from the time of the first execution.


The "weekly" option

The "weekly" option enables you to set your export time on particular days of every week. You can select one to seven days of the week. If you actually select seven days, this is the same as a daily export. It therefore makes sense to select between one and six days of the week. The time is always that of the first execution. The export series is limited by the date and time of the last export.



Minimum selection for "weekly" option

Here, the export is executed on a particular day each week.




Export on six particular days of the week


The "daily" option

The "daily" option is used to execute exports on specific days. You can specify the days on which the export will be executed. The export series is limited by the date and time of the last execution.

You can use the subsidiary option "Every day" to set a continuous daily export.



Continuous daily export



Export on a certain day of the week


The "hourly" option

The hourly repetition pattern enables you to perform your exports at 1 to 12 hour intervals at a particular minute of the hour within a set timeframe.


For example, you can schedule your export for every 2 hours on the 15th minute of the hour between 09:00 and 18:00. The series starts with the hour of the first execution: Time 09:15, date July 01, 2007. The export series ends with the last execution, which occurs at 18:00 on July 01, 2007.

- First execution: 09:15
- Second export: 11:15
- Third export: 13:15
- Fourth export: 15:15
- Last export: 17:15

There is no export at 18:15 because the export time would be after the 18:00 limit for the last execution.



Lowest possible values for "hourly" option




Maximum possible values for "hourly"

Intervals of no more than 12 hours can be configured between two exports.


The "every minute" option

The "every minute" option enables you to export on one to seven days of the week at one to thirty-minute intervals within a set timeframe. A day begins at 00:00 and ends at 24:00. You can set intervals of every 1, 5, 10, 15, 20 or 30 minutes.

For example, an export can be scheduled for Mondays and Tuesdays every 30 minutes between 00:00 and 03:00.



Minimum possible values for "every minute"



Maximum possible values for "every minute"

13.5.4 Quality checks


In addition to a test export, you now have an additional option for checking your settings before the actual export operation.

What is the difference between a quality check and a test export?

In a test export, a temporary export profile is automatically generated for the duration of the export. This profile uses the export format template that is currently being edited. A quality check works through the validation rules set in the export format template, determines any objects that require attention, and outputs the results as a log and in a graphical overview.

Recurring quality checks can also be scheduled to determine the current quality of the individual templates at regular intervals. By default, the last test including the log is displayed in the **Process overview > Data maintenance > Quality check** perspective. Like the export log, it can contain information, error messages, or warnings. The ***Quality check*** view shows a graphical representation of the current status of the check with percentages, which are described in more detail in a table.

The quality check is named after the underlying export profile. A drop-down menu contains all open checks.



Quality check perspective

This view "remembers" user-specific settings, i.e. you can open any number of other test reports in addition to the current one so that they can be continuously compared. If you exit Product 360 Desktop, the last configuration displayed is saved and provided the next time the program is started.

If you select an entry in the ***Current and past processes*** view, the pop-up menu provides various editing options. The table below explains the options in the pop-up menu:

Option	**Functionality**
Copy / Paste	Copies a text from the view and pastes it into another application.
Delete	Deletes not only from the view but also removes the archived quality check from the database. If it is part of a series, this ends the series. A scheduled export check is deleted and is no longer started.
Select all	Selects all entries in the view.
Refresh	Refreshes the contents in the view. You can also execute this command by pressing F5.
Cancel	Aborts a quality check in progress. If it was part of a series, this has no influence on the series. The next execution is performed as scheduled.
Compare	Opens the ***Comparison view.*** This entry is only active if you have selected at least two entries.

Option	Functionality
Run export...	If the result of the check is satisfactory, you can immediately initiate the normal export operation.
Re-run validation rules...	By default, a new check is performed with the same configuration. If required, adjustments can be made.
Properties...	Lists all objects (including different data types) that reference the current object.
Show scheduling information	A message is output showing the underlying scheduling configuration for series.
Show quality check result	Opens a new ***Quality check*** view with the graphical implementation of the selected check.

In the ***Quality check*** view, the Views menu provides various setting options. The table below explains the available options:

Option	Functionality
Open new view	A new view is displayed.
Display own scheduled quality checks only	Filters the display accordingly.
Retain current content	Prevents the content from being recompiled.
Sort quality checks by	• Name • Creation date • Last execution date • Users

13.5.5 Editing exports

You can edit your exports in the ***Process overview*** perspective. If you are not in this perspective, open it by selecting **Management > Process overview**. In the ***Overview*** three subnodes for the expot appear under the “Publications” node:

- Export operations (Supplier Exchange)
- Export operations (one-off)
- Export operations (repeated)
- Test export operations

If you select one of these nodes, the ***Current and past processes*** view shows the corresponding export operations. If you select an entry in the ***Current and past processes*** view, the associated log is displayed in the ***Log*** view. You can use the pop-up menu to download the export files, repeat exports, or exit export series. The table below explains the options in the pop-up menu:

Option	Functionality
Copy / Paste	Copies a text from the view and pastes it into another application.
Delete	Deletes not only from the view but also removes the archived export from the database, and the archived export files from the server. A scheduled export operation is deleted and is no longer started.
Select all	Selects all entries in the view.
Refresh	Refreshes the contents in the view. You can also execute this command by pressing F5.
Cancel	Aborts a quality check in progress. If it was part of a series, this has no influence on the series. The next execution is performed as scheduled.
Compare	Opens the ***Comparison view.*** This entry is only active if you have selected at least two entries.
Show scheduling information	Displays the information for export series for repeated export operations.
Download export file(s)	Downloads the exported fields to a local directory. These include the data files and the multimedia archive (if one was generated). The files can be compressed.
Repeat export	Opens the "Export export profile" dialog box. The selected export operation can be repeated with the parameters used.
Execute immediately	Activates a scheduled export operation irrespective of the set date.

14 Appendix

This appendix contains:

- Rights groups for action rights 333
- Rights groups for visibilities 348
- Import function reference 356
- Export function reference 367
- Data source reference 402

14.1 Rights groups for action rights

The following rights groups are available for action rights:

- General 334
- Item 334
- Item assortments 335
- Item search 335
- Audit Trail 336
- Tasks 336
- Task notifications 336
- Users 336
- Characteristics 348
- Data quality 337
- Document management 337
- E-mail templates 337
- Units 338
- Export 338
- Import 339
- Channel 339
- Catalogs 339
- Customers 340
- Suppliers 340
- Merge 340
- Multimedia attachments 341
- Products 341
- Product assortments 341
- Product search 342
- Process planning 342
- Qualified field rights 342
- Discount groups 343
- Structures 343
- Structure groups 343
- Structure group search 344
- Structure features 344

- Structure preset values 345
- System messages 345
- Text features 345
- Company management 345
- Versions 346
- Predefined queries 346
- Lookups 347
- Workflow 347
- Dictionaries 347
-

14.1.1 Rights group: General

The table below lists all rights that can be assigned in relation to **general access**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
General	Rich client login
General	Service login

14.1.2 Rights group: Item

The table below lists all rights that can be assigned in relation to **items**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Item	Creating items
Item	Remove items from version
Item	Editing items
Item	Release items in version
Item	Clone items
Item	Deleting items
Item	Items, general access
Item	Items, read object rights
Item	Items, manage object rights
Item	Configure attribute transfer
Item	Create extended logistical data

Rights group	Permission
Item	Edit extended logistical data
Item	Delete extended logistical data
Item	Extended logistical data, general access
Item	Create supplier relationships
Item	Edit supplier relationships
Item	View supplier relationships
Item	Delete supplier relationships
Item	Create prices
Item	Create prices (in the past)
Item	Edit prices
Item	Edit prices (in the past)
Item	View prices
Item	Delete prices
Item	Delete prices (in the past)

14.1.3 Rights group: Item assortments

The table below lists all rights that can be assigned in relation to **item assortments**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Item assortments	Create item assortments
Item assortments	Edit item assortments
Item assortments	Delete item assortments
Item assortments	Item assortments, general access
Item assortments	Item assortments, read object rights
Item assortments	Item assortments, manage object rights

14.1.4 Rights group: Item search

The table below lists all rights that can be assigned in relation to the **item search**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Item search	Item search, read object rights
Item search	Item search, manage object rights
Item search	Create item search

Rights group	Permission
Item search	Edit item search
Item search	Delete item search
Item search	Item search management, general access

14.1.5 Rights group: Audit Trail

The table below lists all rights that can be assigned in relation to the **Audit Trail**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Audit Trail	Audit Trail, general access

14.1.6 Rights group: Tasks

The table below lists all rights that can be assigned in relation to **tasks**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Tasks	Manage tasks
Tasks	Show tasks for all users
Tasks	Creating tasks
Tasks	Processing tasks
Tasks	Deleting tasks
Tasks	Task management, general access

14.1.7 Rights group: Task notifications

The table below lists all rights that can be assigned in relation to **task notifications**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Task notifications	Configure task notifications
Task notifications	Notification level for a task notification

14.1.8 Rights group: Users

The table below lists all rights that can be assigned in relation to **users**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Users	Users, general access
Users	Users, read object rights
Users	Users, manage object rights
Users	Create users
Users	Edit users
Users	Delete users

14.1.9 Rights group: Data quality

The table below lists all rights that can be assigned in relation to the **data quality**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Data quality	Executing a data quality rule
Data quality	Data quality rule configuration, general access
Data quality	Data quality scheduling, general access
Data quality	Delete quality status
Data quality	Quality status, general access

14.1.10 Rights group: Document management

The table below lists all rights that can be assigned in relation to **document management**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Document management	Create documents
Document management	Edit documents
Document management	Deleting documents
Document management	Document management, general access
Document management	Create document categories
Document management	Edit document categories
Document management	Delete document categories

14.1.11 Rights group: E-mail templates

The table below lists all rights that can be assigned in relation to **e-mail templates**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
E-mail templates	Manage e-mail templates

14.1.12 Rights group: Units

The table below lists all rights that can be assigned in relation to **units**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Units	Create units
Units	Edit units
Units	Explicitly delete units
Units	Create unit systems
Units	Edit unit systems
Units	Delete unit systems
Units	Unit management, general access
Units	Delete unit assignments for default unit systems
Units	Delete unit assignments

14.1.13 Rights group: Export

The table below lists all rights that can be assigned in relation to the **export**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Export	Run exports
Export	Edit export format templates
Export	Creating export format templates
Export	Delete export format templates
Export	Export format templates, read object rights
Export	Export format templates, manage object rights
Export	Edit export profiles
Export	Creating export profiles
Export	Delete export profiles
Export	Export profiles, read object rights
Export	Export profiles, manage object rights

14.1.14 Rights group: Import

The table below lists all rights that can be assigned in relation to the **import**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Import	Configure hotfolder
Import	Manage HSX
Import	Performing an import
Import	Import mappings, manage object rights
Import	Edit import mappings
Import	Read import mappings
Import	Delete import mappings
Import	Create import mappings

14.1.15 Rights group: Channel

The table below lists all rights that can be assigned in relation to **channels**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Channel	Channel, general access
Channel	Channel, read object rights
Channel	Channel, manage object rights
Channel	Create channel
Channel	Edit channel
Channel	Delete channel

14.1.16 Rights group: Catalogs

The table below lists all rights that can be assigned in relation to **catalogs**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Catalogs	Supplier catalog, read object rights
Catalogs	Supplier catalog, manage object rights
Catalogs	Supplier catalogs, general access
Catalogs	Create supplier catalogs

Rights group	Permission
Catalogs	Remove supplier catalogs from version
Catalogs	Edit supplier catalogs
Catalogs	Release supplier catalogs in version
Catalogs	Delete supplier catalogs
Catalogs	Master catalog, read object rights
Catalogs	Master catalog, manage object rights

14.1.17 Rights group: Customers

The table below lists all rights that can be assigned in relation to **customers**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Customers	Create customers
Customers	Delete customers
Customers	Edit customers
Customers	Customer management, general access

14.1.18 Rights group: Suppliers

The table below lists all rights that can be assigned in relation to **suppliers**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Suppliers	Create suppliers
Suppliers	Delete suppliers
Suppliers	Edit suppliers
Suppliers	Supplier management, general access

14.1.19 Rights group: Merge

The table below lists all rights that can be assigned in relation to the **merge function**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Merge	Perform merge
Merge	Merge, general access

14.1.20 Rights group: Multimedia attachments

The table below lists all rights that can be assigned in relation to **multimedia attachments**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Multimedia attachments	Edit multimedia attachments
Multimedia attachments	Add multimedia attachments
Multimedia attachments	Delete multimedia attachments

14.1.21 Rights group: Products

The table below lists all rights that can be assigned in relation to **products**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Products	Create prices
Products	Create prices (in the past)
Products	Edit prices
Products	Edit prices (in the past)
Products	View prices
Products	Delete prices
Products	Delete prices (in the past)
Products	Creating products
Products	Remove products from version
Products	Editing products
Products	Release products in version
Products	Delete products
Products	Products, read object rights
Products	Products, manage object rights
Products	Product management, general access

14.1.22 Rights group: Product assortments

The table below lists all rights that can be assigned in relation to **product assortments**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Product assortments	Product assortments, general access
Product assortments	Product assortments, read object rights
Product assortments	Product assortments, manage object rights
Product assortments	Create product assortments
Product assortments	Edit product assortments
Product assortments	Delete product assortments

14.1.23 Rights group: Product search

The table below lists all rights that can be assigned in relation to the **product search**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Product search	Product search, general access
Product search	Product search, read object rights
Product search	Product search, manage object rights
Product search	Create product search
Product search	Edit product search
Product search	Delete product search

14.1.24 Rights group: Process planning

The table below lists all rights that can be assigned in relation to **process planning**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Process planning	View processes for all users
Process planning	Edit processes
Process planning	Delete processes
Process planning	Process planning, general access

14.1.25 Rights group: Qualified field rights

The table below lists all rights that can be assigned in relation to **qualified field rights**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Qualified field rights	Edit qualified field rights

Rights group	Permission
Qualified field rights	Qualified field rights, general access

14.1.26 Rights group: Discount groups

The table below lists all rights that can be assigned in relation to **discount groups**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Discount groups	Create discount groups
Discount groups	Remove discount groups from version
Discount groups	Edit discount groups
Discount groups	Release discount groups in version
Discount groups	Delete discount groups
Discount groups	Discount groups, general access
Discount groups	Discount groups, read object rights
Discount groups	Discount groups, manage object rights

14.1.27 Rights group: Structures

The table below lists all rights that can be assigned in relation to **structures**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Structures	Remove structures from version
Structures	Release structures in version
Structures	Structures, general access
Structures	Structures, read object rights
Structures	Structures, manage object rights
Structures	Create structure systems
Structures	Edit structure systems
Structures	Delete structure systems

14.1.28 Rights group: Structure groups

The table below lists all rights that can be assigned in relation to the **structure groups**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Structure groups	Creating structure groups
Structure groups	Edit structure groups
Structure groups	Deleting structure groups
Structure groups	Structure groups, general access
Structure groups	Structure groups, read object rights
Structure groups	Structure groups, manage object rights
Structure groups	Creating a structure group feature
Structure groups	Edit a structure group feature
Structure groups	Delete a structure group feature
Structure groups	Inherit a structure group feature

14.1.29 Rights group: Structure group search

The table below lists all rights that can be assigned in relation to the **structure group search**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Structure group search	Structure group search, read object rights
Structure group search	Structure group search, manage object rights
Structure group search	Create structure group search
Structure group search	Edit structure group search
Structure group search	Delete structure group search
Structure group search	Structure group search management, general access

14.1.30 Rights group: Structure features

The table below lists all rights that can be assigned in relation to **structure features**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Structure features	Create structure features
Structure features	Edit structure features
Structure features	Delete structure features
Structure features	Structure features, general access

14.1.31 Rights group: Structure preset values

The table below lists all rights that can be assigned in relation to **structure preset values**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Structure preset values	Creating structure preset values
Structure preset values	Edit structure preset values
Structure preset values	Delete structure preset values
Structure preset values	Structure preset values, general access

14.1.32 Rights group: System messages

The table below lists all rights that can be assigned in relation to **system messages**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
System messages	Create system messages
System messages	Editing system messages
System messages	Delete system messages
System messages	System messages, general access

14.1.33 Rights group: Text features

The table below lists all rights that can be assigned in relation to **text features**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Text features	Manage text features

14.1.34 Rights group: Company management

The table below lists all rights that can be assigned in relation to **company management**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Company management	Object rights administration (system)
Company management	Create user groups
Company management	Edit user groups

Rights group	Permission
Company management	Delete user groups
Company management	User groups, read object rights
Company management	User groups, manage object rights
Company management	Overwrite object rights
Company management	Edit company data
Company management	Company management, general access

14.1.35 Rights group: Versions

The table below lists all rights that can be assigned in relation to **versions**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Versions	Create versions
Versions	Edit versions
Versions	Delete versions
Versions	Close versions
Versions	Open versions
Versions	Versions, read object rights
Versions	Versions, manage object rights
Versions	Version management, general access

14.1.36 Rights group: Predefined queries

The table below lists all rights that can be assigned in relation to **predefined queries**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Predefined queries	Queries, general access
Predefined queries	Queries, read object rights
Predefined queries	Queries, manage object rights
Predefined queries	Create queries
Predefined queries	Edit queries
Predefined queries	Delete queries

14.1.37 Rights group: Workflow

The table below lists all rights that can be assigned in relation to the **workflow**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Workflow	Workflow, general access
Workflow	Manage workflow instances
Workflow	Delete workflow profiles
Workflow	Maintain workflow profiles

14.1.38 Rights group: Dictionaries

The table below lists all rights that can be assigned in relation to **dictionaries**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Dictionaries	Dictionaries for spellcheck, general access
Dictionaries	Dictionaries for spellcheck, managing object rights
Dictionaries	Dictionaries for spellcheck, reading object rights
Dictionaries	Add words to dictionary for spell check
Dictionaries	Manage dictionaries for spellcheck
Dictionaries	Suggests words for spell check
Dictionaries	Manage words for spellcheck
Dictionaries	Standardization dictionaries, general access
Dictionaries	Standardization dictionaries, manage object rights
Dictionaries	Standardization dictionaries, read object rights
Dictionaries	Manage standardization dictionaries
Dictionaries	Manage values for standardization dictionaries

14.1.39 Rights group: Lookups

The table below lists all rights that can be assigned in relation to **lookups**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Lookups	Values, general access
Lookups	Lookups, manage object rights

Rights group	Permission
Lookups	Lookups, general access
Lookups	Create lookups
Lookups	Lookups, read object rights
Lookups	Edit values
Lookups	Clone lookups
Lookups	Create values
Lookups	Delete values
Lookups	Delete lookups

14.1.40 Rights group: Characteristics

The table below lists all rights that can be assigned in relation to **characteristics**. A right with the "general access" extension means that a user to whom this right has been assigned is simply able to call up the perspective to which it applies.

Rights group	Permission
Characteristics	Characteristics, general access
Characteristics	Create characteristics
Characteristics	Delete characteristics
Characteristics	Edit characteristics

14.2 Rights groups for visibilities

The following rights groups are available for interface visibilities:

- Visibilities in Product 360 Desktop 348
- Visibilities in Product 360 Web 354

14.2.1 Visibilities in PIM Desktop

The table below lists all rights that can be assigned in relation to **interface visibilities in Product 360 Desktop**.

Rights group type	Rights group	Perspective/view
Product 360 Desktop Perspective	Audit Trail	Audit Trail

Rights group type	Rights group	Perspective/view
Product 360 Desktop Perspective	Data maintenance	Attribute assignment (items)
Product 360 Desktop Perspective	Data maintenance	Initial classification (items)
Product 360 Desktop Perspective	Data maintenance	Explorer (items) (default value)

Rights group type	Rights group	Perspective/view
Product 360 Desktop Perspective	Data maintenance	Explorer (products)
Product 360 Desktop Perspective	Data maintenance	Multiple classification (items)
Product 360 Desktop Perspective	Data maintenance	Multimedia attachments
Product 360 Desktop Perspective	Data maintenance	Prices (items)
Product 360 Desktop Perspective	Data maintenance	Discount groups
Product 360 Desktop Perspective	Data maintenance	Structures
Product 360 Desktop Perspective	Data maintenance	Structure group assignments

Rights group type	Rights group	Perspective/view
Product 360 Desktop Perspective	Data transfer	Hotfolder
Product 360 Desktop Perspective	Data transfer	Import
Product 360 Desktop Perspective	Data transfer	Merge

Rights group type	Rights group	Perspective/view
Product 360 Desktop Perspective	Publications	Export format templates

Rights group type	Rights group	Perspective/view
Product 360 Desktop Perspective	Management	Task notification
Product 360 Desktop Perspective	Management	Users
Product 360 Desktop Perspective	Management	Data quality
Product 360 Desktop Perspective	Management	Documents
Product 360 Desktop Perspective	Management	Units
Product 360 Desktop Perspective	Management	Customers
Product 360 Desktop Perspective	Management	Suppliers
Product 360 Desktop Perspective	Management	Supplier catalogs
Product 360 Desktop Perspective	Management	Organization
Product 360 Desktop Perspective	Management	Process overview
Product 360 Desktop Perspective	Management	Versions
Product 360 Desktop Perspective	Management	Workflows
Product 360 Desktop Perspective	Management	Dictionaries

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Administration	Action rights
Product 360 Desktop View	Administration	Tasks
Product 360 Desktop View	Administration	Task notification
Product 360 Desktop View	Administration	Users
Product 360 Desktop View	Administration	User details

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Administration	User groups
Product 360 Desktop View	Administration	Unit maintenance
Product 360 Desktop View	Administration	Unit system
Product 360 Desktop View	Administration	Unit systems
Product 360 Desktop View	Administration	E-mail template
Product 360 Desktop View	Administration	E-mail templates
Product 360 Desktop View	Administration	E-mail preview
Product 360 Desktop View	Administration	Field rights
Product 360 Desktop View	Administration	Customer
Product 360 Desktop View	Administration	Customers
Product 360 Desktop View	Administration	Supplier
Product 360 Desktop View	Administration	Suppliers
Product 360 Desktop View	Administration	Members
Product 360 Desktop View	Administration	Membership
Product 360 Desktop View	Administration	Interface visibilities
Product 360 Desktop View	Administration	Object rights (system)
Product 360 Desktop View	Administration	Qualified field rights
Product 360 Desktop View	Administration	System messages
Product 360 Desktop View	Administration	Company data
Product 360 Desktop View	Administration	Versions
Product 360 Desktop View	Administration	Words
Product 360 Desktop View	Administration	Dictionaries

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Other	Channels
Product 360 Desktop View	Other	Multichannel preview
Product 360 Desktop View	Other	Log
Product 360 Desktop View	Other	Quality check
Product 360 Desktop View	Other	Quality status
Product 360 Desktop View	Other	Comparison view

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Item views	Item #1
Product 360 Desktop View	Item views	Item #2
Product 360 Desktop View	Item views	Items with features
Product 360 Desktop View	Item views	Item attributes

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Item views	Item attributes (cumulative)
Product 360 Desktop View	Item views	Item attribute values
Product 360 Desktop View	Item views	Item details (form)
Product 360 Desktop View	Item views	Item assortments
Product 360 Desktop View	Item views	Item search
Product 360 Desktop View	Item views	Attribute assignments
Product 360 Desktop View	Item views	Purchase prices
Product 360 Desktop View	Item views	Extended logistical data
Product 360 Desktop View	Item views	Item references
Product 360 Desktop View	Item views	Text processing (item)
Product 360 Desktop View	Item views	Selling prices

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Item views (EKI)	Item comparison (supplier/ master catalog)
Product 360 Desktop View	Item views (EKI)	Supplier relationships

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	File attachments	Image preview
Product 360 Desktop View	File attachments	Miniature view
Product 360 Desktop View	File attachments	Multimedia attachments
Product 360 Desktop View	File attachments	Multimedia documents

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Data quality	Data quality configuration
Product 360 Desktop View	Data quality	Data quality scheduler

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Data transfer	Data source
Product 360 Desktop View	Data transfer	Details
Product 360 Desktop View	Data transfer	Field details
Product 360 Desktop View	Data transfer	Function
Product 360 Desktop View	Data transfer	Frequency
Product 360 Desktop View	Data transfer	Hotfolder groups
Product 360 Desktop View	Data transfer	Hotfolder configuration
Product 360 Desktop View	Data transfer	Content
Product 360 Desktop View	Data transfer	Merge preview

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Data transfer	Log
Product 360 Desktop View	Data transfer	Repository

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Documents	Dependencies
Product 360 Desktop View	Documents	Documents
Product 360 Desktop View	Documents	Document categories
Product 360 Desktop View	Documents	Miniature view (documents)
Product 360 Desktop View	Documents	System multimedia attachments

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Export templates	Properties
Product 360 Desktop View	Export templates	Export format template

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	General	Tasks
Product 360 Desktop View	General	Properties
Product 360 Desktop View	General	Error
Product 360 Desktop View	General	Progress
Product 360 Desktop View	General	Organization
Product 360 Desktop View	General	Bookmarks
Product 360 Desktop View	General	Selections
Product 360 Desktop View	General	Navigator
Product 360 Desktop View	General	Palette
Product 360 Desktop View	General	Welcome

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Help	Help

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Background processes	Current and past processes
Product 360 Desktop View	Background processes	Overview

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Catalog views	Context selection
Product 360 Desktop View	Catalog views	Supplier catalog (form)
Product 360 Desktop View	Catalog views	Supplier catalogs

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Classifications and material groups	Class details
Product 360 Desktop View	Classifications and material groups	Class list
Product 360 Desktop View	Classifications and material groups	Feature groups list
Product 360 Desktop View	Classifications and material groups	Primary structure tree
Product 360 Desktop View	Classifications and material groups	Source structure assignments
Product 360 Desktop View	Classifications and material groups	Secondary class list
Product 360 Desktop View	Classifications and material groups	Secondary structure tree
Product 360 Desktop View	Classifications and material groups	Structure group search
Product 360 Desktop View	Classifications and material groups	Structure group assignment
Product 360 Desktop View	Classifications and material groups	Structure features
Product 360 Desktop View	Classifications and material groups	Structure systems
Product 360 Desktop View	Classifications and material groups	Structure preset values
Product 360 Desktop View	Classifications and material groups	Text processing (structure group)
Product 360 Desktop View	Classifications and material groups	Subordinate structure groups
Product 360 Desktop View	Classifications and material groups	Preset values for group feature
Product 360 Desktop View	Classifications and material groups	Preset values for structure feature
Product 360 Desktop View	Classifications and material groups	Values for group features
Product 360 Desktop View	Classifications and material groups	Target structure assignments

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Classifications and material groups	Assignment recommendation

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Product views	Product items
Product 360 Desktop View	Product views	Product attributes
Product 360 Desktop View	Product views	Product attributes (cumulative)
Product 360 Desktop View	Product views	Product attribute values
Product 360 Desktop View	Product views	Product details (form)
Product 360 Desktop View	Product views	Products #1
Product 360 Desktop View	Product views	Products #2
Product 360 Desktop View	Product views	Products with features
Product 360 Desktop View	Product views	Product assortments
Product 360 Desktop View	Product views	Product search
Product 360 Desktop View	Product views	Product references
Product 360 Desktop View	Product views	Text processing (products)
Product 360 Desktop View	Product views	Selling prices

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Product search	Product search

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Discounts	Purchasing discount groups
Product 360 Desktop View	Discounts	Purchasing discount rates
Product 360 Desktop View	Discounts	Selling discount groups
Product 360 Desktop View	Discounts	Selling discount rates

Rights group type	Rights group	Perspective/view
Product 360 Desktop View	Workflow	Workflow profiles
Product 360 Desktop View	Workflow	Workflows

14.2.2 Visibilities in PIM Web

The table below lists all rights that can be assigned in relation to **interface visibilities in Product 360 Web**.

Rights group type	Rights group	Context selection/tab
Product 360 Web Context	Tasks	Tasks

Rights group type	Rights group	Context selection/tab
Product 360 Web Context	Catalogs	Catalogs
Product 360 Web Context	Context selection	Context selection
Product 360 Web Context	Multimedia attachments	Multimedia attachments
Product 360 Web Context	Structure groups	Structure groups
Product 360 Web Context	Simple search	Simple search
Product 360 Web Context	Full text search	Full text search

Rights group type	Rights group	Context selection/tab
Product 360 Web Tab	Item	All texts
Product 360 Web Tab	Item	Attributes
Product 360 Web Tab	Item	Ordering information
Product 360 Web Tab	Item	History
Product 360 Web Tab	Item	Classification
Product 360 Web Tab	Item	Logistics
Product 360 Web Tab	Item	Media attachments
Product 360 Web Tab	Item	Prices
Product 360 Web Tab	Item	References
Product 360 Web Tab	Item	Header
Product 360 Web Tab	Item	Text
Product 360 Web Tab	Item	Translation
Product 360 Web Tab	Item	Surcharges

Rights group type	Rights group	Context selection/tab
Product 360 Web Tab	Media attachments	Image preview
Product 360 Web Tab	Media attachments	Details
Product 360 Web Tab	Media attachments	Header
Product 360 Web Tab	Media attachments	Use

Rights group type	Rights group	Context selection/tab
Product 360 Web Tab	Product	All texts
Product 360 Web Tab	Product	Attributes
Product 360 Web Tab	Product	History
Product 360 Web Tab	Product	Classification
Product 360 Web Tab	Product	Media attachments
Product 360 Web Tab	Product	Prices
Product 360 Web Tab	Product	References

Rights group type	Rights group	Context selection/tab
Product 360 Web Tab	Product	Header
Product 360 Web Tab	Product	Text
Product 360 Web Tab	Product	Translation
Product 360 Web Tab	Product	Variants

Rights group type	Rights group	Context selection/tab
Product 360 Web Tab	Structure group	Item
Product 360 Web Tab	Structure group	History
Product 360 Web Tab	Structure group	Media attachments
Product 360 Web Tab	Structure group	Features
Product 360 Web Tab	Structure group	Products
Product 360 Web Tab	Structure group	Header
Product 360 Web Tab	Structure group	Text

Rights group type	Rights group	Context selection/tab
Product 360 Web Tab	Variant	All texts
Product 360 Web Tab	Variant	Item
Product 360 Web Tab	Variant	Attributes
Product 360 Web Tab	Variant	History
Product 360 Web Tab	Variant	Classification
Product 360 Web Tab	Variant	Media attachments
Product 360 Web Tab	Variant	Prices
Product 360 Web Tab	Variant	References
Product 360 Web Tab	Variant	Header
Product 360 Web Tab	Variant	Text
Product 360 Web Tab	Variant	Translation

14.3 Import function reference

This reference lists all functions that can be used when importing in Product 360 Desktop. The structure of the function descriptions always follows the same pattern:

1. Description of function
2. Use of function and any parameters
3. Examples of using the function

The following functions are available by default:

- concat
- Date

- defaultBoolean 358
- defaultDate 358
- defaultNumber 359
- defaultString 359
- delete 359
- deleteIfEmpty 359
- format 360
- if 360
- left 361
- length 361
- logError 361
- logInfo 362
- logWarning 362
- lower 362
- mid 363
- replace 363
- right 364
- round 364
- search 365
- select 366
- truncate 368
- upper 367

14.3.1 concat

The **concat** function combines two values to give a new value by joining them to represent a new character string.

Alternatively, the "+" operator can be used.

Use

```
concat (<Text1>,<Text2>)
```

The specifications in the function have the following meaning:

- Text 1-2: Text sections to be joined

Example

- concat ("Product", "ID")
  - ⇨ Output: "ProductID"

Nesting enables more than two texts to be joined:

- concat ([Item.Manufacturer], concat (": ", [Item.Item no]))
  - Output: "Erstein: ER-0711"
- concat ("Mini", concat("-", "Screwdriver"))
  - Output: “Mini screwdriver"

14.3.2 Date

The **date** function means that the text is interpreted as a date.

Use

```
date (value)
```

The specifications for the function have the following meaning:

- Date: Date in the relevant location-specific format, in line with ISO standards

Example

- date("2012-05-23")
  - Output: 23.05.2012

14.3.3 defaultBoolean

The **defaultBoolean** function returns a default value of Boolean type (logical value) if the value is blank.

Use

```
defaultBoolean (<Value>,<default>)
```

The specifications in the function have the following meaning:

- Value: Automatic transfer of the current field from the repository
- default: "true" if the field has no content; "false" if the field is not blank.

Example

- defaultBoolean ([Warranty], false)
  - Output: "false"

14.3.4 defaultDate

The **defaultDate** function returns a default value of Date type if the value is blank.

Use

```
defaultDate (<Value>,<default>)
```

The specifications in the function have the following meaning:

- Value: Automatic transfer of the current field from the repository
- default: Definition of the alternative date specification

Example

- defaultDate ([Valid from], date("2012-05-23"))
  - Output: “2012-05-23"

14.3.5 defaultNumber

The **defaultNumber** function returns a default value of Number type if the value is blank.

Use

```
defaultNumber (<Value>,<default>)
```

The specifications in the function have the following meaning:

- Value: Automatic transfer of the current field from the repository
- default: Definition of the alternative number to be output

Example

- defaultNumber ([Tax], 19.0)
  - Output: “19.0"

14.3.6 defaultString

The **defaultString** function returns a default value of Text type if the value is blank.

Use

```
defaultString (<Value>,<default>)
```

The specifications in the function have the following meaning:

- Value: Automatic transfer of the current field from the repository
- default: Definition of the alternative text to be output

Example

- defaultString ([Manufacturer], "Erstein")
  - Output: "Erstein"

14.3.7 delete

The **delete** function deletes the content of the currently selected field. It is irrelevant whether or not the field has any content.

Use

```
delete ()
```

14.3.8 deleteIfEmpty

The **deleteIfEmpty** function deletes the content of the field if the transferred value is blank.

```
deleteIfEmpty (<Value>)
```

The specifications in the function have the following meaning:

- Value: The currently selected field in the repository, whose content is to be removed. The system checks whether or not the field has content.

14.3.9 format

The **format** functions rounds a value to the specified number of decimal places.

Use

```
format (<Value>, Decimal places)
```

The specifications in the function have the following meaning:

- Value: Number to be rounded.
- Decimal places: Number of decimal places.

Example

- format (2.3684, 2)
  - Output: “2.37"

14.3.10 if

The **if** enables conditional output of a value.

Use

```
if (Condition,Then value,Else value)
```

Alternative syntax:

```
if <condition> then <then value> else <else value>
```

The specifications in the function have the following meaning:

- Condition: Criterion that must be met.
- Then value: Value output if the condition is met.
- Else value: Value output if the condition is not met. This value is optional and if nothing is entered it is replaced with the value "Zero”.

Example

- if ([Manufacturer]=="Erstein GmbH", replace ([Manufacturer], "GmbH", "AG"), [Manufacturer])
  - Output: "Erstein AG"

    In this case, the specific manufacturer name "Erstein GmbH" was defined as the condition. If this condition is met, the "GmbH" section of the name is to be replaced with "AG". If the condition is not met, the manufacturer name is to be output.

14.3.11 left

The **left** function outputs the left section of the character string.

Use

```
left (<Text>,Number)
```

The specifications in the function have the following meaning:

- Text: Character string from which the left section is to be output.
- Number: Defines the maximum length of the character string to be output.

Example

- left ("ProductID", 7)
  - Output: "Product"

14.3.12 length

The **length** function determines the length of a character string.

Use

```
length (<Text>}
```

The specifications in the function have the following meaning:

- Text: Character string whose length is to be determined.

Example

- length ("Screws")
  - Output: 6

14.3.13 logError

The **logError** function can be used to generate custom error messages for the import log, independently of the system messages. This enables you to provide additional comments for individual field validations. It is the message with the greatest weighting.

Use

```
logError (<Error message>)
```

The specifications in the function have the following meaning:

- Error message: Text that indicates an error in the import, related to the selected field in the repository.

Example

- if Item no.]=="" then logError ("The 'Item no.' field may not be blank")
  - Output in log: "The 'Item no.' field may not be blank"

14.3.14 logInfo

The **logInfo** function can be used to generate custom information messages for the import log, independently of the system messages. This enables you to provide additional comments for individual field validations. It is the message with the lowest weighting.

Use

```
logInfo (<Information message>)
```

The specifications in the function have the following meaning:

- Information message: Text that highlights discrepancies in the import, related to the active field in the repository.

Example

- if (length ([Item short description] > 100) then logInfo (“The 'Item short description' field is too long”)
  - Output in log: "The 'Item short description' field is too long"

14.3.15 logWarning

The **logWarning** function can be used to generate custom warnings for the import log, independently of the system messages. This enables you to provide additional comments for individual field validations. It is the message with a medium weighting.

Use

```
logWarning (<Warning>)
```

The specifications in the function have the following meaning:

- Warning: Text that warns about sources of errors in the import, related to the selected field in the repository.

Example

- if (length ([Alternative item no.] > 10) then logWarning (“The 'Alternative item no.' field is too long”)
  - Output in log: "The 'Alternative item no.' field is too long"

14.3.16 lower

The **lower** function is used to convert a character string into lower case.

Use

```
lower (<Text>)
```

Text: Character string in which all letters are to be converted into lower case

Example

- lower ("ABC")

- Output: "abc"

- lower ("aBc")
  - Output: "abc"

14.3.17 mid

The **mid** function returns a section of the character string. The section begins at the specified start position.

Use

```
mid (<Text>,Start,Number)
```

The specifications in the function have the following meaning:

- Text: Character string from which a particular section is to be returned.
- Start: Start position, with the first character being position 1.
- Number: Defines the maximum length of the character string returned.

Example

- mid ("123456", 3, 2)
  - Output: “34"

14.3.18 replace

The **replace** function is used to search a text for a particular character string and replace all occurrences of that string with a different character string of your choice. The wildcards **?** and ***** are supported in "glob" mode.

Note: The search is case-sensitive.

Use

```
replace (<Input text>, <Search text>, <Replacement text>, Mode)
```

The specifications for the function have the following meaning:

- Input text: Text to be searched
- Search text: Character string for which the specified text is searched. The following wildcards can be used in "glob" mode:
  a.? stands for any character.
  b.* stands for any character string.
- Replacement text: Text to be used to replace the specified search text
- The following modes are available:
  - "glob": Global search
  - "exact": Exact match

- "regEx": Regular expression. A regular expression defines a pattern for a character string. The most common examples are order numbers, zip codes, e-mail and IP addresses. A brief introduction can be found here.

Example

- replace ("Example text", "Text", "Result", "exact")
  - Example result
- replace ("Example text", "E*ample", "Result", "glob")
  - Result text
- replace ("Example test", "te?t", "text", "glob")
  - Example text
- replace ("abcd", "b?d", "h", "glob")
  - Output: "ah"
- replace ("Max.Mustermann@web.de", "([a-zA-Z0-9_-\.]+)@([a-zA-Z0-9\.]+[a-zA-Z]{2,4})", "$1AT$2", "regEx")
  - Max.MustermannATweb.de

14.3.19 right

The **right** function outputs the right section of the character string.

Use

```
right (<Text>, Number)
```

The specifications in the function have the following meaning:

- Text: Character string from which the right section is to be output.
- Number: Defines the maximum length of the character string to be returned.

Example

- right ("ProductID", 2) }
  - Output: "ID"

14.3.20 round

The **round** function rounds the value up or down to an integer.

Use

```
round (<Value>)
```

The specifications in the function have the following meaning:

- The value is handled in line with the rules for commercial rounding.

Example

- round (1.3)

- Output: 1

- round (1.5)
  - Output: 2
- round (1.49)
  - Output: 1
- round (-1.5)
  - Output: -2

14.3.21 search

The **search** function returns the position of a search text in a character string. If the character string does not appear, "0" is returned. The search begins from the specified start position. The first character has the position 1. The wildcards **?** and ***** are supported in “glob” mode

Note: The search is case-sensitive.

Use

```
search (<Text>, <Search text>, Start, Mode)
```

The specifications for the function have the following meaning:

- Text: Text to be searched
- Search text: Character string for which the specified text is searched.
  a.Search text: Character string for which the specified text is searched. The following wildcards can be used in "glob" mode:
  a.? stands for any character.
  b.* stands for any character string.
- Start: Start position for the search
- The following modes are available:
  - "glob": Global search
- "exact": Exact match
- "regEx": Regular expression. A regular expression defines a pattern for a character string. The most common examples are zip codes, e-mail and IP addresses. A brief introduction can be found here.

Example

- search ("ProductID", "d", 1, "exact")
  - Output: 4

See also: replace

14.3.22 select

The **select** function selects a tag from several XML tags of the same name in an XML document and returns its value. This function cannot be used at entity level.

Use

```
select (<Value>,Position)
```

The specifications in the function have the following meaning:

- Value: Automatic transfer of the current field from the repository
- Position: Position in a tag sequence

Example

The **select** function is suitable for obtaining the minimum and maximum value of a feature property in a BMEcat file. The following default construct is provided:

```
<FEATURE>
  <FNAME>Diameter</FNAME>
  <FVALUE>18</FVALUE>
  <FVALUE>25</FVALUE>
</FEATURE>
```

The first FVALUE tag contains the minimum value and the second tag the maximum value.

- select ([FVALUE],1)
  - Output: 18
- select ([FVALUE],2)
  - Output: 25

14.3.23 truncate

The **truncate** function changes the value into an integer by truncating the decimal places.

Use

```
truncate (<Value>)
```

The specifications in the function have the following meaning:

- Value: Value from which the decimal places are to be removed.

Example

- truncate (1.9)
  - Output: 1
- truncate (-1.9)
  - Output: 1

14.3.24 upper

The **upper** function is used to convert a character string into upper case.

Use

```
upper (<Text>)
```

Text: Text in which all letters are to be converted into upper case

Example

- upper ("abcd")
  - ABCD
- upper ("aBc")
  - ABC

14.4 Export function reference

This reference lists all functions from the Export module. The structure of the function descriptions always follows the same pattern:

1. Description of function
2. Use of function and any parameters
3. Examples of using the function

The following functions are available by default:

- BMEcatDataType 369
- BMEcatMediaAssetQuality 370
- BMEcatMediaAssetType 370
- BMEcatPriceType 370
- BMEcatReferenceType 371
- Calculate 371
- Compare 372
- CompareBooleanValue 372
- CompareDate 373
- CompareIgnoreCase 373
- CompareNumeric 374
- Concat 374
- CreateCDataSection 375
- CreateXMLTagWithContent 375
- CreateXMLTagWithValue 375
- DatasetCounter 376

- DatasetId 376
- DatasetIdentifier 376
- DateGetFirstDay 377
- DateGetLastDay 377
- EscapeValue 378
- FillLeft 378
- FillRight 380
- FormatAttributeValueAsDecimal 380
- FormatDate 382
- FormatDecimal 383
- FormatHierarchicalNumber 384
- FormatSimplePattern 384
- FormatTime 385
- GetDate 385
- GetDecimalSeparator 386
- GetFirstValue 386
- GetTime 387
- GetValue 387
- IfEmptyThen 388
- IfEmptyThenNotEnc 388
- IfNotEmptyThen 388
- IfNotEmptyThenNotEnc 389
- IsoCodeCurrency 389
- IsoCodeLanguage 389
- IsoCodeTerritory 390
- LoopCounter 390
- LowerCase 390
- MimeDerivateGetUNCPath 391
- MimeGetHtmlLink 391
- MimeGetUNCPath 391
- Modulo 391
- NumberGet 392
- NumberIncrement 392
- NumberSet 393

- RemoveBlanks 393
- Replace 393
- ReplaceUmlauts 394
- SplitKeywords 394
- SplitText 395
- SplitTextGetLineCount 396
- StringIndexOf 396
- StringIndexOfIgnoreCase 397
- StringLastIndexOf 397
- StringLastIndexOfIgnoreCase 398
- StringLeftBytes 398
- StringLength 399
- stringRemoveLinebreak 399
- StringTruncateAtSpace 400
- Substring 400
- Trim 401
- UpperCase 401
- UpperCaseFirst 401
- ValueGet 402
- ValueSet 402

14.4.1 BMEcatDataType

The **BMEcatDataType** function is used to output the valid BMEcat data type identifier for the transferred data type.

Use

```
{?BMEcatDataType "Data type"}
```

Example

- {?BMEcatDataType {&Group features.Feature data type}}
  - Output: “Character string"

14.4.2 BMEcatMediaAssetQuality

The **BMEcatMediaAssetQuality** function is used to output the valid value for the quality of the transferred file attachment for the <MIME_TYPE> BMEcat element.

Use

```
{?BMEcatMediaAssetQuality "File attachment quality"}
```

Example

- {?BMEcatMediaAssetQuality "HTML document"}
  - Output: “text/html"

14.4.3 BMEcatMediaAssetType

The **BMEcatMediaAssetType** function is used to output the valid value for the transferred file attachment type for the <MIME_PURPOSE> BMEcat element.

Use

```
{?BMEcatMediaAssetType "File attachment type"}
```

Example

- {?BMEcatMediaAssetType "Standard image"}
  - Output: “normal”
- {?BMEcatMediaAssetType {&File attachments.Type}}
  - Output depends on the relevant file attachment

14.4.4 BMEcatPriceType

The **BMEcatPriceType** function is used to output the valid value for the BMEcat price type for the transferred selling price type.

Use

```
{?BMEcatPriceType "Price type"}
```

Example

- {?BMEcatPriceType "Net customer price"}
  - Output: “net_customer"

- {?BMEcatPriceType {&Selling prices.Price type}}
  - Output depends on the relevant price

14.4.5 BMEcatReferenceType

The **BMEcatReferenceType** function is used to output the valid BMEcat type for the transferred reference type. This BMEcat reference type is fixed as one of the following nine options:

- Component
- Similar item
- Successor item
- Essential spare part
- Optional spare part
- Accessories
- Other reference
- Alternative order unit
- Spart part

Depending on the login language, these fixed constants are assigned user-friendly terms, although these cannot be included in the export. This is ensured by the function.

Use

```
{BMEcatReferenceType "Reference type"}
```

Example

- {?BMEcatReferenceType "Spare part"}
  - Output: “spare part”
- {?BMEcatReferenceType {&Reference.Item reference type}}
  - Output depends on the relevant reference type

14.4.6 Calculate

The **Calculate** function is used to carry out simple calculations with two non-negative numbers. You can use the operators "+", "-", "x" and "/".

Use

```
{?Calculate "Number1 Operator Number2", Decimal separator[optional],
Decimal places[optional]}
```

The specifications in the function have the following meaning:

- Number1: First number in the calculation
- Operator: Operator for the calculation - +, -, x, and / are possible
- Number2: Second number in the calculation
- Decimal separator: Decimal separator to be used in the output
- Decimal places: Number of places after the decimal separator

Example

- {?Calculate "4 + 2"}
  - Output: 6
- {?Calculate"14 / 2", ".", 2}
  - Output: 7.00
- {?Calculate"4 + 2", ".", 2}
  - Output: 6.00

14.4.7 Compare

The **Compare** function is used to compare two character strings and check whether they are identical. Particular character strings are output depending on the result of the comparison.

Use

```
{?Compare "Text", "Comparison text", "Output 1", "Output 2"}
```

The specifications in the function have the following meaning:

- Text: Text to be compared
- Comparison text: Text with which it is to be compared
- Output 1: Text to be output if texts 1 and 2 are identical.
- Output 2: Text to be output if texts 1 and 2 are different.

Example

- {?Compare "Text", "Text", "Identical", "Different"}
  - Output: "equal to"
- {?Compare "Text", "Other text", "Identical", "Different"}
  - Output: “Different"

14.4.8 CompareBooleanValue

The **CompareBooleanValue** function evaluates the transferred value and returns one of the three parameter values depending on the result.

Note: This function checks the content of data fields. The function is not designed to evaluate real logical statements.

Use

```
{?CompareBooleanValue "Value", "Output value = True", "Output value =
False", "Output otherwise"}
```

The specifications in the function have the following meaning:

- Value: Value to be checked (normally a data field)
- Output value = True: Output if the value is true
- Output value = False: Output if the value is not true
- Output otherwise: Output if the value is blank or cannot be interpreted as a truth value

Example

- {?CompareBooleanValue {&Group features.Feature is mandatory field}, "true", "false", "" }}
- {?CompareBooleanValue {&Group features.Feature is a mandatory field}, "y", "n", "-"}}

14.4.9 CompareDate

The **CompareDate** function is used to compare two date entries and check whether they are identical. Particular character strings are output depending on the result of the comparison.

Use

```
{?CompareDate "Date1, "Date2"", "OutputIdentical", "OutputEarlier",
"OutputLater"}
```

The specifications in the function have the following meaning:

- Date1, Date2: The date values to be compared
- OutputIdentical: Output text if Date1 and Date2 are identical
- OutputEarlier: Output text if Date1 is before Date2
- OutputLater: Output text if Date1 is later than Date2

Example

- {?CompareDate "2011-10-03", "2011-11-01", "=", "<", ">" }
  - Output: "<"
- {?CompareDate "2011-11-01 10:11:12", "2011-11-01 10:10:12", "=", "<", ">" }
  - Output: “>"

14.4.10 CompareIgnoreCase

The **CompareIgnoreCase** function is used to compare two character strings and check whether they are identical. Differences in case are ignored. Particular character strings are output depending on the result of the comparison.

Use

```
{?CompareIgnoreCase "Text1", "Text2", "Output 1", "Output 2"}
```

The specifications in the function have the following meaning:

- Text1: Text to be compared
- Text2: Text with which it is to be compared
- Output 1: Output text if text 1 and 2 are identical
- Output 2: Output text if text 1 and 2 are different

Example

- {?CompareIgnoreCase "Text", "Text", "Identical", "Different"}
  - Output: "equal to"
- {?CompareIgnoreCase "Text", "TEXT", "Identical", "Different"}
  - Output: "equal to"
- {?Compare "Text", "Other text", "Identical", "Different"}
  - Output: “Different"

14.4.11 CompareNumeric

The **CompareNumeric** function is used to compare two numbers. Particular character strings are output depending on the result of the comparison.

Use

```
{?CompareNumeric Number1, Number2, "Output1", "Output2", "Output3"}
```

The specifications in the function have the following meaning:

- Number1 and Number2: The two numbers to be compared
- Output1: Output text if Number1 and Number2 are equal
- Output2: Output text if Number1 is less than Number2
- Output3: Output text if Number1 is greater than Number2

Example

- {?CompareNumeric 2, 4, "Equal", "Less than", "Greater than" }
  - Output:Less than
- {?CompareNumeric 4, 4, "Equal", "Less than", "Greater than" }
  - Output: "Equal"
- {?CompareNumeric 4, 2, "Equal", "Less than", "Greater than" }
  - Output: Greater than

14.4.12 Concat

The **Concat** function joins the transferred texts in the order they were transferred.

Use

```
{?Concat "Text 1", "Text 2", "Text 3", "Text 4"}
```

The specifications in the function have the following meaning:

- Text 1-4: Text sections to be joined

Example

- {?Concat {"Mini", " ", "screwdriver"}
  - Output: “Mini screwdriver"
- {?Concat {&Item.Manufacturer, ": ", &Item.Item no.}
  - Output: "Erstein: ER-0711"

14.4.13 CreateCDataSection

The **CreateCDataSection** function is used to create a CDATA section.

Use

```
{?CreateCDataSection "Content"}
```

In "Content", you transfer the text/content to be reproduced by the CDATA section.

Example

- {?CreateCDataSection "Content with special characters ?&%"}
  - Output: ““

14.4.14 CreateXMLTagWithContent

The **CreateXMLTagWithContent** function is used to create an XML fragment based on the transferred fragment, in which the character "?" is replaced with the transferred value.

Note: If the value is blank, no tag is created. The transferred fragment and the value are not encoded.

Use

```
{?CreateXMLTagWithContent "content", "xmlFragment"}
```

The individual specifications mean:

- content: Node/submodule, below which the new XML fragment is attached
- xmlFragment: Specifies the XML fragment

Example

- {?CreateXMLTagWithContent {$references, "<ARTREFERENCE>?</ARTREFERENCE>"}
- {?CreateXMLTagWithContent {$Submodule}, "<ARTICLE_FEATURES>? </ ARTICLE_FEATURES>"}

14.4.15 CreateXMLTagWithValue

The **CreateXMLTagWithValue** function is used to create an XML fragment based on the transferred fragment, in which the character "?" is replaced with the transferred value.

Note: If the value is blank, no tag is created. The transferred fragment itself is not encoded. In contrast to the CreateXMLTagWithContent function, no XML can be transferred in the value.

Use

```
{?CreateXMLTagWithValue "value", "xmlFragment"}
```

The individual specifications mean:

- value: Node/submodule, below which the new XML fragment is attached
- xmlFragment: Specifies the XML fragment with its content

Example

- {?CreateXMLTagWithValue{&Item properties.Unit}, "<FUNIT>?</FUNIT>"}
  - Output: “<FUNIT>kg</FUNIT>"

14.4.16 DatasetCounter

The **DatasetCounter** function returns the sequential number of the current data record.

Use

```
{?DatasetCounter}
```

The **DatasetCounter** function is used to output line numbers.

14.4.17 DatasetId

The **DatasetId** function returns the internal numerical ID of the current data record.

Use

```
{?DatasetId}
```

Example

When exporting to HTML an overview page containing a list of all items is generated. It is possible to link from this item list to a detail view for a particular item. The **DatasetId** function is used to generate the links:

- Detail view of item

14.4.18 DatasetIdentifier

The **DatasetIdentifier** function returns the alphanumeric ID of the current data record. If this is not available, the internal numerical ID is output as an alternative.

Use

```
{?DatasetIdentifier}
```

The **DatasetIdentifier** is similar to the DatasetId function, except that it uses an alphanumeric ID.

14.4.19 DateGetFirstDay

The **DateGetFirstDay** function returns the date of the first day in a period of time. If you do not specify a date, the current date is used.

Use

```
{?DateGetFirstDay "Date", "Period", "Counter[optional]"}
```

The specifications for the function have the following meaning:

- Date: The date to which the output will relate. This can be blank if the current date is to be used.
- Period: A pattern identifying the period
  a. W = Week (the first day is always a Monday)
  b. M = Month
  c. Q = Quarter
  d. Y = Year
- Counter: (optional) Specifies whether the period to be used is the period containing the specified date or a subsequent period, e. g. 1 for the immediately following period.

Example

- {?DateGetFirstDay "01.08.2006", "Q"}
  - Output: "01.07.2006"
- {?DateGetFirstDay "01.08.2006", "Q", 2}
  - Output: “01.01.2007"

14.4.20 DateGetLastDay

The **DateGetLastDay** function returns the date of the last day in a period of time. If you do not specify a date, the current date is used.

Use

```
{?DateGetLastDay "Date", "Period", "Counter[optional]"}
```

- Date: The date to which the output will relate. This can be blank if the current date is to be used.
- Period: A pattern identifying the period:
  a. W = Week (the first day is always a Monday)
  b. M = Month
  c. Q = Quarter
  d. Y = Year
- Counter (optional): Specifies whether the period to be used is the period containing the specified date or a subsequent period, e. g. 1 for the immediately following period.

Example

- {?DateGetLastDay "01.08.2006", "Q"}
  - Output: "30.09.2006"
- {?DateGetLastDay "01.08.2006", "Q", 2}
  - Output: “31.03.2007"

14.4.21 EscapeValue

The **EscapeValue** function masks all special characters in the transferred character string in line with the file format specified in the format template.

Use

```
{?EscapeValue " Character string to be masked"}
```

Example

- {?EscapeValue "groß"}
  - Output: "groß"
- {?EscapeValue "Anhänge"}
  - Output: “Anhänge"

14.4.22 ExportMime

The **ExportMime** function selects the multimedia document transferred by its document identifier for exporting the file, taking account of the additional export settings.

Use

```
{?ExportMime "Multimedia document identifier"}
```

The document identifier is a unique identifier for the document added as a file attachment.

Example

The **ExportMime** function specifies the path to the location where the standard image of the item is saved:

- <img src="{?ExportMime {&Item.Standard image(Internet image,English)}}" alt="Item image">

14.4.23 FillLeft

The **FillLeft** function is used to pad the transferred character string to the specified length to the left using the transferred character.

Use

```
{?FillLeft "Character string", Length, "Character" }
```

The specifications for the function have the following meaning:

- Character string: Text to be padded to the left

- Length: Length to which the specified text is to be padded
- Characters: Character to be used to pad the specified text to the specified length

Example

- {?FillLeft "Example text", 17, "-"}
  - Output: "-----Example text"

- {?FillLeft "Example text", 13, ":"}
  - Output: “:Example text"

14.4.24 FillRight

The **FillRight** function is used to pad the transferred character string to the specified length to the right using the transferred character.

Use

```
{?FillRight "Character string", Length, "Character" }
```

The specifications for the function have the following meaning:

- Character string: Text to be padded to the right
- Length: Length to which the specified text is to be padded
- Characters: Character to be used to pad the specified text to the specified length

Example

- {?FillRight "Example text", 17, "-"}
  - Output: "Example text-----"
- {?FillRight "Example text", 13, ":"}
  - Output: "Example text:"

14.4.25 FormatAttributeValueAsDecimal

The function tries to interpret the transferred value as a number and formats it in accordance with the specified decimal separator and number of decimal places. If the value cannot be interpreted as a number, an error is generated based on the transferred data type and mode, and a blank result or the original value is returned.

A distinction is made between the following cases:

1. Data type is numeric, e.g., floating point, decimal, integer, range
   - The value can be interpreted as a number: The value is formatted with the specified settings.
   - The value cannot be interpreted as a number: An error is generated.
2. Data type is "Character string"
   - The value can be interpreted as a number: The value is formatted with the specified settings.
   - The value cannot be interpreted as a number: In "STRICT" mode, an error is generated; otherwise, the value is returned unchanged.
3. Data type is neither numeric nor "Character string", e.g., logical value, date
   - The transferred value is returned unchanged.

Use

```
{?FormatAttributeValueAsDecimal "Data type", "Value", "Mode", "Decimal
separator", "Decimal separator output", NumberDecimalplaces}
```

The specifications for the function have the following meaning:

- Data type: The data type represented by the transferred value, e.g., "character string", "integer". A data field should normally be transferred, e.g., {&Item.Property data type}.
- Value: The value that is to be formatted. A data field should normally be transferred, e.g., {&Item.Attribute value}.
- Mode (IGNORE (default value) or STRICT): If the value is blank, the default value is used.
- Decimal separator: The decimal separator to be used to interpret the transferred value as a number; usually "," or ".". If no value is transferred, the default decimal separator from the current login information is used.
- Decimal separator output: The decimal separator to be used to format the number that is output
- Number of decimal places: The number of decimal places to be used to format the number that is output

Example

- {?FormatAttributeValueAsDecimal "Floating point", "4.42", "STRICT", ".", ",", 3}
  - Output: 4.420
- {?FormatAttributeValueAsDecimal "Character string", "4.42", "STRICT", ".", ",", 3}
  - Output: 4.420 (formatted number)
- {?FormatAttributeValueAsDecimal "Floating point", "4.42 x 5.68", "STRICT", ".", ",", 3}
  - Error output
- {?FormatAttributeValueAsDecimal "Floating point", "4.42 x 5.68", "IGNORE", ".", ",", 3}
  - Error output
- {?FormatAttributeValueAsDecimal "Character string", "4.42 x 5.68", "STRICT", ".", ",", 3}
  - Error output
- {?FormatAttributeValueAsDecimal "Character string", "4.42 x 5.68", "IGNORE", ".", ",", 3}
  - Output: 4.42 x 5.68 (unchanged value)

- {?FormatAttributeValueAsDecimal "Character string", "4.420.070", "IGNORE", ",", ",", 3}
  - Output: 4420070.000 (formatted number)
- {?FormatAttributeValueAsDecimal "Character string", "4.420.070", "IGNORE", ".", ",", 3}
  - Output: 4.420.070 (unchanged value)
- {?FormatAttributeValueAsDecimal "Character string", "4.420.070", "STRICT", ".", ",", 3}
  - Error output
- {?FormatAttributeValueAsDecimal "Character string", "4.420.070,951", "IGNORE", ",", ",", 3}
  - Output: 4420070.951 (formatted number)
- {?FormatAttributeValueAsDecimal "Character string", "4.420.070", "IGNORE", ".", ",", 3}
  - Output: 4.420.070 (unchanged value)
- {?FormatAttributeValueAsDecimal "Character string", "4.420.070", "STRICT", ".", ",", 3}
  - Error output
- {?FormatAttributeValueAsDecimal "Character string", "4.42.70", "IGNORE", ",", ",", 3}
  - Output: 4.42.70 (unchanged value)
- {?FormatAttributeValueAsDecimal "Character string", "4.42.70", "STRICT", ",", ",", 3}
  - Error output

14.4.26 FormatDate

The **FormatDate** function is used to format any date in the relevant location-specific format using a set pattern.

Use

```
{?FormatDate "Date", "Pattern" }
```

The specifications for the function have the following meaning:

- Date: Date in location-specific format
- The following input options are available for the pattern:

  a.d = Day single digit

  b.dd = Day two digit

  c.M = Month single digit

  d.MM = Month two digit

  e.yy = Year, two digits

  f. yyyy = Year, four digits

Also, any separator can be used.

Example

- {?FormatDate "2010-09-01", "dd.MM.yyyy"}
  - Output: "01.09.2010"
- {?FormatDate "01.09.2010", "d.M.yy"}

- Output: "1.9.10"
- {?FormatDate "01.09.2010", "MM/dd/yyyy"}
  - Output: "09/01/2010"

14.4.27 FormatDecimal

The **FormatDecimal** function is used to format the number to be transferred using the specified decimal separator and number of decimal places. If the transferred number has more decimal places than is specified here, the number is rounded off. If it has fewer decimal places than are specified here, zeroes are added. The function generates an error if the first parameter cannot be interpreted as a number.

Use

```
{?FormatDecimal "Number", "Decimal separator", "NumberDecimal places",
"No error[optional]"}
```

The specifications for the function have the following meaning:

- Number: Number to be formatted
- Decimal separator: Decimal separator to be used
- NumberDecimalplaces: Number of decimal places to be used
- No error (optional): If this parameter is not blank, no error is generated if the first parameter cannot be interpreted as a number.

Example

- {?FormatDecimal "1.5", ",", 2}
  - Output: "1.50"
- {?FormatDecimal "15", ".", 3}
  - Output: "15,000"
- {?FormatDecimal "1.3785", ".", 3}
  - Output: "1,378"
- {?FormatDecimal "test", ".", 3}
  - Error output

- {?FormatDecimal "test", ".", 3, "No error"}
  - No error output, i.e. blank result

14.4.28 FormatHierarchicalNumber

The **FormatHierarchicalNumber** function is used to group the 8-digit hierarchical numbers transferred into blocks of two digits and inserts the transferred separator.

Use

```
{?FormatHierarchicalNumber "Number", "Separator" }
```

The specifications for the function have the following meaning:

- Number: 8-digit hierarchical number to be broken down into blocks of two digits.
- Separator: Separator to be used to break down the specified number

Example

- {?FormatHierarchicalNumber "10203040", "-"}
  - Output: “10-20-30-40”
- {?FormatHierarchicalNumber "10203040", "."}
  - Output: "10.20.30.40"
- {?FormatHierarchicalNumber "10203040", "/"}
  - Output: “10/20/30/40”

14.4.29 FormatSimplePattern

The **FormatSimplePattern** function is used to format the transferred text based on the specifications ("pattern").

Use

```
{?FormatSimplePattern "Text", "Pattern" }
```

The specifications for the function have the following meaning:

- Text: Character string to be formatted.
- Pattern: Pattern to be used for formatting.
  a."#" stands for a character from the text in the pattern.
  b.Every other character is interpreted as a separator.

Example

- {?FormatSimplePattern "102030405060", "############"}
  - Output: "102030405060"
- {?FormatSimplePattern "102030405060", "##-##-##-##-##-##"}
  - Output: "10-20-30-40-50-60"
- {?FormatSimplePattern "102030405060", "####.##.######"}

- Output: "1020.30.405060"

14.4.30 FormatTime

The **FormatTime** function is used to format any time based on the specifications ("patterns").

Use

```
{?FormatTime "Time", "Pattern" }
```

The specifications for the function have the following meaning:

- Time: Time in location-specific format.
- The following input options are available for the pattern:

  a.h = Hours single digit (1-12 am/pm)

  b.hh = Hours two digit (1-12 am/pm)

  c.H = Hours single digit (0-23)

  d.HH = Hours two digit (0-23)

  e.m = Minutes single digit

  f. mm = Minutes two digit

  g.a = Time of day (PM/AM)

Also, any separator can be used.

Example

- {?FormatTime "20:45", "hh:mm a"}
  - Output: "08:45 PM"
- {?FormatTime "20:45", "h:mm a"}
  - Output: "8:45 PM"
- {?FormatTime "20:45", "HH:mm"}
  - Output: "20:45"

14.4.31 GetDate

The **GetDate** function returns the current date. You can format the date output using optional specifications ("pattern").

Use

```
{?GetDate "Pattern"[optional]}
```

The following input options are available for the pattern:

- d = Day single digit
- dd = Day two digit
- M = Month single digit
- MM = Month two digit

- yy = Year, two digits
- yyyy = Year, four digits

Also, any separator can be used.

Example

On the 1st day of the 9th month in 2010, the function returns:

- {?GetDate "dd.MM.yyyy"}
  - Output: "01.09.2010"
- {?GetDate "d.M.yy"}
  - Output: "1.9.2010"
- {?GetDate "yyyy-MM-dd"}
  - Output: "2010-09-01"
- {?GetDate "MM/dd/yyyy"}
  - Output: "09/01/2010"

14.4.32 GetDecimalSeparator

The **GetDecimalSeparator** function returns the decimal separator used in the current login language. By default, "." is returned if English is the login language, and "," for German.

Use

```
{?GetDecimalSeparator}
```

14.4.33 GetFirstValue

The **GetFirstValue** function returns the first value in a parameter list that is not blank.

Use

```
{?GetFirstValue "Parameter1", "Parameter2", "Parameter3"}
```

At least two parameters are expected.

The specifications for the function have the following meaning:

- Parameter1: Any expression, which is returned if it is not blank
- Parameter2: Text to be returned if Parameter1 is blank
- Parameter3: Text to be returned if Parameter1 and Parameter2 are blank

Example

- {?GetFirstValue "", "Value1", "Value2"}
  - Value1
- {?GetFirstValue "", " ", "Not blank"}
  - Not blank

14.4.34 GetTime

The **GetTime** function returns the current time. You can format the time output using optional specifications ("pattern").

Use

```
{?GetTime "Pattern" [optional] }
```

You can choose from the following format options:

- h = Hours single digit (1-12 am/pm)
- hh = Hours two digit (1-12 am/pm)
- H = Hours single digit (0-23)
- HH = Hours two digit (0-23)
- m = Minutes single digit
- mm = Minutes two digit
- a = Time of day (PM/AM)

Any separator can be used.

Example

At 14:35, the function returns:

- {?GetTime "hh:mm a"}
  - 2:35 PM
- {?GetTime "h:m"}
  - 2:35
- {?GetTime "HH:mm"}
  - 14:35

14.4.35 GetValue

The **GetValue** function returns the first parameter if it is not blank, otherwise the second parameter is returned. You can use this function to output a default value for a data field if it is blank.

Use

```
{?GetValue "Parameter 1", "Parameter 2" }
```

The specifications for the function have the following meaning:

- Parameter 1: Any expression, which is returned if the parameter is not blank
- Parameter 2: Text to be returned if Parameter1 is blank.

Example

- {?GetValue "#123456", "Not available"}
  - #123456

- {?GetValue "", "Not available"}
  - Not available

14.4.36 IfEmptyThen

The **IfEmptyThen** function returns a character string of your choice if the first parameter is blank.

Use

```
{?IfEmptyThen "Parameter 1", "Parameter 2" }
```

The specifications for the function have the following meaning:

- Parameter 1: Any character string
- Parameter 2: Text to be returned if Parameter1 is blank.

Example

- {?IfEmptyThen "#123456", "No item number available"}
  - (No output as the first parameter is not blank.)
- {?IfEmptyThen "", "No item number available"}
  - No item number available

14.4.37 IfEmptyThenNotEnc

The **IfEmptyThenNotEnc** function returns a character string of your choice if the first parameter is not blank. This character string is not encoded.

Use

```
{?IfEmptyThenNotEnc "Parameter 1", "Parameter 2"}
```

The specifications for the function have the following meaning:

- Parameter 1: Any character string
- Parameter 2: Text to be returned if Parameter1 is blank.

Example

- {?IfEmptyThenNotEnc "#123456", "No item number available"}
  - (No output as the first parameter is not blank.)
- {?IfEmptyThenNotEnc "", "No item number available"}
  - No item number available

14.4.38 IfNotEmptyThen

The **IfNotEmptyThen** function returns a character string of your choice if the first parameter is not blank.

Use

```
{?IfNotEmptyThen "Parameter 1", "Parameter 2"}
```

The specifications for the function have the following meaning:

- Parameter 1: Any character string
- Parameter 2: Text to be returned if Parameter 1 is not blank.

Example

- {?IfNotEmptyThen "#123456", "Item number available"}
  - Item number available
- {?IfNotEmptyThen "", "Item number available"}
  - (No output as the first parameter is blank.)

14.4.39 IfNotEmptyThenNotEnc

The **IfNotEmptyThenNotEnc** function returns a character string of your choice if the first parameter is not blank. This character string is not encoded.

Use

```
{?IfNotEmptyThenNotEnc "Parameter 1", "Parameter 2"}
```

The specifications for the function have the following meaning:

- Parameter 1: Any character string
- Parameter 2: Text to be returned if Parameter 1 is not blank.

Example

- {?IfNotEmptyThenNotEnc "#123456", "Item number available"}
  - Item number available
- {?IfNotEmptyThenNotEnc "", "Item number available"}
  - (No output as the first parameter is blank.)

14.4.40 IsoCodeCurrency

The **IsoCodeCurrency** function gives you the ISO code for the transferred currency.

Use

```
{?IsoCodeCurrency "Currency name"}
```

Example

- {?IsoCodeCurrency "Euro"}
  - EUR

14.4.41 IsoCodeLanguage

The **IsoCodeLanguage** function gives you the ISO code for the transferred language.

Use

```
{?IsoCodeLanguage "Language"}
```

Example

- {?IsoCodeLanguage "German"}
  - deu

14.4.42 IsoCodeTerritory

The **IsoCodeTerritory** function gives you the ISO code for the transferred region.

Use

```
{?IsoCodeTerritory "Region"}
```

Example

- {?IsoCodeTerritory "Germany"}
  - DE

14.4.43 LoopCounter

Within a loop, you can use the **LoopCounter** function to determine the current loop count (based on 0).

Use

```
{?LoopCounter}
```

The **LoopCounter** function is not used directly.

14.4.44 LowerCase

The **LowerCase** function is used to convert a character string into lower case.

Use

```
{?LowerCase "Text" }
```

Text: Character string in which all letters are to be converted into lower case

Example

- {?LowerCase "ABC"}
  - abc

- {?LowerCase "aBc"}
  - abc

14.4.45 MimeDerivateGetUNCPath

The **MimeDerivateGetUNCPath** function allows you to determine the UNC path to the original multimedia document on the MediaAsset server (Product 360 Media Manager server) for the transferred document identifier and document quality.

Use

```
{?MimeDerivateGetUNCPath "Identifier of multimedia document", Quality
of multimedia document}
```

Example

- {?MimeDerivateGetUNCPath {&Assigned items.Standard image (Internet image, English)}, "PNG"}
  - \\<Name of server>\CatalogImages\<Directory>\<File name>

14.4.46 MimeGetHtmlLink

The **MimeGetHtmlLink** function is used to generate a link that can be used for the preview in HTML files.

Use

```
{?MimeGetHtmlLink "Multimedia document identifier"}
{?MimeGetHtmlLink "Multimedia document identifier", "Multimedia
document quality"}
```

14.4.47 MimeGetUNCPath

The **MimeGetUNCPath** function allows you to determine the UNC path to the original multimedia document on the MediaAsset server (Product 360 Media Manager server) for the transferred document identifier.

Use

```
{?MimeGetUNCPath "Multimedia document identifier"}
```

Example

- {?MimeGetUNCPath {&Assigned items.Standard image (Internet image, English)}}
  - \\<Name of server>\CatalogImages\<Directory>\<File name>

14.4.48 Modulo

The **Modulo** function can be used to define two different return values using a division calculation. If the division has no remainder, "Parameter 1" is returned. If the division has a remainder, the return value is "Parameter 2".

Use

```
{?Modulo "?Value 1", "Value 2", "Parameter 1", "Parameter 2"}
```

The specifications for the function have the following meaning:

- Value 1: A whole number that is divided by the number specified in "Value 2"
- Value 2: Divisor of the number in "Value 1".
- Parameter 1: Return value (character string) if the division does not have a remainder
- Parameter 2: Return value (character string) if the division results in a remainder

Example

- {?Modulo "6", "2", "Divisible", "Not divisible"}
  - Divisible
- {?Modulo "7", "2", "Divisible", "Not divisible"}
  - Not divisible

14.4.49 NumberGet

The **NumberGet** function is used to calculate the value of an integer previously saved under the specified name, which you have generated using the NumberSet 393 or NumberIncrement 392 function.

Use

```
{?NumberGet "Name"}
```

Example

- {?NumberGet "Counter"}
  - 25

14.4.50 NumberIncrement

The **NumberIncrement** function is used to increase the value of an integer previously saved under the specified name, which you have generated using the NumberSet 393 function. If the **NumberSet** function has not previously been called up, the value of the number is set to 1. The function generates a blank return.

Use

```
{?NumberIncrement "Name", "Increment[optional]"}
```

The specifications for the function have the following meaning:

- Name: Name under which the value to be increased has been saved or is to be saved
- Increment (optional): Integer that specifies the value by which you want the number to increase; the default value is 1.

Example

- {?NumberIncrement "Data record counter", 3}
  - The value in "Data record counter" is increased by 3.

14.4.51 NumberSet

The **NumberSet** function is used to register the transferred value under the specified name. You can retrieve or change the value later using the NumberGet or NumberIncrement function. The function generates a blank return.

Use

```
{?NumberSet "Name", Value}
```

The specifications for the function have the following meaning:

- Name: Name under which the value is to be saved
- Value: Number to be saved

Example

- {?NumberSet "Counter", 1}
  - The value of "Counter" is set to 1.

14.4.52 RemoveBlanks

The **RemoveBlanks** function is used to remove all spaces from a character string.

Use

```
{?RemoveBlanks "Text" }
```

Text: Character string from which all spaces are to be removed

Example

- {?RemoveBlanks "1 2 3 4 5 6"}
  - "123456"
- {?RemoveBlanks " 500 kg "}
  - "500kg"

14.4.53 Replace

The **Replace** function is used to search a text for a particular character string and replace all occurrences of that string with a different character string of your choice. The wildcards **?** and ***** are supported.

Note: The search is case-sensitive.

Use

```
{?Replace "Text", "Search text", "Replacement text" }
```

The specifications for the function have the following meaning:

- Text: Text to be searched
- Search text: Character string for which the specified text is searched. The following wildcards can be used in the search text:
  a.? stands for any character.
  b.* stands for any character string.
  c.If you precede a wildcard with a space, this means that the subsequent character retains its original meaning.
- Replacement text: Text to be used to replace the specified search text

Example

- {?Replace "Example text", "Text", "Result"}
  ⇨ Example result
- {?Replace "Example text", "E*mple", "Result"}
  ⇨ Result text
- {?Replace "Example test", "te?t", "text"}
  ⇨ Example text

14.4.54 ReplaceUmlauts

The **ReplaceUmlauts** function converts all umlauts in a German character string into standard vowels; the "ß" character is replaced by "ss".

Use

```
{?ReplaceUmlauts "Text" }
```

Text: Character string in which all umlauts (ä, ö, ü, Ä, Ö, Ü) are to be replaced

Example

- {?ReplaceUmlauts "Kühlwasser"}
  ⇨ Kuehlwasser
- {?ReplaceUmlauts "Öl"}
  ⇨ Oel

14.4.55 SplitKeywords

The **SplitKeywords** function is used to break down the transferred character string at the separator ";". It is also possible to supplement the resulting character strings with an optional prefix or suffix.

Use

```
{?SplitKeywords "Keywords", "Prefix[optional]", "Postfix[optional]",
"Line break[optional]", MaxL[optional], MaxZ[optional]}
```

The specifications for the function have the following meaning:

- Keywords: Character string containing all keywords separated by ";"
- Prefix (optional): Text to be used before each keyword
- Postfix (optional): Text to be appended to each keyword
- Line break (optional): Specifies whether a line break is to be inserted after every keyword section
  a. 1 or true (default) activates the line break.
  b. 0 or false deactivates the line break.
- MaxL (optional): Maximum length of an individual keyword. If this length is exceeded, the keyword is truncated.
- MaxZ (optional): Maximum number of keywords to be output. If more keywords are specified, only the first of them are output and the rest are ignored.

Example

- {?SplitKeywords "keyword1;keyword2;keyword3", "<tag>", "</tag>"}
  <tag>keyword1</tag>
  <tag>keyword2</tag>
  <tag>keyword3</tag>
- {?SplitKeywords "keyword1;keyword2;keyword3", "<tag>", "</tag>", 1, 3, 1}
  <tag>key</tag>

14.4.56 SplitText

The **SplitText** function is used to create fragments of the specified length from a text and insert them into the transferred pattern. The pattern should include placeholders for the text fragments ("<TEXT>") and a continuous counter ("<NO>"). The counter itself can be padded to the left or to a specified length using a padding character.

Use

```
{?SplitText "Text", "Pattern", Fragment length, "Padding character
[optional]", Counter length[optional]"}
```

The specifications for the function have the following meaning:

- Text: The text to be broken down into fragments
- Pattern: The pattern into which the text fragments are to be incorporated; “<TEXT>" for a text fragment, "<NO>" for the text fragment counter
- Fragment length: The maximum length of an individual text fragment
- Padding character (optional): A character to be used to pad the counter to the left; only evaluated in conjunction with the counter length
- Counter length (optional): Length of the counter character string padded to the left; only evaluated along with the padding character

Example

- {?SplitText "abcde", "<NO>:<TEXT>;", 2}
  - 1:ab;2:cd;3:e
- {?SplitText "abcde", "<NO>:<TEXT>;", 2, "0", 2}
  - 01:ab;02:cd;03:e

14.4.57 SplitTextGetLineCount

The **SplitTextGetLineCount** function returns the number of lines that would be created if the specified text were to be broken down into fragments of the specified length and each fragment were to be output on a new line. As an option, you can specify how many fragments are added to each line.

Use

```
{?SplitTextGetLineCount "Text", "Fragment length", "Fragments per line [optional]"}
```

The specifications for the function have the following meaning:

- Text: Text to be broken down into fragments
- Fragment length: Maximum length of an individual text fragment
- Fragments per line (optional): Number of text fragments to appear on a line (default: 1)

Example

- {?SplitTextGetLineCount "abcde", 2}
  - 3
- {?SplitTextGetLineCount "abcde", 2, 2}
  - 2

14.4.58 StringIndexOf

The **StringIndexOf** function allows you to search within a text for the first occurrence of a particular character or character string. If the character or character string is not found in the text, the value -1 is returned.

Use

```
{?StringIndexOf "Text", "Search text", "Start position[optional]"}
```

- Text: Character string in which you want to search
- Search text: Character or text you are searching for
- Start position (optional): Optionally, you can specify the position in the text you want to start searching from.

Example

- {?StringIndexOf "This is an example text", "s"}

- Output: 4
- {?StringIndexOf "This is an example text", "S"}
  - Output: -1
- {?StringIndexOf "This is an example text", "ex"}
  - Output: 10
- {?StringIndexOf "This is an example text", "ex", 12}
  - Output: 15

14.4.59 StringIndexOfIgnoreCase

The **StringIndexOfIgnoreCase** function allows you to search within a text for the first occurrence of a particular character or character string. Differences in case are ignored. If the character or character string is not found in the text, the value -1 is returned.

Use

```
{?StringIndexOfIgnoreCase "Text", "Search text", "Start position
[optional]"}
```

- Text: Character string in which you want to search
- Search text: Character or term you are searching for
- Start position (optional): Optionally, you can specify the position in the text you want to start searching from.

Example

- {?StringIndexOfIgnoreCase "This is an EXAMPLE TEXT", "S"}
  - Output: 4
- {?StringIndexOfIgnoreCase "This is an EXAMPLE TEXT", "EX"}
  - Output: 10
- {?StringIndexOfIgnoreCase "This is an EXAMPLE TEXT", "ex", 12}
  - Output: 15

14.4.60 StringLastIndexOf

The **StringLastIndexOf** function allows you to search within a text for the last occurrence of a particular character or character string. If the character or character string is not found in the text, the value -1 is returned.

Use

```
{?StringLastIndexOf "Text", "Search text"}
```

- Text: Character string in which you want to search
- Search text: Character or term you are searching for

Example

- {?StringLastIndexOf "This is an example text", "s" }
  - Output: 17
- {?StringLastIndexOf "This is an example text", "S" }
  - Output: -1
- {?StringLastIndexOf "This is an example text", "ex"}
  - Output: 15

14.4.61 StringLastIndexOfIgnoreCase

The **StringLastIndexOfIgnoreCase** function allows you to search within a text for the last occurrence of a particular character or character string. Differences in case are ignored. If the character or character string is not found in the text, the value -1 is returned.

Use

```
{?StringLastIndexOfIgnoreCase "Text", "Search text"}
```

- Text: Character string in which you want to search
- Search text: Character or term you are searching for

Example

- {?StringIndexOfIgnoreCase "This is an EXAMPLE TEXT", "S"}
  - Output: 17
- {?StringIndexOfIgnoreCase "This is an EXAMPLE TEXT", "S"}
  - Output: 17
- {?StringIndexOfIgnoreCase "This is an EXAMPLE TEXT", "EX"}
  - Output: 15

14.4.62 StringLeftBytes

The **StringLeftBytes** function truncates a character string after the specified number of bytes, thus guaranteeing the consistency of a UTF-8 character string.

Use

```
{?StringLeftBytes "Character string", Max. number of bytes}
```

- Character string: The character string whose length is limited by the maximum number of bytes
- Max. number of bytes: The maximum number of bytes that the returned character string can have

Example

- {?StringLeftBytes "Text","3"}
  - Output: "Tex"
- {?StringLeftBytes "1€, 2€, 3€","3"}

- Output: "1"
- {?StringLeftBytes "1€, 2€, 3€","4"}
  - Output: "1€"
- {?StringLeftBytes "1€, 2€, 3€","5"}
  - Output: "1€"

14.4.63 StringLength

The **StringLength** function determines the number of characters in a character string.

Use

```
{?StringLength "Text"
```

- Text: Character string whose length is to be determined.

Example

- {?StringLength "A simple character string"}
  - Output: "26"
- {?StringLength ""}
  - Output: “0"

14.4.64 StringRemoveLinebreak

The **StringRemoveLinebreak** function removes line breaks in the specified text. As an option, you can specify that the line break should be replaced by another character string.

Use

```
{?StringRemoveLinebreak "Text with
line break", "Character string[optional]"}
```

- Text: Character string in which a line break occurs
- Character string (optional): As an option, you can specify which character string will replace the line break.

Example

- {?StringRemoveLinebreak "Hello World"}
  - Output: Hello World
- {?StringRemoveLinebreak "Hello
  World"}
  - Output: HelloWorld
- {?StringRemoveLinebreak "Hello
  World", " "}
  - Output: Hello World

14.4.65 StringTruncateAtSpace

The **StringTruncateAtSpace** function returns a number of characters from a text. The section of the text begins on the left and entire words are returned. This means that the text is truncated before the next space before or at the specified number of characters. If there are no spaces for truncating in the required number of characters, the text is truncated at the exact position specified.

Use

```
{?StringTruncateAtSpace "This is an example text containing several
spaces.", Number}
```

- Text: Character string with spaces
- Number: Number of characters to be returned

Example

- {?StringTruncateAtSpace "This is an example text containing several spaces.", 2}
  - Output: "Th"
- {?StringTruncateAtSpace "This is an example text containing several spaces.", 4}
  - Output: "This is"
- {?StringTruncateAtSpace "This is an example text containing several spaces.", 7}
  - Output: "This is"
- {?StringTruncateAtSpace "This is an example text containing several spaces.", 27}
  - Output: "This is an example text"
- {?StringTruncateAtSpace "This is an example text containing several spaces.", 50}
  - Output: "This is an example text containing several spaces."

14.4.66 Substring

The **Substring** function returns a particular section of a character string. This is specified using a start and end position, in which the number 1 represents the first character. If no end position is specified, the character string is output from the start position to the end of the original text.

Use

```
{?Substring "Text", Start position, End position }
```

The specifications for the function have the following meaning:

- Text: Character string from which a particular section is to be output
- Start position: Start position of the section to be output
- End position: End position of the section to be output

Example

- {?Substring "Example text", "9", "12"}
  - Text

14.4.67 Trim

The **Trim** function is used to remove all spaces from the beginning and end of a character string. Spaces that occur within the character string are unaffected.

Use

```
{?Trim "Text"}
```

Text: Character string from which the spaces are to be removed at the beginning and end

Example

- {?Trim " 500 kg "}
  - "500 kg"

14.4.68 UpperCase

The **UpperCase** function is used to convert a character string into upper case.

Use

```
{?UpperCase "Text" }
```

Text: Text in which all letters are to be converted into upper case

Example

- {?UpperCase "abc"}
  - ABC
- {?UpperCase "aBc"}
  - ABC

14.4.69 UpperCaseFirst

The **UpperCaseFirst** function is used to convert the first letters of all words in a character string into upper case.

Use

```
{?UpperCaseFirst "Text" }
```

Text: Text in which the first letters of all words are to be converted into upper case

Example

- {?UpperCaseFirst "abc"}
  - Abc
- {?UpperCaseFirst "Sentence to illustrate the result"}
  - Sentence To Illustrate The Result

14.4.70 ValueGet

The **ValueGet** function allows you to determine the content of a text previously saved under the specified name and created using the ValueSet function.

Use

```
{?ValueGet "Group"[optional], "Name"}
```

- Group (optional): Specifies a group
- Name: Name under which the character string is saved

Example

- {?ValueGet "Language"}
  - Output: English
- {?ValueGet "Group1", "Language"}
  - Output: English
- {?ValueGet "Group2", "Language"}
  - Output: German

14.4.71 ValueSet

The **ValueSet** function saves a text under the specified name. Existing values under the selected name are overwritten. You can either use a simple name for saving or specify a name within a group. The ValueGet function is used to retrieve the saved texts. The **ValueSet** function creates a blank return.

Use

```
{?ValueSet "Group"[optional], "Name", "Text"}
```

- Group (optional): Specifies a group
- Name: Name under which the character string is saved
- Text: Character string to be saved

Example

- {?ValueSet "Language", "German" }
  - The character string "German" is saved under the name "Language".
- {?ValueSet "Group1", "Language", "German"}
  - The character string "German" is saved under "Language" in "Group1".
- {?ValueSet "Group2", "Language", "English"}
  - The character string "English" is saved under "Language" in "Group2".

14.5 Data source reference

The available data sources are listed in the following section. After a short description of the data

source itself, its parameters are listed and explained. Data sources can have mandatory and optional parameters. While a value must always be set for a mandatory parameter, an optional parameter always has a default value, which is used if no other value is set. Data sources always have a data type, such as item. However, they may also have several sub-data types, such as attributes or purchase price.

14.5.1 Data type: Item

The following data sources are available for the **Item** data type:

- Item list 403
- Items by product assignments 406
- Changed and new items 409
- Structure group item 413

14.5.1.1 Item list

This data source outputs all items in an item assortment or an item list. No other configuration options are available.

Parameters

Parameter	Description
Catalog	This parameter contains the catalog identifier. Either the master catalog or a supplier catalog is selected as the catalog. Variables can be created for the catalog. If the catalog is in "dynamic" mode, you are provided with a list of variables.
Assortment	This mandatory parameter contains the item assortment or the list of items to be output. An item assortment can be selected from the list of available item assortments. A static item list from an item table is assigned to the relevant template using drag & drop.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Item file attachments	This sub-data type supplies all file attachment information for the current item. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. For details of exporting file attachments themselves, see the "File attachments" tab.
Item attribute values	All attribute values for the current item attribute are output, regardless of the identifier or language. Assignment of the item attributes to a structure feature is ignored; the "Feature values" sub-data type can be used here. Filtering by purpose is possible.
Attributes	All attributes of the current item are output, regardless of whether they are linked to features of structure groups. Filtering by purpose is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. Example: "Name" is selected as a mandatory field. The attribute names are to be output in German and English. Both field contents are checked and data records are only exported if they contain both a German and English name.
Purchasing information and prices	All purchasing information and purchase prices of the current item are output. Filtering by region(s) of validity, time(s) of validity, price type(s), price boundary/boundaries and currency/currencies is possible, and it is useful to specify a single supplier for this purpose.
Purchase prices (with intervals)	All purchase prices of the current item are output, together with all quantity intervals. Filtering by region(s) of validity, time(s) of validity, supplier(s), price type(s) and currency/currencies is possible, and it is useful to specify a single supplier for this purpose.
Extended logistical data	Extended logistical information, e.g. the eight-digit or 13-digit GTIN. You can filter the data by specifying the supplier or packing unit.
Free attributes	Free attributes are all attributes of the current item that are not linked to structure group features of one or more classification systems (to be specified here). Filtering by purpose is possible. As with attributes, mandatory fields can also be specified.

Sub-data type	Description
Features	In this context, features refer to all attributes of the current item that are linked to structure group features of a classification system (to be specified here). Filtering by purpose is possible. As with attributes and free attributes, mandatory fields can also be specified.
Features (with identifier)	This sub-data type can be used in the same way as the "Features" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Feature values	Like the "Item attribute values" sub-data type, this sub-data type can output all values regardless of the identifier or language. However, only those attributes that are assigned to a structure group feature are output.
Feature values (with identifier)	This sub-data type can be used in the same way as the "Feature values" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Metal surcharges	All metal surcharges for the current item are output. Filtering by metal type is possible.
Referenced items	All items referenced by the current item are output. Filtering by reference type is possible. All data fields containing the reference information, for example, the referenced object number, reference type and number, are available. The data of the referenced item can also be accessed. The item data fields of the referenced item (as for the "Item" data type) are available for this purpose. Note that the referenced items do not have to be contained in the assortment that is to be output. It may even be the case that the reference item is not contained in the master catalog, in other words, that no item data exists. However, you can also use a filter to specify that only the references contained in a particular assortment should be output.
Referenced items (filtered)	All items that are referenced by the current item and are contained in the assortment that is to be output are also output. Filtering by reference type is possible. All data fields as described above are available.
Referenced products	All products referenced by the current item are output. Filtering by reference type is possible. All data fields containing the reference information, for example, the referenced object number, reference type and number, are available.

Sub-data type	Description
	The data for the referenced products themselves can also be accessed. The product data fields for the referenced products (as for the "Product" data type) are available for this purpose. Note that the referenced products do not have to be contained in the assortment that is to be output. It may even be the case that the referenced products are not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular product assortment should be output.
Language-specific data	Provides all language-specific data.
Structure assignments	All assignments of the current item to structure groups of the specified classification system or all structure systems are output. The data fields of the assigned structure groups are also available.
Selling prices	This sub-data type supplies all selling prices for the current item. The prices must be qualified based on their quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s) and currency/currencies is possible.
Selling prices (with price bands)	This sub-data type supplies all selling prices of the current item with quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s), currency/currencies and price boundary/ boundaries is possible.
Higher-level product	The higher-level product for the current item is output. The data for the higher-level product itself can also be accessed. The product data fields (as for the "Product" data type) are available for this purpose.

14.5.1.2 Items by product assignments

This data source supplies all items assigned to products from a particular product assortment.

Parameters

Parameter	Description
Assortment	This mandatory parameter contains the product assortment or the list of products whose assigned items are to be output. A product assortment can be selected from the list of available product assortments. A static product list can be assigned to the relevant template from the ***Products #1*** view using the drag and drop function.

Parameter	Description
Update assortment	This parameter is only used for non-static product assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new products are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Item file attachments	This sub-data type supplies all file attachment information for the current item. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. For details of exporting file attachments themselves, see the “File attachments” tab.
Item attribute values	All attribute values for the current item attribute are output, regardless of the identifier or language. Assignment of the item attributes to a structure feature is ignored; the "Feature values" sub-data type can be used here. Filtering by purpose is possible.
Attributes	All attributes of the current item are output, regardless of whether they are linked to features of structure groups. Filtering by purpose is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. Example: "Name" is selected as a mandatory field. The attribute names are to be output in German and English. Both field contents are checked and data records are only exported if they contain both a German and English name.
Purchasing information and prices	All purchasing information and purchase prices of the current item are output. Filtering by region(s) of validity, time(s) of validity, price type(s), price boundary/boundaries and currency/currencies is possible, and it is useful to specify a single supplier for this purpose.
Purchase prices (with intervals)	All purchase prices of the current item are output, together with all quantity intervals. Filtering by region(s) of validity, time(s) of validity, supplier(s), price type(s) and currency/currencies is possible, and it is useful to specify a single supplier for this purpose.

Sub-data type	Description
Extended logistical data	Extended logistical information, e.g. the eight-digit or 13-digit GTIN. You can filter the data by specifying the supplier or packing unit.
Free attributes	Free attributes are all attributes of the current item that are not linked to structure group features of one or more classification systems (to be specified here). Filtering by purpose is possible. As with attributes, mandatory fields can also be specified.
Features	In this context, features refer to all attributes of the current item that are linked to structure group features of a classification system (to be specified here). Filtering by purpose is possible. As with attributes and free attributes, mandatory fields can also be specified.
Features (with identifier)	This sub-data type can be used in the same way as the "Features" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Feature values	Like the "Item attribute values" sub-data type, this sub-data type can output all values regardless of the identifier or language. However, only those attributes that are assigned to a structure group feature are output.
Feature values (with identifier)	This sub-data type can be used in the same way as the "Feature values" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Metal surcharges	All metal surcharges for the current item are output. Filtering by metal type is possible.
Referenced items	All items referenced by the current item are output. Filtering by reference type is possible. All data fields containing the reference information, for example, the referenced object number, reference type and number, are available. The data of the referenced item can also be accessed. The item data fields of the referenced item (as for the "Item" data type) are available for this purpose. Note that the referenced items do not have to be contained in the assortment that is to be output. It may even be the case that the reference item is not contained in the master catalog, in other words, that no item data exists. However, you can also use a filter to specify that only the references contained in a particular assortment should be output.

Sub-data type	Description
Referenced items (filtered)	All items that are referenced by the current item and are contained in the assortment that is to be output are also output. Filtering by reference type is possible. All data fields as described above are available.
Referenced products	All products referenced by the current item are output. Filtering by reference type is possible. All data fields containing the reference information, for example, the referenced object number, reference type and number, are available. The data for the referenced products themselves can also be accessed. The product data fields for the referenced products (as for the "Product" data type) are available for this purpose. Note that the referenced products do not have to be contained in the assortment that is to be output. It may even be the case that the referenced products are not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular product assortment should be output.
Language-specific data	Provides all language-specific data.
Structure assignments	All assignments of the current item to structure groups of the specified classification system or all structure systems are output. The data fields of the assigned structure groups are also available.
Selling prices	This sub-data type supplies all selling prices for the current item. The prices must be qualified based on their quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s) and currency/currencies is possible.
Selling prices (with price bands)	This sub-data type supplies all selling prices of the current item with quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s), currency/currencies and price boundary/ boundaries is possible.
Higher-level product	The higher-level product for the current item is output. The data for the higher-level product itself can also be accessed. The product data fields (as for the "Product" data type) are available for this purpose.

14.5.1.3 Changed and new items

This data source supplies all items changed or created within an assortment after a certain date. The "Last change" and "Created on" item data are evaluated for this purpose.

All item data fields released are available. All data fields that can be qualified must be fully qualified.

Parameters

Parameter	Description
Catalog	This parameter contains the catalog identifier. Either the master catalog or a supplier catalog is selected as the catalog. Variables can be created for the catalog. If the catalog is in "dynamic" mode, you are provided with a list of variables.
Assortment	This parameter contains an item assortment or a list of items. An item assortment can be selected from the list of available item assortments. A static item list from an item view is assigned to the relevant template using drag & drop.
Reference date	The reference date is a mandatory parameter. This is the date on which the change or creation took place, and which serves as a basis for the search.
Type of change	You can use this mandatory parameter to specify which type of item changes are to be taken into account. The following values are available: • Changed items All items that belong to the specified item assortment and were changed after the specified reference date • New items All items that belong to the specified item assortment and were created after the specified reference date • Changed and new items All items that belong to the specified item assortment and were changed or created after the specified reference date
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Item file attachments	This sub-data type supplies all file attachment information for the current item. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. For details of exporting file attachments themselves, see the "File attachments" tab.
Item attribute values	All attribute values for the current item attribute are output, regardless of the identifier or language. Assignment of the item attributes to a structure feature is ignored; the "Feature values" sub-data type can be used here. Filtering by purpose is possible.
Attributes	All attributes of the current item are output, regardless of whether they are linked to features of structure groups. Filtering by purpose is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. Example: "Name" is selected as a mandatory field. The attribute names are to be output in German and English. Both field contents are checked and data records are only exported if they contain both a German and English name.
Purchasing information and prices	All purchasing information and purchase prices of the current item are output. Filtering by region(s) of validity, time(s) of validity, price type(s), price boundary/boundaries and currency/currencies is possible, and it is useful to specify a single supplier for this purpose.
Purchase prices (with intervals)	All purchase prices of the current item are output, together with all quantity intervals. Filtering by region(s) of validity, time(s) of validity, supplier(s), price type(s) and currency/currencies is possible, and it is useful to specify a single supplier for this purpose.
Extended logistical data	Extended logistical information, e.g. the eight-digit or 13-digit GTIN. You can filter the data by specifying the supplier or packing unit.
Free attributes	Free attributes are all attributes of the current item that are not linked to structure group features of one or more classification systems (to be specified here). Filtering by purpose is possible. As with attributes, mandatory fields can also be specified.

Sub-data type	Description
Features	In this context, features refer to all attributes of the current item that are linked to structure group features of a classification system (to be specified here). Filtering by purpose is possible. As with attributes and free attributes, mandatory fields can also be specified.
Features (with identifier)	This sub-data type can be used in the same way as the "Features" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Feature values	Like the "Item attribute values" sub-data type, this sub-data type can output all values regardless of the identifier or language. However, only those attributes that are assigned to a structure group feature are output.
Feature values (with identifier)	This sub-data type can be used in the same way as the "Feature values" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Metal surcharges	All metal surcharges for the current item are output. Filtering by metal type is possible.
Referenced items	All items referenced by the current item are output. Filtering by reference type is possible. All data fields containing the reference information, for example, the referenced object number, reference type and number, are available. The data of the referenced item can also be accessed. The item data fields of the referenced item (as for the "Item" data type) are available for this purpose. Note that the referenced items do not have to be contained in the assortment that is to be output. It may even be the case that the reference item is not contained in the master catalog, in other words, that no item data exists. However, you can also use a filter to specify that only the references contained in a particular assortment should be output.
Referenced items (filtered)	All items that are referenced by the current item and are contained in the assortment that is to be output are also output. Filtering by reference type is possible. All data fields as described above are available.
Referenced products	All products referenced by the current item are output. Filtering by reference type is possible. All data fields containing the reference information, for example, the referenced object number, reference type and number, are available.

Sub-data type	Description
	The data for the referenced products themselves can also be accessed. The product data fields for the referenced products (as for the "Product" data type) are available for this purpose. Note that the referenced products do not have to be contained in the assortment that is to be output. It may even be the case that the referenced products are not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular product assortment should be output.
Language-specific data	Provides all language-specific data.
Structure assignments	All assignments of the current item to structure groups of the specified classification system or all structure systems are output. The data fields of the assigned structure groups are also available.
Selling prices	This sub-data type supplies all selling prices for the current item. The prices must be qualified based on their quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s) and currency/currencies is possible.
Selling prices (with price bands)	This sub-data type supplies all selling prices of the current item with quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s), currency/currencies and price boundary/ boundaries is possible.
Higher-level product	The higher-level product for the current item is output. The data for the higher-level product itself can also be accessed. The product data fields (as for the "Product" data type) are available for this purpose.

14.5.1.4 Structure group item

This data source outputs all items assigned to the specified structure groups. You have the option of using an item assortment to filter the output. In this case, the output only includes items that belong to the item assortment and are assigned to the structure groups.

Parameters

Parameter	Description
Structure group list	Only items assigned to one of the structure groups on this list are output. This structure group list is assigned to the relevant template from a structure group table using the drag and drop function.

Parameter	Description
Catalog	This parameter contains the catalog identifier. Either the master catalog or a supplier catalog is selected as the catalog. Variables can be created for the catalog. If the catalog is in "dynamic" mode, you are provided with a list of variables.
Assortment	You can specify an item assortment to be used as a filter criterion. In this case, only items belonging to the specified assortment are output.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Item file attachments	This sub-data type supplies all file attachment information for the current item. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. For details of exporting file attachments themselves, see the “File attachments” tab.
Item attribute values	All attribute values for the current item attribute are output, regardless of the identifier or language. Assignment of the item attributes to a structure feature is ignored; the "Feature values" sub-data type can be used here. Filtering by purpose is possible.
Attributes	All attributes of the current item are output, regardless of whether they are linked to features of structure groups. Filtering by purpose is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. Example: "Name" is selected as a mandatory field. The attribute names are to be output in German and English. Both field contents are checked and data records are only exported if they contain both a German and English name.

Sub-data type	Description
Purchasing information and prices	All purchasing information and purchase prices of the current item are output. Filtering by region(s) of validity, time(s) of validity, price type(s), price boundary/boundaries and currency/currencies is possible, and it is useful to specify a single supplier for this purpose.
Purchase prices (with intervals)	All purchase prices of the current item are output, together with all quantity intervals. Filtering by region(s) of validity, time(s) of validity, supplier(s), price type(s) and currency/currencies is possible, and it is useful to specify a single supplier for this purpose.
Extended logistical data	Extended logistical information, e.g. the eight-digit or 13-digit GTIN. You can filter the data by specifying the supplier or packing unit.
Free attributes	Free attributes are all attributes of the current item that are not linked to structure group features of one or more classification systems (to be specified here). Filtering by purpose is possible. As with attributes, mandatory fields can also be specified.
Features	In this context, features refer to all attributes of the current item that are linked to structure group features of a classification system (to be specified here). Filtering by purpose is possible. As with attributes and free attributes, mandatory fields can also be specified.
Features (with identifier)	This sub-data type can be used in the same way as the "Features" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Feature values	Like the "Item attribute values" sub-data type, this sub-data type can output all values regardless of the identifier or language. However, only those attributes that are assigned to a structure group feature are output.
Feature values (with identifier)	This sub-data type can be used in the same way as the "Feature values" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Metal surcharges	All metal surcharges for the current item are output. Filtering by metal type is possible.
Referenced items	All items referenced by the current item are output. Filtering by reference type is possible. All data fields containing the reference information, for example, the referenced object number, reference type and number, are available.

Sub-data type	Description
	The data of the referenced item can also be accessed. The item data fields of the referenced item (as for the "Item" data type) are available for this purpose. Note that the referenced items do not have to be contained in the assortment that is to be output. It may even be the case that the reference item is not contained in the master catalog, in other words, that no item data exists. However, you can also use a filter to specify that only the references contained in a particular assortment should be output.
Referenced items (filtered)	All items that are referenced by the current item and are contained in the assortment that is to be output are also output. Filtering by reference type is possible. All data fields as described above are available.
Referenced products	All products referenced by the current item are output. Filtering by reference type is possible. All data fields containing the reference information, for example, the referenced object number, reference type and number, are available. The data for the referenced products themselves can also be accessed. The product data fields for the referenced products (as for the "Product" data type) are available for this purpose. Note that the referenced products do not have to be contained in the assortment that is to be output. It may even be the case that the referenced products are not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular product assortment should be output.
Language-specific data	Provides all language-specific data.
Structure assignments	All assignments of the current item to structure groups of the specified classification system or all structure systems are output. The data fields of the assigned structure groups are also available.
Selling prices	This sub-data type supplies all selling prices for the current item. The prices must be qualified based on their quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s) and currency/currencies is possible.
Selling prices (with price bands)	This sub-data type supplies all selling prices of the current item with quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s), currency/currencies and price boundary/ boundaries is possible.
Higher-level product	The higher-level product for the current item is output.

Sub-data type	Description
	The data for the higher-level product itself can also be accessed. The product data fields (as for the "Product" data type) are available for this purpose.

14.5.2 Data type: Units

The following data sources are available for the **Units** data type:

- All units in the unit system 417

14.5.2.1 All units in the unit system

This data source outputs all units of a unit system. All data fields of units are available, for example, Code, Name, Symbol.

Parameter: Unit system

This mandatory parameter is assigned the unit system whose units are to be output.

14.5.3 Data type: Deleted relationships

The following data sources are available for the **Deleted relationships** data type:

- Deleted item references 417
- Deleted product references 418
- Deleted assignments of items to Media Assets 419
- Deleted assignments of items to products 419
- Deleted assignments of items to structure groups 420
- Deleted assignments of products to Media Assets 420
- Deleted assignments of products to structure groups 421
- Deleted assignments of structure groups to Media Assets 422

14.5.3.1 Deleted item references

This data source outputs all deleted item references for the existing items in a catalog. The item references can optionally be filtered by a delete date, i.e. only those references deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these appear in the table below.

Parameters

Parameter	Description
Date	Optional delete date entry

Parameter	Description
Catalog	This parameter contains the catalog identifier. Either the master catalog or a supplier catalog is selected as the catalog. Variables can be created for the catalog. If the catalog is in "dynamic" mode, you are provided with a list of variables.
Assortment	This parameter contains an item assortment or a list of items. An item assortment can be selected from the list of available item assortments. A static item list from an item view is assigned to the relevant template using drag & drop.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.3.2 Deleted product references

This data source outputs all deleted product references for the existing products in a catalog. The product references can optionally be filtered by a delete date, i.e. only those references deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these appear in the table below.

Parameters

Parameter	Description
Date	Optional delete date entry
Assortment	This parameter contains a product assortment or a list of products. A product assortment can be selected from the list of available product assortments. A static product list can be assigned to the relevant template from a product table using the drag & drop function.
Update assortment	This parameter is only used for non-static product assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new products are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.3.3 Deleted assignments of items to Media Assets

This data source outputs all deleted assignments of items to media assets for the existing items in a catalog. The assignments can optionally be filtered by a delete date, i.e. only those assignments deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these appear in the table below.

Parameters

Parameter	Description
Date	Optional delete date entry
Catalog	This parameter contains the catalog identifier. Either the master catalog or a supplier catalog is selected as the catalog. Variables can be created for the catalog. If the catalog is in "dynamic" mode, you are provided with a list of variables.
Assortment	This parameter contains an item assortment or a list of items. An item assortment can be selected from the list of available item assortments. A static item list from an item view is assigned to the relevant template using drag & drop.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.3.4 Deleted assignments of items to products

This data source outputs all deleted assignments of items to products for the existing items. The assignments can optionally be filtered by a delete date, i.e. only those assignments deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these appear in the table below.

Parameters

Parameter	Description
Date	Optional delete date entry
Assortment	This parameter contains an item assortment or a list of items. An item assortment can be selected from the list of available item assortments. A static item list from an item view is assigned to the relevant template using drag & drop.

Parameter	Description
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.3.5 Deleted assignments of items to structure groups

This data source outputs all deleted assignments of items to structure groups for the existing items in a catalog. The assignments can optionally be filtered by a delete date, i.e. only those assignments deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these appear in the table below.

Parameters

Parameter	Description
Date	Optional delete date entry
Catalog	This parameter contains the catalog identifier. Either the master catalog or a supplier catalog is selected as the catalog. Variables can be created for the catalog. If the catalog is in "dynamic" mode, you are provided with a list of variables.
Assortment	This parameter contains an item assortment or a list of items. An item assortment can be selected from the list of available item assortments. A static item list from an item view is assigned to the relevant template using drag & drop.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.3.6 Deleted assignments of products to Media Assets

This data source outputs all deleted assignments of products to Media Assets for the existing products. The assignments can optionally be filtered by a delete date, i.e. only those assignments deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these appear in the table below.

Parameters

Parameter	Description
Date	Optional delete date entry
Assortment	This parameter is only used for non-static product assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new products are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.3.7 Deleted assignments of products to structure groups

This data source outputs all deleted assignments of products to structure groups for the existing products. The assignments can optionally be filtered by a delete date, i.e. only those assignments deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these appear in the table below.

Parameters

Parameter	Description
Date	Optional delete date entry
Assortment	This parameter is only used for non-static product assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new products are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.3.8 Deleted assignments of structure groups to Media Assets

This data source outputs all deleted assignments of structure groups to Media Assets for the existing structure groups in a structure. The assignments can optionally be filtered by a delete date, i.e. only those assignments deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these appear in the table below.

Parameters

Parameter	Description
Date	Optional delete date entry
Structure	The structure system for which the deleted assignments for structure groups are to be displayed is assigned to this mandatory parameter.
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.4 Data type: Deleted objects

The following data sources are available for the **Deleted objects** data type:

- Deleted items
- Deleted Media Assets
- Deleted products
- Deleted structure groups

14.5.4.1 Deleted items

This data source outputs all deleted items from a catalog. The items can optionally be filtered by a delete date, i.e. only those items deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these appear in the table below.

Parameters

Parameter	Description
Catalog	This parameter contains the catalog identifier. Either the master catalog or a supplier catalog is selected as the catalog. Variables can be created for the catalog. If the catalog is in "dynamic" mode, you are provided with a list of variables.
Date	Optional delete date entry
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.4.2 Deleted Media Assets

This data source outputs all deleted media assets in the system. The media assets can optionally be filtered by a delete date, i.e. only those media assets deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these are described below.

Parameter: Date

This parameter can be used to specify an optional delete date.

14.5.4.3 Deleted products

This data source outputs all deleted products. The products can optionally be filtered by a delete date, i.e. only those products deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these are described below.

Parameters

Parameter	Description
Date	Optional delete date entry
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.4.4 Deleted structure groups

This data source outputs all deleted structure groups from a structure system. The structure groups can optionally be filtered by a delete date, i.e. only those structure groups deleted after this date will be exported. There are no sub-data types for this data source. Only a limited choice of data fields is available, and these are described below.

Parameters

Parameter	Description
Structure	This mandatory parameter is assigned the unit system whose structure group data is to be output.
Date	Optional delete date entry
Version	This parameter contains the version to be used for output. If no entry is specified, the data from all versions is output.

14.5.5 Data type: Customer

The following data sources are available for the **Customer** data type:

- Customers 424

14.5.5.1 Customers

This data source supplies a list of all customers. All data fields for customers are available, for example Name, Code. This data source has no parameters or sub-data types.

14.5.6 Data type: Supplier

The following data sources are available for the **Supplier** data type:

- Suppliers 424

14.5.6.1 Suppliers

As with the "Customers" data source 424 the data source supplies a list of all suppliers. All supplier data fields are provided and no additional configuration options are available.

14.5.7 Data type: Media Assets

The following data sources are available for the **Media Assets** data type:

- Media Assets 424

14.5.7.1 Media Assets

This data source outputs all media assets in the system.

Parameter: Date

If an optional date is specified, only the media assets changed after that date are exported.

Sub-data types: Multimedia documents

This sub-data type can be filtered by quality or language.

14.5.8 Data type: Product

The following data sources are available for the **Product** data type:

- Changed and new products 424
- Products by item assignments 428
- Product list 431
- Structure group products 434

14.5.8.1 Changed and new products

This data source supplies all the products changed or created within an assortment after a certain date. The "Last change in version" product data is evaluated for this purpose.

All the released product data fields are available. All the data fields that can be qualified must be fully qualified.

Parameters

Parameter	Description
Assortment	This mandatory parameter contains a product assortment or a list of products. You can select a product assortment from the list of available product assortments. A static product list can be assigned to the relevant template from a product table using the drag & drop function.
Reference date	The reference date is a mandatory parameter. This is the date when the change or creation took place and serves as a basis for the search.
Type of change	You can use this mandatory parameter to specify the type of changes that are to be taken into account. The following values are available: • Changed products. All products that belong to the specified assortment were changed after the specified reference date. • New products. All products that belong to the specified assortment were created after the specified reference date. • Changed and new products. All products that belong to the specified assortment were changed or created after the specified reference date.
Include Subordinate Item References	This mandatory parameter allows you to specify whether to include the products that did not change, but certain child items were added to them or removed from them. The following values are available: • Yes. Includes products belonging to the specified assortment with modified subordinate item references. • No. Does not include any products with modified subordinate item references.
Include Subordinate Item Content	This mandatory parameter allows you to specify whether to include the products that did not change, but the content of the child items was updated. The following values are available: • Yes. Includes products belonging to the specified assortment with modified subordinate item content. • No. Does not include any products with modified subordinate item content.
Update assortment	This parameter is only used for non-static product assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new products are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.

Parameter	Description
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Attributes	All product attributes of the current product are output, regardless of whether they are linked to features of structure groups. Filtering by purpose is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. Example: "Name" is selected as a mandatory field. Both field contents are checked and data records are only exported if they contain both a German and English name.
Free attributes	Free attributes are all attributes of the current product that are not linked to structure group features of one or more classification systems (to be specified here). Filtering by purpose is possible. As with attributes, mandatory fields can also be specified.
Features	In this context, features refer to all attributes of the current product that are linked to structure group features of a classification system (to be specified here). Filtering by purpose is possible.
Features (with identifier)	This sub-data type can be used in the same way as the "Features" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Feature values	Like the "Product attribute values" sub-data type, this sub-data type can output all values regardless of the identifier or language. However, only those attributes that are assigned to a structure group feature are output.
Feature values (with identifier)	This sub-data type can be used in the same way as the "Feature values" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.

Sub-data type	Description
Product file attachments	All file attachments assigned to the current product are output. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. For details of exporting file attachments themselves, see the "File attachments" tab.
Product attribute values	All attribute values for the current product attribute are output, regardless of the identifier or language. Assignment of the product attributes to a structure feature is ignored; the "Feature values" sub-data type can be used here. Filtering by purpose is possible.
Product references	All items and products referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. Data for the referenced objects themselves cannot be accessed.
Referenced items	All items referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. The data of the referenced item can also be accessed. The item data fields of the referenced item (as for the "Item" data type) are available for this purpose. Note that the referenced items do not have to be contained in the assortment that is to be output. It may even be the case that the referenced item is not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular item assortment should be output.
Referenced products	All products referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. The data for the referenced products themselves can also be accessed. The product data fields for the referenced products (as for the "Product" data type) are available for this purpose. Note that the referenced products do not have to be contained in the assortment that is to be output. It may even be the case that the referenced products are not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular assortment should be output.

Sub-data type	Description
Referenced products (filtered)	All products that are referenced by the current product and are contained in the assortment that is to be output are also output. Filtering by reference type is possible. All data fields as described above are available.
Language-specific data	Provides all language-specific data.
Structure assignments	All assignments of the current product to structure groups of the specified classification system or all structure systems are output. The data fields of the assigned structure groups are also available.
Variants	All items assigned to variants of the current product are output. The item data fields for the variants are available, as for the "Item" data type.
Selling prices	This sub-data type supplies all selling prices for the current product. The prices must be qualified based on their quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s) and currency/currencies is possible.
Selling prices (with price bands)	This sub-data type supplies all selling prices for the current product with quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s), currency/currencies and price boundary/ boundaries is possible.

14.5.8.2 Products by item assignment

This data source supplies all products assigned to items in an item assortment, i.e. for which there are variants in the specified item assortment.

All released product data fields are available. All data fields that can be qualified must be fully qualified.

Parameters

Parameter	Description
Item assortment	This mandatory parameter contains an item assortment or a list of items for which the higher-level products are to be output. An item assortment can be selected from the list of available master catalog item assortments. A static item list can be assigned to the relevant template from an item view using the drag & drop function.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.

Parameter	Description
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Attributes	All product attributes of the current product are output, regardless of whether they are linked to features of structure groups. Filtering by purpose is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. Example: "Name" is selected as a mandatory field. Both field contents are checked and data records are only exported if they contain both a German and English name.
Free attributes	Free attributes are all attributes of the current product that are not linked to structure group features of one or more classification systems (to be specified here). Filtering by purpose is possible. As with attributes, mandatory fields can also be specified.
Features	In this context, features refer to all attributes of the current product that are linked to structure group features of a classification system (to be specified here). Filtering by purpose is possible.
Features (with identifier)	This sub-data type can be used in the same way as the "Features" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Feature values	Like the "Product attribute values" sub-data type, this sub-data type can output all values regardless of the identifier or language. However, only those attributes that are assigned to a structure group feature are output.
Feature values (with identifier)	This sub-data type can be used in the same way as the "Feature values" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.

Sub-data type	Description
Product file attachments	All file attachments assigned to the current product are output. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. For details of exporting file attachments themselves, see the “File attachments” tab.
Product attribute values	All attribute values for the current product attribute are output, regardless of the identifier or language. Assignment of the product attributes to a structure feature is ignored; the "Feature values" sub-data type can be used here. Filtering by purpose is possible.
Product references	All items and products referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. Data for the referenced objects themselves cannot be accessed.
Referenced items	All items referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. The data of the referenced item can also be accessed. The item data fields of the referenced item (as for the "Item" data type) are available for this purpose. Note that the referenced items do not have to be contained in the assortment that is to be output. It may even be the case that the referenced item is not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular item assortment should be output.
Referenced products	All products referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. The data for the referenced products themselves can also be accessed. The product data fields for the referenced products (as for the "Product" data type) are available for this purpose. Note that the referenced products do not have to be contained in the assortment that is to be output. It may even be the case that the referenced products are not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular assortment should be output.

Sub-data type	Description
Referenced products (filtered)	All products that are referenced by the current product and are contained in the assortment that is to be output are also output. Filtering by reference type is possible. All data fields as described above are available.
Language-specific data	Provides all language-specific data.
Structure assignments	All assignments of the current product to structure groups of the specified classification system or all structure systems are output. The data fields of the assigned structure groups are also available.
Variants	All items assigned to variants of the current product are output. The item data fields for the variants are available, as for the "Item" data type.
Selling prices	This sub-data type supplies all selling prices for the current product. The prices must be qualified based on their quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s) and currency/currencies is possible.
Selling prices (with price bands)	This sub-data type supplies all selling prices for the current product with quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s), currency/currencies and price boundary/ boundaries is possible.

14.5.8.3 Product list

This data source outputs all products from a product assortment or a product list. No other configuration options are available.

Parameters

Parameter	Description
Assortment	This mandatory parameter contains the product assortment or the list of products to be output. A product assortment can be selected from the list of available product assortments. A static product list can be assigned to the relevant template from the ***Products*** view using the drag and drop function.
Update assortment	This parameter is only used for non-static product assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new products are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Attributes	All product attributes of the current product are output, regardless of whether they are linked to features of structure groups. Filtering by purpose is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. Example: "Name" is selected as a mandatory field. Both field contents are checked and data records are only exported if they contain both a German and English name.
Free attributes	Free attributes are all attributes of the current product that are not linked to structure group features of one or more classification systems (to be specified here). Filtering by purpose is possible. As with attributes, mandatory fields can also be specified.
Features	In this context, features refer to all attributes of the current product that are linked to structure group features of a classification system (to be specified here). Filtering by purpose is possible.
Features (with identifier)	This sub-data type can be used in the same way as the "Features" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Feature values	Like the "Product attribute values" sub-data type, this sub-data type can output all values regardless of the identifier or language. However, only those attributes that are assigned to a structure group feature are output.
Feature values (with identifier)	This sub-data type can be used in the same way as the "Feature values" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Product file attachments	All file attachments assigned to the current product are output. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. For details of exporting file attachments themselves, see the “File attachments” tab.
Product attribute values	All attribute values for the current product attribute are output, regardless of the identifier or language. Assignment of the product attributes to a structure feature is ignored; the "Feature values" sub-data type can be used here. Filtering by purpose is possible.

Sub-data type	Description
Product references	All items and products referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. Data for the referenced objects themselves cannot be accessed.
Referenced items	All items referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. The data of the referenced item can also be accessed. The item data fields of the referenced item (as for the "Item" data type) are available for this purpose. Note that the referenced items do not have to be contained in the assortment that is to be output. It may even be the case that the referenced item is not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular item assortment should be output.
Referenced products	All products referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. The data for the referenced products themselves can also be accessed. The product data fields for the referenced products (as for the "Product" data type) are available for this purpose. Note that the referenced products do not have to be contained in the assortment that is to be output. It may even be the case that the referenced products are not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular assortment should be output.
Referenced products (filtered)	All products that are referenced by the current product and are contained in the assortment that is to be output are also output. Filtering by reference type is possible. All data fields as described above are available.
Language-specific data	Provides all language-specific data.
Structure assignments	All assignments of the current product to structure groups of the specified classification system or all structure systems are output. The data fields of the assigned structure groups are also available.

Sub-data type	Description
Variants	All items assigned to variants of the current product are output. The item data fields for the variants are available, as for the "Item" data type.
Selling prices	This sub-data type supplies all selling prices for the current product. The prices must be qualified based on their quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s) and currency/currencies is possible.
Selling prices (with price bands)	This sub-data type supplies all selling prices for the current product with quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s), currency/currencies and price boundary/ boundaries is possible.

14.5.8.4 Structure group products

This data source outputs all products in a product assortment that are assigned to the specified structure groups. The structure groups can be assigned using drag & drop. No other configuration options are available.

Parameters

Parameter	Description
Structure group list	Only items assigned to one of the structure groups on this list are output. This structure group list is assigned to the relevant template from a structure group table using the drag and drop function.
Assortment	You can specify an item assortment to be used as a filter criterion. In this case, only items belonging to the specified assortment are output.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Attributes	All product attributes of the current product are output, regardless of whether they are linked to features of structure groups. Filtering by purpose is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. Note that all fields are checked. Example: "Name" is selected as a mandatory field. Both field contents are checked and data records are only exported if they contain both a German and English name.
Free attributes	Free attributes are all attributes of the current product that are not linked to structure group features of one or more classification systems (to be specified here). Filtering by purpose is possible. As with attributes, mandatory fields can also be specified.
Features	In this context, features refer to all attributes of the current product that are linked to structure group features of a classification system (to be specified here). Filtering by purpose is possible.
Features (with identifier)	This sub-data type can be used in the same way as the "Features" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Feature values	Like the "Product attribute values" sub-data type, this sub-data type can output all values regardless of the identifier or language. However, only those attributes that are assigned to a structure group feature are output.
Feature values (with identifier)	This sub-data type can be used in the same way as the "Feature values" sub-data type. The difference here is that the "Attribute value" data field contains the identifier of the feature rather than its value, provided it is a structure preset value. If this does not exist, the field contains the value of the feature.
Product file attachments	All file attachments assigned to the current product are output. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. For details of exporting file attachments themselves, see the “File attachments” tab.
Product attribute values	All attribute values for the current product attribute are output, regardless of the identifier or language. Assignment of the product attributes to a structure feature is ignored; the "Feature values" sub-data type can be used here. Filtering by purpose is possible.

Sub-data type	Description
Product references	All items and products referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. Data for the referenced objects themselves cannot be accessed.
Referenced items	All items referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. The data of the referenced item can also be accessed. The item data fields of the referenced item (as for the "Item" data type) are available for this purpose. Note that the referenced items do not have to be contained in the assortment that is to be output. It may even be the case that the referenced item is not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular item assortment should be output.
Referenced products	All products referenced by the current product are output. Filtering by reference type is possible. All data fields containing the reference information (for example, the referenced object number, reference type and number) are available. The data for the referenced products themselves can also be accessed. The product data fields for the referenced products (as for the "Product" data type) are available for this purpose. Note that the referenced products do not have to be contained in the assortment that is to be output. It may even be the case that the referenced products are not contained in the master catalog, in other words, that no product data exists. However, you can also use a filter to specify that only the references contained in a particular assortment should be output.
Referenced products (filtered)	All products that are referenced by the current product and are contained in the assortment that is to be output are also output. Filtering by reference type is possible. All data fields as described above are available.
Language-specific data	Provides all language-specific data.
Structure assignments	All assignments of the current product to structure groups of the specified classification system or all structure systems are output. The data fields of the assigned structure groups are also available.

Sub-data type	Description
Variants	All items assigned to variants of the current product are output. The item data fields for the variants are available, as for the "Item" data type.
Selling prices	This sub-data type supplies all selling prices for the current product. The prices must be qualified based on their quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s) and currency/currencies is possible.
Selling prices (with price bands)	This sub-data type supplies all selling prices for the current product with quantity intervals. Filtering by region(s) of validity, time(s) of validity, customer(s), price type(s), currency/currencies and price boundary/ boundaries is possible.

14.5.9 Data type: Structure

The following data sources are available for the **Structure** data type:

- Structure system

14.5.9.1 Structure system

The "Structure system" data source outputs the assigned structure system. The data fields for structure systems are available, including Name and Description, as well as the unit and structure features and preset value list for the structure system. This data source does not output the system's structure groups. To do this, you require the specified structure group data sources.

Parameter

Parameter	Description
Structure system	You assign the structure system to be used for the output to this mandatory parameter.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Units	The list of all units assigned to the structure system is output. All data fields for units are available.
Structure features	The list of structure features comprises all features of the structure to be output, regardless of their assignment to structure groups.
Structure preset values	For this list, you can access the names and document identifiers of the structure preset values, for example.

Sub-data type	Description
Structure feature preset values	The list of preset values for the structure features can be filtered by mandatory fields or preset value.

14.5.10 Data type: Structure group

The following data sources are available for the **Structure group** data type:

- All groups in structure system (with item filter) 438
- All groups in structure system (with product filter) 440
- Changed and new structure groups of a structure system 442
- Structure group list 443
- Structure sub-tree 444

14.5.10.1 All groups in structure system (with item filter)

This data source outputs a list of all groups in the selected structure system. You can filter the list by specifying an item assortment. In this case, only groups containing items that are assigned to the specified assortment are output. The structure groups can be sorted in the output and output of the root node can be suppressed.

Parameters

Parameter	Description
Structure system	This mandatory parameter is assigned the unit system whose structure group data is to be output.
Catalog	This parameter contains the catalog identifier. Either the master catalog or a supplier catalog is selected as the catalog. Variables can be created for the catalog. If the catalog is in "dynamic" mode, you are provided with a list of variables.
Item assortment (filter)	A list of items can be assigned to this optional parameter for filtering the groups in the structure system. If an item list is assigned, structure groups are only output if they are assigned to items from the list or are contained in a subtree that contains subordinate structure groups with assigned items. This filtering works the same way as the "Show only groups containing items" function in the structure tree.
Root node output options	This parameter specifies the use of the root node of the structure. The root node represents the highest node in the structure. It is not displayed in the structure tree and, in many cases, is not required for output. The following options are supported:

Parameter	Description
	• No root node The root node of the structure is not output. • Root node conforming to BMEcat The root node is output manipulated in the following way: Document identifier equals "1", parent identifier equals "0", parent identifier for all referencing structure groups equals "1". • Root node unchanged The data for the root node of the structure is output without any changes. If no setting is made here, the root node is output without any changes.
Sorting of structure groups	With this optional parameter, you specify whether the structure groups are to be sorted in the same sequence in which they are displayed in the tree. The default value is "no".
Filter structure groups	Here you can set whether structure groups are only to be output if items (specified in the "Item assortment (filter)" parameter) have been assigned to them. This parameter is only evaluated if the "Item assortment (filter)" parameter has a value. The default value is "no", i.e. all structure groups are output if items have been assigned to them or if they are higher-level nodes of such structure groups.
Update assortment	This parameter is only used for non-static item assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new items are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Item	All items assigned to the current structure group are output. This list of items can be restricted using the value for the "Item assortment (filter)" parameter. All item data fields are available.
Group features	All features assigned to the current structure group are output.
Group feature preset values	All preset values assigned to the current structure group are output. Filtering by purpose, feature name or preset value is possible.

Sub-data type	Description
Group feature values	All feature values for the current structure group are output, regardless of identifier or language. Filtering by purpose, identifier, feature name or language is possible.
Language-specific data	Provides all language-specific data.
Structure group file attachments	All file attachments assigned to the current structure group are output. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. For details of exporting file attachments themselves, see the “File attachments” tab.
Structure assignments	List of structure groups to which assignments exist. Filtering by the structure system is possible.
Subordinate structure groups	All structure group data fields are available for the list of subordinate structure groups for the current structure group.
Subordinate structure groups (filtered)	All subordinate structure groups from the current structure group are displayed that contain items from the assortment specified in the "Item assortment (filter)" parameter. All data fields described above are available.

14.5.10.2 All groups in structure system (with product filter)

This data source outputs a list of all groups in the selected structure system. You can filter the list by specifying a product assortment. In this case, only groups containing products that are assigned to the specified assortment are output. The structure groups can be sorted in the output and output of the root node can be suppressed.

Parameters

Parameter	Description
Structure system	This mandatory parameter is assigned the unit system whose structure group data is to be output.
Product assortment (filter)	This optional parameter can be set for a product assortment for filtering the groups in the structure system. If a product assortment is assigned, structure groups are only output if products are assigned to them or they are contained in a subtree that contains subordinate structure groups with assigned products.
Root node output options	This parameter specifies the use of the root node of the structure. The root node represents the highest node in the structure. It is not displayed in the structure tree and, in many cases, is not required for output. The following options are supported:

Parameter	Description
	• No root node The root node of the structure is not output. • Root node conforming to BMEcat The root node is output manipulated in the following way: Document identifier equals "1", parent identifier equals "0", parent identifier for all referencing structure groups equals "1". • Root node unchanged The data for the root node of the structure is output without any changes. If no setting is made here, the root node is output without any changes.
Sorting of structure groups	With this optional parameter, you specify whether the structure groups are to be sorted in the same sequence in which they are displayed in the tree. The default value is "no".
Filter structure groups	Here you make a setting to determine whether structure groups are only to be output if products (specified in the "Product assortment (filter)" parameter) have been assigned to them. This parameter is only evaluated if the "Product assortment (filter)" parameter has a value. The default value is "no", i.e. all structure groups are output if items have been assigned to them or if they are higher-level nodes of such structure groups.
Update assortment	This parameter is only used for non-static product assortments. Here you specify whether the assigned assortment is to be updated immediately before output. Note that new products are only included in the assortment after it is updated. If you do not set a value here, the assortment is not updated.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Group features	All features assigned to the current structure group are output.
Group feature preset values	All preset values assigned to the current structure group are output. Filtering by purpose, feature name or preset value is possible.
Group feature values	All feature values for the current structure group are output, regardless of identifier or language. Filtering by purpose, identifier, feature name or language is possible.

Sub-data type	Description
Products	All products assigned to the current structure group are output. This list of products can be restricted using the value for the "Product assortment (filter)" parameter. All item data fields are available.
Language-specific data	Provides all language-specific data.
Structure group file attachments	All file attachments assigned to the current structure group are output. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. For details of exporting file attachments themselves, see the “File attachments” tab.
Structure assignments	List of structure groups to which assignments exist. Filtering by the structure system is possible.
Subordinate structure groups	All structure group data fields are available for the list of subordinate structure groups for the current structure group.
Subordinate structure groups (filtered)	All subordinate structure groups from the current structure group are output that contain products from the assortment specified in the "Product assortment (filter)" parameter. All data fields as described above are available.

14.5.10.3 Changed and new structure groups of a structure system

This data source supplies all structure groups in a structure system that were changed or created after a certain date. The "Last change in version" field is evaluated for this purpose.

Parameters

Parameter	Description
Structure system	This mandatory parameter is assigned the unit system whose structure group data is to be output.
Reference date	The reference date is a mandatory parameter. This is the date on which the change or creation took place, and which serves as a basis for the search.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Group features	All features assigned to the current structure group are output.

Sub-data type	Description
Group feature preset values	All preset values assigned to the current structure group are output. Filtering by purpose, feature name or preset value is possible.
Group feature values	All feature values for the current structure group are output, regardless of identifier or language. Filtering by purpose, identifier, feature name or language is possible.
Language-specific data	Provides all language-specific data.
Structure group file attachments	All file attachments assigned to the current structure group are output. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. For details of exporting file attachments themselves, see the "File attachments" tab.
Structure assignments	List of structure groups to which assignments exist. Filtering by the structure system is possible.
Subordinate structure groups	All structure group data fields are available for the list of subordinate structure groups for the current structure group.

14.5.10.4 Structure group list

This data source outputs all assigned structure groups. No additional configuration options are available.

Parameters

Parameter	Description
Structure groups	The list of structure groups to be output is assigned from a structure group table to a template using the drag & drop function.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Group features	All features assigned to the current structure group are output.
Group feature preset values	All preset values assigned to the current structure group are output. Filtering by purpose, feature name or preset value is possible.
Group feature values	All feature values for the current structure group are output, regardless of identifier or language. Filtering by purpose, identifier, feature name or language is possible.
Language-specific data	Provides all language-specific data.

Sub-data type	Description
Structure group file attachments	All file attachments assigned to the current structure group are output. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. For details of exporting file attachments themselves, see the “File attachments” tab.
Structure assignments	List of structure groups to which assignments exist. Filtering by the structure system is possible.
Subordinate structure groups	All structure group data fields are available for the list of subordinate structure groups for the current structure group.
Assigned items	All items of the master catalog assigned to the current structure group are output.

14.5.10.5 Structure sub-tree

This data source outputs all structure groups below the specified structure group. Output of the root node can be suppressed.

Parameters

Parameter	Description
Structure system	This mandatory parameter is assigned the unit system whose structure group data is to be output.
Identifier of the root structure group	Identifier or hierarchical number of the structure group from which the sub-tree is to be output.
With root node	Specifies whether the root structure group itself will also be output.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data types

Sub-data type	Description
Group features	All features assigned to the current structure group are output.
Group feature preset values	All preset values assigned to the current structure group are output. Filtering by purpose, feature name or preset value is possible.
Group feature values	All feature values for the current structure group are output, regardless of identifier or language. Filtering by purpose, identifier, feature name or language is possible.
Language-specific data	Provides all language-specific data.

Sub-data type	Description
Structure group file attachments	All file attachments assigned to the current structure group are output. Filtering by quality, language and type is possible. It is also possible to specify mandatory fields: All data records that do not contain a value for the specified mandatory fields are not output. For details of exporting file attachments themselves, see the "File attachments" tab.
Structure assignments	List of structure groups to which assignments exist. Filtering by the structure system is possible.
Subordinate structure groups	All structure group data fields are available for the list of subordinate structure groups for the current structure group.

14.5.11 Data type: Selling discount groups

The following data sources are available for the **Selling discount groups** data type:

- All selling discount groups

14.5.11.1 All selling discount groups

A list of all selling discount groups filtered by customer (to be specified here) can be output. All discount group data fields are available.

Parameters

Parameter	Description
Customer	This optional parameter specifies the customer for which the discount group list is to be output. If a customer is not specified, a list of all available discount groups is returned.
Version	This mandatory parameter contains the version that is to be used for output. If you do not specify a version here, the working version is used by default.

Sub-data type: Selling discount rates

All selling discount rates for the current selling discount group are output. Filtering by the validity date is possible.

14.6 Glossary

Item

An item in the narrow sense is the specific instance of a product.

Attribute

The properties of an item or product that are not described by features of classification systems are referred to as attributes.

Users

A user is an actual person who uses a software system. A user can work with a software system after being authenticated, i.e. logging in to the system by entering the user name and valid password.

BMEcat

XML-based standard format for transferring electronic product catalogs.

CMP

Cross-media publishing of content based on media-neutral data.

CRM

Customer Relationship Management; CRM systems are used for storing and evaluating customer information centrally.

CSV

CSV = comma separated value, text file format. CSV is a simple data exchange format, where each line contains a data record, i.e. the individual data records are separated by line breaks. The individual fields in a data record are separated by a defined character, for example, a comma or semicolon.

Datanorm

A standard procedure for the exchange of item and master data published by the Datanorm working group for suppliers of the installation and building trade; item numbers, item names, and pricing conditions are read in by Datanorm and can then be forwarded electronically.

Data field

The master catalog contains data objects (data records) of a particular data type, for example the "Item" data type. A data type provides data fields for data content, e.g. the "Item" data type has the data fields "Item number", "Manufacturer", etc.

There are both simple data fields and data fields that can be qualified. A qualified data field must be specified in more detail with additional settings. For example, this is the case for language-specific data fields, where an item can have a short description in German or English.

Data source

A data source provides particular data fields. The data fields that can be selected depend on the data source's data type and sub-data types. When the export is performed, the data source provides the data to be exported.

The data source can be defined in more detail using parameters. For example, the "Item list" data source supplies the "Item number" data field and the "Attributes" sub-data type.

Data type

A data type expresses the data category for a data source, a variable or parameter of a data source or a post-export step. Each data source, variable and parameter has a single data type. Data types include: Customers, Suppliers, Selling discount groups, Structure groups and Structure system.

DMS

Document Management System

DUNS® number

Dun & Bradstreet identification number; DUNS® stands for "Data Universal Numbering System".

EANCOM®

Standard for electronic data interchange, which is derived from the official UN/EDIFACT standard and is used worldwide in the consumer goods industry.

eClass, eCl@ss

Structure system

EDI

Electronic Data Interchange.

EDIFACT

Electronic Data Interchange for Administration, Commerce and Transport; international, cross-industry standard for the format of electronic data in commerce.

Eldanorm

Eldanorm is structured like Datanorm, but this standard is used specifically in the electrical trade.

Entity

The term "entity" (or information object) is used in data modeling to describe a uniquely identifiable object that is to be used to store or process information. This object may be tangible or intangible, concrete or abstract. The properties of entities are mapped as attributes. Attributes are used to distinguish between entities with an identical entity type.

EPC

Electronic Product Code in RFID technology; based on the EAN standard; also common: EPC/RFID. EPC/RFID.

ERP system

ERP = Enterprise Resource Planning; ERP systems are extensive merchandise management systems for corporate management that are designed to use capital, equipment and/or personnel resources in the most efficient way.

ETIM

(Electro Technical Information Model) is a classification scheme that is supported jointly by a cooperation of industry, the wholesale trade and craft trade in the "electrical" sector.

GLN

International designation: Global Location Number

GPC

International classification system: Global Product Classification

GTIN

International designation for EAN: Global Trade Item Number

Manufacturer

A company that manufactures products or has them manufactured.

Catalog

In the broadest sense, the term "catalog" refers to objects that are available in printed form (print catalog) or electronic form (file, database) in an enormous range of formats. These objects always contain data about the catalog itself, for example, a catalog name and item data as well as other information that helps to group or structure the data, e.g. material group systems.

In more precise terms, the term catalog refers to the database object as distinct from the catalog file, which represents the source for importing or the target for exporting a catalog that is stored in a database.

Catalog format

The format of a catalog refers to the file format. Accordingly, the format does not relate to the catalog itself but to the catalog file. Examples include BMEcat, XLS, CSV, xCBL, cXML, Datanorm.

Catalog identifier

Unique, language-independent designation for identifying the catalog in Product 360 Desktop. The catalog identifier corresponds to the CATALOG_ID field in BMEcat.

Catalog name

Language-specific name of the catalog.

Buyer

For the purposes of Product 360 Desktops, the term buyer is defined by the fact that catalogs are transferred between a supplier and buyer in one direction only, namely from the supplier to the buyer. If you receive a catalog from your supplier, as an Product 360 Desktop operator you are the buyer. However, if you supply a catalog to your customer, the customer is the buyer and you are the supplier.

Classification system

See Structure system

Classification

The assignment of an object (item) to a structure system.

Supplier

Business partner who supplies you with merchandise. The supplier provides you with a catalog of his items.

Supplier catalog

Catalog from your supplier, see also Master catalog.

MAM

Media Asset Management: Management system for multimedia data that can be provided as visual item descriptions

Feature

In a classification system, features are standardized identifiers for properties that are to be defined for all products or items in a classification group to ensure comparability.

ODETTE

Organisation for Data Exchange by Tele Transmission in Europe: a subset of EDIFACT for data exchange via FTP servers.

openTRANS

An XML-based transaction standard; it can be regarded as complementing the catalog exchange format BMEcat.

PDM

Product Data Management

PIM

Product Information Management

Product

An output commodity. In commercial terms, a product is the result of a preceding transformation process, i.e. production.

Master catalog

The master catalog contains a dealer's complete and enhanced assortment, some or all of which is available for various purposes. Selected items from the supplier and manufacturer are imported into the master catalog. The master catalog supplies the e-catalogs and publications with current data.

proficl@ss

Classification in the "construction and tools" and "sanitation/heating/air conditioning" sectors.

PZN

Central pharmaceutical number.

RFID

Radio frequency identification technology for identification purposes.

RosettaNet

The XML-based RosettaNet standard is mainly aimed at automating supply chain management in the information technology, telecommunications, electronic components, logistics and semiconductor production sectors.

Assortment

The master catalog contains the complete assortment, which is typically not completely available in e-catalogs and publications. Assortments are used to define a subset of a catalog.

Language

A catalog can include data in one or more languages. Not all the data associated with an item is language-specific. Language-specific data consists primarily of text information such as the designation, the description, and keywords.

A catalog file can only include data in one language; an extra file must be added to include the data for each additional language.

Structure system

A structure system can be used to divide items into structured classes. There are standard structure systems such as eClass and UNSPSC, but you can also develop and use custom structure systems.

UNSPSC

United Nations Standard Products and Services Code is classification that comes from North America.

Workflow

A workflow is a collection of tasks organized in such a way that the processing of these tasks corresponds to a business process. A task can either be executed by a user, a user group or a system. The workflow specifies not only the tasks but also the sequence in which or the conditions under which they are processed.

XML

XML = Extensible Markup Language. XML is a text file format in which data records and entities are identified using markups. A markup element has opening and closing markers ("tags"). These markers are typically short texts identified by angle brackets, with a forward slash preceding the name of the closing markup.

Example: <family name>Hoover</family name>

Complex data structures can be created by skilled nesting of the markups. For more information about the XML standard, visit http://www.w3c.org/XML/.

Index

- A -

Action rights 246
  Assign 246
Administrator 259
Alternative language 280
Assignment
  Create 49, 51
  Duplicate node 51
Assignment recommendation 127, 128
Assortment 152
  Assigning a products 149
  Assigning items 149
  Copy 151
  Create 148
  Delete 151
  dynamic 147, 149
  explicit 147
  Item 147
  Manage 151
  Media Attachment 151
  New 148
  Object rights 151
  Product 147
  static 149
  Version 151
Assortment filter
  Activate 150
  Deactivate 150
Attribute
  Assign to structure feature 111
  Attribute assignments 111
  Preset value 111
Attribute assignment (items) 109
Automatic import
  Configuration 72
  Create groups 75
  Deactivate 72
  Define groups 75
  Error mode 72
  File sample 72
  Group assignment 72
  Groups 75
  Import mode 72
  Time limit 75
  Waiting time 75

- B -

BMEcat
  ART_ID 69
  ARTICLE_DETAILS 66
  ARTICLE_PRICE_DETAILS 67
  CATALOG_GROUP_ID 69
  DESCRIPTION_SHORT 66
  FNAME 68
  FVALUE 68
  GROUP_ID 69
  GROUP_SYSTEM_ID 69
  MIME_INFO 67
  MIME_PURPOSE 67
  MIME_SOURCE 67
  MIME_TYPE 67
  PARENT_ID 69
  PRICE_AMOUNT 67
  PRICE_CURRENCY 67
  REFERENCE_FEATURE_GROUP_ID 68
  SUPPLIER_AID 66
  TERRITORY 67

- C -

Catalog
  Create 45
  Delete 45
  Edit 45
  Electronic 264
  Header data 45
  Manage 45
  New 61
  Set default catalog 90
Classification 122
Classification mapping 129
client 18
  Preferences 255
Comment 267
Company data 242
Compare
  Item 156
  Product 156
Comparison view 156
Content 53
Context selection 90
Customer 44
  Create 46
  Delete 46
  Edit 46
  Manage 46

- D -

Data
- Create new 33
- Customer-specific 108
- Export 285
- Input 33
- Load 31
- Save 33

Data field 267, 274
- Qualified 280, 281

Data fields
- Export error classification 296
- Validation rules 296

Data maintenance 85

Data quality
- Accuracy 161
- Completeness 161
- Comprehensibility 161
- Consistency 161
- Correctness 161
- Definition 161
- Freedom from redundancy 161
- Relevance 161
- Reliability 161
- Unambiguity 161
- Uniformity 161
- Up-to-datedness 161

Data quality checks
- Overview 176

Data source 48, 266, 402
- All groups in structure system (with product filter) 440
- Customers 424
- Definition 272
- Deleted assignments of items to Media Assets 419
- Deleted assignments of items to products 419
- Deleted assignments of items to structure groups 420
- Deleted assignments of products to Media Assets 420
- Deleted assignments of products to structure groups 421
- Deleted assignments of structure groups to Media Assets 422
- Deleted item references 417
- Deleted items 422
- Deleted Media Assets 423
- Deleted product references 418
- Deleted products 423
- Deleted structure groups 423
- Discount groups: all selling discount groups 445
- Item list 403
- Item: changed and new items 409
- Item: Structure group item 413
- Items by product assignments 406
- Media Assets 424
- Parameter 295
- Product list 431
- Products: Changed and new products 424
- Select 272, 273
- Structure group list 443
- Structure groups: All groups in structure system (with item filter) 438
- Structure groups: Changed and new structure groups of a structure system 442
- Structure sub-tree 444
- Structure system 437
- Suppliers 424
- Units: All units in the unit system 417

Data transfer 90

Description
- Item 105
- Structure group 105

Details 54

Dictionaries
- Action rights 85
- Import 87
- Maintain entries 87

Discount groups 132, 140
- Assign object rights 141
- Create 141

Discount rates 140
- Create 140

Document category 77
- Add category 183
- Add subcategory 183
- Copy 183
- Create preview images 183
- Delete 183
- Insert 183
- New 183
- Rename 183
- Update 183

Documents 179
- Open 187
- Show unused 187
- Show used 187

- E -

E-mail notification
- Configure 223

E-mail notification
Create 223
Delete 223
Manage 223
Preview 223
E-mail templates
Configure 224
Create 224
ETL process
Definition 161
Explorer (items) 98
Export 264
CSV 270
Edit 330
Export immediately 319
Format mapping table 312
One-off 268
Perform 290
Plan output 279
Repeat 330
Repeated 268
Repetition interval 324
Repetition pattern 325
Result 291
Schedule 317
Schedule export (once) 322
Schedule export (repeating) 323
Test export 276
Export file 267, 291, 300
Check 286
Download 82, 330
Format 277
header 287
Multiple 287
Select 288
Export format template 264, 266, 313
Category 309
Character set 294
Check 308
Create 270, 279, 291
Data fields 293, 296
Data sources 293, 295
Delete 309
Export 310
File attachments 293, 301
File management 293, 300
Format mapping table 294
Import 311
Log 294
Manage 309
Module 291
New 291
Object limitation 291
Object rights 309
Output format 294
Post-processing 293, 302
Prevalidate 328
Preview function 294
Properties 272, 287, 293
Purpose 309
Save 291
Settings 293, 294
Time limitation 291
Variables 293, 296
Export module
Editing options 265
Perspective 265
Export operations 82
Export parameters 266, 276, 284, 290, 313
Edit 316
Export principle 268
Export profile 266
Category 315
Create 284, 290, 313
Delete 317
Edit 316
Manage 315
New 313
Object rights 315
Rename 316
Save 284, 290, 313
Select 317
Temporary 276
Export profiles 90
Export series
Exit 330
Repetition interval 323
Repetition pattern 323
Scheduling information 330

- F -

Feature
Add 214
Overwrite 214
Replace completely 214
Field details 58
Field filter
Use 37
Field rights
Assign 246
Qualified 247
Field selection 35

Fields
Filter 62
hide 62
Qualification 36
Find and Replace 106
Frequency 54
Function 267
BMEcatDataType 369
BMEcatMediaAssetQuality 370
BMEcatMediaAssetType 370
BMEcatPriceType 370
BMEcatReferenceType 371
Calculate 371
Compare 372
CompareBooleanValue 372
CompareDate 373
CompareIgnoreCase 373
CompareNumeric 374
Concat 357, 374
Conditional output 360
CreateCDataSection 375
CreateXMLTagWithContent 375
CreateXMLTagWithValue 375
DatasetCounter 376
DatasetId 376
DatasetIdentifier 376
date 358
DateGetFirstDay 377
DateGetLastDay 377
defaultBoolean 358
defaultDate 358
defaultNumber 359
defaultString 359
delete 359
Delete blank field 359
Delete field 359
deleteIfEmpty 359
Determine character string length 361
Determine text position 365
EscapeValue 378
ExportMime 378
FillLeft 378
FillRight 277, 380
format 360
Format in lower case 362
FormatAttributeValueAsDecimal 380
FormatDate 382
FormatDecimal 383
FormatHierarchicalNumber 384
FormatSimplePattern 384
FormatTime 385
Formatting in upper case 367
GetDate 385
GetDecimalSeparator 386
GetFirstValue 386
GetTime 387
GetValue 387
if 360
IfEmptyThen 388
IfEmptyThenNotEnc 388
IfNotEmptyThen 388
IfNotEmptyThenNotEnc 389
Import 55
IsoCodeCurrency 389
IsoCodeLanguage 389
IsoCodeTerritory 390
left 361
length 361
Link values 357
logError 361
logInfo 362
logWarning 362
LoopCounter 390
lower 362
LowerCase 390
mid 363
MimeDerivateGetUNCPath 391
MimeGetHtmlLink 391
MimeGetUNCPath 391
Modulo 391
NumberGet 392
NumberIncrement 392
NumberSet 393
Output default text 359
Output error message 361
Output info message 362
Output logical value 358
Output preset date 358
Output preset number 359
Output warning message 362
Reference 356, 367
RemoveBlanks 393
Replace 363, 393
Replace character string 363
ReplaceUmlauts 394
right 364
round 364
Round value 360
Round value down 364
Round value up 364
search 365
select 366

Function 267
Set date format 358
Show left section of character string 361
Show middle section of character string 363
Show right section of character string 364
SplitKeywords 394
SplitText 395
SplitTextGetLineCount 396
StringIndexOf 396
StringIndexOfIgnoreCase 397
StringLastIndexOf 397
StringLastIndexOfIgnoreCase 398
StringLeftBytes 398
StringLength 399
StringRemoveLinebreak 399
StringTruncateAtSpace 400
Substring 400
Trim 401
truncate 366
Truncate decimal places 366
upper 367
UpperCase 401
UpperCaseFirst 401
Value selection 366
ValueGet 402
ValueSet 402

- G -

Grouping 39
Save 41

- H -

Hotfolder 70
Perspective 71
System defaults 76

- I -

Ignore rules 176
Image
Delete 191
Download 189, 191
Open 191
Properties 189, 191
Rename 191
Usage list 191
View 189
Import 44, 48, 49
Add data source 62
Assign item number 63
Automatic 43, 70
BMEcat 65, 66, 67, 68, 69
Create assignment 51, 63, 66, 67, 68, 69
CSV 60
Duplicate node 63, 69
Excel 60, 61, 62, 63
Function 55
Item attributes 63, 68
Manage data sources 62
Material group structure 69
Multimedia attachments 67
Schedule 43, 64
Selecting the language 66
Start 64
Structure assignments 68, 69
Structured data 65
Table data 60
Test import 64
Import function
select 68
Import processes 82
Import project 48
Create 49
Download 82
New 49, 61, 65
Open 47
Initial classification 123
Input wizard 274
Interface visibilities
Assign 245
Introductory example 270
Creating an export format template 270
Multiple output files 286
Qualified data field 278
Sub-modules 286
Use variable 278
Item
Arrangement by assortment 99
Assign discount group 140
Assign multimedia document 196
Attribute 114, 288
Change 103
Change assignment 124
Change structure group 124
Classify 120, 122, 123
Clone 99, 102
Compare 99, 156
Copy 99, 102
Create 101
Delete 99, 102
Delete assignment 125
Delete product assignment 144

Item
Edit 97
Edit descriptions 103
Import 66
Import assignment 126
Link multimedia files 194
Maintain 85, 103
Merge 78
Multiple assignment 124
Multiple classification 127, 128
New 101
Object rights 99
Price 135
Properties 99
Purchase price 134
Save 101
Search 90
Setting object rights 102
Show assigned products 99
Show assigned structure groups 126
Status 104
Structure group 126
Tasks 99
Version 153
Versioning 99
Item attribute 109, 114
Assign structure feature 125
Assign to structure feature 110
Attribute value 109, 112
Change 112
Create 109, 112
Create automatically 125
Cumulative 112
Data type 109
Delete 109
Delete assignment 110, 125
Edit 109
Import 68
Language-independent 109
Multiple values 112
New 109, 112
Output 281
Purpose 109
Unit 109, 110
Item attributes 120
Assign to structure feature 111
Unit 111
Item comparison
Master catalog 116
Supplier catalog 116
Item details
Form 103

- L -

Licenses
Manage 245
Log 59, 64, 308, 330

- M -

Main supplier 115
Mapping 47, 66
Create 51
Import 51
Load 51
Save 51
Mapping template
Import 49
Load 49
Mappings
Category 47
Create 47
Delete 47
Manage 47
Object rights 47
Purpose 47
Save 47
Save as file 47
Master catalog 78, 90, 122
Classify 129
Material group structure
Import 69
Media Asset Manager 180
Menu
dynamic 20
Merge 78
catalog-specific 80
global 80
Schedule 81
Setting 79, 80
Simulation 79
Merge mode
Add 80, 257
Ignore 80, 257
Overwrite 80, 257
Replace 80, 257
Merge preview 79
Merge processes
Selecting items in the master catalog 82
Metal surcharge 139
MIME 181
MIME data
Assign 181

MIME data
Check 181
Compare 181
Convert 181
Copy 181
Edit 181
Manage 181
Miniature view 190
Miniature view (documents) 191
Module
Create 273, 304
Edit 274, 307
New 304
Output header 279
Output item data 280
Processing 268
Properties 273, 304, 305
Sorting 305
Module editor 274
Input wizard 307
Multimedia archive 267
Multimedia attachment 181
Assign 67
Change 195
Create 194
Edit 195
Export 301
New 194, 196
Overwrite 194
Multimedia attachments 179
Create 188
New 188
System 189
Multimedia data 179, 200
Add 77
Advanced search 193
Displaying changes automatically 196
Image preview 180
Link 194
Link automatically 198
Manage 183
Management systems 180
Media portal integration 180
Miniature view 180
Search 192
System settings 180
Updating changes 197
Multimedia data search
Simple search 192
Multimedia document 188, 189
Assign 195
Change 195
Copy 196
Delete 199
External 196
Multimedia file
Copy 190
Download 190
Export 302
Open 190
Properties 190
Show items 190
Show structure groups 190
Multimedia links 77
Multiple assignment 124
Multiple classification 128
Import 129
Multiple classification (items) 127

- N -

Natural Language Processing
Definition 161

- O -

Object right types
Individual 249
Inherited 249
System 249
Object rights
Create 251
Delete 248, 251
Edit 251
Full access 248
Inheritance 249, 251
New 251
Read 248
System 251
Version 249
Write 248
Organization 242

- P -

Packaging costs 138
Password
Change 253
Perspective 19, 21
Adapt 24
Adapt menu 26
Create your own 24
Open 24
Perspectives

Perspectives
Overview 21
PIM 16
Pop-up menu
Filter 39
Post-export step 268
Copy export file 302
Execute command file 302
File attachment export 302
Supplier Exchange 302
Validate XML file(s) 302
Preferences
Default values 255
Image preview 257
Import settings 257
Item attributes 256
Item classification 257
Merge preview 257
Miniature view 258
Multimedia attachments 258
Products 258
Structure editor 258
Structures – Basic settings 259
Table settings 255
Users 255
Preview
of items 157
of products 157
of structure groups 157
Preview function
Call up 157
Detail view 157
Limitation 157
Multiple selection 157
Price 132
Change 135, 136
Compare 137
Create 135
Currency 133
Edit 135
Import 67
New 135
Price tier 133
Purchase price 133
Selling price 133
Type 133
Validity 136
Validity period 133
Price change 137
Price surcharge 132
Check 138
Maintain 138
Packaging costs 138
Surcharge calculation 138
Process overview 48, 82, 330
Update modification date 196
Processes
Data maintenance 82
Data transfer 82
Log 82
System processes 82
Product
Assign item 144
Classify 120
Compare 156
Create 143
Create reference 145
Create structure assignment 144
Creating a multimedia attachment 146
Creating assortments 143
Delete reference 145
Edit 143
Import 143
Maintain 85
New 143
Referenced items 141
Search 90, 143
Version 153
Product attributes 120
Create 147
Delete 147
Edit 147
Purpose 147
Product data 264
Product details
Form 147
Product Information Management 16
Product references 145
Program interface 19
Properties 251
Purchase price 132, 133
Change 134
Create 134
Purchasing discount groups 141
Purchasing discount rates 140
Purchasing info record (EKI) 115

- Q -

Qualified field rights
Assign 247
Quality check
Determining the status 176

Quality check
Editing options 328
layout 328
Overview 328
Quality checks 161
Configure 164
Create 164
Create new channel 172
Creating your own fields 164
Event driven 170
Perform 175
Removing field assignments 164
Schedule 170
Specify channel 172
Specify conditions 172
Time based 170
Quality rules
Overview 162
Perspective 162

- R -

Reference data
Adding from a file 164, 167
Import 167
Maintain 167
References
Create manually 117
Drag & drop 117
Item 117
Product 117
Repository 62
Rights 246
Assign 246
Rights group 246
Audit Trail 336
Catalogs 339
Channel 339
Company management 345
Customers 340
Data quality 337
Dictionaries 347
Discount groups 343
Document management 337
E-mail templates 337
Export 338
General 334
Import 339
Item 334
Item assortments 335
Item search 335
Merge 340
Multimedia attachments 341
Predefined queries 346
Process planning 342
Product assortments 341
Product search 342
Products 341
Qualified field rights 342
Structure features 344
Structure group search 344
Structure groups 343
Structure preset values 345
Structures 343
Suppliers 340
System messages 345
Task notifications 336
Tasks 336
Text features 345
Units 338
Users 336
Versions 346
Workflow 347
Rights groups
for action rights 333
for interface visibilities 348, 354
Rights management 242
Rule category 164
Rule group 164
Rules
Adding from a file 164

- S -

Search
Call up 93
editing 93
Item 93
Manage 93
Phrase search 192
Product 93
Save 93
Stop words 192
Structure group 93
Wildcard search 192
Wildcards 192
Selling discount groups 141
Selling discount rates 140
Selling price 132, 133
Customers 135
Point in time 135
Price type 135
server 18
Settings

Settings
Import settings 48
Merge preview 80
Structure system 121
Spellchecking
Activate 88
Basic principles 85
Deactivate 88
in single-line fields 88
in the text editor 88
Modes 85
Parameter 88
Settings 88
Use 88
Standardization dictionaries
Create 167
Delete 167
Import 167
Maintain 167
Synchronize 167
Status 104
Structure assignment
Delete 125
Import 68
Structure editor 76
Structure feature 120
Attribute type 208
Create 209, 210
Data type 208
Delete 210
Edit 210
Multiple values 208, 210
New 209
Preset value 210
Purpose 208
Sequence 210
Transfer as item attributes 113
Unit 111, 208
Structure group
Assign multimedia data 200
Change sequence 205
Create 205, 207
Delete 206
Description 206
Feature 208, 210, 288
Hierarchical number 207
Inherit feature 214
Maintain feature 114
Move 203
New 205, 207
Rename 206
Subordinate 205, 207
Structure group assignments
Create 130
Delete 130
Source structure 130
Target structure 130
Structure group feature
Create preset value 211
Delete preset value 211
Manage 210
Multiple values 212
Structure group name
Set display 95
Structure preset value 209, 210
Create 209
Delete 209
New 209
Structure system 123, 124
Change language 202
Copy 215
Copy subtree 215
Create 76, 204
Default 201
Edit 201
Feature 125
Hidden groups 76
Hierarchical number 206
Import 76
New 204
Object rights 208
Open 202, 203
Properties 204
User-defined 76, 201
Structure tree
Navigate 95, 202
Primary 202
Search 95, 202
Secondary 202
Sub-module 304
Consistency check 305
Create 289
Data source 289
Reference 290
Supplier 44
Supplier catalog 44, 122
Merge 78
Supplier relationship 115
Create 115
Delete 115
Suppliers
Create 44

Suppliers
Delete 44
Edit 44
Manage 44
Surcharge
Based on jump 139
Metal 139
Packaging costs 138
System message 259
Activate 261
Create 260
Deactivate 261
Edit 261
New 260

- T -

Table 31
Add columns 35
Arrange columns 36
Change sequence 36
Changing the column width 37
Field qualification 36
Filter 37, 39
Group 39
Remove columns 35
Rename column 36
Save CSV 41
Save layout 42
Sort 34
Versioning 155
Task
accepted 219
Assign task group 221
Assigning to users 222
Create 217
Create in task group 221
Creating a task group 221
Delete 223
dynamic 217
Edit 222
Execute 222
Mark as completed 222
Mark as not completed 222
My tasks 217
New 217
Open 222
Responsibility 217
static 217
Tasks not accepted 217
Task group
accepted 219
Create 220
New 220
Task notification
Default 225
Levels 225
Tasks
Move 220
Sort 220
Test import 49, 64
Text
Edit 105, 107
Format 105
Text feature
Manage 107
Own 105, 107
User-defined 105

- U -

Unit system 261, 262
Default 262
User-defined 262
Units
Convert 262
Create 262
Manage 261, 262
Usage list 188
User group 246
Action rights 246
Clone 243
Create 243
Manage 243
User group matrix 243
User management 242
Users
Administrator 259
Assign user groups 253
Create 253
Delete 253
Edit 253
Login 18
Manage 253

- V -

Value
Set new 106
Variable 266
Create 282, 296
Data type 296
Editable 296
Mandatory value 296
Use 282

Version
Add 154
Close 156
Create 153
Delete 154, 156
Display 154
Field selection 155
Item 152
New 153
Open 156
Price groups 152
Products 152
Structure groups 152
Structures 152
View 19, 26
Block 29
Change layout 30
Obtain content 29
Open 28
Retain content 29
Size 30
Views
Overview 26
Visibilities 348, 354
Visibility
Assign 245

- W -

Window 19, 26
Change layout 30
Resize 30
Words
Add to dictionary 87
Exclude 87
Working version 152