How-To Library

Informatica

IP Address Binding in Dynamic Data Masking

© Copyright Informatica LLC 1993, 2021. Informatica and the Informatica logo are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html

Abstract

This article describes how to configure IP address binding in Dynamic Data Masking.

Supported Versions

- Dynamic Data Masking 9.8.2 with EBF 7341, 9.8.1 with EBF 7341

Table of Contents

Overview. 2
Server Control setAddress Command. 2
Server Control removeAddress Command. 2
Server Control displayAddress Command. 3
Configure IP Address Binding. 3

Overview

You can use the Server Control setAddress command to enable IP address binding if you want multiple Dynamic Data Masking Servers to run on the same machine and use the same listener port. You can also use the same port for multiple Dynamic Data Masking services when the same service is defined on different Dynamic Data Masking Servers.

Server Control setAddress Command

The setAddress command creates a `server.address=<IP address>` property in the `config.properties` file and allows Dynamic Data Masking to identify the server or service by `<IP address>:<port>` or `<hostname>/<IP address>:<port>`.

The Dynamic Data Masking Server must be shut down to run the command.

The command uses the following syntax:

```
server setAddress <IP address>
```

For example, you might enter the following command:

```
server setAddress 123.45.678.9
```

Server Control removeAddress Command

The removeAddress command removes the Dynamic Data Masking Server network address that you added with the setAddress Server Control command.

The Dynamic Data Masking Server must be shut down to run the command.

The command uses the following syntax:

```
server removeAddress
```

Server Control displayAddress Command

The displayAddress command returns a message indicating whether the Dynamic Data Masking Server network address has been set with the setAddress command. If the address has been set, it displays the address.

The command uses the following syntax:

```
server displayAddress
```

Configure IP Address Binding

Perform the following steps to configure IP address binding in Dynamic Data Masking.

1. Install Dynamic Data Masking.
2. Open a Server Control Window and run the following command:

   ```
   server stop
   ```
3. In the Server Control window, run the following command to set the network address for the Dynamic Data Masking Server:

   ```
   server setAddress <IP address>
   ```

   The IP address that you enter is the address that Dynamic Data Masking uses to route requests to the correct server.
4. Install the second instance of Dynamic Data Masking on the same machine.
5. Open a Server Control window for the second Dynamic Data Masking Server and run the following commands:

   ```
   server stop
   server setAddress <IP address>
   ```
6. Start both of the Dynamic Data Masking Servers by running the following command in their respective Server Control windows:

   ```
   server start
   ```
7. You can use the following command to verify that the address is set correctly:

   ```
   server displayAddress
   ```

Author

Coral Waters