Informatica® Cloud Data Governance and Catalog

October 2026

Asset Management

Informatica Cloud Data Governance and Catalog Asset Management
October 2026

© Copyright Informatica LLC 2021, 2026

Publication Date: 2026-11-01

Table of Contents

Preface 6

Chapter 1: Overview 7

Chapter 2: Manage access to assets 8

Key concepts 9

Roles, users, and user groups 9

Access policies 10

Asset groups 10

Asset privileges in Administrator 11

Feature privileges in Administrator 12

Predefined user roles 15

Data Access Owner role 15

Governance Administrator role 16

Governance Owner role 19

Governance User role 20

Predefined access policies 21

Use cases 26

Use case: Control access to unpublished glossary changes 26

Use case: Cross-unit glossary collaboration 27

Chapter 3: Manage assets 28

Business assets 28

Creating assets and assigning stakeholders 28

Working with reference IDs for business assets 31

Risk and evaluation 32

Creating a questionnaire template 33

Associating questionnaires with an asset 34

Associating risks with an asset 35

Associating mitigation plans with an asset 35

Manual data element 35

Creating a manual data element 36

Technical assets 37

Assign stakeholders for technical assets 38

Creating AI models from technical assets 38

Creating data sets from technical assets 40

Creating system assets from technical assets 41

Propagate stakeholders to asset hiearchies 42

View and configure stakeholder propagation 45

Associate reference data from Reference 360 47

Associating reference data with business terms or metrics. . . . 47
Associating reference data with manual data elements. . . . 48
Associating reference data with data elements. . . . 49
Modifying assets. . . . 50
Obsolete assets. . . . 51
Changing between Published and Obsolete lifecycle status. . . . 52
Deleting assets. . . . 53

Chapter 4: Enrich technical assets. . . . 55

Curate technical assets with glossary. . . . 55
Associate business names and descriptions with technical assets. . . . 61
Curate technical assets with data classifications. . . . 66
Curate unstructured technical assets with document classifications. . . . 69
Working with generated classifications. . . . 70
Promoting a generated classification. . . . 71
Rejecting a generated classification. . . . 71
Demoting a generated classification. . . . 72
Example of promoting, demoting and rejecting a generated classification. . . . 73
Custom attributes for assets. . . . 73

Chapter 5: Curation Center. . . . 77

Reviewing recommendations and curating assets. . . . 79
Curating assets in bulk. . . . 79

Chapter 6: Collaboration. . . . 81

Rating an asset. . . . 81
Rating an asset for the first time. . . . 81
Editing the rating of an asset. . . . 82
Certifying an asset. . . . 83
Decertifying an asset. . . . 84
Commenting on an asset. . . . 86

Chapter 7: Workflows and tickets. . . . 90

What is a workflow?. . . . 90
Prerequisites for workflows. . . . 92
Minimum privileges to create workflow tickets in Data Governance and Catalog. . . . 92
Minimum privileges to work with workflow tickets in Data Governance and Catalog. . . . 93
Minimum privileges to view all tasks in Data Governance and Catalog. . . . 93
Minimum privileges to assign or reassign a task in Data Governance and Catalog. . . . 93
Minimum privileges to cancel open workflow tickets in Data Governance and Catalog. . . . 94
What is a ticket?. . . . 94
Creating a ticket. . . . 96
Creating a ticket when you create or modify an asset. . . . 97

Viewing a ticket. . . . 99
Manage tickets. . . . 100
Commenting on a ticket. . . . 101
Resolving a ticket. . . . 103
Canceling a ticket. . . . 103
Tasks Inbox. . . . 104
Performing actions on multiple tasks. . . . 108
Assigning a task. . . . 109
Participating in a workflow. . . . 110
Viewing audit history of tickets. . . . 113

Chapter 8: Customization for layouts. . . . 116

Custom layout for asset pages. . . . 116
Custom layout for preview panes. . . . 117
Customize grid layout for asset pages. . . . 118
Applicable pages. . . . 120

Index. . . . 122

Preface

Read *Asset Management* to learn how to create assets, enrich assets with governance context, and collaborate with stakeholders to keep the assets up to date.

CHAPTER 1

Overview

Use Data Governance and Catalog to govern data according to the security and compliance requirements of your organization. Add governance context to technical assets to better understand your data. Involve the data stakeholders to collaborate and collectively assess the value of the data. Use workflows to create and update assets using checks and balances according to your organization's policies.

CHAPTER 2

Manage access to assets

As your organization's data rapidly evolves, a robust and centralized mechanism to control access to assets becomes crucial to effectively manage the assets in your organization. Metadata access control is the practice of managing the level of user access to assets in your organization through a set of rules called access policies.

With metadata access control, you can view and perform actions on specific assets or groups of assets only if your organization administrator has explicitly granted access and permissions to you through access policies. This ensures that with appropriate permissions the right users have access to the right assets.

The following concepts apply as you implement metadata access control in your organization:

- Roles, users, and user groups. See "Roles, users, and user groups" on page 9.
- Access policies. See "Access policies" on page 10.
- Asset groups. See "Asset groups" on page 10.

How it works

The organization administrator can implement access control in your organization through a combination of privileges in Administrator and access policies in Metadata Command Center. The following tasks describe how the administrator enforces metadata access control.

In Administrator, perform the following steps:

1. Create users, user roles, and user groups.
2. Assign users and user groups to user roles.
3. Grant minimum asset and feature privileges to user roles.

In Metadata Command Center, perform the following steps:

1. Extend the Administrator user role definitions and create access policies to determine the level of access that users have on assets. Optionally, use asset groups or attribute groups in access policies to control access to a group of assets or to certain attributes of assets.
2. Publish the access policies to enforce metadata access control.

In Data Governance and Catalog, perform the following steps:

1. Users interact with assets based on the permissions and level of access defined in access policies.
2. If using asset groups, assign asset groups to assets to enforce access control over the assets.
3. Assign a user as the stakeholder of the asset to grant asset permissions that are unique to the stakeholder.

Key concepts

To understand how your administrators can manage access to assets using metadata acccess control, you need a basic understanding of the following key concepts.

Roles, users, and user groups

To use Data Governance and Catalog, the organization administrator must create the users, user groups, and user roles in Administrator for your organization.

A user is an individual Intelligent Data Management Cloud™ (IDMC) account that can perform tasks and access assets based on the roles that are assigned to the user. You can assign roles directly to the user or to a group that the user is a member of. Administrators can create user accounts for the organization in Administrator.

A user group is a group of users who can perform tasks and access assets based on the roles that you assign to the group. Administrators can create user groups for the organization in Administrator.

A role is a set of privileges that you can assign to users and user groups. When the organization administrator creates roles and sets the correct permissions and privileges, the roles define the boundaries within which the users can act. Data Governance and Catalog provides three predefined user roles that you can assign to users and user groups in Administrator. See "Predefined user roles" on page 15.To create custom roles, you can create a new role or clone an existing custom role in the Administrator.

With metadata access control, there are two types of roles that administrators can use to grant different types of access to users.

User roles

A user role defines the permissions and privileges for different types of assets and features. Administrators can create and assign user roles for the organization in Administrator. You can assign a user role to the users or user groups in your organization.

The user roles that the organization administrator creates for your organization appear on the **Users** tab on the **Access Control** page in Metadata Command Center. You can use the user roles in access policies to grant users access and permissions for different types of assets.

For more information about creating user roles and assigning them to users and user groups, see *User Administration* in Administrator.

Stakeholder roles

A stakeholder role is a defined organizational responsibility that you declare on assets. Stakeholder roles allow you to control how authorized users interact with the assets for which they are responsible.

A stakeholder role reflects a user's responsibilities as a stakeholder of an asset and allows them to perform governance activities with only the permissions and privileges necessary to perform their tasks. In Metadata Command Center, you can create stakeholder roles from user roles and use them in access policies to grant users granular access to assets. If a stakeholder is assigned to an asset, the level of access and permissions for users who are not stakeholders of the asset are determined by the stakeholder role policies configured with the non-stakeholder option.

View user roles, stakeholder roles, and stakeholders on the **Users** tab on the **Access Control** page in Metadata Command Center.

For information about using user roles, user groups, and stakeholder roles in access policies, see the *Administration* help in Metadata Command Center.

Access policies

Access policies are sets of rules that the administrator creates in Metadata Command Center to define permissions and control the level of access to the assets in the organization.

Access policies are an extension of the asset and feature privileges that are granted to your user role through Administrator. Along with the asset and feature privileges that are assigned to the user roles in Administrator, your organization administrator must create and assign access policies in Metadata Command Center that determine whether users can read, create, update, delete or manage access for the assets. Administrators can use predefined policies or define custom policies specific to their organization in Metadata Command Center. Predefined policies are associated with predefined user roles defined in Administrator. See "Predefined user roles" on page 15.

Administrators can grant access to assets, asset groups, or individual attributes of an asset using the following types of access policies:

- User role policy. Defines the access level of users who are assigned a user role in Administrator.
- Stakeholder role policy. Defines the access level of users who are assigned a stakeholder role in Metadata Command Center. A stakeholder role policy grant asset permissions that are unique to the stakeholder of the asset.
- User group policy. Defines the access level of users who are assigned a user group in Administrator. You can also use this access policy to control the access level to all users in the organization.

For information about managing access policies, see the *Administration* help in Metadata Command Center.


Asset groups

You can use asset groups to control access to a set of assets. By grouping assets, you can use user group policies to grant or restrict access to multiple assets at a time.

For the access policies associated with asset groups to take effect, assign the asset groups to specific assets in Data Governance and Catalog or associate asset groups with assets when you run a catalog source job in Metadata Command Center. After you publish a user group policy that includes asset groups, you can use the access policy to control the access level on assets that are associated with the asset group.

When you create an asset group, you can create a hierarchy of up to four levels by selecting a parent asset group.

The following image shows the **Asset Groups** tab on the **Customize** page with a list of hierarchical asset groups in Metadata Command Center:



Asset privileges in Administrator

An organization administrator can assign some asset privileges for the Metadata Command Center service to user roles in Administrator. To perform cataloging and governance tasks, the administrator must create and assign access policies to users in Metadata Command Center.

To assign asset privileges for user roles in Administrator, select the service, and select one or more privileges on the **Assets** tab for the service. For more information about assigning asset privileges to user roles, see *User Administration* in the Administrator help.

For information about creating access policies and assigning them to user roles, user groups, or stakeholder roles, see *Administration* in the Metadata Command Center help.

The following table explains the asset privileges that are available for the Metadata Command Center service in Administrator:

Asset	Description
Catalog Source Configuration	Asset privileges to create, update, delete, purge, and run a catalog source.
Custom Catalog Source Types	Asset privileges to create a custom catalog source type that represents the custom source system.
Custom Models	Asset privileges to create a custom model for custom metadata integration.

Feature privileges in Administrator

An organization administrator can assign privileges for some features of Data Governance and Catalog and Metadata Command Center to user roles in Administrator. To perform cataloging and governance tasks, the administrator must create and assign access policies to users in Metadata Command Center.

To assign feature privileges to user roles in Administrator, open a role, select the service, and select one or more features on the **Features** tab for a service. For more information about assigning feature privileges to user roles, see *User Administration* in the Administrator help.

For information about creating access policies and assigning them to user roles, user groups, or stakeholder roles, see *Administration* in the Metadata Command Center help.

Feature privileges for Metadata Command Center

The following table explains the feature privileges that are available for the Metadata Command Center service in Administrator:

Feature	Description
Access Metadata Command Center application	Grants access to Metadata Command Center. If disabled, users can't access Metadata Command Center.
Manage Autonomous Enrichments	Allows users to enable and manage global Autonmous Enrichment settings.
View Autonomous Enrichments	Allows users to view global Autonomous Enrichment settings.
Manage Custom Attributes	Allows users to manage asset relationships, predefined attributes, and custom attributes for asset types that appear in Data Governance and Catalog.
View Custom Attributes	Allows users to view attributes for asset types in Data Governance and Catalog.
Manage Data Classifications	Allows users to create and manage data classification inclusion rules.
View Data Classifications	Allows users to view data classifications in Data Governance and Catalog after you enable the capability and run the catalog source job in Metadata Command Center.
Manage Lookup Tables	Allows users to import and publish lookup tables that you can use in data classification.
View Lookup Tables	Allows users to view lookup tables in Metadata Command Center.
Monitor Jobs	Allows users to monitor jobs.
Manage Lineage Settings	Allows users to perform the following tasks: - Assign or unassign connections to one or more catalog sources. - Link catalog sources to generate lineage.
View Lineage Settings	Allow users to view data lineage from the Lineage tab.
Manage Access Control	Allows users to create and manage stakeholder roles and access policies. Also allows users to share saved searches, dashboards, and set default dashboards for other users.
View Access Control	Allows users to view access policies.

Feature	Description
Manage Asset Groups	Allows users to create, update, or delete asset groups.
View Asset Groups	Allows users to view asset groups.
Manage Workflows	Allows users to create or modify workflows.
View Workflows	Allows users to view workflows.
Workflow Designer	Allows users to design new workflows.
Manage System Settings	Allows users to modify system settings.
View System Settings	Allow user to view the **Reference IDs** tab.
Manage Asset page customization	Allows users to create, update and delete the layout of pages and preview panes of assets. Also allows users to assign default layouts to other users based on their roles, user groups, or to all users in the organization.
View Asset page customization	Allows users to view the layout of pages.
Manage IDMC Metadata Settings	Allows users to synchronize metadata from Data Integration tasks and Application Integration objects with the catalog.
View IDMC Metadata Settings	Allow users to view IDMC metadata.
Manage Upgrade	Allows users to initiate upgrades to the latest version of Data Governance and Catalog.
Manage Usage Analytics	Allows users to enable and disable usage analytics.
Super Admin	Allows users access to unique administrator capabilities beyond the Governance Administrator role.

Feature privileges for Data Governance and Catalog

The following table explains the feature privileges that are available for the Data Governance and Catalog service in Administrator:

Feature	Description
Access Data Governance and Catalog application	Enable this feature to grant access to Data Governance and Catalog. If disabled, you can't access Data Governance and Catalog to perform any governance tasks.
Export	Allows users the ability to export assets from Data Governance and Catalog.
Export Usage Metrics	This privilege is not in use.
Force Delete	Allows users the following privileges: - Delete assets with incoming relationships. - Delete assets with all the child assets in the hierarchy through bulk import.

Feature	Description
Import	Allows users the ability to download predefined templates and import business assets into Data Governance and Catalog. To enable this privilege, also grant users the following asset privileges to import assets: - Business assets. Create and update privilege - Technical assets. Update privilege
Manage Tickets	Allows users the following privileges: - Resolve or cancel tickets without being a stakeholder of the asset. - Receive notifications for manual tickets without being a stakeholder of the asset.
Manage Workflow Tasks	Allows users the following privileges: - View all the tasks on the **Tasks Inbox** page in Data Governance and Catalog. - Manage tasks in Data Governance and Catalog. - Assign and reassign tasks in Data Governance and Catalog.
Participate in Change Approvals	Allows users the following privileges: - Participate in workflow approvals in Data Governance and Catalog. The role for which you grant this privilege appears in the **Role** in Metadata Command Center when a user creates or modifies a workflow task. - Add stakeholders to assets in Data Governance and Catalog. - Configure workflows in Metadata Command Center.
Preview Data	Allows user to view the latest preview of failed rows for data quality rule occurrences in Data Governance and Catalog. **Important:** Effective in the July 2026 release, the Preview Data feature privilege is deprecated. Deprecated functionality is supported, but Informatica intends to drop support in a future release.
View Reference Data	Allows users to view reference data on the **Reference Data** tab for business terms, metrics, manual data elements, and data elements.
View Restricted Metrics	Allow users to view restricted metric data on usage analytics dashboards.
View Usage Metrics	Allows users to view metric data, to edit widgets on usage analytics dashboards, and to clone and share usage analytics dashboards.

Predefined user roles

As an organization administrator, you can assign predefined user roles to users and user groups in Administrator.

Predefined user roles are system-defined roles that define certain privileges to the services that your organization uses. Some asset and feature privileges are enabled by default for predefined user roles. You cannot modify, rename, or delete predefined roles.

Data Governance and Catalog provides the following predefined roles:

- "Data Access Owner role" on page 15
- "Governance Administrator role" on page 16
- "Governance Owner role" on page 19
- "Governance User role" on page 20

To extend the user role privileges provided in Administrator, you can assign the predefined access policies to user roles and stakeholder roles in Metadata Command Center. See "Predefined access policies" on page 21.

Data Access Owner role

A user with the Data Access Owner role has the feature privileges assigned in Administrator to perform certain tasks in Data Governance and Catalog. In Metadata Command Center, a user with this role also automatically receives the default privileges to perform tasks on data access policies in Data Governance and Catalog.

Data Governance and Catalog

The following table lists the feature privileges that are enabled or disabled by default in Data Governance and Catalog for the Data Access Owner role:

Features	Status
Access Data Governance and Catalog Application	Enabled
Export	Disabled
Force Delete	Disabled
Import	Disabled
Manage Tickets	Disabled
Manage Workflow Tasks	Disabled
Participate in Change Approvals	Disabled
Preview Data	Disabled
View Reference Data	Enabled

Governance Administrator role

A user with the Governance Administrator role has asset and feature privileges assigned in Administrator that assist in working with features and assets in Metadata Command Center, Data Governance and Catalog and Data Marketplace. The Governance Administrator role also includes features and privileges that you need to configure and run Application Integration processes and Human Tasks services using custom workflows.

Metadata Command Center

The following table lists all the asset privileges that are enabled or disabled by default for the Governance Administrator role in Metadata Command Center:

Assets	Privileges enabled	Privileges disabled
Catalog Source Configurations	Create, read, update, delete, run, set permission	None
Custom Catalog Source Type	Create, read, update, delete	Run, set permission
Custom Models	Create, read, update, delete	Run, set permission

The following table lists the feature privileges that are enabled or disabled by default for the Governance Administrator role in Metadata Command Center:

Features	Status
Access Metadata Command Center Application	Enabled
Manage Access Control	Enabled
Manage Asset Groups	Enabled
Manage Asset Page Customization	Enabled
Manage Autonomous Enrichments	Enabled
Manage Custom Attributes	Enabled
Manage Data Classifications	Enabled
Manage IDMC Metadata Settings	Enabled
Manage Lineage Settings	Enabled
Manage Lookup Table	Enabled
Manage System Settings	Enabled
Manage Upgrade	Disabled
Manage Workflows	Enabled
Monitor Jobs	Enabled
Super Admin	Disabled

Features	Status
View Access Control	Enabled
View Asset Groups	Enabled
View Asset Page Customization	Enabled
View Autonomous Enrichments	Enabled
View Custom Attributes	Enabled
View Data Access Audit	Enabled **Note:** This privilege is for a future release.
View Data Access Management	Enabled
View Data Classifications	Enabled
View IDMC Metadata Settings	Enabled
View Lineage Settings	Enabled
View Lookup Table	Enabled
View System Settings	Enabled
View Workflows	Enabled
Workflow Designer	Enabled

Data Governance and Catalog

The following table lists the feature privileges that are enabled or disabled by default for the Governance Administrator role in Data Governance and Catalog:

Features	Status
Access Data Governance and Catalog Application	Enabled
Export	Enabled
Force Delete	Disabled
Import	Enabled
Manage Tickets	Disabled
Manage Workflow Tasks	Enabled
Participate in Change Approvals	Enabled

Features	Status
Preview Data	Enabled
View Reference Data	Enabled

Data Marketplace

The following table lists the feature privileges that are enabled or disabled by default for the Governance Administrator role in Data Marketplace:

Features	Status
Access Data Marketplace	Enabled
Approve or Reject Orders	Disabled
Cancel Your Orders And Data Collection Requests	Enabled
Complete or Reject Data Collection Requests	Disabled
Configure And Manage Data Marketplace	Disabled
Fulfill Or Reject Orders	Disabled
View Set up page	Disabled
Withdraw Consumer Accesses	Disabled

Application Integration

The following table lists the asset privileges that are enabled or disabled by default for the Governance Administrator role in Application Integration:

Assets	Privileges enabled	Privileges disabled
Application Integration Assets	Create, read, update, delete, run, set permission	None

The following table lists the feature privileges that are enabled or disabled by default for the Governance Administrator role in Application Integration:

Features	Status
Administration	Enabled
Console Administration	Enabled
Data Viewer	Enabled
Development	Enabled

Features	Status
Monitoring	Enabled
Publish Application Integration Assets	Enabled
View Application Integration Console	Enabled
View Application Integration Designer	Enabled

Human Tasks

The following table lists the asset privileges that are enabled or disabled by default for the Governance Administrator role in Human Tasks:

Assets	Privileges enabled	Privileges disabled
Human Task Assets	Create, read, update, delete, run, set permission	None

The following table lists the feature privileges that are enabled or disabled by default for the Governance Administrator role in Human Tasks:

Features	Status
Development	Enabled
View Human Task Application	Enabled
View Tasks	Enabled

Governance Owner role

A user with the Governance Owner role has the privileges assigned in Administrator to perform certain tasks and manage assets in Data Governance and Catalog and Data Marketplace.

Data Governance and Catalog

The following table lists the feature privileges that are enabled or disabled by default in Data Governance and Catalog for the Governance Owner role:

Features	Status
Access Data Governance and Catalog Application	Enabled
Export	Enabled
Force Delete	Disabled
Import	Enabled

Features	Status
Manage Tickets	Disabled
Manage Workflow Tasks	Disabled
Participate in Change Approvals	Enabled
Preview Data	Enabled
View Reference Data	Enabled

Data Marketplace

The following table lists the feature privileges that are enabled or disabled by default in Data Marketplace for the Governance Owner role:

Features	Status
Access Data Marketplace	Enabled
Approve or Reject Orders	Disabled
Cancel Your Orders And Data Collection Requests	Enabled
Complete or Reject Data Collection Requests	Disabled
Configure And Manage Data Marketplace	Disabled
Fulfill Or Reject Orders	Disabled
View Set up page	Disabled
Withdraw Consumer Accesses	Disabled

Governance User role

A user with the Governance User role is assigned specific privileges in Administrator that assist in working with features and assets in Data Governance and Catalog and Data Marketplace.

Data Governance and Catalog

The following table lists the feature privileges that are enabled by default for the Governance User role in Data Governance and Catalog:

Features	Status
Access Data Governance and Catalog Application	Enabled
Export	Enabled
Force Delete	Disabled

Features	Status
Import	Disabled
Manage Tickets	Disabled
Manage Workflow Tasks	Disabled
Participate in Change Approvals	Disabled
Preview Data	Disabled
View Reference Data	Enabled

Data Marketplace

The following table lists the feature privileges that are enabled by default for the Governance User role in Data Marketplace:

Features	Status
Access Data Marketplace	Enabled
Approve or Reject Orders	Disabled
Cancel Your Orders And Data Collection Requests	Enabled
Complete or Reject Data Collection Requests	Disabled
Configure And Manage Data Marketplace	Disabled
Fulfill Or Reject Orders	Disabled
View Set up page	Disabled
Withdraw Consumer Accesses	Disabled

Predefined access policies

Predefined access policies provide an extension of the access privileges that the organization administrator provides through user roles in Administrator. To perform cataloging and governance tasks, the administrator must assign the predefined access policies to user roles and stakeholder roles in Metadata Command Center.

The predefined access policies have a set of predefined rules that grants different levels of access to users based on the user roles or stakeholder roles assigned to the users. You cannot modify the predefined access policies but you can disable and clone them to create custom access policies that are specific to your organization.

To view all the predefined access policies, go to the **Access Policies** tab on the **Access Control** page in Metadata Command Center, and apply the filter on **Category**.

The following table lists the predefined access policies that are enabled and disabled by default:

Access Policy	Description	Type	Status
Data Access Owner	Defines permissions on data access controls for a user with the Data Access Owner user role.	User Role Policy	Enabled
Data Access Stakeholder	Defines permissions on data access controls for a stakeholder with the Data Access Owner user role.	Stakeholder Role Policy	Enabled
Data Marketplace Data Collection Owner Stakeholder	Defines the permissions that a user will have as a stakeholder with Data Marketplace Data Collection Owner stakeholder role on a data collection. When in effect, the policy allows a user to manage a data collection and the assets within it.	Stakeholder Role Policy	Enabled
Data Marketplace Data Collection Technical Owner Stakeholder	Defines the permissions that a user will have as a stakeholder with Data Marketplace Data Collection Technical Owner stakeholder role on a data collection. When in effect, the policy allows a user to manage the assets and deliveries of a data collection.	Stakeholder Role Policy	Enabled
Non-Stakeholder Policy for Marketplace Assets	Grants read permission on Data Marketplace assets to users who are not stakeholders of Data Marketplace assets.	Stakeholder Role Policy	Enabled
Data Marketplace Delivery Template Owner Stakeholder	Defines the permissions that a user will have as a stakeholder with Data Marketplace Data Collection Delivery Template Owner stakeholder role on a delivery template. When in effect, the policy allows a user to manage a delivery template.	Stakeholder Role Policy	Enabled

Access Policy	Description	Type	Status
Data Marketplace Category Owner Stakeholder	Defines the permissions that a user will have as a stakeholder with Data Marketplace Category Owner stakeholder role on a category. When in effect, the policy allows a user to manage a category and the assets within it.	Stakeholder Role Policy	Enabled
Governance Owner Stakeholder	Defines the permissions that a user will have as a stakeholder with Governance Owner stakeholder role on business and technical asset types. When in effect, the policy allows a user to manage business and technical assets.	Stakeholder Role Policy	Enabled
Governance Administrator Stakeholder	Defines the permissions that a user will have as a stakeholder with Governance Administrator stakeholder role on business and technical asset types. When in effect, the policy allows a user to manage business and technical assets.	Stakeholder Role Policy	Enabled
Non Stakeholder policy for Business and Technical assets	Grants read permission to non-stakeholders on business and technical asset types.	Stakeholder Role Policy	Enabled
Data Marketplace Delivery Template Owner	Grants permissions to the Data Marketplace Delivery Template Owner user role to manage delivery templates in Data Marketplace. Also grants read permission on business and technical assets in Data Governance and Catalog.	User Role Policy	Enabled

Access Policy	Description	Type	Status
Data Marketplace User	Grants permission to the Data Marketplace User role to view and consume data collections in Data Marketplace. In addition, grants read permission on business and technical assets in Data Governance and Catalog.	User Role Policy	Enabled
Data Marketplace Technical Administrator	Grants permissions to the Data Marketplace Technical Administrator user role to perform technical administrative tasks such as managing delivery options, specifying the general terms of use and customizing the appearance of Data Marketplace. In addition, grants read permission on business and technical assets in Data Governance and Catalog.	User Role Policy	Enabled
Data Marketplace Category Owner	Grants permissions to the Data Marketplace Category Owner user role to manage categories and the data within them. In addition, grants read permission on business and technical assets in Data Governance and Catalog.	User Role Policy	Enabled
Admin	Grants read permissions to the Admin user role on business and technical asset types and limited permissions on marketplace asset types.	User Role Policy	Enabled

Access Policy	Description	Type	Status
Data Marketplace Administrator	Grants all permission to the Data Marketplace Administrator user role on all Data Marketplace assets. In addition, grants read permission on business and technical assets in Data Governance and Catalog.	User Role Policy	Enabled
Governance Administrator	Grants all permissions to the Governance Administrator user role on business and technical asset types and limited permission on marketplace asset types. Provides the ability to manage catalog source configuration in Metadata Command Center.	User Role Policy	Enabled
Governance User	Grants read permission to the Governance User role on business and technical asset types and limited permissions on marketplace asset types.	User Role Policy	Enabled
Governance Owner	Grants all permissions to the Governance Owner user role on business and technical asset types and limited permissions on marketplace asset types.	User Role Policy	Enabled
Data Marketplace Data Collection Technical Owner	Grants permission to the Data Marketplace Data Collection Technical Owner user role to manage deliveries of data collections. Also grants read permission on business and technical assets in Data Governance and Catalog.	User Role Policy	Enabled

Access Policy	Description	Type	Status
Data Marketplace Data Collection Owner	Grants permissions to the Data Marketplace Data Collection Owner user role to manage data collections and the data within them. Also grants read permission on business and technical assets in Data Governance and Catalog.	User Role Policy	Enabled
Super Admin	Grants the manage access permission to the Governance Administrator user role to manage stakeholders on business and technical asset types.	User Role Policy	Disabled
No Asset Group	Grants all permissions to users on assets that do not belong to asset groups. Other user role or stakeholder role policies can restrict permissions granted by this policy.	User Group Policy	Enabled

Use cases

The following use cases show how you can use metadata access control to effectively manage access to the assets in your organization:

- "Use case: Control access to unpublished glossary changes" on page 26
- "Use case: Cross-unit glossary collaboration " on page 27

Use case: Control access to unpublished glossary changes

HypoStores is a popular online shopping retail company that offers a wide range of products, from clothing to electronics. HypoStores uses Data Governance and Catalog to manage its data assets effectively.

Problem statement

The *HypoStores* business is growing, and the website team needs to keep the business glossary updated with product categories, pricing models, and promotional terms. The glossary stewards collaborate with stakeholders to update and finalize the glossary definitions. In the meantime, they want to make sure that only the glossary stewards have access to the unpublished changes. Otherwise, confidential information might be leaked.

Solution

HypoStores can use attribute groups in access policies to explicitly grant glossary stewards in their organization access to assets that contain unpublished or draft changes.

With access control in Data Governance and Catalog, the organization administrator can perform a few simple steps:

1. In Administrator, define a user role called *Glossary Steward* and assign this role to users who manage glossary assets in the organization.
2. In Metadata Command Center, create and publish a user role-based access policy for the *Glossary Steward* role. The access policy can contain the following rules:
   - Grant data stewards permissions to create, read, update, and manage access on business asset types. This grants data stewards permissions to all lifecycle statuses of business assets.
   - Grant read permission on the **Unpublished Changes** attribute group for all business asset types.

After the access policy is published in Metadata Command Center, users with the *Glossary Steward* role can access the unpublished changes or the draft version of the business assets in Data Governance and Catalog.

Use case: Cross-unit glossary collaboration

Acme Inc. is a finance company that provides loans, credit, and other financial services. *Acme Inc.* uses Data Governance and Catalog for compliance, data quality, and collaboration.

Problem Statement

The company has three separate business units that want to work together on a common enterprise glossary. While they need to collaborate on the common glossary, each unit has its own assets that must stay private and separate from the others for security, legal, and operational reasons.

Solution

Acme Inc. can use asset groups to segregate assets based on the business units that use them, ensuring that only the employees of a particular business unit can interact with the business unit's assets.

With metadata access control in Data Governance and Catalog, *Acme Inc.* can segregate assets using asset groups while ensuring collaboration among employees in a few simple steps:

1. In Metadata Command Center, create an asset group called *Acme Inc*.
2. Under the *Acme Inc* asset group, create three child asset groups that correspond to the business units. For example, create: *Acme France*, *Acme UK*, and *Acme India*.
3. Assign each child asset group to the corresponding assets from each business unit and assign the parent asset group to common glossary assets that all users can collaborate on.
4. Use these asset groups in access policies to grant different levels of user access for each asset group. Each asset group can have the following rules:
   - Grant read permission to data stewards to view all technical and business assets that belong to the asset group.
   - Grant read permission to business users to view all business assets that belong to the asset group.
   - Grant read permissions to all users to view glossary assets that are assigned to the *Acme Inc* asset group.

After the access policies are published and the assets are assigned to asset groups, only users that are part of each asset group will have permission to interact with the assets in those groups. All users can collaborate on the glossary assets that belong to the parent asset group.

CHAPTER 3

Manage assets

Assets in Data Governance and Catalog add business and technical metadata to your data elements. By adding the metadata, you can enrich your data with additional context that you can use for catalog and governance purposes.

With appropriate permissions, you can create, modify, or delete assets. For example, you can create business assets like Policy and Process to capture business functions for documentation purposes. Or, create a technical asset to enrich the data in a database table so that you can understand the lineage of the data.

Business assets

Business assets allow you to describe why you use the data, where you use the data, and how you use the data to make business decisions. Business assets provide context to your data using relationships with other business assets and by using simpler representations of technical data.

In Data Governance and Catalog, you can create business assets of various types such as AI model, business term, process, domain, or metric. A business asset can represent an actual asset in your organization or represent a business concept like finance or human resources.

When you create a business asset, you can populate several predefined attributes to define the asset. You can also add your own attributes to include additional details about an asset that are unique to your business requirement. You can rate or comment on business assets to collaborate with the users in your organization. When users collaborate on an asset, they might gain insight into the quality of the data and expose details of the asset's usage in your business. You can also define relationships between assets, assign stakeholders, keep an audit of changes performed on an asset, and view change request tickets created for the assets.

For more information about business assets, see the *Understanding Business Assets* help.

Creating assets and assigning stakeholders

Assets in Data Governance and Catalog represent data elements in your data stores. Create an asset and enter properties that add technical or business context to the data elements.

The following prerequisites apply if you want to create assets and add stakeholders for business or technical assets:


- The organization administrator must grant you the **Create** permission for the asset through access policies in Metadata Command Center.
- To assign stakeholders to the asset, the organization administrator must grant you the **Manage Access** permission on the asset through access policies in Metadata Command Center.

For more information about the available privileges and privileges that the organization administrator can enable, see Chapter 2, “Manage access to assets” on page 8.

Note: When you create a business asset in Data Governance and Catalog, the default values for custom attributes are not pre-populated, and the fields are blank. This applies to optional and mandatory attributes. If there is a mandatory attribute, you need to specify a value for the asset creation to be successful. Additionally, it is recommended to define default values for custom attributes when they are associated with technical assets.

To create an asset and assign stakeholders, perform the following steps:

1. Go to the **Home** page, and click **New**.
2. In the **New** dialog box, select the asset type that you want to create.




3. On the new asset page, populate the mandatory properties on the asset. For more information about the properties for each asset type, see the *Understanding Business Assets* help.

   The following table shows the properties on the asset:

Field	Description
Name	Required. Name of the asset.
Parent	Optional. The parent asset for the open asset. Click the action menu to select the parent asset. The **Parent** dialog box displays only the asset types that are applicable to be added as a parent for the open asset. **Note:** If you add a parent asset with stakeholder propagation enabled, the new asset inherits the stakeholders of the parent asset. For more information, see *Parent-child relationships* in the *Asset Discovery* help. Also, see “Propagate stakeholders to asset hiearchies” on page 42.


Field	Description
Description	Optional. Description of the asset. You can also add images that are less than 1 MB. When you create a glossary business asset, you can manually enter a description or leverage CLAIRE to generate a description. To use CLAIRE to generate a description, click the **Generate with CLAIRE** icon. You can specify the industry context in which you want CLAIRE to generate the description, and also specify the length of the generated description. Before you use CLAIRE to generate a description, specify a name for the asset. CLAIRE uses the asset name to formulate a description for the glossary business asset. **Note:** If you want to use CLAIRE to generate a description for an asset, your organization administrator must enable the **Enable CLAIRE Generative AI Services** setting in Administrator. For more information about glossary business assets, see the *Understanding Business Assets* help.
Reference ID	Optional. Unique identifier that you can provide for the asset. If you do not provide the reference ID, the system automatically generates a reference ID for the business asset. For more information on reference ID for business assets, see "Working with reference IDs for business assets" on page 31.
Alias Names	Optional. Alternative name for the asset. Enter synonyms of the asset that are commonly used in your organization.

4. To assign stakeholders to the asset, click the **Add** icon in the **Stakeholders** section.



5. In the dialog box that opens when you click **Add**, select a role, and then select the users or user groups that you want to add as stakeholders to the asset. Click **OK**.
6. Click **Create**. The asset is created in the `Draft` state.

7. Click **Submit** to start the workflow defined for the asset.



The system creates a ticket for the asset and notifies the stakeholders. For more information about workflows, see Chapter 7, “Workflows and tickets” on page 90.

Working with reference IDs for business assets

The reference ID is a unique identifier assigned to every business asset. It comprises a prefix, a separator, and a value. For example, a policy asset can have the reference ID 'POLIC-123'. Here, 'POLIC' is the prefix, '123' is the unique policy value, and the hyphen '-' is the separator.

For each business asset type, the prefix values are pre-configured and provided by default in Metadata Command Center. If you want to modify the prefix value for any asset type, the organization administrator must assign the **Manage System Settings** feature privilege to your user role for the Metadata Command Center service in Administrator.

For more information on prefix values for business asset reference IDs, see the *Administration* help module in Metadata Command Center.

Enter your own reference ID

If you are a data owner or a business user, then you can create or modify an asset. The **Reference ID** field is optional. You can choose to specify a reference ID or leave the field blank. If you specify a reference ID, do not enter the prefix defined in Metadata Command Center. The prefix is reserved for reference IDs that are automatically assigned to assets. You can instead enter any combination of alphanumeric or special characters. To quickly check the prefix that is defined, click the tooltip of the **Reference ID** field.

For example, if the prefix for Policy assets is defined as 'POLIC' in Metadata Command Center, do not enter `POLIC-20` as the reference ID. Instead, you can enter `POL-20` , `PolicyHR` or `Pol20` as the reference ID. The system will save your reference ID correctly.

Automatically assign a reference ID

The reference ID is an optional field. If you do not specify a reference ID when you create or modify an asset, Data Governance and Catalog automatically assigns a reference ID according to the prefix defined in Metadata Command Center.

For example, if you leave the **Reference ID** field blank for a Policy asset, the system might automatically assign the 'POLIC-21' reference ID to the asset.

Modify a reference ID

To modify a user-provided reference ID or auto-generated reference ID, open the asset page, go to the **Overview** tab and edit the reference ID on the **Attributes** pane. After modifying the reference ID, save the changes.

Reference ID for bulk imported assets

The same guidelines apply for bulk imported assets. If you choose to specify a reference ID in a bulk import template, do not enter the prefix defined in Metadata Command Center. If you leave the **Reference ID** column blank for an asset, the system assigns a reference ID automatically.

Risk and evaluation

The **Risk and Evaluation** tab on the **Browse** page lists the template assets you use for a governance assessment. They are Questionnaire Template, Risk Template, and Mitigation Plan Template assets.

You use these template assets to define the questions, identify a perceived risk, or define the mitigation plan for a risk. You then associate that template with an asset, such as an AI use case. Association creates a unique instance of the risk, mitigation plan and questionnaire on the asset.

Example

Your procurement team plans an AI agent that approves supplier payments. They search the AI use case registry first. No existing initiative covers supplier-payment approval, so they log a new AI use case. Other supply-chain teams can find that record and reuse it.

They run a risk assessment questionnaire on the use case. The questionnaire has sections for business justification, data and models, and regulatory compliance, and stakeholders answer the questions in each section. Based on those answers, the team identifies the risks and plans mitigations to remediate them.

After the use case is approved, the team develops the agent in an AI ecosystem of its choice, such as Google Vertex AI. Periodic scans discover the payment-approval agent and associate it with the use case. Stakeholders then have a 360-degree view of the assets, including the ideation, the assessment, the mitigations, what was agreed with the AI governance council, and the actual implementation.

Template Assets

The following table describes the template assets on the **Risk and Evaluation** tab:

Asset type	Description
Questionnaire Template	Gathers structured input from stakeholders for a governance assessment, such as an impact, risk, or intake review.
Risk Template	Documents a potential risk in an enterprise initiative. You can associate one or more mitigation plans with the risk to address it.
Mitigation Plan Template	Documents how you address a risk.

For more information about each template assets, see the *Questionnaire Template*, *Risk Template*, and *Mitigation Plan Template* topics in *Asset Reference* help.

For more information about creating Risk Template and Mitigation Plan assets, see the *Creating assets and assigning stakeholders* topic in *Asset Management* help.

For more information about creating Questionnaire Template asset, see the *Creating a questionnaire template* topic in *Asset Management* help.

Creating a questionnaire template

Create a questionnaire template and add the relevant sections, questions, and responses for your AI use case. After you associate the questionnaire template with an asset, stakeholders of that asset can respond to the questions.

1. Go to the **Home** page and click **New**.
2. In the **New** dialog box, select **Risk and Evaluation**.
3. Select the **Questionnaire Template** asset type and click **Create**.
4. On the **New Questionnaire Template** page, populate the required properties of the asset.

   For more information about all the properties of a Questionnaire Template asset, see the *Asset Reference* help.

   The following table describes the properties of a questionnaire asset:

Entry	Description
Name	Required. Name of the asset.
Description	Optional. Description of the asset. The total size of the contents of this field should be less than 1 MB.
Reference ID	Optional. Unique identifier that you can provide for the asset. If you don't provide the reference ID, the system automatically generates a reference ID for the business asset. For more information on reference ID for business assets, see "Working with reference IDs for business assets" on page 31.
Asset Groups	Optional. One or more asset groups assigned to the Questionnaire Template asset. Access policies use asset groups to control who can access the template.
Type	Required. The category of assessment for which you want to use the questionnaire, such as impact assessment, risk assessment, or intake.

5. To assign stakeholders to the asset, click the **Add** icon in the **Stakeholders** section.
6. In the dialog box that opens when you click **Add**, select a role, and then select the users or user groups that you want to add as stakeholders to the asset. Click **OK**.
7. Click **Create and Continue**.

   Note: Data Governance and Catalog creates the Questionnaire Template asset. You can add questions now or browse for the template later to add sections and questions.
8. In the questionnaire template, select a section and click **Add Question**.
9. In the **Add Question** dialog box, enter the following information:

Field	Description
Section	Required. Section that contains the question.
Question	Required. Text of the question.
Response Type	Required. Format of the response. Select **Free Text**, **Single Choice**, or **Multiple Choice**.

Field	Description
Other Option	Optional. Select **Other Option** as an answer type to let a stakeholder enter an answer that is not in the list. Appears when the response type is **Single Choice**.
Responses	Required. Predefined responses for free text, single choice, or multiple choice question.

10. To save the question to the section, click **Save**. To keep on adding questions to the section, Select **Save and Add New**.

    The following table describes the options to manage a question in the Questionnaire Template asset:

Option	Description
Edit	Opens the question so that you can edit it.
Delete	Deletes the question.
More actions	Moves the question to another section. Select **Move to** and specify the section name.

11. Click **Done**.

    Data Governance and Catalog creates the Questionnaire Template asset with the sections and questions.

12. If the Questionnaire Template asset has associated workflows, Data Governance and Catalog displays the **Submit** button. To start a workflow, click **Submit**.

    Data Governance and Catalog creates a ticket and notifies the stakeholders. If the Questionnaire Template asset has no associated workflows, Data Governance and Catalog publishes the asset automatically.

Associating questionnaires with an asset

Associate a Questionnaire Template asset with another asset to assess that asset. When you associate the questionnaire template, stakeholders of the asset answer a questionnaire that's created from it.

1. Open the asset with which you want to associate the Questionnaire Template asset.
2. On the asset page, go to the **Questionnaire** tab and click the **Add** icon.
3. In the **Select Questionnaires** stage of the **Add Questionnaire** wizard, select the the Questionnaire Template assets that you want to associate with the asset.
4. In the **Add Stakeholders** stage of the **Add Questionnaire** wizard, select the stakeholders of the questionnaire and its sections, and enter the response due date. You can select only the stakeholders of the asset that is associated with the questionnaire template. Stakeholders answer the questions in the questionnaire.
5. To associate the questionnaire template with the asset, click **Save**.

   When you associate a template, Data Governance and Catalog creates a questionnaire instance.

Subsequent changes to the questionnaire template don't apply to a questionnaire instance. To use the latest version of a questionnaire template, remove the questionnaire instance and associate the updated template.

Associating risks with an asset

Associate a Risk Template asset with another asset to identify a potential risk to that asset. After you associate a risk template, you can associate mitigation plans with the risk to address it.

1. Open the asset with which you want to associate the Risk Template asset.
2. On the asset page, go to the **Risks and Mitigations** tab and click the **Add** icon.
3. In the **Select Risks** stage of the **Add Risks** wizard, select the the Risk Template assets that you want to associate with the asset.
4. In the **Add Stakeholders** stage of the **Add Risks** wizard, select the stakeholders of the risk and enter the due date. Enter a risk score to indicate the severity of the risk. You can select only the stakeholders of the asset that is associated with the risk template.
5. To associate the risk template with the asset, click **Save**.

   When you associate a template, Data Governance and Catalog creates a risk instance.

Subsequent changes to the risk template don't apply to a risk instance. To use the latest version of a risk template, remove the risk instance and associate the updated template.

Associating mitigation plans with an asset

Associate a Mitigation Plan Template asset with a risk to document how to address the risk. After you associate a mitigation plan template, you can track the progress of the plan.

1. Open the asset with which you want to associate the Mitigation Plan Template asset.
2. On the asset page, go to the **Risks and Mitigations** tab and click the **Add** icon.
3. In the **Select Mitigation Plans** stage of the **Add Mitigation Plans** wizard, select the the Mitigation Plan Template assets that you want to associate with the asset.
4. In the **Map Risks and Stakeholders** stage of the **Add Mitigation Plans** wizard, select the risk that each plan addresses and the stakeholders who execute the plan. You can select only the stakeholders of the asset that is associated with the mitigation plan template. Enter the due date for each plan. Optionally, add the actions in the plan and evidence of their completion.
5. To associate the questionnaire template with the asset, click **Save**.

   When you associate a template, Data Governance and Catalog creates a mitigation plan instance.

Subsequent changes to the mitigation plan template don't apply to a mitigation plan instance. To use the latest version of a mitigation plan template, remove the mitigation plan instance and associate the updated template.

Manual data element

A manual data element is the business representation of data that might not be available in the catalog but is essential to capture for governance purposes in your organization.

A manual data element represents a data element that the business understands or consumes which might not directly translate to a technical data element. Manual data elements are not found in catalog sources and, therefore, their metadata is not extracted.

If you are a business user, you can manually create a data element within a data set. A data set can either have technical data elements or manual data elements or a combination of both. Although a manual data element is a type of business asset, it exists in a business data set and not as a standalone business asset. You can associate a manual data element with one business data set only.

If you want to create a large number of manual data elements, consider creating a custom catalog source for all the manual data elements in Metadata Command Center and scan the catalog source. You can also create a manual data element through API and bulk upload.

You can create a manual lineage between the manual data element and other assets to visually represent the complete flow of data between catalogued and non-catalogued assets. For more information about manual lineage, see the *Lineage types* topic in the *Asset Discovery* help.


Creating a manual data element

Create a manual data element that represents a data that might not be available in the catalog but is essential to capture for governance purposes in your organization. Enter properties that add technical or business context to the manual data element.

To create a manual data element in a business data set, perform the following steps:


1. Open a business data set in Data Governance and Catalog.
2. Select the **Contains** tab, and click the Add icon. Select **Create Manual Data Element** option.

   The **New Manual Data Element** dialog box opens.



3. Enter all the mandatory field values, and click **Create**.


   You have successfully created a manual data element.



Note: You cannot create a manual data element with the same name within a single data set. However, you can create a manual data element with the same name across different data sets.

4. Go back to the business data set, select the **Contains** tab, and click the Refresh icon.

   The manual data element that you created appears along with other technical data elements in the business data set.



Note: You cannot add stakeholders for a manual data element. Stakeholders are automatically inherited from the parent data set.

Technical assets

Technical assets are representations of data elements, technical data sets, data containers that Metadata Command Center extracts from a source system.

The technical assets that you see in Data Governance and Catalog depend on the configurations that your organization administrator applies in Metadata Command Center. These configurations include the metadata extraction settings for the catalog sources, the capabilities that are enabled, the profiling filters that are applied, the job schedules that are defined, and other factors. For more information about catalog source configurations, see *Administration* in the Metadata Command Center help.

The following list explains the various categories of technical assets that appear in Data Governance and Catalog:

- Data elements. Data elements are the smallest unit of data in a source system. Columns, files, fields are examples of data elements.
- Technical data sets. Technical data sets are collections of data elements. For example, a table is a technical data set as it is a collection of columns.
- Catalog sources. Catalog sources are objects that represent the source system from which you extract metadata. You can create catalog sources in Metadata Command Center to extract metadata from source systems like Amazon S3 and Oracle.

For more information about technical assets, see the *Understanding Technical Assets* help.

Assign stakeholders for technical assets

Understand how stakeholder assignments for technical assets work, including how inherited and specifically assigned stakeholders behave when you add, remove, or search for them.

The following conditions apply when you assign stakeholders to technical assets:

- By default, propagation is enabled in a technical hierarchy. If you don't assign stakeholders to technical assets, they inherit stakeholders from a parent asset.
- Controls for **Propagate Stakeholders** and **Append Stakeholders** appear only when you modify the stakeholders of the topmost asset in a technical hierarchy. A technical asset at an intermediate level of the hierarchy can only inherit stakeholders. It doesn't show its own propagation controls.
- If a user group is associated to an asset, you can view the stakeholders in the user group by expanding the user group on the **Stakeholders** tab of the asset page.
- When you search for `assets with stakeholders`, the search returns the parent assets along with the child assets that have inherited the stakeholders of the parent asset.
- If the parent asset has **Append Stakeholders** enabled, you can associate the assigned stakeholders alongside the asset's inherited stakeholders on the asset. The inherited stakeholders show as **Inherited**.

For more information about stakeholder propagation and inheritance, see "Propagate stakeholders to asset hiearchies" on page 42.

Creating AI models from technical assets

Create an AI Model business asset from an AI Model Core Version technical asset. When you create an AI model from a technical asset, you add business context and meaning to the technical asset. You can assign stakeholders to the AI Model.

The following prerequisites apply if you want to create an AI model asset from an AI Model Core Version technical asset:


- The organization administrator must grant you the **Create** permission for the AI Model business asset through access policies in Metadata Command Center.
- To establish associations between the AI Model and Data Set assets, the organization administrator must grant you the **Update** permission for the AI Model business asset, Data Set business asset, and the AI Model Core Version technical asset through access policies in Metadata Command Center.
- To assign stakeholders to the asset, the organization administrator must grant you the **Manage Access** permission on the asset through access policies in Metadata Command Center.

When you create an AI model from a technical asset, consider the following:

- You can import AI Model Core Version technical assets from only the Databricks source system.
- If the AI Model Core Version asset that you select is associated with more than 20 data sets, when you create the AI Model business asset, it initially has a maximum of 20 associated data sets. You can add additional associations after the AI Model asset is created.

1. Open the AI Model Core Version technical asset for which you want to create an AI Model business asset.


2. On the AI Model Core version asset page, click **Create AI Model**.



3. On the **Overview** tab of the **New AI Model** wizard, configure the properties of the AI Model asset that you want to create.


   The following table describes the fields that you can configure for the new AI Model asset:

Field	Description
Name	Name of the AI model.
Description	Functional definition of the AI model. The size of the field can't exceed 1 MB.
Asset Groups	The asset group of the AI model. Asset groups can be used in access policies to control access to assets.



4. To assign stakeholders to the AI model, click the add icon in the **Stakeholders** section.
5. In the **Modify Stakeholders** dialog box, select a role, and then select the users or user groups that you want to add as stakeholders to the asset. Click **OK**.
6. Click **Next**.

7. On the **Metrics** tab of the **New AI Model** wizard, select the evaluation metrics for the AI model. You can use the static value scanned from the source system or manually enter a value.



8. Click **Create** to create a new AI Model asset.


Creating data sets from technical assets

Create a data set from a technical asset, such as a table, to establish an automatic relationship between them. When you create a data set from a technical asset, you add business context and meaning to the technical asset. You can assign stakeholders to the data set, relate the data set to other assets, and view the data elements related to the data set.

The following prerequisites apply if you want to create a data set from a technical asset:

- The organization administrator must grant you the **Create** permission for the Data Set business asset through access policies in Metadata Command Center.
- To assign stakeholders to the asset, the organization administrator must grant you the **Manage Access** permission on the asset through access policies in Metadata Command Center.

1. Open the technical asset for which you want to create a data set.
2. On the **Overview** tab, click **Create Data Set**.



3. On the **New Data Set** page, enter the following properties of the data set that you want to create:

Field	Description
Name	Name of the data set.
Parent	Select the name of the parent AI system asset or the system asset to which the data set belongs.

Field	Description
Description	Description that adds meaning or context to the data set.
Reference ID	Unique identifier for the data set.

The data elements associated with the technical asset are displayed on the **Data Elements** section of the **New Data Set** page.

4. To run rule occurrences and data profiling tasks on data elements from multiple sources, perform the following steps:
   a. Select a source mapplet in the **Technical Reference** section and click **Next**.

      The output ports of the mapplet are automatically mapped to the data elements in the business data set based on the hierarchy match.

      Note: The following information is applicable for source mapplets:

      - A mapplet is a reusable transformation logic that you create in Data Integration. A source mapplet is a mapplet that has a source connection and a single output.
      - Before you select a source mapplet, verify that the source mapplet is valid. Also, verify that the source connections are associated with an active Secure Agent and test your connection.

   b. Map the data elements from the data set to the output ports from the source mapplet as needed, and then click **Save**.

      You can modify the mappings or exclude output ports from the mapping.

      Note: For a mapplet with output ports that don't trace back to columns in a technical data set, the output ports are not mapped automatically. For example, a query-type mapplet or a mapplet with calculated output ports such as fields derived from a transformation. You can create manual data elements to map such output ports.

      The mapplet is associated with the data set.
5. To assign stakeholders to the data set, click the add icon in the **Stakeholders** section.
6. In the **Modify Stakeholders** dialog box, select a role, and then select the users or user groups that you want to add as stakeholders to the asset. Click **OK**.
7. Click **Create** to create a new Data Set asset.

When you open the data set asset page, you see different tabs on the page. For more information about what each tab on the data set asset page means, see the *Understanding Business Assets* help.

Creating system assets from technical assets


Create a system asset from a catalog source to establish an automatic relationship between them. When you create a system from a catalog source, you add business context and meaning to the data contained in the catalog source. You can assign stakeholders to the system, relate the system to other assets, and more.

The following prerequisites apply if you want to create a system asset from a catalog source:

- The organization administrator must grant you the **Create** permission for the System business asset through access policies in Metadata Command Center.
- To assign stakeholders to the asset, the organization administrator must grant you the **Manage Access** permission on the asset through access policies in Metadata Command Center.

1. Open any catalog source asset for which you want to create a system.

2. On the **Overview** tab, click **Create System**.



3. On the **New System** page, enter the following properties of the system that you want to create.

Field	Description
Name	Name of the system.
Parent	Select another system asset to be the parent of the system asset that you are creating.
Description	Description that adds meaning or context to the system.
Reference ID	Unique identifier for the system.
System Type	Choose the type of the system that you want to create.
Purpose	Choose from a list of predefined values the purpose of the system that best describes its function.
Long Name	Name of the system that makes it identifiable in a business context.

   The catalog source associated with the system appears in the **Catalog Sources** section of the **New System** page.

4. To assign stakeholders to the system, click the add icon in the **Stakeholders** section.
5. In the **Modify Stakeholders** dialog box, select a role, and then select the users or user groups that you want to add as stakeholders to the asset. Click **OK**.
6. Click **Create** to create a new System asset.

When you open the system asset page, you see different tabs on the page. For more information about what each tab on the system asset page means, see the *Understanding Business Assets* help.

Propagate stakeholders to asset hiearchies

For assets in a hierarchy, you can configure parent assets to propagate its stakeholders to the child assets. You can also control the associations an asset can make with stakeholders.

Propagation in an asset hierarchy starts from a parent asset and continues downwards in the hierarchy to child assets. On a parent asset, you can configure settings that let you propagate stakeholders to child assets that are with and without stakeholders. You can enable stakeholder propagation in business and technical hierarchies.


You can enable stakeholder propagation on technical and business assets in the following manner:

Propagation on technical assets

When configuring a catalog source in Metadata Command Center, an administrator can enable propagation for technical hierarchies for the catalog source. The administrator assigns stakeholders to the catalog source and enables their propagation throughout the technical hierarchy. An administrator can also override the propagation settings for a catalog source from its Data Governance and Catalog asset page.

For more information, see *Stakeholder propagation in a catlog source* in the *Administration* help in Metadata Command Center.


The following image shows the propagation options for a catalog source in Metadata Command Center:



Propagation on business assets

On the asset type that you create, you can assign a parent-child relationship to an asset enabled with propagation. If you assign a new child asset to a parent asset's hierarchy, the child asset inherits the parent asset's stakeholders through propagation.

The following image shows different routes of stakeholder propagation on a new business asset:



For more information about parent-asset relationships, see *Parent-child relationships* in the *Asset Discovery* help. Also, see "Creating assets and assigning stakeholders" on page 28.

In Data Governance and Catalog pages for business assets, you can modify the settings for propagation when you modify stakeholders.

Details for stakeholder propagation also appear when you export assets. You can modify the propagate and apppend stakeholder columns in the export files and re-import them to configure stakeholder propagation through bulk import.

For more information about stakeholder propagation through bulk import, see *Update stakeholder propagation in bulk* in the *Bulk Import* help.

View and configure stakeholder propagation

Learn how you can manage propagation in an asset hierarchy to configure the stakeholders with the child assets can associate with.


Assigned and inherted stakeholders

On Data Governance and Catalog asset pages, the **Stakeholder** tab contains details pertaining to the asset's propagation and its stakeholders. The header of the **Stakeholder** grid indicates whether the asset's propagation and append is enabled or disabled. The **Stakeholder Source** column in the grid also shows how the asset associates with various stakeholders.

You can associate an asset with stakeholders through the hierarchy or through direct assignment. Depending on the type of association, a stakeholder on an asset is either inherited or assigned. You can configure an asset hierarchy to have inherited stakeholders, assigned stakeholders, or both .

In a hierarachy, the stakeholder associations you can create depend on a parent asset's propagation settings. If a parent asset is propagating, the stakeholders that the child assets receive show as **Inherited**. Associations created through assignments on the asset page or through bulk import show as **Assigned**.


The following image shows the a Metric asset with **Assigned** and **Inherited** stakeholders:



Propagation settings

For an asset, the **Modify Stakeholders** dialog box shows indications of a parent asset propagation on the asset. It also shows propagation options for the asset. You can configure the **Propagate Stakeholders** and **Append Stakeholders** options to control whether child assets inherit stakeholders and whether they keep their own stakeholders.

The following image shows the **Modify Stakeholders** dialog box with details of a parent asset's propagation on the asset and the **Stakeholder Source** column for the asset:



Select the following options in the **Modify Stakeholder** dialog box of an asset:

- **Propagate Stakeholders**. Allows child assets without stakeholders to inherit the stakeholders of the parent asset.
- **Append Stakeholders**. Allows child assets that already have **Assigned** stakeholders to inherit stakeholders from a parent asset.

  Note: To enable **Append Stakeholders**, you must enable **Propagate Stakeholders**.

Guidelines for propagation

Consider the following guidelines when you configure stakeholder propagation for a parent asset:

- If you disable **Propagate Stakeholders** after an asset propagates to child assets, the child assets lose the **Inherited** stakeholders propagated from its parent asset.
- If you disable **Append Stakeholders** after an asset propagates to child assets, the child assets lose their inherited stakeholders.
- If you disable **Propagate Stakeholders**, the child asset can have only **Assigned** stakeholders.
- If you enable **Propagate Stakeholders** and **Append Stakeholders**, the child asset can receive manually assigned stakeholders alongside stakeholders inherited from a parent asset.
- After you save changes to the propagation settings of an asset, a propagation job updates the child assets in the hierarchy.

Consider the following guidelines if want to modify an asset with a parent asset propagating stakeholders to it:

- You can assign stakeholders to an asset regardless of a parent asset's propagation settings.
- To remove an inherited stakeholder from an asset, remove the stakeholder from the parent asset that holds the original assignment.
- If you add or delete a stakeholder of a child asset, the stakeholder assignment of its parent asset remains unchanged.
- If you assign a stakeholder to an asset whose parent asset has **Append Stakeholders** disabled, it replaces the stakeholders the child inherited from the parent asset. Only assigned stakeholders remain on the asset.

Associate reference data from Reference 360

You can associate reference data from Reference 360 with business terms, metrics, manual data elements, and data elements in Data Governance and Catalog.

From Data Governance and Catalog, you can browse reference data sets and view code values of various reference data. You can link data elements either to new reference data or to existing glossaries already associated with reference data. You can assign reference data only if you are a stakeholder of the asset.

Ensure that your organization administrator grants the minimum required privileges and permissions to your user role.

The following shows the requirements for user roles to associate and modify reference data with assets:

- The **View Reference Data** privilege for Data Governance and Catalog in Administrator
- The **Read** permission for the asset type, configured through access policies in Metadata Command Center
- The Reference 360 Basic Edition license
- An IDMC catalog source in Metadata Command Center that extracts Reference 360 metadata
- The **Update** permission for the asset type, configured through access policies in Metadata Command Center
- A Reference 360 Business Analyst role
- Stakeholder access on the asset

Note: The **View Reference Data** privilege and the **Read** permission allow you to see reference data. The **Update** permission allows you to associate or change it.

Reference 360 simplifies access to reference data through Data Governance and Catalog and offers a marketplace where trusted reference data is easily shared and available to anyone who needs it.

For more information about configuring catalog sources, see the *Catalog Source Configuration* module in Metadata Command Center.

For more information, see the following topics:

- "Associating reference data with business terms or metrics" on page 47
- "Associating reference data with manual data elements" on page 48
- "Associating reference data with data elements" on page 49


Associating reference data with business terms or metrics

You can view and associate reference data from Reference 360 with business terms and metrics. You can browse available reference data sets, and view attributes of the sample code values. From the asset, you can also navigate to Reference 360 to view more code values.

To associate reference data from Reference 360 to a business term or a metric, perform the following steps:

1. Open the asset, and go to the **Reference Data** tab.
2. Click **Add Reference Data.** The **Select Reference Data** dialog box appears. Optionally, you can also add reference data from the **Reference Data** panel of the **Overview** page.

3. From the **Select Code List** tab, select the code list that you want to associate with your business term or metric and click **Next**.



4. From the **Select Attribute** tab, select the attributes of the code values you want to associate with business term or metric.
5. Click **Finish**.

   The first 50 code values from the code list is displayed in the **Reference Data** tab. You can navigate to Reference 360 to view the complete list of code values.

   To associate a different reference data that is more suitable with the asset that is opened, click **Change Reference Data**.

   To remove the associated reference data, click the **Remove associated reference data** icon.

Associating reference data with manual data elements

You can view and associate reference data from Reference 360 with manual data elements. You can associate the manual data element with a new reference data or link the manual data element to a glossary that is already associated with reference data.

To associate reference data from Reference 360 to a manual data element, perform the following steps:

1. Open the manual data element, and go to the **Reference Data** tab.
2. Click **Add Reference Data**. The **Select Reference Data** dialog box appears.
3. From the **Select Attribute** tab, select the attributes you want to associate the manual data element.
4. Click **Save**.
5. If you selected **New reference data**, from the **Select Code list** section, select a code list you want to associate with your manual data element and click **Next**.

   You can view additional information of the selected code list.

6. From the **Select Attribute** tab, select the attributes you want to view in the **Reference Data** tab and click **Finish**.

   The **Reference Data** tab displays the first 50 code values.
   To view the complete list of code values, click **Reference 360** beside the data set name to navigate to Reference 360.

   To associate a different reference data that is more suitable with the asset that is opened, click **Switch Reference Dataset**.

   To remove the associated reference data, click the **Remove associated reference data** icon.


Associating reference data with data elements

You can view and associate reference data from Reference 360 with data elements. You can associate the data element with a new reference data or link the data element to a glossary that is already associated with reference data.

To associate and view reference data, the following privileges and permissions are required for your role:

- You should have a Reference 360 Business Analyst role.
- Your organization must have the Reference 360 Basic Edition license.
- Your administrator must configure the IDMC catalog source in Metadata Command Center and must extract Reference 360 metadata.
- Your role must have the **View Reference Data** privilege for Data Governance and Catalog in Administrator.
- Your role must have the **Read** and **Update** permissions for the specific asset types. This permission is configured through access policies in Metadata Command Center.

1. Open the data element, and go to the **Reference Data** tab.
2. Click **Add Reference Data**. The **Select Reference Data** dialog box appears.



3. Choose from the options to indicate how you want to associate the reference data with the data element.

Option	Description
Reference data linked to the glossary	Associate the data element with a glossary that already has an associated reference data.
New reference data	Associate the data element with new reference data from Reference 360.

4. If you selected **Reference data linked to the glossary**, from the **Select Glossary** section, select the glossary you want to associate with your data element.
5. From the **Select Attribute** tab, select the attributes you want to associate the data element.
6. Click **Save**.
7. If you selected **New reference data**, from the **Select Code list** section, select a code list you want to associate with your data element.

   You can view additional information of the selected code list.
8. Click **Next**.
9. From the **Select Attribute** tab, select the attributes you want to view in the **Reference Data** tab.
10. Click **Save**.

    The **Reference Data** tab displays the first 50 code values.
    To view the complete list of code values, click **Reference 360** beside the data set name to navigate to Reference 360.

    To associate a different reference data that is more suitable with the asset that is opened, click **Switch Reference Dataset**.

    To remove the associated reference data, click the **Remove associated reference data** icon.

Modifying assets

To modify an asset, you can modify the details of an asset, change its properties, add hierarchical assets, or assign new stakeholders.

If you want to modify business or technical assets, ensure that you meet the following prerequisites:


- The organization administrator must grant you the **Update** permission on the asset through access policies in Metadata Command Center.
- If there's a workflow configured for the asset, then the organization administrator must enable the **Participate in Change Approvals** privilege for your user role in Administrator.
- To modify the stakeholders for assets, the organization administrator must grant you the **Manage Access** permission on the asset through access policies in Metadata Command Center.
- You cannot publish the draft version of an asset if there are inactive stakeholders associated with the asset. First, delete the inactive stakeholders from the **Stakeholders** tab of an asset to start the workflow for the asset.

For more information about the available permissions and privileges for managing access to assets, see Chapter 2, “Manage access to assets” on page 8.

Perform the following steps to modify an asset:

1. Open the asset that you want to modify.
2. On the panel that you want to modify, click the **Edit** icon.
3. Modify the asset description or attributes, and click **Save**.

   If you are the stakeholder of the asset or if the organization administrator has configured a workflow for the asset, the **Lifecycle** status changes to Draft.
4. Click **Submit** to send the latest changes to the stakeholders defined in the workflow.



Note: You can delete the modifications made to the asset if they're no longer needed by clicking the action menu on the asset page and selecting **Delete Draft Version**. You cannot delete the draft version of the asset in the following conditions:

- If the asset has incoming relationships with other assets.
- If the asset has outgoing parent-child relationships with other assets.
- If the asset has outgoing and indirect parent-child relationships with other assets.
- If the asset has tickets in the **Open** status.

Obsolete assets

If some business assets are no longer of active interest to the organization, you can manually change the lifecycle status of such business assets to `Obsolete`. You can use these assets to generate reports for audits. You can make the lifecycle status of an asset to `Obsolete` only when the asset is in `Published` lifecycle status and not in `Draft` or `In Review` lifecycle status.

When the lifecycle status of an asset changes from `Published` to `Obsolete`, the existing recommended glossary associations are deleted.

You can take the following actions on obsolete assets if your organization administrator has granted you the **Update** permission on the asset through access policies in Metadata Command Center:

- View and change the description of the obsolete asset.
- Delete an existing relationship of the obsolete asset.
- Remove an existing reference data set association from the obsolete asset.

- Update the stakeholders for the obsolete asset.
- Add comments to the obsolete assets.

If your organization administrator grants you the **Manage Access** permission on the asset, you can assign a stakeholder for the asset and modify the asset groups for the asset.

However, you can't take the following actions on obsolete assets:


- Add a new relationship to the obsolete asset.
- Associate reference data set with an obsolete asset.
- Create tickets for obsolete assets.
- Update the lifecycle status of data quality rule occurrences and data quality rule templates to `Obsolete`.
- Add new data elements to obsolete asset.

Changing between Published and Obsolete lifecycle status


You can change between `Published` and `Obsolete` lifecycle status for business assets only.

To change the lifecycle value of a business asset from `Published` to `Obsolete`, perform the following steps:

1. Open the business asset.
2. Click the **Action** menu.
3. Click **Change to Obsolete Lifecycle**.




4. In the **Change Lifecycle Status** dialog box, click **OK**.




To change the lifecycle value of a business asset from `Obsolete` to `Published`, perform the following steps:

1. Open the business asset.
2. Click the **Action** menu.
3. Click **Change to Published Lifecycle**.



4. In the **Change Lifecycle Status** dialog box, click **OK**.



Deleting assets

If a business asset is no longer relevant, you can delete the asset.

To delete assets in Data Governance and Catalog, ensure that you meet the following prerequisites:

- Your organization administrator must grant you the **Delete** permission on the asset through access policies in Metadata Command Center.
- If the organization administrator enables the **Force Delete** privilege for your user role in Administrator, you can delete assets along with all its inbound relationships and the child assets involved in the hierarchy. For example, consider a scenario where a domain asset called 'Finance' is the parent of the subdomain asset 'Retail Finance', and the subdomain asset 'Retail Finance' is the parent asset of the business term asset 'Org Finance'. If a user with the **Force Delete** privilege deletes the 'Retail Finance' subdomain, all the parent-child relationships are deleted and the child business term asset 'Org Finance' is also deleted.


- You cannot delete an asset that has inbound or outbound parent-child relationships with other assets. This is because the other assets are directly dependent on this asset. However, if there is a business asset that has data quality scores, you can delete the asset if it has an outbound parent-child relationship with another asset. To see if the asset is involved in any inbound or outbound relationship, see the **Relationships** tab on the asset page.
- You cannot delete any asset that has an associated workflow ticket in the **Open** status. If you delete an asset that has associated workflow tickets in the **Closed** status, the asset is deleted along with the closed workflow tickets.

You can delete business assets from Data Governance and Catalog if the asset that you are trying to delete or its child assets do not have open tickets associated with them.

To delete an asset that you no longer need, perform the following steps:

1. Open the business asset that you want to delete.
2. From the Action menu on the top right corner of the page, select **Delete Asset**.

   The following image shows the Action menu on a sample Metric asset page:



3. A delete warning appears. If there are any tickets in the **Open** status associated with the asset or its child assets, ensure that the tickets are in the **Closed** status in order to delete the asset. Click **Delete** to confirm.

CHAPTER 4

Enrich technical assets

You can enrich your catalog assets to add business context to the technical metadata from catalog sources. Enrichment enhances searchability and transforms your technical metadata into trusted, contextualized assets in the catalog.

Curate technical assets with glossary

As a stakeholder, you can curate technical assets with glossaries to add more business context to your technical metadata and to make your data easily discoverable.

When you curate technical assets with glossaries, you either accept or decline the glossaries recommended for technical assets, or you manually associate technical assets with one or more glossary assets. Data Governance and Catalog can also automatically associate suitable glossaries with technical assets.

You can curate technical assets with glossaries from the following locations in Data Governance and Catalog:

- The **Overview** tab or the **Contains** tab of technical asset pages.
- The **Curation Center** page, where you can review and act on the enrichment recommendations for all your catalog source assets in one place. For more information, see Chapter 5, “Curation Center” on page 77.

Prerequisites

The following prerequisites apply if you want to curate technical assets with glossaries:

- The glossary asset should be in the **Published** lifecycle stage.
- Your organization administrator must grant you the **Read** permission on business glossary assets and the **Update** permission on technical assets through access policies in Metadata Command Center.
- The glossary asset type must be a business term or a metric.
- The technical asset that you want to curate must be a data element, a technical data set, or an unstructured file in a supported file format.

Automatically associate glossary with technical assets

Data Governance and Catalog can infer and automatically associate meaningful glossary assets with your technical assets.

Configuration in Metadata Command Center


Your organization administrator can automatically associate glossary with technical assets:

- Enable the **Glossary Association** capability for the catalog source and select the **Enable Auto-Acceptance** option in Metadata Command Center. Based on the confidence score that the administrator specifies, glossary assets are automatically accepted or recommended for the technical assets in Data Governance and Catalog. For information about the glossary association configuration settings, see *Administration* in the Metadata Command Center help.
- Select the **Enable Lineage-based Propagation** option on the **Automation** tab of the catalog source configuration in Metadata Command Center. The administrator can specify how the catalog source assets receive enrichments propagated from connected catalog sources. Based on the settings, glossary assets are either auto-accepted or recommended for the technical assets. For more information about configuring lineage-based propagation, see *Administration* in the Metadata Command Center help.

Behavior in Data Governance and Catalog

When you open the **Overview** tab for a technical asset in Data Governance and Catalog, glossary assets may appear in the **Accepted** list or in the **CLAIRE® Recommendations** list. The accepted glossary asset is assigned as the business name of the asset. If there are several automatically accepted glossary assets with the same confidence score, the first asset in the alphabetical order is assigned as the business name of the technical asset. You can accept or decline recommended glossary business names and descriptions. For more information, see "Accept or decline recommended glossary for technical assets" on page 56.

The following image shows a sample asset page for a column named `Phone Number_Demo`. The **Glossaries** panel shows the automatically accepted and CLAIRE® recommended terms:



In the above example image, the column named `Phone Number` belongs to an Oracle catalog source. Assume that the confidence score threshold defined for the catalog source in Metadata Command Center is 86%. The business term `Phone Number` matches the column with a confidence score of 88%, and the term is automatically accepted as the business term for the column.


Accept or decline recommended glossary for technical assets

Data Governance and Catalog can recommend glossary terms for the technical assets through the **Glossary Association** or **Lineage-based Propagation** enrichment sources in Metadata Command Center.

You can accept or decline business names and descriptions for technical assets from the following locations in Data Governance and Catalog:

- The **Overview** tab or the **Contains** tab of technical asset pages.
- The **Curation Center** page, where you can you can review and act on the enrichment recommendations for all your catalog source assets in one place. For more information, see Chapter 5, “Curation Center” on page 77.

The following image shows the CLAIRE® recommended term and the options for accepting or declining the recommendation for the sample column `PHONE_NUMBER`:




For each CLAIRE® recommendation, you can perform one of the following actions:

- Select **Accept** to accept the CLAIRE® recommendation. The glossary asset then moves to the **Accepted** list.
- Select **Decline** to decline the CLAIRE® recommendation. The glossary asset then moves to the **Declined** list.
- Select **Accept and save as Business Name** to accept the CLAIRE® recommendation and assign this glossary asset as the business name of the asset. The asset then moves to the **Accepted** list and the business name of the asset is assigned.
- Select **Accept and Decline other CLAIRE Recommendations** to accept only this glossary asset and decline other recommended assets. The accepted glossary asset then moves to the **Accepted** list and other recommendations are moved to the **Declined** list.

Optionally, you can bulk accept or decline all CLAIRE® recommended glossary assets at once. You can also bulk accept all the declined glossary assets or decline all accepted glossary assets.


The following image shows the options for bulk accepting and declining glossary assets for a column:



Manually associate glossary with technical assets


If you want to associate specific business terms or metrics with technical assets, you can manually associate them in one of the following ways:

- From the **Overview** tab of a technical asset page. To manually associate glossary assets, click the add icon on the **Glossaries** panel to open the **Add Glossary Assets** dialog box. In the dialog box, you can select one or more meaningful glossary assets to associate with the technical asset and then choose to assign the business name, description, and reference data from one glossary asset to the technical asset.
  The following image shows the **Add Glossary Assets** dialog box that highlights the selected business terms to associate with the technical assets, along with the option to assign the business name, description, and reference data from one glossary asset to the technical asset.



After you associate the glossary assets, you can select one glossary asset to assign as the business name of the technical asset.


The following image shows the **Add Glossary Assets** dialog box with the highlighted option to select one glossary asset to assign as the business name of the technical asset:



After you assign a business name, you can choose to link the asset to the reference data that is already associated with the glossary. Then, you can select one code list attribute from the reference data to associate with the technical asset.

After you save and finish the changes, the selected glossary assets appear in the **Accepted** section of the **Glossaries** panel. The business name, description and reference data of the technical asset changes to the name, description and the reference data of the glossary asset that you selected.

- From the **Contains** tab of a technical data set page. Use the **Curate** option from the Action menu on the data element that you want to curate. The **Curate Glossaries and Data Classifications** dialog box opens. On this dialog box, you can manually associate glossaries with specific data elements.
  The following image shows the **Contains** tab of a table:




Remove all declined glossary assets

You can remove the glossary assets that are declined for a technical asset.

Optionally, you can bulk remove all of the glossaries. To bulk remove all the declined glossaries for a technical asset, click the action menu and select the appropriate option.

The following image shows the option for bulk removing declined glossary assets:




Associate business names and descriptions with technical assets

For better governance of technical assets, you can assign meaningful business names and descriptions to technical assets. Business names make the technical assets meaningful, readable, and identifiable.

You can automatically assign business names and descriptions to technical assets, accept or decline recommended business names, or manually assign business names to technical assets.

The following image shows a technical asset with an automatically assigned business name:



Prerequisites and guidelines

The following prerequisites and guidelines apply if you want to associate business names and descriptions to technical assets:

- Your organization administrator must grant you the **Read** permission on the glossary business assets and the **Update** permission on technical assets through access policies in Metadata Command Center.
- The technical asset to which you want to assign a business name should be a data element, a technical data set, or an unstructured file, such as a PDF, DOC, DOCX, or PPT file.
- The glossary asset that you want to associate should be in the **Published** lifecycle stage.
- You can use the name and description of an existing business term or metric asset to associate with a technical asset.
- If a business term and a metric asset are associated with the same technical asset from a catalog source, and you decline the business name recommendation from either the business term or the metric, the business name disappears from the technical asset.
- If you edit the business name, change the description, and decline the recommendation of an automatically associated business term or metric, the existing business name and description do not disappear.
- When you link a technical asset to a glossary asset so that the technical asset obtains its name and description from the glossary asset, Data Governance and Catalog can automatically update the technical asset details if the name or description of the glossary asset changes.
  If the glossaries were assigned manually through UI or bulk import to technical data elements, to automatically update the business name and description, perform the following actions:
  1. Export the assets.
  2. Set the **Automatic Assignment** column value to **Enabled**.

3. Verify the values in the **Glossary:Accepted** and **Business Name** columns.
4. Reimport the file to trigger glossary synchronization.

Automatically assign business names and descriptions

You can automatically assign meaningful business names and descriptions to technical assets to enhance clarity and governance.

Configuration in Metadata Command Center

Your organization administrator can automatically assign business names and descriptions to technical assets in the following ways:

- In Metadata Command Center, enable the **Glossary Association** capability for the catalog source and select the **Enable Auto-Acceptance** option. Based on the confidence score that the administrator specifies, glossary assets are automatically accepted or recommended for the technical assets in Data Governance and Catalog.
  The administrators can also specify whether to assign business names and descriptions only to the assets that don't already have them or assign to all assets. If they choose the latter option, the system overwrites the existing business names and descriptions. By default, the system assigns business names only to the assets that don't already have them. For more information about the glossary association configuration settings, see *Administration* in the Metadata Command Center help.
- In Metadata Command Center, select the **Enable Lineage-based Propagation** option on the **Automation** tab of the catalog source configuration in Metadata Command Center. The administrator can specify how the catalog source assets receive enrichments propagated from connected catalog sources. Based on the settings, glossary assets are either auto-accepted or recommended for the assets in the catalog source. For more information about configuring lineage-based propagation, see *Administration* in the Metadata Command Center help.

Behavior in Data Governance and Catalog

When you open the **Overview** tab for a technical asset in Data Governance and Catalog, glossary assets may appear as accepted in the **Accepted** list or as recommendations in the **CLAIRE® Recommendations** list based on the specified criteria. You can accept or decline recommended glossary business names and descriptions. For more information, see "Accept or decline recommended glossary for technical assets" on page 56.

The name and description of the accepted glossary asset are automatically assigned to the associated technical asset. If multiple glossary assets are accepted with the same confidence score, the name and description of the asset that appears first in alphabetical order is assigned to the associated technical asset.

Accept or decline recommended business names and descriptions

Data Governance and Catalog can recommend glossary business names and descriptions for the catalog source assets through the **Glossary Association** or **Lineage-based Propagation** enrichment sources in Metadata Command Center.

You can accept or decline business names and descriptions for technical assets from the following locations in Data Governance and Catalog:

- The **Overview** tab or the **Contains** tab of technical asset pages.
- The **Curation Center** page, where you can you can review and act on the enrichment recommendations for all your catalog source assets in one place. For more information, see Chapter 5, "Curation Center" on page 77.

For each CLAIRE® recommendation, you can perform one of the following actions:

- Select **Accept** to accept the CLAIRE® recommendation. The glossary asset then moves to the **Accepted** list.
- Select **Decline** to decline the CLAIRE® recommendation. The glossary asset then moves to the **Declined** list.
- Select **Accept and save as Business Name** to accept the CLAIRE® recommendation and assign this glossary asset as the business name of the asset. The asset then moves to the **Accepted** list and the business name of the asset is assigned.
- Select **Accept and Decline other CLAIRE Recommendations** to accept only this glossary asset and decline other recommended assets. The accepted glossary asset then moves to the **Accepted** list and other recommendations are moved to the **Declined** list.

To accept or decline business names and descriptions simultaneously for multiple data elements in a catalog source, perform the following steps:

1. From the **Contains** page of the technical data set page, select the data elements for which you want to accept or decline business names and descriptions.
   The **Business Name** and **Description** columns display CLAIRE's recommendations.
2. From the Action menu for the selected data elements, use one of the following options:
   - To accept CLAIRE's recommendations for business names, select the **Accept Recommendations** > **Business Names** option. To accept CLAIRE's recommendations for descriptions, select the **Accept Recommendations** > **Descriptions** option in the Action Menu.
   - To decline CLAIRE's recommendations for business names, select the **Decline Recommendations** > **Business Names** option. To accept CLAIRE's recommendations for descriptions, select the **Accept Recommendations** > **Descriptions** option in the Action Menu.


Manually assign business names and descriptions

You can manually assign business names and descriptions for technical assets from the following locations in Data Governance and Catalog:

- The **Overview** tab or the **Contains** tab of technical asset pages.
- The **Curation Center** page, where you can you can review and act on the enrichment recommendations for all your catalog source assets in one place. For more information, see Chapter 5, “Curation Center” on page 77.

To manually assign business names and descriptions to catalog source assets, you can either type them directly, generate them using CLAIRE, or select a published glossary asset that is already associated with the technical asset.

To do so, open the technical asset and click the edit icon next to the name of the asset on the header of the page. The following image shows the edit icon next to the name of the column on the header of the column asset page:




In the **Edit Business Name** dialog box, use one of the following options to assign a business name to the technical asset:

- **Type or use CLAIRE to generate a business name**. Select this option to add your own business name. You can manually enter a business name or leverage CLAIRE to generate a business name. To use CLAIRE to generate a business name, click the **Generate with CLAIRE** icon. You can specify the industry context in which you want CLAIRE to generate the business name, and also specify the length of the generated name.


  Note: If you want to use CLAIRE to generate a business name or description for a technical asset, your organization administrator must enable the **Enable CLAIRE Generative AI Services** setting in Administrator.
- **Select from accepted glossaries**. Select this option to use the name of a glossary asset that is already associated with the technical asset.
- **Link asset to the associated reference data**. Optionally, you can link the technical asset to the reference data that is associated with the glossary that you selected. For more information,
- **Select Attribute**. Select one code list attribute from the reference data to associate with the technical asset.

The following image shows the **Edit Business Name** dialog box:



To add a description to a technical asset, open the technical asset and click the edit icon in the **Description** section. You can manually enter a description or leverage CLAIRE to generate a description. To use CLAIRE to generate a description, click the **Generate with CLAIRE** icon. You can specify the industry context in which you want CLAIRE to generate the description, and also specify the length of the generated description.


The following image shows the **Description** section of a technical asset:



You can also generate business names and descriptions simultaneously for multiple data elements of a technical data set. You can generate business names and descriptions simultaneously for a maximum of 20 data elements. Perform the following steps:

1. Open the **Contains** tab of a technical data set page.
2. Select the data elements to which you want to add business names and descriptions.
3. In the Action menu for the selected data elements, click **Generate Text**.
4. In the **Generate Text** dialog box, specify whether you want to generate a business name or description. You can also specify the industry context in which you want CLAIRE to generate the description, and also specify the length of the generated description.

The following image shows the **Contains** tab of a technical asset:



Curate technical assets with data classifications

As a stakeholder, if you want to label or classify data into various categories that are critical to your organization, you can curate the technical assets in your catalog with data classifications.

You can curate technical assets with data classifications from the following locations in Data Governance and Catalog:

- The **Overview** tab or the **Contains** tab of technical asset pages.
- The **Curation Center** page, where you can review and act on the enrichment recommendations for all your catalog source assets in one place. For more information, see Chapter 5, “Curation Center” on page 77.

Prerequisites

The following prerequisites apply if you want to curate technical assets with data classifications:

- The data classifications should be in the Published **Lifecycle** stage.
- The organization administrator must grant you the **Read** permission on data classification assets and the **Update** permission on technical assets through access policies in Metadata Command Center.
- You can associate data classifications that have been configured with or without inclusion rules in Metadata Command Center.

Automatically associate data classifications with technical assets

Data Governance and Catalog can infer, recommend or automatically associate data classifications with technical assets.

Your organization administrator can automatically associate data classifications with technical assets in the following ways:

- Enable the **Data Classification** capability for the catalog source and add data classification rules in Metadata Command Center. Based on the data classification rules defined, the system infers one or more data classifications for the catalog source assets. If your role has the required privileges, you can see the inferred data classifications in the **Accepted** data classification section of the asset pages in Data Governance and Catalog. You can decline the data classification association if it is not suitable to your business context. For more information about configuring data classification, see *Administration* in the Metadata Command Center help.
- Select the **Enable Lineage-based Propagation** option on the **Automation** tab of the catalog source configuration in Metadata Command Center. The administrator can specify how the catalog source assets should receive data classification enrichments from connected catalog sources. Based on the settings, data classifications are either auto-accepted or recommended for the technical assets in Data Governance and Catalog. You can accept or decline recommended data classifications for assets. For more information about configuring lineage-based propagation, see *Administration* in the Metadata Command Center help.

For information about accepting or declining inferred data classifications, see “Accept or decline inferred data classifications” on page 66.

Accept or decline inferred data classifications

Data Governance and Catalog can recommend data classifications for technical assets if your organization administrator has enabled lineage-based propagation for the catalog source and selected the **Recommended** option in Metadata Command Center. For more information about configuring lineage-based propagation, see *Administration* in the Metadata Command Center help.

Data classifications appear as suggestions that you can accept or decline. You can accept or decline data classifications for assets from the following locations in Data Governance and Catalog:

- The **Overview** tab of technical asset pages.
- The **Curation Center** page, where you can review and act on the enrichment recommendations for all your catalog source assets in one place. For more information, see Chapter 5, “Curation Center” on page 77.


If the recommended or accepted data classifications for the technical asset are not suitable, you can decline the data classifications. The declined classifications move to the **Declined** section of the **Data Element Classifications** or **Data Entity Classifications** panel.

Manually associate data classifications with technical assets


If you want to associate specific data classifications with technical assets, you can manually add data classifications to technical assets in Data Governance and Catalog. To manually associate data classifications with technical assets, perform one of the following actions:

- On the **Data Element Classifications** or **Data Entity Classifications** panel, click the add icon, and select one or more data classifications to associate with the data element or the data set.
  The associated data classifications appear in the **Accepted** section of the **Data Element Classifications** panel for a data element or in the **Data Entity Classification** panel for a data set.

  The following image shows the add icon and the manually associated classifications in the **Data Elements Classifications** panel on the column page.




- On the **Contains** tab of a technical data set page, use the **Curate** option from the Action menu on the data element that you want to curate. This opens the **Curate Glossaries and Data Classifications** dialog box. On this dialog box, you can manually associate data classifications with specific data elements.
  The following image shows the **Contains** tab of a table:



Bulk accept or decline inferred and manually associated data classifications

You can also bulk accept or decline all inferred and manually associated data classifications for a column or a table. To bulk accept or decline data classifications for a technical asset, click the action menu and select the appropriate option.

The following image shows the options for bulk accepting or declining data classifications:




Remove declined data classifications

You can remove the data element classifications and data entity classifications that are declined for a technical asset.

Optionally, you can bulk remove all of the declined data classifications. To bulk remove all the declined classifications for a technical asset, click the action menu and select **Remove All Declined Classifications**.

The following image shows the option for bulk removing declined data classifications:



Curate unstructured technical assets with document classifications

As a stakeholder, if you want to label or classify unstructured data into different categories specific to your organization, you can curate unstructured technical assets with document classifications in Data Governance and Catalog. You can use document classification to classify PDFs, text files, and Microsoft Word files.

To associate technical assets with document classifications, the organization administrator must grant you the **Read** permission on document classification assets and the **Update** permission on technical assets through access policies in Metadata Command Center.

Automatically associate document classifications with technical assets

In Metadata Command Center, administrators can create document classifications and specify the confidence score threshold for auto-acceptance and recommendations. When the document classification capability for the catalog source is enabled, relevant document classifications are either automatically accepted or recommended for the technical assets in Data Governance and Catalog. All document classifications that match or exceed the specified confidence score are automatically accepted and appear in the **Accepted** list. All document classifications that are below the specified confidence score appear as recommendations in the **Recommended** list. For more information about creating and configuring document classification, see *Administration* in the Metadata Command Center help.

If your role has the required privileges, you can see the **Accepted** and **Recommended** document classifications on the asset pages in Data Governance and Catalog. You can either accept the recommended document classifications to associate them to technical assets, or decline the document classification associations. For information, see "Accept or decline inferred document classifications" on page 69.

Accept or decline inferred document classifications

Data Governance and Catalog can recommend document classifications for unstructured assets if your organization administrator has configured document classification capability for the catalog source in Metadata Command Center.

Based on your business context, you can accept or decline recommended document classifications. If the automatically accepted document classifications for the asset are not suitable, you can decline them from the **Accepted** section.

You can accept or decline document classifications for assets from the following locations in Data Governance and Catalog:

- The **Overview** tab of technical asset pages.
- The **Curation Center** page, where you can review and act on the enrichment recommendations for all your catalog source assets in one place. For more information, see Chapter 5, "Curation Center" on page 77.

Manually associate document classifications with technical assets

If you want to associate specific document classifications with technical assets, you can manually add document classifications to technical assets in Data Governance and Catalog. Your organization administrator creates the document classifications in Metadata Command Center. In Data Governance and Catalog, you can manually associate the document classifications with assets even if the classification engine is not trained with the document classifications in Metadata Command Center.

To manually associate data classifications with technical assets, go to the **Document Classification** panel of the asset page. Click the add icon, and select one or more document classifications to associate with the asset. The associated classifications appear in the **Accepted** section.

Bulk accept or decline associated document classifications

You can also bulk accept or decline inferred and manually associated document classifications for an asset. Click the action menu and select the appropriate option.

Optionally, you can bulk remove all of the declined data classifications for the technical asset. To bulk remove all the declined classifications for a technical asset, click the action menu and select **Remove All Declined Classifications**.

Working with generated classifications


Use CLAIRE to automatically generate data classifications for the data elements extracted from the source system. CLAIRE can identify, analyze, and classify the data contained in the data elements without any human input.

If you enable the **Generated Data Classification** option in Metadata Command Center while configuring a catalog source, CLAIRE identifies and automatically generates data classifications for the data elements of that catalog source. On the technical asset page for data elements belonging to the catalog source, you can view the generated classifications.

You can view generated classifications only if your organization administrator has granted you the **Read** permission on data classification assets through access policies in Metadata Command Center.

You can promote, reject, or demote a generated classification. The following image shows the lifecycle of a generated classification:

Figure 1.



Promoting a generated classification

You can promote a selected generated classification to a data element classification so that it can be associated automatically with the columns in a data element. Promotion means associating generated classifications to data element classifications and also to data elements associated with generated classifications.

You can promote generated classifications only if your organization has granted you the following permissions and privileges:

- **Read**, **Create**, and **Update** permissions on data classification assets through access policies in Metadata Command Center
- **Update** permission on technical assets associated with generated classifications, granted through access policies in Metadata Command Center
- **Manage Data Classifications** privilege for the Metadata Command Center service in Administrator

To promote a generated classification, perform the following steps:

1. On the generated classification page, click **Promote** on the top right corner or click the **Promote Generated Classification** option in the **Promotion** section to associate the generated classification with the data element classification.
2. To promote a generated classification to associate an existing data element classification, select the data element classification from the existing list and enter the following information:

Field	Description
Data Element Classification	Name of the data element classification.
Sensitivity	Sensitivity of the data element classification.
Description	Description of the data element classification.

3. To promote a generated classification to associate with a newly created data element classification, enter the details about the new data element classification that you want to create:

Field	Description
Name	Name of the new data element classification.
Description	Description of the new data element classification.
Sensitivity	Sensitivity of the new data element classification.

4. Click **Promote**. A generated classification promotion job is triggered.
5. Click **View Status** to view the progress of the promotion job or go to the **Job Monitoring** page to see the job status. After a promotion job is complete, you can view the data element classification that is associated with the generated classification on the generated classification asset page.

   Note: You cannot promote or reject the generated classification while the promotion job is in progress.

Rejecting a generated classification


To remove the generated classification from the system, you can reject a generated classification. To reject a generated classification, ensure that your organization administrator enables the **Curate Data Classifications**

privilege for Data Governance and Catalog and **Manage Data Classifications** privilege for Metadata Command Center.

You can reject generated classifications only if your organization has granted you the following permissions and privileges:

- **Read**, **Update** and **Delete** permissions on data classification assets through access policies in Metadata Command Center
- **Update** permission on technical assets associated with generated classifications, granted through access policies in Metadata Command Center

▶ On the generated classification page, click **Reject** on the top right corner to remove the generated classification. The generated classification is no longer discoverable in the catalog.



Rejecting associations from a generated classification

You can also reject a maximum of 25 associations from a generated classification at a time in any one of the following ways:

1. Select the associations you want to reject. Click **Reject** from the selection list. You can reject multiple associations.
2. Select the association you want to reject. Clear the selected associations from the **Generated Classifications** section on the asset page. You can only remove one selected association.

   Note: You can remove the associations even after the generated classification is promoted.

Demoting a generated classification

To remove the association of the generated classification with the data element classification, you can demote a generated classification.

You can demote generated classifications only if your organization has granted you the following permissions and privileges:


- **Read**, **Update** and **Delete** permissions on data classification assets through access policies in Metadata Command Center
- **Update** permission on technical assets associated with generated classifications, granted through access policies in Metadata Command Center

- **Manage Data Classifications** privilege for the Metadata Command Center service in Administrator

You can run a demotion job only after the promotion job of the generated classification is complete. A demotion job is triggered when you remove the association of the data element classification with the generated classification.

1. View the promoted generated classification in the generated classification asset page.
2. Clear the data element classification to remove the association of the generated classification with the data element classification. When you clear the entry, the classification is no longer promoted.

   Note: When you clear the created classification, the classification is discoverable, but it is no longer promoted as the mentioned classification.



Example of promoting, demoting and rejecting a generated classification

Assume you are a user who wants to promote a generated classification. In this example, if City is the generated classification for columns C1, C3, C4, and C6 in a table and you promote this generated classification as USA City, then the columns C1, C3, C4, and C6 have the values as USA City. If you run a generated classification job and want to add columns C7 and C9 to the same table later, you can promote these columns as USA City.

When you want to add newer columns, C10 and C11 to the table and do not want to promote the new columns as USA City, you can demote the generated classification. After you demote the USA city classification, the columns C10 and C11 no longer have the values as USA City. You can again promote these new columns with a new generated classification. However, the columns C1, C3, C4, C6, C7, and C9 still have generated classification values as USA City.

If you do not want the generated classification to be found in the system, you can reject it. In this situation, none of the columns remain associated with the generated classification that is rejected.

Custom attributes for assets


Custom attributes are properties defined for technical or business assets to capture additional information. Custom attributes allow you to specify and store specific information relevant to your assets beyond the predefined attributes.

In Metadata Command Center, the organization administrator can create custom attributes for assets according to the governance requirements of your organization. The attributes that the organization administrator creates are displayed in Data Governance and Catalog when a user creates an asset. For more information on creating attributes, see the *Administration* help module in Metadata Command Center.

On a technical asset page, you can view the system and custom attributes on the **Overview** tab and **Attributes** tab. On a business asset page, you can view custom attributes on the **Attributes** section of the **Overview** tab.


Note: If the organization administrator creates a custom attribute for an asset in Metadata Command Center and defines a default value for it, the default value does not appear in Data Governance and Catalog if the asset existed before the attribute was created.

The following image shows the system and custom attributes on the **Overview** page of a technical asset:



To modify the custom attribute values, click **Edit** either on the **Custom Attributes** section of the **Overview** page or the **Custom Attribute** sub-tab of the **Attributes** page. You cannot edit the values of system attributes.

The following image shows the **Attributes** tab of a technical asset page:



CHAPTER 5

Curation Center

The Curation Center is a one-stop page where you can review and act on recommendations for assets across the catalog sources you have access to.

The Curation Center consolidates recommendations across multiple assets into a single page so that you can review and curate assets with glossary associations, data classifications, business names and descriptions without having to navigate between multiple pages.

In the Curation Center, you can curate assets in the catalog sources on which you have **Read** and **Edit** permissions. If you don't have any one of these permissions on a catalog source, its assets and recommendations do not appear in the Curation Center.


Accessing the Curation Center

You can access the Curation Center from the following locations:

- From the left navigation panel, click **Curation Center**.
- From the CLAIRE Activity widget. The widget shows the total number of recommendations across all assets in the catalog. Click the widget to open the Curation Center, which shows the total number of assets that have recommendations from various enrichment sources. In the Curation Center, you can view and act only on assets for which you're responsible. You can also click a specific recommendation type on the widget, such as glossary or classification recommendations, to open the Curation Center with that recommendation type already filtered.
- From an in-app or email notification that CLAIRE generates when a catalog source is scanned and there are new pending and auto-accepted recommendations. Click **Review All Recommendations** in the in-app notification or use the link in the email notification to open the Curation Center scoped to that catalog source and recommendation status.
- From the **Assets with Recommendations** panel on a catalog source page. The panel shows pending and auto-accepted recommendation counts for that catalog source and includes a link to view them in the Curation Center.

Curation Center interface

The following image shows the **Curation Center** page:



The image calls out two grids in the Curation Center:

1. Asset Recommendation Summary. This grid displays summary information to help you prioritize your review. The grid show the following summary details:
   - A list of the catalog sources you have access to and the number of assets with pending recommendations in each catalog source. You can select a catalog source to filter the assets on the page to that specific- catalog source.
   - A chart of assets by recommendation status that shows the counts of assets that have pending, auto-accepted, user-accepted, or declined recommendations. You can click each status to filter the assets on that page by the selected recommendation status.
   - An asset completeness chart that shows the percentage of completeness for glossaries, business descriptions, business names, and classifications.
2. Assets with Recommendations. This grid displays all assets for which you have permissions along with their recommendations. You can select a catalog source in the summary grid to filter the page to assets that have recommendations in the selected catalog source. You can act on these recommendations by accepting or rejecting the asset enrichment suggestions.
   For assets without recommendations, you can add glossary and data classifications, or generate business names and descriptions.

   You can further filter the assets in the grid using the following criteria:
   - Asset state to view assets with or without recommendations
   - Assets such as catalog source or data elements
   - Recommendation status such as pending, auto-accepted, user accepted and declined
   - Recommendation type such as glossary, business name. description or data classifications
   - Recommendation sources such as lineage-based propagation, intelligent glossary association, Gen AI and so on.
   - Asset types within the catalog source
   - Assets with or without asset groups
   - When the asset was last updated

Reviewing recommendations and curating assets

At the Curation Center, you can review glossary, business name, description and data classification recommendations for an asset. You can accept or decline recommendations or generate text for business names and descriptions.

To view and act on recommendations, you must have Read and Edit permissions on the catalog source that contains the asset.

1. Open the **Curation Center**.

   You can open it from the left navigation panel, the CLAIRE Activity widget on the dashboard, a recommendation notification, or the **Assets with Recommendations** widget on a catalog source page.
2. In the asset grid, locate the asset whose recommendations you want to review.

   Use the available filters to narrow the grid. For more information about the available filter criteria, see Chapter 5, “Curation Center” on page 77.
3. Expand the asset row to view all the recommendations of the asset.
4. Click or hover over a recommendation to view its details in the tooltip.

   The detail view shows the confidence score, the recommendation source, the user who curated it, whether it was added manually, when it was last updated, its reference ID, and its description.
5. Accept or decline the recommendation.

   For business name and business descriptions, you can also generate or regenerate the suggested text. You can also manually add a glossary association or classification instead of acting on a recommendation.

The recommendation status of the asset updates immediately in the grid, and the action is recorded in the asset history.

Curating assets in bulk

Accept or decline pending recommendations for multiple assets at the same time instead of reviewing each asset individually. You can also generate text for business names and descriptions in bulk.

To view and act on recommendations, you must have Read and Edit permissions on the catalog sources that contain the assets you want to curate.

1. In the asset grid, select two or more assets that have pending recommendations.
2. From the Actions menu, select one of the following options:
   - Accept Pending Recommendations
   - Decline Pending Recommendations
   - Generate Text. Use this option to generate text for business names and descriptions for all selected assets
   - Advanced Edit. Use this option to make inline curation edits to multiple assets and submit all changes at once. This opens a new page where you can bulk curate up to 100 assets.
3. Select the type of recommendation to accept or decline, such as all types, only glossary, only business names, or only classifications.

4. Confirm the action when prompted.

   The confirmation dialog box lists the number of assets that will be updated and the count of each recommendation type.

The selected assets are updated with your curation decisions.

CHAPTER 6

Collaboration

You can enhance assets in Data Governance and Catalog to indicate various types of collaboration, which helps you in making collective decisions on using data for business needs.

You can collaborate on an asset with other users in the following ways:

- Rating an asset: Provide a rating on an asset to indicate your assessment of the quality of the asset.
- Certifying and decertifying an asset: As a stakeholder, if you want to endorse an asset for business decisions, you can certify the asset. At a later time, if you think that the asset is no longer relevant, you can decertify the asset.
- Commenting on an asset: Add your comments to an asset to provide your inputs on the data within the asset. Other users in the organization can see the comments and provide their own inputs. Users can collaborate on assets and make collective decisions on using the data.

Rating an asset

You can indicate the reliability of a business or technical asset by rating the asset. You can search for assets with or without ratings to narrow down your search results.


Ensure that the asset is in the Published **Lifecycle** state to view the ratings of an asset.

Rating an asset for the first time

Perform the following steps if you are rating an asset for the first time:

1. Open the asset for which you want to add a rating.
2. Click on a rating star, or click **Add** to rate the asset.

3. In the **Add Rating** dialog box, select the stars to add your rating for the asset and add your comments about the asset.




4. Click **Add** to add your rating.

Editing the rating of an asset

Perform the following steps to edit the rating of an asset:

1. Open the asset for which you want to edit the ratings.
2. Click **Edit Rating** to edit the rating of the asset.

3. In the **Edit Rating** dialog box, modify your rating for the asset and add your comments about the asset.



4. Click **OK** to save the rating of the asset.

   Note: To view all the ratings added to the asset in the **Comments** dialog box, click **View: All Comments**.

You can view all the ratings in the **Comments** dialog box. For more information on comments, see "Commenting on an asset" on page 86.

Certifying an asset

Endorse a technical asset as valid by certifying the asset. Certifying an asset helps users trust the asset and use it for business decisions or in other applications.


You can certify an asset if you are the stakeholder of the asset or if you have the **Update** permission on the asset.

You can certify a technical data set or a BI report. For example, you can certify tables, views, files, reports, workbooks, and worksheets.


To certify a technical asset, perform the following steps:

1. Open the technical data set or BI report that you want to certify.


2. Click the **Certify Asset** icon to certify the asset.



3. In the **Certify Asset** dialog box, provide an explanation to help users understand why this asset is reliable, and click **Certify**.



You can use search queries to search and find the assets that are certified. For information about collaboration search query examples, see the *Search query examples* topic in the *Asset Discovery* help. If you hover over the certification badge of a certified asset, you can view the stakeholder name and the comments about the asset.



You can also view the certification comments in the **Comments** dialog box. For more information about comments, see "Commenting on an asset" on page 86.


Decertifying an asset

As a stakeholder, if you think that a certified asset is no longer relevant, you can decertify the asset.


You can decertify technical data sets that are displayed from a catalog source.

1. Open the technical asset that you want to decertify.

2. Click the **Decertify Asset** icon ( ) option to decertify the technical asset.



3. In the **Decertify Asset** dialog box, add your comments and select **Decertify** option to decertify the technical asset.



To recertify the technical asset, you need to certify the asset. For more information about certifying the technical asset, see "Certifying an asset" on page 83.

You can search for technical assets that are without certifications in the search box, and you can filter the corresponding search results to narrow down to an individual technical asset that is not certified.

You can view the certification comments in the **Comments** dialog box. For more information on comments, see "Commenting on an asset" on page 86.


Commenting on an asset

You can add additional context to a business or a technical asset by adding comments about the asset. This helps users to view additional information such as discussions, questions, ratings, and certifications about the asset.


You can use '@' to tag a stakeholder. You can also add links and images in the comments.

Perform the following steps to comment about an asset:

1. Open the asset for which you want to add a comment.
2. Click the **Comment** icon.




3. To start a new comment thread, click **+ Start a new Thread**



4. To modify your comment, click the action menu and click the **Edit Comment** button. Type your comments and press ENTER.
5. To reply to a comment, click **Reply** for the comment that you want to reply. Type your comments and press ENTER.


6. To modify an earlier rating that you had provided on the asset, click the **Edit Rating** button, and click **OK** to save the rating of an asset.



7. To view the different types of comments for the asset, click **View: All**.

   From the drop-down list, you can select an option to narrow down to a comment.

8. To search for previous comments for an asset within the **Comments** dialog box, use the Find option. Type the words that you want to search. The search results will be highlighted within the **Comments** dialog box.



When you tag other stakeholders in a comment, the users receive a notification so that they can join the discussion. Open the **Notifications** panel to see all the notifications tagged for the stakeholder.

CHAPTER 7

Workflows and tickets

The Metadata Command Center administrator can define workflows that Data Governance and Catalog implements when users want to create or modify assets. A workflow specifies the steps to create or modify an asset. It includes the stakeholders that must be involved in providing inputs for the change process.

When a user attempts to create or modify an asset, Data Governance and Catalog creates a ticket for the change process. This ticket starts the workflow associated with the asset and involves the relevant stakeholders in the process. You can also create a ticket without associating it with a workflow to report any issues to the stakeholder of an asset.

What is a workflow?

A workflow specifies a series of predefined steps that a service follows when a user attempts to create or modify an asset, and includes the stakeholders that must be involved in providing inputs for the change process. Each step is a task that a stakeholder of the asset must perform. A workflow ensures that the right people have the opportunity to provide inputs, challenge, and approve matters related to the asset that is created or modified.

The steps in a workflow ensure that assets are created or modified according to the data governance principles of your organization. Only users with the right access can create or modify assets. For more information, see Chapter 2, “Manage access to assets” on page 8.

In Metadata Command Center, the administrator defines the workflow that is used to create or modify assets of a particular type. At each step in the workflow, Data Governance and Catalog notifies the stakeholders that they must make a decision about the asset. If the workflow requires the role of approvers at various stages of the lifecycle, the approvers must approve the asset so that the workflow can move to the next stage. The administrator can configure the workflow based on asset types and several conditions for asset hierarchies, relationships, asset groups, attributes, stakeholder roles, and other parameters.

Note: You can still view an asset in the **Draft**, **In Review** and **Published** versions even if you are not the stakeholder of an asset.

For more information about participating in a workflow, see “Participating in a workflow” on page 110.

When you create or modify an asset, the asset's **Lifecycle** is modified to one of the following values:

Draft

You can start a workflow by publishing your changes. For a newly created asset, ensure that you have already assigned stakeholders to the asset.

In Review

If the workflow is in progress, the **Lifecycle** value of the asset changes to **In Progress**. Now the asset moves through the stakeholders that are defined in the workflow.

If the **Lifecycle** value of the asset is in the **In Progress** status, other stakeholders cannot participate in the workflow until the **Lifecycle** of the asset is in **Approved** or **Rejected** status. If several different users attempt to modify an asset, the system creates tickets for each attempt to modify the asset. If an approval ticket is already created and is in open state, you cannot create any ticket on that asset.

Published

If the workflow is complete, the **Lifecycle** value of the asset changes to **Published**. This indicates that the asset has moved through all the stakeholders and reached the end of the workflow.


Note: For assets that have had their previously associated workflows disabled or if the workflow configuration conditions are modified or invalidated, the asset page displays the **Publish** button. You can click **Publish** to manually publish the asset. The asset now moves from the Draft to Published lifecycle.

Example

Your organization requires that any new finance policy document must go through the following workflow:

1. Only the Payroll Manager can create a policy document. When the Payroll Manager creates a Policy asset, the asset moves to the Finance Director for approval. The **Lifecycle** of the asset is `Draft`.
2. The Finance Director must go through the document and choose to approve or reject it.
   a. If the Finance Director approves the document, the document is published as a new Policy asset in Data Governance and Catalog. The **Lifecycle** status changes to `Published`.
   b. If the Finance Director rejects the policy document, it goes to the Accounting Manager. The **Lifecycle** of the asset changes to `In Review`.
3. The Accounting Manager can take a second look at the document and choose to approve or reject it.
   a. If the Accounting Manager approves the document, it goes again to the Finance Director for further approval. The **Lifecycle** value remains at `In Review`. The Finance Director can again choose to approve or reject the document. The workflow moves to step 2.
   b. If the Accounting Manager rejects the document, it goes back to the Payroll Manager. The **Lifecycle** status changes to `Deleted`. The Payroll Manager can reconsider the document and send it to the Finance Director again. The workflow moves to step 1.

This workflow can be represented by the following diagram:



Prerequisites for workflows

Each workflow requires one or more specific user roles to act on the asset. The stakeholders that can participate in a workflow depend on the steps and the user roles that are defined in the workflow by the Metadata Command Center administrator. To start a workflow or participate in ongoing workflows, the organization administrator must grant you the correct set of privileges in Administrator and access policies in Metadata Command Center.

Minimum privileges to create workflow tickets in Data Governance and Catalog

To create workflow tickets, ensure that your organization administrator grants the minimum required privileges and permissions to the user role.

The following table lists the minimum privileges and permissions needed to create workflow tickets:

Service	Privileges and Permissions
Metadata Command Center	- **Access Metadata Command Center Application** - **Read** and **Update** permissions for the technical, business, or data access asset types configured through access policies in Metadata Command Center.
Data Governance and Catalog	**Access Data Governance And Catalog Application**

Minimum privileges to work with workflow tickets in Data Governance and Catalog

If you are a stakeholder and you want to work with workflow tickets, ensure that your organization administrator grants the minimum required privileges and permissions to your user role.

The following table lists the minimum privileges and permissions needed for stakeholders to work with workflow tickets:

Service	Privileges and Permissions
Metadata Command Center	- **Access Metadata Command Center Application** - **Read** permission for the technical, business, or data access asset types configured through access policies in Metadata Command Center. - **Delete** permission for the business or data access asset types configured through access policies in Metadata Command Center. Required to reject workflows for creating a new asset. - **Read** and **Update** permissions on the **Unpublished Changes** attribute group for the technical, business, or data access asset types configured through access policies in Metadata Command Center. Required to reject workflows for modifying an existing asset.
Data Governance and Catalog	- **Access Data Governance And Catalog Application** - **Participate in Change Approvals** - You must be a stakeholder on the asset.

Minimum privileges to view all tasks in Data Governance and Catalog

To view all tasks that are available on the **Tasks Inbox** page in Data Governance and Catalog, ensure that your organization administrator grants the minimum required privileges and permissions to your user role.

The following table lists the minimum privileges needed for users to view all tasks on the **Tasks Inbox** page:

Service	Privileges and Permissions
Data Governance and Catalog	- **Access Data Governance And Catalog Application** - **Manage Workflow Tasks**

Minimum privileges to assign or reassign a task in Data Governance and Catalog

To assign an unclaimed task or to reassign a task that is already claimed by a user, ensure that your organization administrator grants the minimum required privileges and permissions to your user role.

The following table lists the minimum privileges needed for users to assign tasks to other users:

Service	Privileges and Permissions
Data Governance and Catalog	- **Access Data Governance And Catalog Application** - **Manage Workflow Tasks**

Minimum privileges to cancel open workflow tickets in Data Governance and Catalog

To cancel open workflow tickets when you are not a stakeholder on the asset, ensure that your organization administrator grants the minimum required privileges and permissions to your user role.

The following table lists the minimum privileges and permissions needed for users to cancel open workflow tickets:

Service	Privileges and Permissions
Metadata Command Center	- **Access Metadata Command Center Application** - **Read** permission for the technical, business, or data access asset types configured through access policies in Metadata Command Center.
Data Governance and Catalog	- **Access Data Governance And Catalog Application** - **Manage Tickets**. This privilege is needed only if you are not a stakeholder of the asset.

What is a ticket?


A ticket is an object in Data Governance and Catalog that either tracks the workflow for a particular asset or can be created to notify the stakeholders of an asset about any issue that might need remediation.

If the administrator has configured workflow approvals, the system creates a ticket when a user attempts to create an asset, to modify an asset, or to remediate a poor data quality score in a rule occurrence. After a ticket is created, Data Governance and Catalog starts the workflow that is associated with the asset type. To view all tickets that the system has created for the asset, open the **Tickets** tab of the asset.


You can use the following types of tickets in the workflow of an asset:

- **Approval Request for Create**. Use this ticket to start a workflow when you want to create an asset.
- **Approval Request for Change**. Use this ticket to start a workflow when you want to modify an asset.
- **Data Quality Failure**. Use this ticket to start a workflow when you want to remediate a poor data quality score in a rule occurrence.

The following image shows the **Tickets** widget with a sample workflow ticket:



The following image shows the sections that appear on the **Overview** tab of a ticket:



The following table describes the sections that appear on the **Overview** tab of a ticket:

Section	Description
Approver	You can view the following properties in the **Approver** section: - **Assigned To**. Details of the stakeholder that is responsible for approving the change. - **Description**. Details of the action taken as specified by the stakeholder. - **Due Date**. Date by which the participant should complete the current task. **Note:** This section appears only on open tickets.
Description	Description of the ticket.
Workflow Overview	A pictorial representation of the workflow that is used for the asset.
Workflow Timeline	A summary of the progression of events in the workflow.
Changes	A summary of the changes made to the asset as part of this ticket. You can view the following properties in the **Changes** section: - **Field**. An attribute of the asset. - **Original Value**. The current value assigned to the attribute. - **New Value.** The new value assigned to the attribute. To view the changes, use the **Highlight Changes** check box.
Resolution	Indicates whether or not the ticket is resolved.
Asset Details	Details of the asset for which the ticket was created.


Section	Description
Stakeholders	Details of the users that are assigned as stakeholders for the asset.
Status	Details of the user that created the workflow and the latest user that updated the workflow. You can view the following properites in the **Status** section: - **Created By**. Details of the user that created the ticket. - **Updated By**. Details of the user that last updated the ticket.

Creating a ticket

Create a workflow ticket when you create an asset, modify an asset, or report a data quality failure. Use a ticket with a workflow to provide a controlled and audited change approval process. The ticket that you create can be assigned to one or more workflows for an asset, or associated with one or more assets.

1. Open the **New** dialog box.
2. In the **New** dialog box, select **Others** > **Ticket**.

   The **New Ticket** page opens.



3. On the **New Ticket** page, configure the ticket properties.

   The following table describes the properties that you can configure on the **New Ticket** page:

Property	Description
Name	Enter a name for the ticket.
Type	Select one of the following ticket types: - **Approval Request for Create**. Select if you want to create an asset. - **Approval Request for Change**. Select if you want to modify an asset. - **Data Quality Failure**. Select if you want to report data quality failure issues.

Property	Description
Asset Details	To create an **Approval Request for Create** or an **Approval Request for Change** ticket, select an existing asset from the list of assets in the **Select Assets** dialog box. To create a **Data Quality Failure** ticket, configure the following fields: - **Data Element**. Select an existing data element from the system or the catalog source. **Note:** If you have selected rule occurrences generated from data quality score cards, this field isn't mandatory. - **Rule Occurrences**. This is a mandatory field. Select manually created, automatically generated, or data quality score card-generated rule occurrences from the list.
Severity	Specify the severity of the ticket. You can configure one of the following statuses: - High - Medium - Low
Urgency	Specify the urgency of the ticket. You can configure one of the following urgency values: - Blocker - Major - Minor
Status	Displays the initial status of the ticket.
Description	Enter a description for the ticket.

The **Stakeholders** section displays the stakeholders that are assigned to the asset for which you are creating the ticket. You can view the role that the user or user group is assigned to, the name and email of the user.

4. To create the ticket, click **Create**.

The new ticket is created. You can view the ticket on the **Ticket Manager** page or on the **Tickets** tab of the asset.
For more information about how you can view tickets for an asset, see "Viewing a ticket" on page 99.

Creating a ticket when you create or modify an asset


When you create or modify an asset, you must create a ticket if a workflow is configured for the asset.

To create a workflow ticket when you try to create or modify an asset, the following conditions apply:

- Your organization administrator grants you the **Update** permission on the asset through access policies in Metadata Command Center.
- A workflow is configured for the asset.


- The lifecycle of the asset must be in **Draft** state.

1. Create or modify the asset, and click **Save**. For more information about creating assets, see "Creating assets and assigning stakeholders" on page 28.



2. Click **Submit**.

   The **New Ticket** dialog box appears.



3. In the **New Ticket** dialog box, provide the context of the change to other participants in the workflow.

   The following table describes the properties that you can configure in the **New Ticket** dialog box:

Property	Description
Asset Type	Indicates the type of the asset for which you want to create the ticket. You can't modify this field.
Ticket	Specify whether you want to create a new ticket or select an existing open ticket. You can select one of the two values: - Assign an existing open ticket - Create New Ticket If you have an existing ticket for an asset, the ticket is displayed in the **Tickets** tab of the asset or it appears when you edit the asset and send it for review.
Name	Enter a name for the ticket.
Description	Enter a description for the ticket.
Severity	Specify the severity of the ticket. You can configure one of the following statuses: - High - Medium - Low
Urgency	Specify the urgency of the ticket. You can configure one of the following urgency values: - Blocker - Major - Minor

4. Click **Submit**.


The new ticket is created. You can view the ticket on the **Ticket Manager** page or on the **Tickets** tab of the asset.
For more information about how you can view tickets for an asset, see "Viewing a ticket" on page 99.

Viewing a ticket


View a ticket that is created for a Data Governance and Catalog asset.

1. Click the **Ticket Manager** icon at the top of a page.
2. To view workflow tickets, use the **Ticket Type** filter to view the **Approval Request for Create**, **Approval Request for Change**, and the **Data Quality Failure** type tickets. The **Approval Request for Create** type tickets pertain to creation of new assets, the **Approval Request for Change** type tickets pertain to any

proposed changes to existing assets, and the **Data Quality Failure** type tickets pertain to remediation of poor data quality scores in a rule occurrence.



3. Click a ticket to open the ticket in a new page.
4. To view the latest status of the ticket, click the **Refresh** icon.
5. If you have configured the **Tickets** widget on your dashboard, you can view tickets that are specific to an asset type or based on the ticket statuses. Click the header of the **Tickets** widget to open and view the tickets on the **Tickets** page.



6. If you do not want any further action to be taken on the ticket that you created, click **Cancel** on the **Action** button of the ticket. You can cancel tickets only if you are the stakeholder of the asset or if your user role is assigned the **Manage Tickets** feature privilege in Administrator.

Manage tickets

You can collaborate on tickets with other users, resolve a ticket, or a cancel a ticket.


Commenting on a ticket

You can add comments to a ticket to provide inputs on the ticket. You can also tag other users in your comment. The comments are visible only to users who have access on the asset for which the ticket is created.


1. Open a ticket.

   For more information about how you can open a ticket, see "Viewing a ticket" on page 99.

2. On the ticket page, click the **Comment** icon.
3. To enter a comment, type your comment and press the ENTER key on your keyboard.



4. To start a new comment thread, click **+ Start a new Thread**



5. To modify your comment, click the action menu and click the **Edit Comment** button. Type your comments and press ENTER.
6. To reply to a comment, click **Reply** for the comment that you want to reply. Type your comments and press ENTER.
7. To view the different comments from all users on the ticket, select **View: All Comments**.

   To view only your comments, select **View: My Comments**.
8. To search for a specific comment within the **Comments** dialog box, use the **Find** bar. The search results will be highlighted within the **Comments** dialog box.

When you tag other users in a comment, the users receive a notification in the **Notifications** panel so that they can join the discussion.

Resolving a ticket


If you are a stakeholder of a ticket or if your user role has the **Manage Tickets** feature privilege assigned in Administrator, you can resolve an open status ticket that does not have a workflow. The tickets without workflow need to be manually resolved to bring them to the terminal state. The tickets with workflow are automatically resolved when the tasks are completed.

1. Open a ticket.

   For more information about how you can open a ticket, see "Viewing a ticket" on page 99.
2. On the ticket page, click **Resolve**.
3. In the **Resolution** dialog box, enter the resolution summary.

   The following table describes the properties that you can configure in the **Resolution** dialog box:

Property	Description
Resolution Type	Select one of the following resolution types: - Request was completed. - Request was partially completed. - Request was not completed.
Description	Enter a description to provide an explanation of the resolution. By default, the description is set to **NOT RESOLVED**.
Comment	Enter any comment related to the resolution status or other details associated with the ticket. **Note:** When you enter the comments, you can view them in the **Comments** dialog box of the ticket.



4. Click **Yes**.

After you resolve a ticket, the status of the ticket changes to **Resolved** and you can't edit the ticket. All the stakeholders receive an email notification regarding the resolution of the ticket.

Note: If you resolve the ticket without updating the description, the resolution description displays **NOT RESOLVED** even after the ticket is resolved.

Canceling a ticket

If you have created the ticket or your user role has the **Manage Tickets** feature privilege assigned in Administrator, you can cancel tickets with or without a workflow. You can cancel an open ticket with workflow if the ticket is not required or if the approving stakeholder of the asset leaves the organization or is

absent for a long time. You can cancel a ticket without a workflow if the issue reported through the ticket is no longer relevant.


1. Open a ticket.

   For more information about how you can open a ticket, see "Viewing a ticket" on page 99.

2. On the ticket page, click **Cancel**.
3. In the **Cancel Ticket** dialog box, enter the resolution summary.

   The following table describes the properties that you can configure in the **Cancel Ticket** dialog box:

Property	Description
Description	Provide an explanation for canceling the ticket.
Comment	Enter a comment. **Note:** When you enter the comments, you can view them in the **Comments** dialog box of the ticket.



4. Click **Yes**.


After you cancel a ticket, the status of the ticket changes to **Canceled** and you can't edit the ticket.

Tasks Inbox

The **Tasks Inbox** is a centralized location where you can view all tasks that are assigned to you.

To access the **Tasks Inbox** page, click the **Tasks Inbox** icon at the top of each page.

The following image shows the **Tasks Inbox** page:



On the **Tasks** tab, you can view all the tasks that are available to you as a stakeholder. You can claim the tasks that you want to work on. However, you don't need to claim a task to perform actions on it. Additionally, you can unclaim a task you previously claimed to release yourself from its responsibilities. For more information about how you can perform actions on a task, see "Participating in a workflow" on page 110.

You can also assign or reassign the tasks that are available on the **Tasks Inbox** page. For more information about how you can assign or reassign a task, see "Assigning a task" on page 109.

Overview section

In the Overview section, you can view metrics that pertain to the tasks in the selected tab. In this section, you can view the following metrics:

- **Priority**. A graphical representation of the total number of tasks categorized by priority levels, **Low**, **Medium**, **High**.
- **Event Type**. A graphical representation of the total number of tasks categorized by the event type.
- **Due Date**. A graphical representation of the total number of tasks, categorized by whether they are within their due date or past the due date.

To hide the Overview section, open the Action menu and click **Hide Overview**.

Tasks section

The **Tasks** section lists the tasks that are available to you as a stakeholder. You can view the tasks in a grid or card format. The grid view shows the tasks in a table, and the card view shows the tasks as individual tiles.

The following table describes the properties that you can view on the **Tasks** grid:

Property	Description
Priority	Priority level of the task. The levels can be, **Low**, **Medium** or **High**.
Name	Name of the task.
Asset Name	Name of the sub-group within a task group. In a grouped view, the asset name helps you distinguish between the various tasks within a task group.
Event Type	The event type of the task. This property can have one of the following values: - **Approval Request for Create**. Task pertain to creation of new assets. - **Approval Request for Change**. Task pertains to any proposed changes to existing assets.
Asset Type	Type of the asset for which the ticket is created.
Due Date	Date by which the participant should complete the current task.
Description	Description of the ticket associated with the task.
Created Date	Date on which the task is created.
Task Owners	The user that has claimed the task. If no user has claimed the task, the **Task Owners** field displays all users that are eligible to claim the task.

You can perform the following activities in this section:

- To sort the tasks in the **Tasks** grid, click on the columns of the grid. To select the columns that you want to see in the grid or reorder the columns, open the Action menu and click **Column Settings**.
- Find tasks in the grid using the **Find** bar. You can also apply filters to help you find a task.
- To open a task in a new tab, click the **Open** icon for the selected task.

To view more details about a task, click the task. The following table lists the tabs that you can view for a task that you select on the **Tasks** grid:

Tab	Description
Asset Details	Details of the asset for which the workflow was created. You can view the following properties in the **Asset Details** tab: - **Name**. Name of the asset. - **Description**. Description of the asset. - **Participants**. Details of the user that created the ticket and the latest user that updated the ticket. - **Stakeholders**. Details of the users that are assigned as stakeholders for the asset.
Task Details	Details of the selected workflow task. You can view the following properties in the **Task Details** tab: - **Overview**. An overview of the task. - **Role**. The user roles of the stakeholders of the task. - **Stakeholders**. Details of the users that are assigned as stakeholders for the task. The task is assigned a maximum of 20 stakeholders of a specific role, including individual users and user groups. For example, if the roles Data Governance Owner and Data Steward are assigned as stakeholders of a task, the task can be assigned a maximum 20 stakeholders for each role.

Tab	Description
Ticket Details	Details of the ticket that is associated with the workflow. You can view the following properties in the **Ticket Details** tab: - **Overview**. An overview of the ticket. - **Resolution**. Indicates whether or not the ticket is resolved. - **Stakeholders**. Details of the users that are assigned as stakeholders for the asset. - **Workflow Overview**. A pictorial representation of the workflow that is associated with the ticket. If a workflow includes multiple tasks that run concurrently, you can view those tasks in the **Workflow Overview** section. - **Workflow Timeline**. A summary of the progression of events in the workflow.
Changes	A summary of the changes made to the asset as part of this ticket. You can view the following properties in the **Changes** tab: - **Field**. An attribute of the asset. - **Original Value**. The current value assigned to the attribute. - **New Value.** The new value assigned to the attribute
Comments	The comments that are added while performing an action on the task and to the ticket that is associated with the task. The comments are visible only if you have access to the asset for which the ticket is created. Use one of the following filters to specify the type of comments you want to view on the **Comments** tab: - **All**. Show all comments added while performing an action on the task and to the ticket that is associated with the task. - **Comment Threads**. Show only the comments that are added directly to the ticket. For more information, see "Commenting on a ticket" on page 101. - **Actions with Comments**. Show only the comments that are added by a stakeholder while performing an action on the task. For more information, see "Participating in a workflow" on page 110. - **My Comments**. Show only the comments that you added to the ticket that is associated with the task.


View tasks in grouped view

On the **Tasks** grid, you can optionally group the tasks that share a common workflow event and outcome. A common outcome refers to a common action such as 'approve' or 'complete' that allows you to simultaneously process multiple tasks. A same workflow event ensures that all the tasks in a group have a consistent business logic.

To group tasks, select **Grouped by Workflows** from the Action menu in the **Tasks** grid. By grouping multiple tasks that require the same action, you can act on several tickets simultaneously.

In the **Tasks** grid, the task group names correspond to the workflow events. Each group contains sub-groups that represent active tasks.

The following image shows the preview section where you can view all the tasks within a selected sub-group from the left panel:




Performing actions on multiple tasks

To act on multiple tasks that belong to the same workflow, perform the following steps:

1. On the **Tasks Inbox** page, click the Action menu icon and select **View Tasks** > **Grouped by Workflows**.
2. In the **Tasks by Workflows** grid, expand a task group to view the tasks within the group.
3. In the preview section, select the tasks on which you want to perform an action.

   You can can act on specific tasks for completion within a task group. For example, if you choose to act on two out of five tasks, those two tasks will either move to the next task group or be resolved after you complete them. The remaining three tasks will continue to remain in the current task group.
4. To assign multiple tasks to stakeholders, enable the **Show users, user groups, and roles that are stakeholders to the selected tasks** toggle.

   The toggle filters the list to display only the stakeholders.



Assigning a task


If a task is not claimed, you can assign the task to a user. If a stakeholder claims a task, you can reassign the task to another user.

To assign a task, ensure that your organization administrator grants you the **Manage Workflow Tasks** feature privilege in Administrator.

1. Open the **Tasks Inbox** page.
2. In the **Tasks** section, select the task that you want to assign to a user.

   You can use the **Find** bar and apply filters to locate the task.
3. On the selected task, click the **Assign** icon.

   The following image shows the **Task Inbox** and highlights the icon:



4. In the **Assign Task** dialog box, select the user to whom you want to assign the task. You can select a user that has the relevant stakeholder role assigned either directly or through a user group.
5. Click **Assign**.

The task is assigned to the selected user.

Participating in a workflow

As a stakeholder of an asset, you can participate in an ongoing workflow for the asset.

To participate in a workflow, the following conditions apply:

- Your organization administrator grants you the relevant permissions for an asset so that you can create or modify the asset and approve or reject a workflow request. For more information about the assets and permissions required to participate in workflows, see "Prerequisites for workflows" on page 92.
- In Metadata Command Center, the administrator must add your user role as a stakeholder in the workflow of the relevant asset type. For more information about how an administrator designs workflows, see the *Designing a workflow* topic in Metadata Command Center.


  Note: Ensure that the latest user that modified the asset is added as a stakeholder on the asset with the following permissions:

  - To reject workflows for creating a new asset, ensure that the user is assigned the **Delete** permission for the business asset types or data access asset types configured through access policies in Metadata Command Center.
  - To reject workflows for modifying an existing asset, ensure that the user is assigned the **Read** and **Update** permissions on the **Unpublished Changes** attribute group for the technical, business or data access asset types configured through access policies in Metadata Command Center.

    When a stakeholder approves a task, Data Governance and Catalog assigns the lifecycle change to the user who last modified the asset. If that user is unavailable, for example because the user was deleted or lacks update permissions, Data Governance and Catalog uses the ticket creator instead.

1. Open a ticket.

   For more information about how you can open a ticket, see "Viewing a ticket" on page 99.




2. Click **Start**.

   The **Lifecycle** value of the associated asset changes according to how the administrator has designed the workflow in Metadata Command Center. The system starts the workflow associated with the asset and notifies the stakeholder that is defined next in the workflow. Data Governance and Catalog consolidates notifications for workflow tasks and sends them once every hour.

   If you modify the stakeholder of the asset, the newly added stakeholder receives notifications for the active workflow tasks that are associated with the asset. Data Governance and Catalog sends only new task notifications to the newly added stakeholder. Notifications that were sent before the stakeholder was added will not be reissued to the new stakeholder.

3. To perform an action on the ticket, click the corresponding action button.

   Optionally, you can click the **Claim** button to assign the task to yourself. You can claim a ticket only if the workflow specifies a user role, and you are one of the many users that have the relevant role.



4. Alternatively, you can participate in a workflow by performing the actions from the **Tickets** tab of the corresponding asset or from the **Ticket Manager** page, or from the **Tickets** widget.

   To take action on a ticket from the **Tickets** tab of the corresponding asset or from the **Ticket Manager** page, perform the following steps:

   a. On the **Tickets** grid, select the ticket that is associated with the workflow.

   b. On the preview pane of the ticket, click the button that corresponds to the action that you want to perform.

      When performing an action on the ticket, you can add a comment and tag other users in it. When designing the workflow in Metadata Command Center, your administrator might configure commenting as a mandatory requirement when performing an action on a ticket. For more information about designing workflows, see the *Administration* help in Metadata Command Center.


   To take action on a ticket from the **Tickets** widget, perform the following steps:

   a. Click the header of the **Tickets** widget.

   b. On the **Tickets** grid, select the ticket that is associated with the workflow.

c. On the preview pane of the ticket, click the button that corresponds to the action that you want to perform.

When performing an action on the ticket, you can add a comment and tag other users in it. When designing the workflow in Metadata Command Center, your administrator might configure commenting as a mandatory requirement when performing an action a ticket. For more information about designing workflows, see the *Administration* help in Metadata Command Center.



After you complete your task, you can view the workflow progress in the **Workflow Overview** section on the ticket page. Depending on how the administrator has designed the workflow in Metadata Command Center, the workflow moves to the next task or is resolved after you complete your task. If a workflow includes multiple tasks that run concurrently, you can view those tasks in the **Workflow Overview** section.


5. Alternatively, you can participate in a workflow by performing the actions from the **Tasks Inbox** page.

To complete a workflow task from the **Tasks Inbox** page, perform the following steps:

a. On the **Tasks Inbox** page, select the workflow task from the **Tasks** grid.

b. In the task preview section, click the button that corresponds to the action that you want to perform.

When performing an action on a task, you can add a comment and tag other users in it. When designing the workflow in Metadata Command Center, your administrator might configure commenting as a mandatory requirement when performing an action on a task. For more information about designing workflows, see the *Administration* help in Metadata Command Center.



Viewing audit history of tickets


Use the **History** tab of a ticket to observe and track changes that you make for the tickets. The audit history is available for two years.

1. Open an asset, select the **Tickets** tab and select a ticket.
2. On the ticket page, select the **History** tab.


   The following table describes the properties displayed on the **History** tab of a ticket:

Property	Description	Displayed by default
Date	Displays the created and last updated dates of the asset.	Yes
Event Type	Displays the type of the event that is performed on the asset. For example, this field displays the changes in the name, description, or the reference ID of the asset.	Yes
Action	Displays the following actions that are performed on the asset: - Create. Displayed if the asset is created. - Updated. Displayed if the asset is updated. - Deleted. Displayed if the asset is deleted.	Yes
Current Attributes	Displays the recently changed attributes of the asset.	Yes
Previous Attributes	Displays the earlier attributes of the asset.	Yes
Changed By	Displays the latest user that has performed the action on the asset. **Note:** Currently, the **Changed By** attribute displays the creator of the ticket instead of the latest user that performed the action on the asset.	Yes
Ticket Name	Displays the name of the ticket.	No
Ticket Path	Displays the origin path of the ticket.	No
Ticket Type	Displays the type of the ticket.	No
Trace ID	Displays the unique ID for the ticket.	No


3. To narrow the information you see in the **History** tab, click the **Filter** icon and add filters based on the various properties.



For example, apply the **Event Type** filter to view the event history of the asset when you change the name, description, or the reference ID of the asset:



4. From the **Settings** icon on the **History** tab, select the layout changes to display for the page.



The following table describes the options displayed in the **Settings** menu:

Option	Description
Columns	Apply the default columns or choose columns based on your requirement.
Save Layout	Save your preferences for the grid layout.
Reset Layout	Reset your grid layout preference to its default settings. You can select one of the following reset options: - **Reset to Default**. Layout resets to the default system settings. - **Reset to Last Saved Layout**. Layout resets to the previously saved user-preference layout settings.
Grid Settings	Select the columns that you want to display, reorder the selected columns, sort the order of columns, determine the grid density, and specify number of rows per page.

CHAPTER 8

Customization for layouts

When you open an asset in Data Governance and Catalog, you can view the attributes of the asset in a customized layout that is defined by your administrator.

Through customization, an administrator can organize a list of panels and attributes to appear in a particular order on the page or arrange attributes in meaningful categories. Each layout contains a different customization of tabs, panels and attributes ahout the asset or the page.

An administrator can customize the following Data Governance and Catalog layouts:

- The **New Asset** page
- The **Overview** tab of an asset page
- The asset preview pane on various pages
- The grid layout for asset pages


Custom layout for asset pages

For Data Governance and Catalog asset pages, you can view custom layouts for the **New Asset** page, and the **Overview** tab. If you have several layouts assigned to you, you can switch between them.

Switch between layouts

Click the **Layout** icon on an asset page, you can view the layouts available to you. To see or create the asset in other formats, select a layout from the layouts menu on the page.


The following image shows the layout switcher for an asset page:



Set a layout as your default

You can set the current layout of an asset as your default layout. Click the bookmark icon on the layout switcher menu to set the layout as the default.

The following image shows the option to set a layout as default for the asset type:



Custom layout for preview panes


When a list of assets appear in a grid, you might have more than one layout to view the contents of the preview pane. If you have several preview pane layouts assigned to you, you can switch between them to see the attributes of the asset in various display formats.

A layout is a customization with a specific list of attributes that appear in a particular order on the pane. Each layout typically contains a different customization of attributes for the asset. An administrator customizes a layout for an asset type in Metadata Command Center and assigns the layout to your user group or user role.

Switch between layouts

By default, a preview pane appears in the layout specified by the administrator in Metadata Command Center. To see the preview pane in other display formats, click on the layouts icon on the page.


The following image shows the layouts switcher for a preview pane:



Set a layout as default

From the available options, you can override the default layout with another layout by clicking the bookmark icon. When you click on an asset of that asset type the next time, the preview pane will appear in the layout that you now set as default.

The following image shows the option to set a layout as default for the preview pane:




Customize grid layout for asset pages

Modify the grid layout of asset pages and save the layout changes to retain them even after you log out and log in again.

You can modify the grid layout in the following ways:

- Order, resize, sort, and hide or show columns.
- Reset the grid layout to its default settings
- Change page size and layout view as required.

The following image displays an asset page with several layout settings:




From the **Setting** icon on an asset page, select the layout changes to display for the pages.

The following table displays the layout settings:

Settings	Description
Columns	Apply the default columns or choose columns based on your requirement.
Layout Settings	Select grid, card, or details view, and determine the grid density.
Grid Settings	Select the columns that you want to display, reorder the selected columns, sort the order of columns, determine the grid density, and specify number of rows per page.
Save Layout	Save your preferences for the grid layout.
Reset Layout	Reset your grid layout preference to its default settings. You can select one of the following reset options: - **Reset to Default**: Layout resets to the default system settings. - **Reset to Last Saved Layout**: Layout resets to the previously saved user-preference layout settings.

The following image shows the **Grid Settings** pane:



Applicable pages

You can customize the grid layout for many types of pages in Data Governance and Catalog.

- Customize the grid layout for the following **Home** page items:
  - **Browse** page
  - **Job Monitoring** page
  - **Ticket Manager** page
  - **Search Results** page
  - CLAIRE-recommended widgets in the **Home** page
  - Data Quality Scores in the **Data Quality** widget
- Customize the grid layout for the following pages when you open an asset:
  - **Data Quality** tab
  - **Relationships** tab
  - **Stakeholders** tab
  - **Associations** tab
  - **Contains** tab
  - **Data** tab
  - **Hierarchy** tab

- **Lineage** tab
- **Rule Occurrences** tab
- **History** tab
- **Tickets** tab
- **Relationships** tab
- **History** tab on a ticket page
- **Overview** tab > **Changes** table
- Job page > **Imported Assets** dialog box
- **Data Quality Rule Template** > **Secondary Glossary** > **Items Secondary Glossary** dialog box

- Customize the grid layout when you create new assets of the following types:
  - **New** > **Data Set** > **System** > **Items System** dialog box
  - **New** > **System** > **Parent** > **Items Parent** dialog box
  - **New** > **Data Quality Rule Occurrence** > **Rule Template** > **Items Rule Template** dialog box
  - **New** > **Data Quality Rule Template** > **Primary Glossary** > **Items Primary Glossary** dialog box
  - **New** > **Data Set** > select a system > add new data element > **Add Data Elements** dialog box
  - **New** > **Business Term** > add a stakeholder > **Add Users** > **Add Users as Stakeholders** dialog box
  - **New** > **Business Term** > add a stakeholder > **Add User Groups** > **Add User Groups as Stakeholders** dialog box
  - **New** > **Data Set** > add a stakeholder > **Add Users** > **Add Users as Stakeholders** dialog box
  - **New** > **Data Set** > add a stakeholder > **Add User Groups** > **Add User Groups as Stakeholders** dialog box
  - **New** > **System** > add a catalog source > **Select Catalog Sources** dialog box
  - **New** > **Ticket** > **Stakeholders** table
  - **New** > **Ticket** > select 'Data Quality Failure' in the **Type** field > **Rule Occurrences** > **Select Rule Occurrence** dialog box
  - **New** > **Ticket** > select 'Data Quality Failure' in the **Type** field > **Data Element** > **Select Data Element** dialog box
  - **New** > **Process** > **Parent** > **Items Parent** dialog box
  - **New** > **Data Quality Rule Occurrence** > **Primary Data Element** > **Items Primary Data Element** dialog box
  - **New** > **Data Quality Rule Occurrence** > select a primary data element > **Secondary Data Element** > **Items Secondary Data Element** dialog box

INDEX

A

assets
  collaboration 81
  decertifying an asset 84
  rating an asset 81

D

decertifying
  decertifying an asset 84

F

features
  assign privileges 12

P

privileges
  for features 12

R

rating
  rating an asset 81

S

Stakeholder propagation 42