Informatica® Business 360 Console
October 2026

Modernize On-Premises Objects

Informatica Business 360 Console Modernize On-Premises Objects
October 2026

© Copyright Informatica LLC 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices and AI assistant acknowledgements are included with the product.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-10-30

Table of Contents

Preface 5

Informatica Resources. 5

    Informatica Documentation. 5
    Informatica Intelligent Cloud Services web site. 5
    Intelligent Data Management Cloud Communities. 5
    Informatica Intelligent Cloud Services Marketplace. 5
    Informatica Knowledge Base. 6
    Informatica Intelligent Cloud Services Trust Center. 6
    Informatica Global Customer Support. 6

Chapter 1: Modernize on-premises objects. 7

Advantages of modernization. 7

MDM Hub and MDM SaaS. 8

Key concepts. 8

    Lookup tables. 8
    Base objects. 8
    Business entities. 8
    Match rule sets. 9
    Survivorship. 9
    Users and user roles. 9
    Hierarchies and relationships. 9

Modernization strategies for on-premises objects. 9

Chapter 2: Getting started with modernization using Business 360 Console. . 11

Exporting configuration details. 11

Exporting user account details. 12

User roles mapping. 13

    Create a user role mapping file. 13

Chapter 3: Modernization process. 14

Defining a project. 14

Mapping fields. 14

    Custom mapping. 15
    Smart field mapping. 17
    Compatible data types. 18

Standardizing configurations. 19

MDM Hub objects in the modernization process. 19

    Data models. 19
    Match rule sets. 20
    Hierarchies and relationships. 24

User accounts and user roles. 24
Guidelines for modernization process. 25

Chapter 4: Modernizing the MDM Hub objects. 27

Define a modernization project. 27
Mapping fields using custom mapping. 28
Step 1. Retrieve reference data configuration. 28
Step 2. Map attributes. 31
Step 3. Retrieve business entity configuration. 31
Step 4. Map fields. 33
Mapping fields using smart field mapping. 34
Modernize. 35
Step 1. Standardize configuration. 35
Step 2. Modernize data models. 35
Step 3. Modernize match rule sets. 36
Step 4. Modernize hierarchies. 36
Step 5. Modernize relationship graph. 37
Step 6. Modernize user roles. 37
Step 7. Modernize user accounts. 37

Chapter 5: Migrating data. 38

Chapter 6: Managing modernization projects. 39

Modernization mapping files. 39
Reference data mapping file. 40
Data model mapping file. 42
Generating mapping files. 44
Guidelines for mapping objects in modernization mapping files. 46
Download event logs. 46
Deleting modernization projects. 46
Archiving modernization projects. 47
Summary of modernization projects. 47
Creating a summary of modernization projects. 47
Modernization summary. 48
Modernization metrics. 48
Modernization details. 48
Regenerating summaries. 53
Deleting summaries. 53

Index. 54

Preface

Follow the instructions in *Modernize the On-Premises Objects* to migrate the on-premises MDM Hub configuration to MDM SaaS.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

Informatica Intelligent Cloud Services web site

You can access the Informatica® Intelligent Data Management Cloud™ (Informatica Intelligent Cloud Services) web site at http://www.informatica.com/cloud.

Intelligent Data Management Cloud Communities

Use the Informatica Intelligent Cloud Services Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

To access the Informatica Intelligent Cloud Services Community, see Master Data Management SaaS Community.

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

Informatica Intelligent Cloud Services Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

Informatica Intelligent Cloud Services Trust Center

The Informatica Intelligent Cloud Services Trust Center provides information about Informatica security, compliance, and privacy practices.

You can access the trust center at https://trust.informatica.com/.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the Informatica Intelligent Cloud Services Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Modernize on-premises objects

Modernization is the process that helps you transition from an on-premises MDM implementation to the MDM SaaS implementation. MDM SaaS is a cloud-native service that enables organizations to master their data within a secure, scalable, and reliable environment. Migrating to MDM SaaS enables you to take advantage of the scalability, flexibility, and continuous updates that MDM SaaS provides.

For example, you can modernize the on-premises configuration from Multidomain MDM to MDM SaaS. For the MDM Hub, you can modernize objects, such as lookup tables, business entities, user roles, users, match rule sets, survivorship configurations, source systems, hierarchies, and relationships. You can extract these objects from the MDM Hub as a change list XML file and as a CSV file. The Hub Console provides tools to export these configuration files, which serve as the foundation for modernization.

Use Business 360 Console to modernize the MDM Hub objects. Use the REST APIs to modernize objects from third-party MDM providers, such as IBM and Semarchy.

For more information about modernizing objects from third-party MDM providers, see *Business 360 REST API*.

Advantages of modernization

MDM SaaS is a cloud-native service that enables organizations to master their data within a secure, scalable, and reliable environment.

After you modernize the configuration, you can load data to MDM SaaS and then master it. Managing master data in MDM SaaS has the following benefits:

- Removes the infrastructure burden of managing the Hub Server, application server, and database.
- Provides a highly scalable infrastructure.
- Provides a consumption-based pricing model.
- Enables faster deployments with minimal downtime.
- Provides access to the latest version of the service.
- Integrates seamlessly with Data Integration, Data Quality, Application Integration, and Reference 360.

MDM Hub and MDM SaaS

Before you start the modernization process, ensure that you understand the differences between the MDM Hub and MDM SaaS.

The following table lists the key differences between the MDM Hub and MDM SaaS:

MDM Hub	MDM SaaS
An on-premises MDM application.	A cloud-native service that runs on Intelligent Data Management Cloud (IDMC).
Manually integrate with the following on-premises products: - PowerCenter. To ingress and egress data. - Data Quality. To verify, standardize, and improve data quality. - ActiveVOS. To automate business processes.	Seamless out-of-the-box integration with the following services: - Data Integration. To ingress and egress data. - Data Quality. To verify, standardize, and improve data quality. - Application Integration. To automate business processes. - Reference 360. To manage reference data.
Uses the following types of data models: - Business entity - Subject area	Uses the business entity-based data model.
Uses the lookup tables for reference data.	Uses Reference 360 to manage reference data.

Key concepts

Before starting the modernization process, ensure that you are familiar with some of the key concepts of the MDM Hub.

Lookup tables

Lookup tables manage reference data in the MDM Hub. For example, the Country lookup table contains information about different countries. The business entity fields are associated to the columns in lookup tables.

Base objects

A base object is a table that stores master data, consolidated from cross-reference tables. For example, the Party base object can contain information about a person or organization. The business entity fields are associated to the columns in base objects.

Business entities

Business entities define the data model and are associated with base objects. For example, the Person business entity stores personal information, such as name, address, phone number, and email address of customers. The fields within the Person business entity are associated with the columns in the Party base object.

Match rule sets

The match rule sets in the MDM Hub include multiple match rules that identify duplicate records.

Survivorship

Survivorship determines field values with high trust scores for master records when duplicate records merge.

In MDM SaaS, you can rank source systems as part of the survivorship configuration. A higher rank indicates a higher trust for that source system. In contrast, survivorship configurations in the MDM Hub don't include ranking source systems. After modernizing objects, MDM SaaS automatically assigns the highest rank, Rank 0, to the Informatica Customer 360 or Default source system based on the business application you use. You can manually adjust the source system rankings in Business 360 Console.

Note: The survivorship configuration, along with the trust scores configured for fields, is modernized to MDM SaaS. However, the validation rules aren’t modernized because they aren't part of the survivorship configuration in MDM SaaS. In MDM SaaS, validation rules belong to data quality configuration. Therefore, you must manually review and modify the validation rules in MDM SaaS after modernization.

Users and user roles

A user role contains a collection of privileges, and users assigned to the user role get those privileges.

Hierarchies and relationships

Hierarchies and relationships relate records. For example, you can relate a company as a subsidiary to another company. A hierarchical relationship creates a parent-child relationship. A non-hierarchical relationship relates two records without any hierarchy in the relationship. For example, you can create a non-hierarchical relationship between the family members.

Modernization strategies for on-premises objects

You can choose a modernization strategy based on your business needs and on-premises MDM configuration.

Use the following strategies to modernize the MDM Hub objects:

- Reimplement. Re-create the MDM Hub objects in MDM SaaS. This approach requires more time and effort.
- Migrate. Migrate the MDM Hub objects to MDM SaaS. To migrate the objects, you can use Business 360 Console.

If you choose either the migration or reimplementation strategy, use the same strategy consistently for all remaining objects. However, you can use the reimplementation strategy for objects that aren't supported by the modernization process.

The following table describes the modernization strategy for each object that the modernization process supports:

Supported MDM Hub Object	Description
Data models	Use the migration strategy to modernize data model objects, such as business entities.
Match Rule Sets	Use the migration strategy to modernize the data model objects. The modernization process migrates the match rule sets based on the mapped fields in the business entities.
Survivorship Rules and Trust Settings	Use the migration strategy to modernize the survivorship rules and trust settings. When you use Business 360 Console to migrate the survivorship rules and trust settings, the modernization process automatically migrates the rules and settings associated with each business entity field in the MDM Hub to MDM SaaS.
User Accounts and User Roles	Use the migration strategy to modernize user accounts and roles from the MDM Hub to MDM SaaS.

The following table describes the modernization strategies for unsupported MDM Hub objects:

Unsupported MDM Hub Object	Description
Data Standardization, Enrichment, and Validation	Use the reimplementation strategy for standardization, enrichment, and validation. Use the Enrichment Validation and Orchestrator to validate, cleanse, transform, standardize, and enrich data in MDM SaaS by creating objective groups, objectives, and rule associations.
Siperian Mapping	In the MDM Hub, Siperian mapping manages the mapping between landing and staging tables. In MDM SaaS, the ingress process loads data from external applications to MDM SaaS and the mapping between staging and landing tables is handled internally without user intervention. You can ingress data from the MDM Hub to MDM SaaS without reimplementing Siperian Mappings.
Service Integration Framework	MDM Hub uses the Service Integration Framework APIs to invoke the MDM Hub operations from external applications in real time. However, MDM SaaS doesn’t support Service Integration Framework APIs. You can use Business Entity Services in MDM SaaS to access external applications. Use Cloud Application Integration and MDM SaaS APIs to perform MDM operations from external applications in real time. Additionally, the authorization and authentication process differs between the MDM Hub and MDM SaaS APIs. For more information about MDM SaaS REST APIs, see *Business 360 REST API*.
Subject Area-Based Data Models	To modernize subject area-based data models, upgrade to the MDM Hub version 10.5 and migrate subject area-based data models to business entity-based data models. You can then modernize these data models using the reimplementation strategy.

CHAPTER 2

Getting started with modernization using Business 360 Console

Before you start the modernization process, export the required configurations from an Operational Reference Store of the MDM Hub. Also, ensure that you belong to the MDM Modernization, MDM Designer, and Reference 360 Primary Owner user roles.

The modernization process requires the following details from an Operational Reference Store of the MDM Hub:

- Configuration details. The configuration details include business entities, fields, relationships, match rule sets, survivorship configurations, source systems, hierarchies and relationships, user roles, and lookup tables. The privileges related to each user role are part of the change list XML file. You can export the configuration details from the MDM Hub as a change list XML file.
- User account details. List of users and their user roles. The user account details include personal information, such as name, phone number, and email address of the user. The privileges related to each user role are part of the change list XML file. You can export the user accounts details to a CSV file through the User Migration tool of the MDM Hub.

  Note: By default, the CSV file uses UTF encoding. Ensure that you don't modify the encoding type before uploading the CSV file.
- Mapped user roles. A properties file where you manually map the MDM Hub user roles with the MDM SaaS user roles. When you map MDM Hub user roles to predefined user roles in MDM SaaS, the privileges associated with the MDM Hub roles are replaced by the privileges in MDM SaaS.. However, when you map MDM Hub user roles to custom user roles in MDM SaaS, the privileges defined in the change list XML file for the MDM Hub user roles are assigned to the custom user roles.

When you have all these details handy, you can proceed to create a modernization project in Business 360 Console.

Exporting configuration details

You can use the Repository Manager in the Hub Console to export an Operational Reference Store as a change list XML file.

1. Start the Repository Manager tool.
2. Click the **Export** tab.

3. Select a repository to export.
4. Specify the target location, and click **Save**.

   The **Export Repository** dialog box appears.
5. Navigate to the target directory to save the change list XML file.
6. Enter the following details for the change list file:

Field	Description
Name	Logical name for the change list file.
Description	A short description for the change list file.
File Name	Name for the change list file. The exported change list file uses the following name format: `<File Name>.change.xml`

7. Click **Export**.
8. After a successful export, open the change list XML file in an editor to review its contents.

Exporting user account details

Use the User Migration tool to export the list of users and their details from the MDM Hub as a CSV file. Ensure that you use the same Operational Reference Store from which you extracted the configuration details.

1. Open the MDM Support tools, and click **User Migration**.
2. Select the Operational Reference Store from which you extracted the configuration details, and then click **Retrieve**.

   The User Migration tool displays a list of the MDM Hub users in the selected Operational Reference Store.
3. Select the users that you want to export.
4. Click **Export Users**.

   The **Export Roles** dialog box appears.
5. To include user-to-role assignments in the exported user information, click **Yes**.

   The **Export Users - Result** dialog box appears.
6. Click the download link.

User roles mapping

You can map user roles in the MDM Hub with predefined and custom user roles in MDM SaaS. You can map these user roles in a user role mapping file. The user role mapping file is a properties file that you can create manually to map user roles.

For example, you can map the DataSteward user role in the MDM Hub to a predefined user role in MDM SaaS, such as Customer 360 Data Steward, or to any other custom user roles in MDM SaaS. For more information about modernizing user roles, see “User accounts and user roles” on page 24.

Create a user role mapping file

A user role mapping file is a .properties file. Before you create a user role mapping file, ensure that you have the list of all the user roles in MDM SaaS and the MDM Hub. To get a list of user roles in the MDM Hub, refer to the change list XML and user account details files. To view the list of user roles in MDM SaaS, you can use Administrator.

1. Open a text editor, such as Notepad.
2. Add the user roles in the following format:

   ```
   <MDM Hub user role> = <MDM SaaS user role>
   ```

   The following example maps the DataSteward user role in the MDM Hub with the Customer 360 Data Steward user role in MDM SaaS:

   ```
   DataSteward = Customer 360 Data Steward
   ```

   Note: Ensure that the user roles don't contain any of the following special characters:

   ```
   ~!/'={}|:@#$^&*()-_+,<>?`
   ```

3. Save the file with the .properties file extension.

CHAPTER 3

Modernization process

Before you begin modernizing objects in the MDM Hub, ensure that you understand how the modernization process works.

The modernization process involves defining a modernization project, retrieving the MDM Hub and MDM SaaS configurations, mapping fields and attributes in those configurations, and then modernizing the MDM Hub objects. To define a modernization project, you need MDM Hub configuration files, such as Change List XML, user account details, and user role mappings. After retrieving the configuration files, you can proceed to map fields and attributes. You can map the fields or attributes using custom mapping or smart mapping. Then, you can start modernizing the MDM Hub objects and migrate them to MDM SaaS.

Defining a project

A modernization project is a container that holds all modernization assets. To begin modernizing MDM Hub objects, you must define a modernization project in MDM SaaS.

To start modernizing MDM Hub objects, you must define a modernization project in MDM SaaS. To define the project, you need the configuration files of the Operational Reference Store that you want to modernize to MDM SaaS. These configuration files include the change list XML, user account details, and user role mappings. Ensure that you have these files ready before defining the project.

Mapping fields

After you define a project, manually map business entities and reference data objects in the MDM Hub and MDM SaaS that are similar. If they aren't similar, create the MDM Hub business entities automatically in MDM SaaS.

To manually map your MDM Hub source objects to MDM SaaS business entities and reference data, define a custom mapping project. To automatically create the MDM Hub business entities in MDM SaaS, define a smart mapping project. However, in a smart mapping project, you must map reference data objects manually.

To successfully modernize the MDM Hub objects, ensure that the field types in the MDM Hub and MDM SaaS are compatible.

Custom mapping

You can configure custom mapping to map MDM Hub business entity fields, base object columns, and lookup tables to MDM SaaS business entity fields and Reference 360 code lists in Business 360 Console user interface.

With custom mapping, you can map business entities or base objects and reference data. You can select multiple MDM Hub business entities or base objects and map them to an MDM SaaS business entity, and you can map MDM Hub lookup tables to Reference 360 code lists. You can map fields either manually or automatically.

When MDM Hub fields or field groups have no equivalent in MDM SaaS, you can mark them for creation in MDM SaaS during modernization. You can then map the marked fields to the corresponding MDM Hub fields. Similarly, when an MDM Hub business entity or base object has no equivalent MDM SaaS business entity, you can mark it for creation in MDM SaaS. You can then map the marked custom business entity to the corresponding MDM Hub object.

Retrieving business entity and reference data configurations

Before you map objects, retrieve the business entity and reference data configurations from MDM SaaS. The modernization process builds the configuration from the business entities in MDM SaaS and the change list XML file that you upload from the MDM Hub.

If you use updated configuration files from the MDM Hub, or the data model in MDM SaaS is updated, you can refresh the configuration to retrieve the latest changes. You can also download the configuration as a CSV file to review the source and target fields. If you map the fields and save the mapping before you download the configuration file, the file includes your field mappings.

Automapping fields by confidence score

You can automatically map fields based on a confidence score. The modernization process compares the fields in the MDM Hub and MDM SaaS and maps them automatically. You can then review the automapped fields and modify them if needed.

Automapping is useful when objects contain too many fields and when most fields have clear counterparts. Use automapping as the starting point for a mapping as it reduces manual effort. After automapping runs, manually map the remaining fields that aren't mapped.

You can set a confidence score to control how closely fields must match. The confidence score is a threshold value from 50 through 100, default is 60. To determine the matches, the modernization process calculates a score for each source and target field pair based on rules, such as field name and data type similarity. A pair that scores at or above the threshold is mapped automatically. If no pair meets the threshold, the modernization process marks the source field for creation as a custom field in MDM SaaS.

The following table describes the statuses that a field can have after automapping fields:

Status	Description
Auto-mapped	Indicates that the modernization process automatically mapped an MDM Hub field to the MDM SaaS field.
Unmapped	Indicates that no MDM Hub field matched the MDM SaaS field. The MDM SaaS field remains in the mapping so that you can map it manually.
Auto-created	Indicates that no MDM SaaS field matched the MDM Hub field. The modernization process marks the field for creation as a custom field in MDM SaaS to keep the MDM Hub field in the mapping. The names of auto-created field groups include the X_ prefix, and the names of auto-created fields include the x_ prefix. For example, X_Address and x_first_name.

Rules and guidelines for automapping

Consider the following rules and guidelines for automapping:

- The modernization process doesn't map fields that have incompatible data types, regardless of confidence score. For example, the MDM Hub and MDM SaaS both have a Birth Date field. The MDM Hub field is a VARCHAR field, and the MDM SaaS field is a Date field. Even though the field names match, the fields aren't mapped because their data types are incompatible.
- If you map an MDM Hub business entity or base object to a predefined business entity, such as Person, x_ is prefixed to each auto-created field. For example, home_address becomes x_home_address.
- If you map an MDM Hub business entity or base object to a custom business entity and the name of an auto-created field matches the name of another field in the same field group, _custom is suffixed to the name of the auto-created field. For example, address_line1 becomes address_line1_custom. If that name is also taken, a hash code based on the MDM Hub field path is suffixed, such as address_line1_5004fe. Auto-mapped and unmapped fields are never renamed. Fields in different field groups can have the same name.
- Field name comparisons aren't case sensitive. For example, Address and address count as the same name.
- If the fields of an MDM Hub child node map to a smart field, such as Address, Email, or Phone, the modernization process maps the fields only if all the fields of the node map to that smart field. If only some of the fields map, the mapped fields in the smart field are reset to Unmapped. The modernization process then adds all the fields of the node to a custom field group as auto-created fields.
- If you map a root node of an MDM Hub business entity to a field group, the modernization process manages the unmatched fields of the node in the following ways:
    - If an unmatched field is in the root node, the field is added to the same field group as an auto-created field.
    - If an unmatched field is in a child node, the field is added to a separate custom field group for the child node, even if other fields in the child node map to the field group of the parent node.
      For example, the Person business entity in the MDM Hub has an Address child node. The Address node contains the Address Type and City fields and the Street child node. The Street node contains the Address Line 1 and Address Line 2 fields.

  Address Type and Address Line 1 are automapped to the Address field group in the Person business entity in MDM SaaS because the field group contains fields with similar names. The modernization process then manages the unmapped fields in the following ways:

  - Adds City to the Address field group because City is at the same level as Address Type in the Address node.
  - Adds Address Line 2 to the X_Address.X_Street custom field group because Address Line 2 is in the Street node, which is nested in the Address node.

- If you map a base object to an MDM SaaS business entity, each custom field group that's created is named after the display name of the base object, such as Account. If a base object doesn't have a display name, the modernization process uses the physical name, which is the actual name of the base object table in the database, such as C_ACCOUNT. If two base objects have the same display name, the modernization process adds the physical name to the display name of one of the base objects to keep field group names unique. For example, the C_ACCOUNT and C_CUSTOMER_ACCOUNT base objects both have the display name Account. The modernization process names one custom field group Account and the other custom field group Account_C_CUSTOMER_ACCOUNT.
- If you change the confidence score, the fields that are automapped might change.

Creating custom fields and field groups

When MDM Hub fields or field groups have no equivalent in MDM SaaS, you can mark them as custom fields or field groups for creation in the target MDM SaaS business entity. Use custom fields to retain MDM Hub fields during modernization.

You can mark MDM Hub source fields for creation as custom fields in an existing MDM SaaS field group or as root fields in a business entity. When you mark a custom field for creation in a predefined business entity, the name includes the X_ prefix to identify it as a custom field. Automapping can also mark MDM Hub source fields for creation as custom fields when the confidence score of a field pair doesn't meet the defined threshold.

Creating custom business entities

When an MDM Hub business entity or base object has no equivalent in MDM SaaS, you can mark it as a custom business entity for creation in MDM SaaS. You can then map the marked custom business entity to the corresponding MDM Hub object.

You must enter a unique name for the custom business entity. After you mark a business entity for creation, the modernization process marks all the source fields and field groups in the selected MDM Hub business entity or base object for creation in MDM SaaS. The modernization process then maps each source field to the corresponding field that it marked for creation. For example, if the MDM Hub business entity contains a First Name field, the modernization process marks a First Name field for creation in MDM SaaS and maps the source field to it. You can modify the field mappings in the same way as other field mappings, if required.

Smart field mapping

If business entities in the MDM Hub and MDM SaaS aren't similar, you can choose to create business entities automatically from the MDM Hub. The modernization process creates them in MDM SaaS without the need for mapping fields in data model mapping files.

In the MDM Hub, business entities contain a root node and one or more child nodes within the root node. MDM SaaS uses field groups or smart fields instead of child nodes. The modernization process lists both root and child nodes from the MDM Hub. If you select child nodes, then each child node will be modernized as a separate business entity. To avoid modernizing the child nodes in the MDM Hub as separate business entities in MDM SaaS, you can choose only the root nodes. You can create field groups or smart fields in MDM SaaS after modernization instead of creating separate business entities in MDM SaaS for child nodes.

The following image shows a modernization project that uses smart field mapping to automatically create MDM Hub business entities in MDM SaaS:



Generate the template files, map the objects in the templates, and then upload the mapped files to modernize.

Reference Data

A template includes a list of reference data from MDM SaaS and the lookup tables from the MDM Hub. Map the reference data with the lookup tables.

☑ Include lookup tables from the MDM Hub in the template

Smart Field Mapping

Select the business entities to modernize with their original fields from the MDM Hub.

Business Entities (0)

Name in MDM Hub	Display Name in MDM SaaS

No business entities to display. To select the MDM Hub business entities that you want to create in MDM SaaS, click Add Business Entities

Compatible data types

When you map the MDM Hub objects with MDM SaaS, ensure that their field types are compatible.

The following table lists the compatible field types of the objects in MDM SaaS and the MDM Hub:

Field Type in the MDM Hub	Field Type in MDM SaaS
CHAR	String
VARCHAR	String
NVARCHAR	String
NCHAR	String
DATE	Date
TIMESTAMP	Date and Time
NUMBER	Decimal
INT	Integer
BOOL	Boolean
LOOKUP	Picklist

Standardizing configurations

To modernize the MDM Hub objects, upload your mapped files. The modernization process standardizes the uploaded configuration files into multiple JSON files.

During standardization, the modernization process validates the MDM Hub configuration against MDM SaaS limits and thresholds. For example, the total number of searchable fields across the MDM Hub and MDM SaaS for a business entity is checked against the allowed limit of 30 fields. If the count exceeds the allowed limit, you can't continue with the modernization process until you disable enough searchable fields to meet the limits. If 40 fields are searchable but the limit is 30, you must disable the searchable property for 10 fields before you proceed.

For more information about limits and thresholds on field properties, see
Search and reports properties.*Search and reports properties*.

Consider the following guidelines when you modify the field properties of a business entity:

- If business entity fields in the MDM Hub are mapped to predefined business entity fields in MDM SaaS, the modernization process uses the properties of the fields in MDM SaaS.
- If business entity fields in the MDM Hub are mapped to custom business entity fields in MDM SaaS, the modernization process uses the properties of the field in the MDM Hub.
- If base object columns in the MDM Hub are mapped to predefined or custom business entity fields in MDM SaaS, the modernization process uses the properties of the fields in MDM SaaS. Base object columns don't support field properties, such as searchable and facetable.
- After standardization, you can view the field properties of business entities that are ready for modernization. The business entities that exceeded the defined field property limits are highlighted in red. To stay within limits and proceed to the next step, disable the properties of the fields in the affected business entities.
- You can't disable a field property of a business entity field that has dependent objects unless you remove the dependency.

MDM Hub objects in the modernization process

You can modernize the MDM Hub objects, such as lookup tables, business entities, user roles, users, match rule sets, survivorship configurations, source systems, hierarchies, and relationships, and migrate them to MDM SaaS.

Data models

Data models define the basic structure of your master data. You can modernize the base object columns or business entity fields in the MDM Hub data models.

You can modernize the following MDM Hub objects associated with data model into MDM SaaS:

- Business entities. Modernizes the business entities and their fields or base object columns that you manually or automatically map. If a similar business entity exists in MDM SaaS, you can manually map the fields. If a similar business entity doesn't exist in MDM SaaS, you can create a new business entity in MDM SaaS.
- Reference data. Modernizes the lookup tables and their attributes in the MDM Hub based on the reference data mapping file. The modernization process maps the lookup tables with the corresponding code lists in

Reference 360. For more information about reference data mapping file, see “Reference data mapping file” on page 40.

- Source systems. Modernizes the source systems based on the source system details available in the change list XML file.

Match rule sets

In the MDM Hub, match rule sets contain the rules that identify duplicate records. The match rules defined for the mapped fields in a data model mapping file are modernized and applied to the corresponding fields in MDM SaaS as Directed AI match rules.

If match rules are configured for the mapped fields in the MDM Hub, you might find the corresponding Directed AI match rules in MDM SaaS after modernization.

If a source system is configured as a distinct source in the MDM Hub, the match process doesn't match records within the same source system. However, records from a distinct source system match with records from other source systems. When base object tables or business entities in the mapped files have distinct source systems configured, the modernization process migrates them to MDM SaaS.

After modernization, the match rule sets appear as draft match models in MDM SaaS. Review the drafts before publishing them. The modernization process migrates only root-level match rule sets. Child-level match rule sets aren't migrated.

When you review the draft match models after modernization, you might observe the following changes:

- If a match rule uses the Geocode field type as the candidate selection criteria, the modernization process might add multiple Geocode fields in the candidate selection criteria.
- If multiple fields are used to generate match keys in the MDM Hub, the modernization process might include only the first field in the candidate selection criteria.
- The modernization process might change the preferred key width used in a fuzzy match rule from the MDM Hub to the standard key generation level.

Before you modernize the match rule sets, ensure that you understand the differences between match functionalities in the MDM Hub and MDM SaaS.

The following table compares the match functionalities in the MDM Hub and MDM SaaS:

Functionality	MDM Hub	MDM SaaS
Candidate Selection	Match Column	Candidate Selection Criteria
Match Strategy	Exact Fuzzy	Exact Fuzzy
Merge Strategy	Automated Manual	Automated Manual Skip Threshold-based
Match Algorithm	Match Purpose	Match Criteria
Match Level	Conservative Typical Loose	Conservative Typical Loose

Functionality	MDM Hub	MDM SaaS
Merge Threshold	Not available	Available
Fuzzy Match Key Type	Not available	Available
Segment Matching	Available	Available
Null Matching	Available	Available
Candidate Filtering	Based on SQL queries	Available through candidate selection criteria
Match Subtype	Available	Not available
Non-Equal Matching	Available	Not available
Distinct Source Systems	Available	Available

Supported Populations

You can modernize business entities that use different populations in their match model configurations.

The following table describes the populations supported by match model configurations during modernization:

Population	Description
Arabic	Contains the Arabic Standard script for the Arabia population.
Arabic_m	Contains a mix of Arabic, Romanized Arabic, English, and Arabicized English scripts for the Arabia population.
Arabic_r	Contains the Arabic Romanized Standard script for the Arabia population.
Argentina	Contains the Argentina Standard script for the Argentina population.
Australia	Contains the Australia Standard script for the Australia population.
Belgium	Contains the Belgium Standard script for the Belgium population.
Brasil	Contains the Brasil Standard script for the Brasil population.
Bulgaria_c	Contains the Bulgarian Cyrillic Standard script for the Bulgaria population.
Bulgaria_r	Contains the Bulgarian Romanised script for the Bulgaria population.
Canada	Contains the Canada Standard script for the Canada population.
Chile	Contains the Chile Standard script for the Chile population.
Chinese	Contains the Chinese Standard script for the Chinese population.
Chinese_i	Contains the Traditional Chinese Standard script for the Chinese population.
Chinese_r	Contains the Chinese Romanised Standard script for the Chinese population.

Population	Description
Chinese_s	Contains the Simplified Chinese Standard script for the Chinese population.
Chinese_t	Contains the Traditional Chinese Standard script for the Chinese population.
Colombia	Contains the Colombia Standard script for the Colombia population.
Croatia	Contains the Croatia Standard script for the Croatia population.
Czech	Contains the Czech Standard script for the Czech population.
Denmark	Contains the Denmark Standard script for the Denmark population.
Estonia	Contains the Estonia Standard script for the Estonia population.
Finland	Contains the Finland Standard script for the Finland population.
France	Contains the France Standard script for the France population.
Gaelic	Contains the Gaelic Standard script for the Gaelic population.
Germany	Contains the Germany Standard script for the Germany population.
Greek	Contains the Greek Standard script for the Greek population.
Greek_l	Contains the Greek Mixed Standard script for the Greek population.
Hebrew	Contains the Hebrew Standard script for the Hebrew population.
Hk_r	Contains the Hong Kong Romanized Standard script for the Hong Kong population.
Hungary	Contains the Hungary Standard script for the Hungary population.
India	Contains the India Standard script for the India population.
Indo_chin_r	Contains the Indo-China Standard Standard script for the Indo-China population.
Indonesia	Contains the Indonesia Standard script for the Indonesia population.
International	Contains the International Latin-1 Standard script.
Ireland	Contains the Ireland Standard script for the Ireland population.
Italy	Contains the Italy Standard script for the Italy population.
Japan	Contains the Japan Standard script for the Japan population.
Japan_r	Contains the Japanese Romanized Standard script for the Japan population.
Kazakhstan	Contains the Kazakhstan Standard script for the Kazakhstan population.
Korean	Contains the Korean Standard script for the Korean population.

Population	Description
Korean_r	Contains the Korean Romanized Standard script for the Korean population.
Luxembourg	Contains the Luxembourg Standard script for the Luxembourg population.
Malaysia	Contains the Malaysia Standard script for the Malaysia population.
Malta	Contains the Malta Standard script for the Malta population.
Mexico	Contains the Mexico Standard script for the Mexico population.
Netherlands	Contains the Netherlands Standard script for the Netherlands population.
New Zealand	Contains the New Zealand Standard script for the New Zealand population.
Norway	Contains the Norway Standard script for the Norway population.
Peru	Contains the Peru Standard script for the Peru population.
Philippines	Contains the Philippines Standard script for the Philippines population.
Poland	Contains the Poland Standard script for the Poland population.
Portugal	Contains the Portugal Standard script for the Portugal population.
Puerto_rico	Contains the Puerto Rico Standard script for the Puerto Rico population.
Romania	Contains the Romania Standard script for the Romania population.
Russia	Contains the Russia Standard script for the Russia population.
Singapore	Contains the Singapore Standard script for the Singapore population.
Slovakia	Contains the Slovakia Standard script for the Slovakia population.
South_africa	Contains the South Africa Standard script for the South Africa population.
Spain	Contains the Spain Standard script for the Spain population.
Sweden	Contains the Sweden Standard script for the Sweden population.
Switzerland	Contains the Switzerland Standard script for the Switzerland population.
Taiwan_r	Contains the Taiwan Romanised Standard script for the Taiwan population.
Thai	Contains the Thai Standard script for the Thailand population.
Thai_r	Contains the Thai Romanised Standard script for the Thailand population.
Turkey	Contains the Turkey Standard script for the Turkey population.
Uk	Contains the UK Standard script for the UK population.

Population	Description
Usa	Contains the USA Standard script for the USA population.
Vietnam_r	Contains the Vietnamese Romanized Standard script for the Vietnam population.

Hierarchies and relationships

Hierarchies define the parent-child relationships between records. For example, you can consider a relationship between employer and employee records as a parent-child relationship.

Non-hierarchical relationships are called as network relationships in MDM Hub and relationship graph in MDM SaaS. For example, you can consider the relationship between two family members as a non-hierarchical relationship. You can modernize hierarchies and relationships in the MDM Hub.

Note: After you delete a modernized hierarchy in MDM SaaS and create another hierarchy with the same name, ensure that you use a unique identifier value for the new hierarchy.

User accounts and user roles

Before you modernize user roles and users, ensure that you understand the basic principles behind modernizing these objects.

You can also modernize user accounts configured with single sign-on (SSO) in the MDM Hub. Additionally, you can't modernize user groups in the MDM Hub. By default, user roles in the MDM Hub that are mapped to custom user roles in MDM SaaS are assigned create, read, and update privileges on MDM SaaS business entities after modernization.

The modernization process uses the user role details from the MDM Hub configuration in the following ways:

- If you map a user role from the MDM Hub to a custom user role in MDM SaaS, the custom user role is updated with the privileges from the user role in the MDM Hub.
- If you map a user role from the MDM Hub to a predefined user role in MDM SaaS, the predefined user role isn't updated with the privileges from the user roles in the MDM Hub. You can't modify the privileges of predefined user roles in MDM SaaS.
- The MDM Hub users assigned to the user roles that you mapped are modernized to MDM SaaS. The users assigned to unmapped user roles aren't modernized.

The following table summarizes the modernization process for user roles in the MDM Hub:

MDM Hub User Roles	User Role in MDM SaaS	User Privileges in MDM SaaS
User roles in change list file.	The modernization process creates custom user roles in MDM SaaS based on the resource privileges of MDM Hub fields mapped in the data model mapping file.	The modernization process assigns the same privileges as the MDM Hub user role to the modernized custom user roles in MDM SaaS for the attributes. Also, it assigns create, read, update, and delete privileges for the business entities. **Note:** You can review and modify the privileges after modernization.
User roles mapped to custom MDM SaaS user roles in the user role mapping file.	The modernization process creates custom user roles in MDM SaaS.	The modernization process updates the privileges of MDM SaaS user roles based on the privileges of mapped MDM Hub user roles. After modernization, you can review and modify the privileges as needed.
User roles mapped to predefined MDM SaaS user roles in the user role mapping file.	The modernization process maps the MDM Hub user roles to predefined user roles in MDM SaaS.	The modernization process retains the privileges of predefined user roles in MDM SaaS. You can't modify the privileges of predefined user roles in MDM SaaS.
User roles in the user account details file.	Based on the user account details file of the MDM Hub, the modernization process creates users and assigns them to the modernized user roles. The users who belong to the user roles that aren't modernized are ignored.	The modernization process assigns the privileges based on the user roles.

Guidelines for modernization process

Consider the following guidelines before you start modernizing the MDM Hub objects:

- Based on the business application selected during project creation, the business entities are automatically assigned to that business application after modernization. However, the modernization process assigns search layouts only to business entities that contain fields that are enabled as searchable in the MDM Hub.
- Ensure that the picklist fields in business entities that you want to create automatically through smart field mapping are mapped to their corresponding lookup tables in the reference data mapping file.
- If the modernization process migrates any one of the business entities to MDM SaaS through smart field mapping, you can’t regenerate the mapping even if other business entities in the mapping aren't modernized.
- If you modernize business entities through smart mapping, you can add new fields or field groups to business entities only after the modernization.
- If any of the MDM Hub objects fail during modernization, you can skip them and continue modernizing other objects. However, you can't skip and continue when errors or failures occur when you standardize configurations or migrate data models.
- Ensure that you don’t delete the modernized objects in MDM SaaS. If you try to modernize the deleted objects again, the modernization process generates validation errors.

- When you modernize hierarchies and relationships, ensure that all business entities that the hierarchies use are included in a single modernization project.
- You can create a copy of an existing code list sheet and modify the sheet name and attributes to include the lookup tables that you want in the mapping file. However, manually creating code list sheets using this approach might introduce errors into the mapping file. Therefore, it is recommended to include the lookup tables when generating a mapping file if intend to create code lists for them in Reference 360.

CHAPTER 4

Modernizing the MDM Hub objects

Before you begin the modernization process, ensure that you belong to the MDM Modernization and Reference 360 Primary Owner user roles. You must also have all the required files from the MDM Hub.

For more information about the required files, see Chapter 2, “Getting started with modernization using Business 360 Console” on page 11.

To modernize the MDM Hub object, perform the following steps:

1. Define a modernization project and upload all the configuration files from the MDM Hub.
2. Retrieve reference data and business entity configurations, and then map objects in the configuration files.
3. Preview the objects and then modernize them.

Define a modernization project

A modernization project stores all the modernization assets together. You can define up to 10 modernization projects in an organization.

1. Click **Modernization**.

   The **Modernization** page appears.
2. Click **New Project**.

   The **Define Project** page appears.
3. Enter a project name.
4. To upload a change list file, click **Choose File**, and select an XML file that contains the configuration details of the MDM Hub.

   Note: Ensure that the maximum size of the XML file is 95 MB. Also, in the current release, you can define projects only for change list XML files that use the `Usa` population in the match rule set.
5. Select a business application in MDM SaaS to which you want to add the modernized business entities.
6. To upload the user accounts file, click **Choose File**, and select a CSV file that contains user details.

   Note: Ensure that the CSV file uses commas as delimiters. If any other delimiters are used, the upload fails.
7. To upload the user role mapping file, click **Choose File**, and select a .properties file that you created.

For more information about the user role mapping file, see “User roles mapping” on page 13.

Note: Ensure that the maximum size of the .properties file is 4 MB.

8. Select one of the following options:
    - Custom Mapping. Allows you to map business entities and their fields or base object columns in the MDM Hub and MDM SaaS manually or automatically in the user interface. For more information about modernization mapping files, see “Custom mapping” on page 15
    - Smart Mapping. Creates business entities and their fields in MDM SaaS based on the business entities in the MDM Hub. For more information about smart field mappings, see “Smart field mapping” on page 17
9. Click **Save**.

   The project is saved with the uploaded files, and the **Map Fields** page appears.

Mapping fields using custom mapping

You can map MDM Hub business entity fields, base object columns, and lookup tables to MDM SaaS business entity fields and Reference 360 code lists in Business 360 Console user interface.

During the mapping process, each MDM SaaS business entity and reference data object shows a status that indicates whether its mapping is complete. The status remains incomplete until you review the mapping and mark it as complete. Additionally, each field or attribute shows a status that indicates whether it was mapped.

To map fields using custom mapping, perform the following steps:

- “Step 1. Retrieve reference data configuration” on page 28
- “Step 2. Map attributes” on page 31
- “Step 3. Retrieve business entity configuration” on page 31
- “Step 4. Map fields” on page 33

Step 1. Retrieve reference data configuration

The reference data configuration defines the source and target attributes of code lists from Reference 360 and lookup tables from the MDM Hub. If the source or target definitions change, refresh the configuration to retrieve the latest changes in the reference data configuration.

1. On the **Map Fields** page, navigate to the **Reference Data** section.
2. Click **Get Configuration**.

   The modernization process retrieves the configuration from the MDM Hub lookup tables and code lists in Reference 360. After you retrieve the configuration for the first time, you can also refresh the configuration to retrieve the latest changes.
3. To refresh the configuration, click **Refresh Configuration**.
4. Optionally, to review the retrieved configuration manually, click **Download Reference Data Configuration**.
5. To begin the reference data mapping process, click **Map Reference Data**.

   The **Reference Data Mapping** page appears. You can view a list of lookup tables that were retrieved from the MDM Hub in the **Lookup tables** section.

The following image shows the Reference Data Mapping page along with the retrieved configuration:



Confidence Score: 60 %

Summary

9 Automapped Fields

5 Newly Created Fields

Lookup Tables (15)

Name	Reference 360 Code List	Create as New	Code List Name	Dependent Code List	Mapping Status	Attributes Mapped	Action
C_LU_ADDRESS	AddressType	☐			Manually mapped	3 / 3	Map Attributes
C_LU_CHANNEL		☑	LUChannel		Auto-created	2 / 3	Map Attributes
C_LU_COMM_TYPE		☑	LUCommunicationType		Auto-created	2 / 3	Map Attributes
C_LU_COUNTRY	LUCountry	☐			Auto-mapped	3 / 3	Map Attributes
C_LU_ELECT_ADDR	LUElectronicAddressT...	☐			Auto-mapped	2 / 3	Map Attributes
C_LU_GENDER	Gender	☐			Auto-mapped	3 / 3	Map Attributes
C_LU_GEN_SUFFIX		☑	LUGenerationSuffix		Auto-created	3 / 3	Map Attributes
C_LU_ID_TYPE	AlternateIdType	☐			Auto-mapped	3 / 3	Map Attributes
C_LU_MARITAL_STATUS	MaritalStatus	☐			Auto-mapped	3 / 3	Map Attributes
C_LU_NAME_PREFIX	PrefixName	☐			Auto-mapped	3 / 3	Map Attributes

The following table describes the user interface elements that you can see in the Reference Data Mapping section:

User Interface Elements	Description
Name	Name of the lookup table retrieved from the MDM Hub configuration.
Reference 360 Code List	Code list retrieved from Reference 360. Select a code list to map to the lookup table.
Create as New	Creates the lookup table as a new code list in Reference 360. To skip mapping, create the lookup table as a new code list.
Code List Name	Unique name for the new code list. Applicable when you create the lookup table as a new code list in Reference 360.
Dependent Code List	Code lists whose values depend on the values of a parent code list. For example, the State code list is a dependent code list of the Country code list. You can select a dependent code list only if you have already mapped its parent code list to a lookup table. Select the dependent code list from a list.
Mapping Status	Status of the reference data mapping. The Mapping Status column shows one of the following values: - Auto-mapped. Indicates that the lookup table column is mapped to a code list attribute. - Auto-created. Indicates that the lookup table column has no equivalent in Reference 360 and it is created as a new code list in Reference 360. - Manually Mapped. Indicates that the lookup table and Reference 360 code list were manually mapped. - Unmapped. Indicates that the lookup table isn't mapped to a Reference 360 code list.

User Interface Elements	**Description**
Attributes Mapped	Number of code list attributes mapped, out of the total. For example, 2/3 means two of three attributes are mapped.
Action	Opens the attribute mapping dialog box, where you map the columns of the lookup table to the attributes of the code list.

6. To automatically map the MDM Hub lookup tables to Reference 360 code lists, perform the following steps:
    a. In the **Confidence Score** field, set a confidence score.

       You can set the confidence score value from 0 through 100 percent.

    b. Click **Automap**.

       The MDM Hub lookup tables and their columns are automatically mapped to Reference 360 code lists and their attributes based on the confidence score. If the confidence score of a lookup table or column falls below the threshold, the modernization process doesn't map it, and you can map it manually. For more information about confidence scores, see “Automapping fields by confidence score” on page 15.

    c. Review the mapping results in the **Summary** section.

       The following table describes the metrics that appear in the **Summary** section after you automap lookup tables to code lists:

Metrics	**Description**
Automapped Fields	Total number of lookup table columns automapped to code list attributes.
Newly Created Fields	Total number of code lists created in Reference 360.

7. To manually map the lookup tables from the MDM Hub to code lists in Reference 360, perform the following steps:
    a. In the **Reference 360 Code List** column, select a code list for a lookup table that you want to map.
    b. To create the lookup table as a new code list, select **Create as New**.
    c. Enter a unique name for the code list.
    d. Optionally, select a dependent code list in the **Dependent Code List** column if the code list that you are creating is dependent on another code list.
    e. Repeat steps aon page 30 through don page 30 to map the remaining lookup tables to their corresponding code lists.

Step 2. Map attributes

After you map the MDM Hub lookup tables to Reference 360 code lists, map the lookup table columns to the code list attributes for each mapped lookup table.

If a lookup table is automapped to a code list, then the corresponding lookup table columns are also automapped to the code list attributes. However, if some columns aren't mapped to the attributes, you can manually map them.

1. On the **Reference Data Mapping** page, find the lookup table and its mapped code list, and then click **Map Attributes** in the **Action** column.
2. To map the lookup table columns in the **MDM Hub Lookup Table** section to the code list attributes in the **Reference 360 Code List** section, perform the following steps:
    a. Drag each column from **Column Name** to **Mapped Column** for the corresponding attribute.
    b. Click **Save**.
3. To validate the mapping for errors, click **Validate**.

    The modernization process checks for validation errors in the mapping. If validation errors are found, they are displayed on the **Reference Data Mapping** page. You must fix the validation errors before marking the mapping as complete.
4. To reset the mapping, click **Reset**.

    The modernization process resets the mapping. You can start mapping the lookup tables to code lists from the beginning.
5. To complete the mapping process, click **Mark as Complete**.
6. Click **Save**.
7. Click **Close**.

    The **Map Fields** page appears. You can proceed to retrieve the business entity configuration and map business entity fields.

Step 3. Retrieve business entity configuration

Retrieve the business entity configuration from the MDM Hub and MDM SaaS and then map business entity fields from MDM SaaS. You can then map business entity fields from MDM SaaS to base object columns or business entity fields in the MDM Hub.

You can also create a custom business entity in MDM SaaS and map an MDM Hub business entity or base object that doesn't have an MDM SaaS equivalent.

1. In the **Business Entity** section, select one of the following options:
    - Base Object. Includes base objects of the MDM Hub and their columns in the configuration.
    - Business Entity. Includes business entities of the MDM Hub and their fields in the configuration.
2. Click **Get Configuration**.

    The modernization process retrieves the configuration from the MDM Hub base objects or business entities based on your selection along with the configuration of MDM SaaS. After you retrieve the configuration for the first time, you can also refresh the configuration to retrieve the latest changes.

The following image shows the retrieved configuration from the MDM Hub and MDM SaaS business entities on the Map Fields page:



Retrieve the business entity and reference data configurations, and then map the objects from the MDM Hub and MDM SaaS.

Retrieve business entity configuration from the MDM Hub and MDM SaaS. You can then map business entity fields from MDM SaaS to base objects and columns, or to business entity fields in the MDM Hub.

Select the data model type you use in the MDM Hub: ○ Base Object ● Business Entity

MDM SaaS Business Entity (3) Last Refreshed : 9/30/2026, 2:39:58 PM

Name	Internal ID	Action
Person_Custom_001	person_custom_001_mod_businessentity	Map Fields
Person	c360.person	Map Fields
Organization	c360.organization	Map Fields

Define Project		
Save the project	☑	Success
Map Fields		
Get the reference data configuration	☑	Success
Map reference data objects	ⓘ	In Progress
Get the business entity configuration	☑	Success
Map business entity fields	ⓘ	Yet to Start
Modernize		
Standardize Configuration	ⓘ	Yet to Start
Preview Data Model	ⓘ	Yet to Start
Modernize Data Model	ⓘ	Yet to Start
Preview Match Models	ⓘ	Yet to Start
Modernize Match Models	ⓘ	Yet to Start
Preview Hierarchies	ⓘ	Yet to Start
Modernize Hierarchies	ⓘ	Yet to Start
Preview Relationships	ⓘ	Yet to Start
Modernize Relationships	ⓘ	Yet to Start
Preview Relationship Graph	ⓘ	Yet to Start

The following table describes the user interface elements that you can see in the MDM SaaS Business Entity section:

User Interface Elements	Description
Name	Display name of the MDM SaaS business entity whose fields you map to MDM Hub business entity fields or base object columns.
Internal ID	Internal identifier of the MDM SaaS business entities.
Action	Opens the field mapping page, where you can map the MDM SaaS business entity fields to the MDM Hub business entity fields or base object columns.

3. To refresh the configuration, click **Refresh Configuration**.
4. Optionally, to review the retrieved configuration manually, click **Download Business Entity Configuration**.
5. To create a custom business entity in MDM SaaS, perform the following steps:
    a. In the **MDM SaaS Business Entity** section, click **Create MDM SaaS Business Entity**.
    b. Enter a unique name.
    c. Select the **MDM Hub Object** to map to the business entity.
    d. Click **Create**.

       The newly created custom business entity appears in the **MDM SaaS Business Entity** section.

Step 4. Map fields

After you review the retrieved business entity configuration, map the MDM Hub business entity fields and base object columns to MDM SaaS business entity fields.

1. On the **Map Fields** page, in the **MDM SaaS Business Entity** section, click **Action** > **Map Fields**.

   The business entity field mapping page appears. If you retrieved the MDM Hub base object configuration, the **MDM Hub Base Objects (Source)** appears in the source section. If you retrieved the MDM Hub business entity configuration, the **MDM Hub Business Entities (Source)** appears in the source section.

2. To include the child nodes of an MDM Hub root node, select the **MDM Hub Root Node**.
3. To add the MDM Hub business entities, click **Add MDM Hub Business Entities**.
4. To add the MDM Hub base objects, click **Add MDM Hub Base Objects**.
5. Select the MDM Hub objects for which you want to map the MDM Hub business entity fields.

   Note: You can select multiple MDM Hub objects to map to the selected MDM SaaS business entity.

6. To automatically map fields from the MDM Hub objects with MDM SaaS business entity fields, perform the following steps:
   1. Set a confidence score in the **Confidence Score** field.

      You can set the confidence score value from 0 through 100 percent.

   2. Click **Automap**.

      The modernization process automatically maps the fields or columns from the selected MDM Hub objects to MDM SaaS business entity fields, based on the confidence score. For fields or columns whose confidence score falls below the defined limit, the modernization process creates new business entity fields in MDM SaaS. You can then manually map those fields or columns to the appropriate business entity fields in MDM SaaS. For more information about confidence scores, see "Automapping fields by confidence score" on page 15.

   3. Review the mapping results in the **Summary** section.

      The following table describes the metrics that appear in the **Summary** section:

Metrics	Description
Automapped Fields	Indicates the total count of automapped fields.
Newly Created Fields	Indicates the total count of newly created fields.

7. To manually map fields or columns from the MDM Hub objects to MDM SaaS business entity fields, perform the following steps:
   1. Select the business entity fields or base object columns that you want to map to MDM SaaS business entity fields.
   2. Drag each column from **Column Name** to the **Mapped Hub Fields** column.
   3. Click **Save**.
8. To create source fields that don't have an MDM SaaS equivalent, perform the following steps:
   1. Select the source fields, and then click **Create as New**.

      The **Create as New** dialog appears.

   2. Enter a name for the field.

        Note: For a custom field in a predefined business entity, include the X_ prefix in the name.

    c. To create the selected field as a new field within an existing MDM SaaS field group, select a field group from the **MDM SaaS Field Group** list.
    d. To create the selected field as a root field in MDM SaaS, select **Root Field** from the **MDM SaaS Field Group** list.
    e. Click **Create**.

9. To validate the mapping for errors, click **Validate**.

    The modernization process validates the mapping and lists any validation errors. To view the validation errors, click **View Details**. Correct all the validation errors to save the mapping.

10. To reset the mapping, click **Reset**.
11. Click **Save**.

    The **Map Fields** page appears.

12. To complete the mapping process, click **Mark as Complete**.
13. Click **Next**.

    The **Modernize** page appears.

Mapping fields using smart field mapping

If you select smart field mapping during project definition, you can use smart mapping to automatically create business entities and their fields from the MDM Hub in MDM SaaS. Smart mapping eliminates the need to map business entities and their fields.

1. In the **Smart Field Mapping** section, click **Add Business Entities**.

    The **Add Business Entities** dialog box appears.

2. Select the MDM Hub business entities that you want to create automatically in MDM SaaS and click **Add**.

    The selected business entities appear in the **Business Entities** section. By default, the modernization process uses the names of the business entities from the MDM Hub that you add as their display names in MDM SaaS. If required, you can modify their display names.

3. To update the display names of a business entity, double-click the value in the **Display Name in MDM SaaS** column and update it.
4. Click **Generate Mapping**.

    The modernization process automatically generates a mapping file that contains the business entities and their attribute details. The generated mapping appears in the **Download Files** section. If you add or remove any business entities after generating the mapping file, regenerate the mapping file.

5. Click **Next**.

    The **Modernize** page appears.

Modernize

After you upload the mapped files, you can begin the modernization process.

The modernization process includes the following steps:

1. Standardize configuration.
2. Modernize data models.
3. Modernize match models.
4. Modernize hierarchies.
5. Modernize relationship graph.
6. Modernize user roles.
7. Modernize user accounts.

Step 1. Standardize configuration

To modernize the MDM Hub objects, upload your mapped files. The modernization process standardizes the uploaded configuration files into multiple JSON files.

For more information about standardizing configuration, see “Standardizing configurations” on page 19.

1. To prepare the objects in the uploaded configuration files for modernization, click **Standardize**.

   The **Business Entity Field Configurations** section appears with a list of business entities and their field properties. The business entities that exceed the property limits are highlighted in red.

   Note: The **Business Entity Field Configurations** section appears only when MDM Hub business entities and their field properties are present in the uploaded configuration files.
2. To manage the field properties of a business entity, click **Manage Field Properties** in the **Action** column.

   The **Manage Field Properties** dialog box appears.
3. Review the properties of business entity fields.
4. Disable field properties to stay within the allowed limits.

   Note: After modernization, save the business entity canvas and generate search indexes in MDM SaaS to reflect the changes made to field properties. The modernization process doesn't save the canvas or generate search indexes by default.
5. Click **Apply.**
6. Download the standardized configuration.

   After you download the standardized configuration, you can review the configuration details of the objects in JSON files and proceed to modernize data models. Whenever you re-upload a mapped file, you must standardize the configuration to reflect the changes.

Step 2. Modernize data models

When you modernize the data model, you can either include or exclude the lookup tables in the reference data mapping file.

For more information about modernizing data models, see “Data models” on page 19.

1. In the **Modernization Steps**, click **Data Model**.
2. To include the lookup tables in the mapped reference data mapping file, select **Include lookup tables mapped in the uploaded file**.

Note: If you don't include lookup tables, the modernization process considers only the lookup tables used in the mapping file for modernization. Unmapped lookup tables are excluded from modernization.

3. Click **Preview**.

   The **Preview and Modernize** section appears with a list of data model objects that are ready for modernization.

4. Review the objects.
5. In the **Preview and Modernize** section, click **Modernize**.

   You can view the status of the modernization process in the **Modernization Status** column.

Step 3. Modernize match rule sets

You can modernize the match rule sets and distinct source systems that the business entities use in the MDM Hub. If a match rule created for a business entity in the MDM Hub contains errors, the modernization process skips that rule and continues modernizing the rest of the rules in the rule set.

For more information about modernizing match rule sets, see "Match rule sets" on page 20.

1. In the **Modernization Steps**, click **Match Rule Set**.
2. Click **Preview**.

   The **Preview and Modernize** section appears with a list of match rule sets and distinct source systems that are ready for modernization.

3. To view the distinct source systems for each business entity, go to the **Distinct Source Systems** tab and click **View** next to the business entity.

   The **Distinct Source Systems** dialog box displays the distinct source systems configured for the business entity.

4. In the **Match Rules** tab, review the match rule sets.
5. Click **Modernize**.

   You can view the status of the modernization process in the **Modernization Status** column.

Step 4. Modernize hierarchies

You can modernize hierarchies and relationships from the MDM Hub.

For more information about hierarchies and relationships in the MDM Hub, see "Hierarchies and relationships" on page 24.

1. In the **Modernization Steps**, click **Hierarchies**.
2. Click **Preview**.

   The **Preview and Modernize** section appears with a list of hierarchies that are ready for modernization.

3. Review the hierarchies.
4. In the **Preview and Modernize** section, click **Modernize**.

   You can view the status of the modernization process in the **Modernization Status** column.

Step 5. Modernize relationship graph

You can modernize the relationship graph or non-hierarchical relationships from the MDM Hub.

For more information about non-hierarchical relationships in the MDM Hub, see "Hierarchies and relationships" on page 24.

1. In the **Modernization Steps**, click **Relationship Graph**.
2. Click **Preview**.

   The **Preview and Modernize** section appears with a list of non-hierarchical relationships that are ready for modernization.
3. Review the non-hierarchical relationships.
4. In the **Preview and Modernize** section, click **Modernize**.

   You can view the status of the modernization process in the **Modernization Status** column.

Step 6. Modernize user roles

You can modernize the user roles in the MDM Hub.

For more information about modernizing user roles, see "User accounts and user roles" on page 24.

1. In the **Modernization Steps**, click **User Roles**.
2. Click **Preview**.

   The **Preview and Modernize** section appears with a list of user roles that are ready for modernization. The user roles appear as hyperlinks.
3. Click the user role for which you want to review or modify the privileges.

   The **User Roles** page of the Informatica Intelligent Cloud Services Administrator opens in a new browser tab.
4. Review or modify the privileges in Administrator, and click **Save**.
5. In the **Preview and Modernize** section, click **Modernize**.

   You can view the status of the modernization process in the **Modernization Status** column.

Step 7. Modernize user accounts

You can modernize user accounts from the MDM Hub. After modernization, user accounts become inactive in MDM SaaS and an activation email is sent to the registered email address of users. Users can activate their accounts by following the instructions in the email.

For more information about modernizing user accounts, see "User accounts and user roles" on page 24.

1. In the **Modernization Steps**, click **User Accounts**.
2. Click **Preview**.

   The **Preview and Modernize** section appears with a list of user accounts that are ready for modernization.
3. To view the user roles associated with each user account, click **View**.

   The **User Roles** dialog box appears with the user roles associated with the selected user account.
4. Review the user accounts.
5. In the **Preview and Modernize** section, click **Modernize**.

   You can view the status of the modernization process in the **Modernization Status** column.

CHAPTER 5

Migrating data

After you complete the modernization process, you can migrate data from the MDM Hub to MDM SaaS.

Before you start migrating data from the MDM Hub, ensure that the modernized MDM Hub objects, such as data models, reference data, and data quality rules are configured and available in MDM SaaS.

For more information about migrating data from the MDM Hub to MDM SaaS, see the MDM Modernization Data Migration Knowledge article.

To migrate data, contact Informatica Global Customer Support.

CHAPTER 6

Managing modernization projects

Starting with the October 2026 release, you can't create modernization projects that use excel-based mapping files to modernize MDM Hub objects. However, you can continue to update existing modernization projects using excel-based mapping files that are in progress.

If you map business entities manually, you must generate a data model mapping file and manually map the business entity fields or base object columns from the MDM Hub to the business entity fields in MDM SaaS. For more information about manually mapping objects in a data model mapping file, see "Data model mapping file" on page 42

Modernization mapping files

A modernization mapping file is an XLS or XLSX file that includes details about the objects in the MDM Hub and MDM SaaS. MDM SaaS generates mapping files by using its configuration and the MDM Hub configuration files you upload.

After you generate mapping files, review them thoroughly to understand the objects in MDM SaaS and the MDM Hub.

You can use the following mapping files to modernize the objects in the MDM Hub:

- Reference data mapping file. Contains details of lookup tables and Reference 360 code lists.
- Data model mapping file. Contains details of base objects and their columns or business entities and their fields.

A mapping file contains multiple sheets with object details from MDM SaaS and the MDM Hub.

The following table describes the sheets that you can find in a mapping file:

Sheet Name	Description
M-Index	Provides an overview of the mapping file and the uploaded file.
M-SourceEntities	Lists the lookup tables, base objects and their columns, or business entities and their fields from the change list XML file. The objects vary based on the mapping file.
M-OnPremise-BE	Lists all business entities in the MDM Hub. Applicable only for the data model mapping file.

Sheet Name	Description
<Name of a Code list> | <Name of a lookup table>	Lists all code lists from Reference 360 as individual sheets. Applicable only for the reference data mapping file. You can also include sheets for all the look tables in the MDM Hub. The lookup tables and their columns, base objects and their columns of the MDM Hub appear as drop-down values in the source columns of these sheets.
<Name of a Business Entity>	Lists all business entities from MDM SaaS as individual sheets. Applicable only for data model mapping file. The business entities and their fields of the MDM Hub appear as drop-down values in the source columns of these sheets.
M-Exceptions	Lists the business entities and their fields that aren't mapped in the target and source columns of the mapping file. This sheet appears after you upload the mapping file. The modernization process validates the mapping file and populates the sheet with business entities and their fields that aren't mapped. You can review the details in the sheet and map the required ones.
Error	Lists validation errors in the mapping file, such as field mapping missing in a column or field type mismatch. This sheet appears after you upload the mapping file. The modernization process validates the mapping file and populates the sheet with validation errors. After you resolve the errors in the field mappings, upload the mapping file again to proceed with modernization.

Reference data mapping file

A reference data mapping file includes multiple sheets. Each sheet represents a code list from Reference 360. If you select to include lookup tables when you create a mapping file, the mapping file also includes sheets for all lookup tables.

The source columns in each sheet display lookup tables and their columns as drop-down values. You can map the attributes of code lists, such as Name, Code, and Description, with the columns of a lookup table.

During modernization, if you don't have a corresponding code list for a lookup table, the modernization process can create a code list for the lookup table.

Note: You can't manually add custom attributes of a code list to the sheets in the reference data mapping file. After modernization, you can add custom attributes to the code lists.

Each code list sheet in the mapping file displays the following details:

Column Name	Description
<Reference Codelist>	Name of the code list to which you want to map a lookup table.
<Name of a lookup table>	Name of the lookup table in the MDM Hub that was included in the mapping file. The sheet name uses the name of the lookup table.
Dependent Codelist Parent	Name of the parent code list. For example, the Country code list is the parent of the State code list. Applicable only when the code list related to the sheet is a dependent code list.

Column Name	Description
Target R360 Reference Set	A list of default attributes of the code list related to the sheet, including their data types. The default attributes are Name, Code, and Description.
Source MDM Lookup	Placeholder to map a lookup table and its column for each attribute.

The following image shows a sample sheet in a reference data mapping file:



	A	B	C	D	E
1	Reference Codelist	ExecutiveType			
2					
3					
4	Target R360 Reference Set			Source MDM Lookup	
5	ExecutiveType	Field Info	Custom	Base Object	Field Info
6	Name	String			
7	Code	String			
8	Description	String			

A1
fx
Reference Codelist
ExecutiveType
AddressEnrichedIndicator
RevenueType
Currency
Employment

Sheets for lookup tables

By default, a mapping file contains sheets for all the code lists in Reference 360. These sheets allow you to map lookup tables to every code list.

You can also include sheets for all the lookup tables in the MDM Hub. The modernization process uses these sheets to create code lists in Reference 360.

For example, if the MDM Hub has 50 lookup tables and Reference 360 has 30 code lists, you can map 30 lookup tables to the 30 code lists. For the remaining 20 code lists, you don't have equivalent code lists in Reference 360, but you have a requirement for them in MDM SaaS.

To modernize them, you can choose to add sheets for all the lookup tables. Using these sheets, you can create code lists for these lookup tables in Reference 360 during modernization. You can delete other irrelevant sheets created for lookup tables that you don't need. The sheets that are created for the lookup tables use the following naming format:

```
LU<Name_of_the_lookup_table>
```

The following image shows a sheet created for a lookup table:



	A	B	C	D	E
1	Reference Codelist	LUAddressType			
2	Dependent Codelist Parent				
3					
4	Target R360 Reference Set			Source MDM Lookup	
5	LUAddressType	Field Info	Custom	Base Object	Field Info
6	name	string			
7	code	string			
8	description	string			

A1
fx
Reference Codelist
LUAddressType
LUChannel
LUCommunicationType
LUCountry
LUElectronicA

In the Custom column, enter X to indicate that the code list and its attributes need to be created in Reference 360.

Data model mapping file

A data model mapping file contains details of base objects and their columns or business entities and their fields. The mapping file includes separate sheets for each business entity in MDM SaaS.

You can either generate a data model mapping file based on the base objects or business entities of the MDM Hub.

A data model mapping file based on base objects uses the base objects and their columns of the MDM Hub for mapping. A data model mapping file based on business entities uses the business entities and their fields of the MDM Hub for mapping. Within a sheet, map each business entity field of MDM SaaS to a business entity field or a base object column of the MDM Hub.

If an application has more than one business entity with the same name, the sheet names include a number suffix. For example, if Customer 360 has three business entities named Person, the mapping file contains the Person, Person2, and Person3 sheets. To find the business entity that a sheet maps to, check the business entity name in cell E1 of the sheet.

If business entities in MDM Hub include fields that don't exist in MDM SaaS, you can create those fields as custom fields. For example, consider a business entity called Account in the MDM Hub that contains additional fields, such as Loan_Account and Loan_Type. When you start mapping the fields in the mapping file, you realize that MDM SaaS doesn't have equivalent fields to map with them. You can manually add these fields as custom fields in the mapping file and then map them to a column of a base object or business entity field in the MDM Hub.

Note: For existing projects, you can still upload mapping files that you downloaded in earlier releases. When you download a mapping file again, the first row of each sheet contains the name of the MDM SaaS business entity.

The following image shows a sample sheet in a data model mapping file based on base objects:



A	B	C	D	E
On Premise Root BE	None			
Target SaaS Entity search_match_be	**Field Info**	**Custom**	**Source MDM Base Object**	**Field Info**
firstname	String(255)			
lastname	String(255)			
fullname	String(255)			
middlename	String(255)			
X_age	Integer	X		
X_salary	Double	X		
X_credit_value	Decimal	X		
vehicle	Boolean			
search_match_be.Address (1:M)	**Smart Field Group (PostalAddress)**			
defaultIndicator	Boolean			
addressType	Picklist			
usageType	Picklist			
addressStatus	Picklist			
addressLine1	String(200)			
addressLine2	String(200)			
addressLine3	String(200)			

The following image shows a sample sheet in a data model mapping file based on business entities:



On Premise Root BE	Organization			
Target SaaS Entity custombe1	Field Info	Custom	Source MDM Base Object	Field Info
fullname	String(255)			
col02	String(255)			
col03	String(255)			
networth	Decimal			
custombe1.Address (1:M)	Smart Field Group (PostalAddress)			
defaultIndicator	Boolean			
addressType	Picklist			
usageType	Picklist			
addressStatus	Picklist			
addressLine1	String(200)			
addressLine2	String(200)			
addressLine3	String(200)			
X_city	String(50)	X		
X_county	String(50)	X		
X_country	Picklist	X		
state	Picklist			

Adding custom fields and field groups

If business entities in MDM SaaS don’t include certain fields or field groups present in the MDM Hub, you can add them as custom fields or field groups.

When adding custom fields, prefix the attribute name with either `X_` or `x_` to indicate that it's a custom field. Also, ensure that you mark custom fields with the character `X` in the Custom column to indicate that they are custom fields.

Similarly, you can also add custom field groups to the mapping file. When you add a custom field group, ensure that you prefix the character `X_` to the name of the field group. For example, when you add a custom PostalAddress field group, ensure that you prefix the character `X_` in the following format:

```
c360.person.X_PostalAddress
```

Note: Ensure that you don't delete or add sheets in a data model mapping file.

The following image shows custom fields added to the data model mapping file:



A	B	C	D	E
On Premise Root BE	Person			
Target SaaS Entity c360.person	Field Info	Custom	Source MDM Base Object	Field Info
X_Loan_Account	Picklist	X	CreditCard	CreditCard.accountNumber | VARCHAR (20)
X_Loan_Type	Picklist	X	CreditCard	CreditCard.accountType | VARCHAR (255)
c360.person.X_postaladdress (1:M)				
X_addressline1	String(255)	X		
X_addresstype	Picklist	X		
X_city	String(255)	X		
X_country	Picklist	X		
X_postalcode	String(255)			
X_raw_addressline1	String(255)			
X_raw_city	String(255)			

The following table describes the headers included in a sheet related to a business entity of MDM SaaS:

Column Name	Description
On Premise Root BE	A root business entity from the MDM Hub. For example, if the sheet name is Person, you can select Individual as a root business entity from the MDM Hub. For more information about mapping on-premise root business entity, see "Mapping on-premises root node" on page 44.
Target SaaS Entity	Lists all the attributes of a business entity in MDM SaaS with their data type. You can also add custom attributes of a business entity in MDM SaaS. For more information about adding custom fields and field groups, see "Adding custom fields and field groups" on page 43
Source MDM	Placeholder to map a base object and its column or a business entity and its field to each attribute of the business entity in MDM SaaS.

Note: After you map picklist fields in a data model mapping file, ensure that the corresponding lookup tables are mapped in the reference data mapping file. If you miss to map a lookup table that a business entity field or a base object column uses, the modernization process returns validation errors.

You can insert new rows to the data model mapping file with the field details, such as name and type and then map them to the corresponding MDM Hub fields. When you add the field name, ensure that you prefix the name with the character `X` or `x` to indicate that it's a custom field. Also, ensure that you mark the Custom column with the character `X` or `x` to indicate a custom field. You must prefix the field group name with character `X` or `x` to indicate a custom field group. You can't create custom fields for smart fields, such as address, phone, and email.

After modernization, the custom fields mapped in the mapping file uses the field properties of the MDM Hub including the display name. However, the predefined MDM SaaS fields uses only the privileges from the MDM Hub.

Mapping on-premises root node

In the MDM Hub, the root node is the uppermost node in a business entity. You can add multiple child nodes to a root node within a business entity.

The child nodes within the business entity are equivalent to the field groups in MDM SaaS. For example, a Person root node in the MDM Hub can include Contact Address, Telephone, and Email Address as child nodes. In MDM SaaS, a business entity can include field groups, such as Address, Phone Number, and Email Address.

Generating mapping files

You can generate mapping files based on the configuration details of the MDM Hub and the data model of MDM SaaS. After you download them, you can map the MDM Hub objects with the MDM SaaS objects.

If you choose to map the fields manually, you can generate separate mapping files for reference data and data model objects. If you choose to create business entities in the MDM Hub automatically in MDM SaaS, you can generate a mapping file only for reference data objects.

You can also regenerate mapping files for changes in the data model of MDM SaaS after the initial mapping file generation. For more information about modernization mapping files, see "Modernization mapping files" on page 39.

Step 1. Generate reference data mapping file

By default, a reference data mapping file includes separate sheets for each code list in MDM SaaS.

1. To create separate sheets for all the lookup tables in the MDM Hub, on the **Map Fields** page, select **Include lookup tables from the MDM Hub in the mapping file**.

   Note: For more information about lookup table sheets, see "Sheets for lookup tables" on page 41

2. Click **Generate Mapping File**.
3. Select the file format, and click **Download**.
4. Open the downloaded mapping file, and map the fields.

   For more information about mapping fields in a reference data mapping file, see "Reference data mapping file" on page 40

   Note: You can add or remove any of the sheets and upload the mapped file.

5. To upload the mapped reference data mapping file, click **Browse**, and select the mapped file.

   Note: You can't upload a mapped file that's associated with a different project or an older version of the mapping file.

6. Click **Upload**.

   After you generate a mapping file, if the reference data is updated in Reference 360, you can regenerate the mapping file to reflect the changes.

7. To regenerate a reference data mapping file, click **Regenerate Mapping File** in the **Reference Data** section.
8. To download the latest version of the reference data mapping file, click **Download latest reference list**.

Step 2. Generate data model mapping file

If you select manual mapping during project definition, you can generate a data model mapping file to map business entity attributes from MDM SaaS with base object columns or business entity fields from the MDM Hub.

1. In the **Data Model** section, select one of the following options:
   - Base Object. Indicates to include base objects of the MDM Hub and their columns in the mapping file.
   - Business Entity. Indicates to include business entities of the MDM Hub and their fields in the mapping file.
2. Click **Generate Mapping File**.

   The **Download Mapping File** dialog box appears.

3. Select the file format, and click **Download**.

   Note: If a data model mapping file contains more than 255 base objects, ensure that you download the mapping file as an XLSX file.

4. Open the downloaded mapping file, and map the fields.

   For more information about mapping fields in a data model mapping file, see "Data model mapping file" on page 42

   Note: You can't add or remove any of the sheets.

5. To upload the mapped data model mapping file, click **Browse**, and select the mapped mapping file.

   Note: You can't upload a mapped mapping file that's associated with a different project or an older version of the generated mapping file.

6. Click **Upload**.

After you upload a mapping file, if the data model is updated in MDM SaaS, you can regenerate the mapping file to reflect the changes.

7. To regenerate a data model mapping file, click **Regenerate Mapping File** in the **Data Model** section.
8. To download the latest version of the data model mapping file, click **Download latest entity list.**
9. Click **Next**.

   The **Modernize** page appears.

Guidelines for mapping objects in modernization mapping files

When you map objects in the modernization mapping files, consider the following guidelines:

- You can add or remove sheets from the reference data mapping file before uploading it. However, you can't add or remove sheets from the data model mapping file.
- Don't modify the names of code list attributes or business entities and their data types in the mapping files. The modernization process doesn't process these changes.
- Ensure that the lookup table columns mapped with business entity fields in the data model mapping file are also mapped in the reference data mapping file.
- If you don't want to modernize hierarchies and relationships, ensure that you don't map any business entity to the On Premise Root BE field in the data model mapping file.
- Regenerating modernization mapping files resets the existing mappings. After regenerating, you need to remap the fields and upload the mapping files. If you re-upload the configuration files or if MDM SaaS includes configuration changes, you must regenerate mapping files.
- Don't map MDM SaaS field types if their length is shorter than that of the corresponding MDM Hub object fields.

Download event logs

You can download event logs to analyze important events or troubleshoot issues encountered during the modernization process. The log file is available for download after you create a modernization project. You can download the event log file in .ZIP format.

1. Open the modernization project for which you want to download the event logs.
2. Click **Download Logs**.

Deleting modernization projects

You can create up to 10 modernization projects within an organization. If you want to create additional projects, you need to delete existing ones.

If you delete modernization projects after you map the fields, or preview the assets but before you modernize them, the delete process removes the projects without affecting MDM SaaS because the assets don't exist in MDM SaaS yet. If you delete modernization projects after their assets are successfully modernized and migrated to MDM SaaS, the delete process doesn't remove the project folder or the assets associated with those projects from MDM SaaS.

1. On the **Modernization** page, click **Active Projects**.
2. Select the project that you want to delete, and click **Actions**.
3. Click **Delete**.

   A confirmation dialog box appears.
4. Click **OK**.

   The project is deleted.

Archiving modernization projects

You can have up to 10 active modernization projects and up to 20 archived projects in an organization. Archive projects you no longer need to free up space for new projects.

You can still include archived projects in summaries, and delete them if you no longer need them.

1. On the **Modernization** page, click **Active Projects**.
2. Select the project that you want to archive, and click **Actions**.
3. Click **Archive**.

   A confirmation dialog box appears.
4. Click **OK**.

   The project is archived. You can view the project on the **Archived Projects** tab.

Summary of modernization projects

After you modernize MDM Hub objects, you can view a consolidated summary of modernization progress for your modernization projects. The summary aggregates key metrics and details by object type so that you can track your modernization progress from the MDM Hub to MDM SaaS.

You can create up to five summaries. A summary can include both active and archived projects, but not deleted projects. You can view summaries, but you can't export or download them. If you delete a project that a summary includes, you can't regenerate the summary.

Creating a summary of modernization projects

You can create up to five summaries of modernization projects. To create more summaries, delete some of your summaries.

1. On the **Modernization** page, click **Create Summary**.
2. In the **Create Summary** dialog box, enter a unique summary name.
3. Select the projects to include in the summary.

   Note: You can select up to 5 projects to include in the summary.
4. Click **Create**.

   The **Modernization Summary** page appears.

Modernization summary

Use the Modernization Summary page to track your modernization progress across projects. You can use the modernization metrics and modernization details to see which objects are in progress, yet to start, or failed.

Modernization metrics

The modernization metrics show the count of MDM Hub objects in the selected projects and their modernization status.

The following table describes each metric:

Metric	Description
Total Objects	Total number of MDM Hub objects in the selected projects. **Note:** If a summary includes more than one project, the summary counts each MDM Hub object once in the overall total, even if the object appears in more than one project.
Successfully Modernized	Number of MDM Hub objects that are modernized.
In Progress	Number of MDM Hub objects that are currently undergoing modernization.
Yet to Start	Number of MDM Hub objects that aren't modernized yet.
Skipped	Number of MDM Hub objects that are skipped because they already exist in MDM SaaS.
Failed	Number of MDM Hub objects that failed to modernize.
Overall Progress	Percentage of successfully modernized MDM Hub objects out of the total objects in the selected projects. **Note:** The overall progress includes skipped MDM Hub objects. If all the MDM Hub objects in a project already exist in MDM SaaS, the progress of the project shows 0%.

Modernization details

The modernization details display the mapping between each MDM Hub object and its corresponding MDM SaaS object, along with the modernization status. You can view the modernization details to track the modernization status of each object and identify the objects that aren't modernized.

When you select an object type, you can view its modernization metrics, including the total number of objects and how many are successfully modernized, in progress, yet to start, or failed.

You can view the modernization details for one object type at a time. Select an object type, such as lookup table or user, to view its mapping details. You can filter the modernization details by status. For example, you can filter a lookup table by status to view only the objects that failed to modernize.

Lookup Table

The following table describes the mapping details that you can view for a lookup table:

Mapping Details	Description
Project Name	Name of the project.
MDM Hub Lookup Table	Lookup table retrieved from the MDM Hub configuration.
Reference 360 Code List	Reference 360 code list that the MDM Hub lookup table is mapped to.
Mapping Type	Type of mapping applied. The mapping type can have one of the following values: - One-to-One (Name Unchanged). An MDM Hub object is mapped to a code list. - Many-to-One. Multiple MDM Hub objects are mapped to a single code list. - Create as New. An MDM Hub object is created as a code list in MDM SaaS. - Yet to Map. The MDM Hub object isn't mapped to any code list.
Status	Modernization status of the object. The status can have one of the following values: - Yet to Start. The object isn't modernized yet. - In Progress. The object is currently undergoing modernization. - Migrated. The object is successfully modernized. - Failed. The object failed to modernize. - Skipped. The object was excluded from modernization.

Base Object

The following table describes the mapping details that you can view for a base object:

Mapping Details	Description
Project Name	Name of the project.
MDM Hub Base Object	Base object that stores master data in the MDM Hub.
MDM SaaS Business Entity	Corresponding business entity in MDM SaaS.

Mapping Details	Description
Mapping Type	Type of mapping applied. The mapping type can have one of the following values: - One-to-One (Renamed). An MDM Hub object is mapped to a target business entity and renamed in MDM SaaS. - One-to-One (Name Unchanged). An MDM Hub object is mapped to a predefined MDM SaaS business entity. - Many-to-One. Multiple MDM Hub objects are mapped to a single MDM SaaS business entity - Yet to Map. The MDM Hub object isn't mapped to any MDM SaaS business entity. - Unmapped. The MDM Hub object isn't transformed and appears as is.
Status	Modernization status of the object. The status can have one of the following values: - Yet to Start. The object isn't modernized yet. - In Progress. The object is currently undergoing modernization. - Migrated. The object is successfully modernized. - Failed. The object failed to modernize. - Skipped. The object was excluded from modernization.

Business Entity

The following table describes the mapping details that you can view for a business entity:

Mapping Details	Description
Project Name	Name of the project.
MDM Hub Business Entity	Business entity that defines the data model in the MDM Hub.
MDM SaaS Business Entity	Corresponding business entity in MDM SaaS.
Mapping Type	Type of mapping applied. The mapping type can have one of the following values: - One-to-One (Renamed). An MDM Hub object is mapped to a target business entity and renamed in MDM SaaS. - One-to-One (Name Unchanged). An MDM Hub object is mapped to a predefined MDM SaaS business entity. - Many-to-One. Multiple MDM Hub objects are mapped to a single MDM SaaS business entity. - Yet to Map. The MDM Hub object isn't mapped to any MDM SaaS business entity.
Status	Modernization status of the object. The status can have one of the following values: - Yet to Start. The object isn't modernized yet. - In Progress. The object is currently undergoing modernization. - Migrated. The object is successfully modernized. - Failed. The object failed to modernize. - Skipped. The object was excluded from modernization.

Match Rule Set

The following table describes the mapping details that you can view for a match rule set:

Mapping Details	Description
Project Name	Name of the project.
MDM Hub Business Entity	Business entity that the match rule set is configured for in the MDM Hub.
MDM SaaS Match Model	Corresponding match model in MDM SaaS.
Status	Modernization status of the object. The status can have one of the following values: - Yet to Start. The object isn't modernized yet. - In Progress. The object is currently undergoing modernization. - Migrated. The object is successfully modernized. - Failed. The object failed to modernize. - Skipped. The object was excluded from modernization.

Source System

The following table describes the mapping details that you can view for a source system:

Mapping Details	Description
Project Name	Name of the project.
MDM Hub Business Entity	Name of the source system in the MDM Hub.
MDM SaaS Business Entity	Corresponding business entity in MDM SaaS.
Status	Modernization status of the object. The status can have one of the following values: - Yet to Start. The object isn't modernized yet. - In Progress. The object is currently undergoing modernization. - Migrated. The object is successfully modernized. - Failed. The object failed to modernize. - Skipped. The object was excluded from modernization.

Hierarchy Relationship

The following table describes the mapping details that you can view for a hierarchy relationship:

Mapping Details	Description
Project Name	Name of the project.
MDM Hub Hierarchy Relationship	Hierarchy relationship between records in the MDM Hub.

Mapping Details	Description
MDM SaaS Hierarchy Relationship	Corresponding hierarchy relationship in MDM SaaS.
Status	Modernization status of the object. The status can have one of the following values: - Yet to Start. The object isn't modernized yet. - In Progress. The object is currently undergoing modernization. - Migrated. The object is successfully modernized. - Failed. The object failed to modernize. - Skipped. The object was excluded from modernization.

Network Relationship

The following table describes the mapping details that you can view for a network relationship:

Mapping Details	Description
Project Name	Name of the project.
MDM Hub Network Relationship	Non-hierarchical relationship between records in the MDM Hub.
MDM SaaS Non-Hierarchical Relationship Graph	Corresponding non-hierarchical relationship graph in MDM SaaS.
Status	Modernization status of the object. The status can have one of the following values: - Yet to Start. The object isn't modernized yet. - In Progress. The object is currently undergoing modernization. - Migrated. The object is successfully modernized. - Failed. The object failed to modernize. - Skipped. The object was excluded from modernization.

User Role

The following table describes the mapping details that you can view for a user role:

Mapping Details	Description
Project Name	Name of the project.
MDM Hub User Role	User role defined in the MDM Hub.
MDM SaaS User Role	Corresponding user role in MDM SaaS.
Status	Modernization status of the object. The status can have one of the following values: - Yet to Start. The object isn't modernized yet. - In Progress. The object is currently undergoing modernization. - Migrated. The object is successfully modernized. - Failed. The object failed to modernize. - Skipped. The object was excluded from modernization.

User

The following table describes the mapping details that you can view for a user:

Mapping Details	Description
Project Name	Name of the project.
MDM Hub User	User defined in the MDM Hub.
MDM SaaS User	Corresponding user in MDM SaaS.
Status	Modernization status of the object. The status can have one of the following values: - Yet to Start. The object isn't modernized yet. - In Progress. The object is currently undergoing modernization. - Migrated. The object is successfully modernized. - Failed. The object failed to modernize. - Skipped. The object was excluded from modernization.

Regenerating summaries

As you continue to modernize on-premises objects, the metrics and statuses in an existing summary might become outdated. Regenerate a summary to update it with the latest modernization progress for the selected projects. Regenerating updates the existing summary instead of creating a new one.

You can regenerate a summary only after the modernization process compiles the summary data.

1. On the **Modernization** page, click **Generated Summaries**.
2. Select the summary you want to regenerate.
3. On the **Modernization Summary** page, click **Regenerate**.

   The summary is regenerated.

   Note: If you delete a project that a summary includes, you can't regenerate the summary.

Deleting summaries

You can create up to five summaries. If you've reached the limit, delete a summary before creating another.

1. On the **Modernization** page, click **Generated Summaries**.
2. Select the summary you want to delete, and click **Delete**.

   A confirmation dialog box appears.
3. Click **OK**.

   The summary is deleted.

INDEX

I

Informatica Global Customer Support
  contact information 6
Informatica Intelligent Data Management Cloud
  web site 5

M

maintenance outages 6

S

status
  IDMC 6
system status 6

T

trust site
  description 6

U

upgrade notifications 6

W

web site 5