
The guide

Google Artemis: the setup guide

Control your Android phone with plain English, from a web page, the terminal or your AI coding tool. For anyone with an Android phone (or emulator) and a computer.



Free guide from the reel

29 October 2026

Quick start

1. Turn on USB debugging on your Android phone and plug it in.
2. Run `git clone https://github.com/google/artemis.git`, then `cd artemis` and `./start.sh` (Windows: `.\start.bat`).
3. Add one AI model key to `.env`, then run `uv run artemis ui` and open http://localhost:8000.

What it is

Artemis is Google's open-source tool (Apache 2.0) that turns instructions like "Open Settings, find Battery and tell me the level" into actions on a real Android device. You can drive it from a web console, the command line, an MCP server for AI IDEs, or a Python SDK.

Before you start

- **A computer:** macOS, Linux or Windows. iOS phones are not supported yet (it is on the roadmap).
- **Python 3.12 or newer.**
- **An Android phone with USB debugging on**, or an Android emulator.
- **One AI model key:** Gemini, Google, OpenAI, Anthropic, OpenRouter or xAI. Each provider bills its own model use, so check their pricing.
- You don't need to install ADB, scrcpy, FFmpeg or uv first: the start script adds them if they are missing.

Step 1: Turn on USB debugging

1. On the phone, open **Settings → About phone** and tap **Build number** seven times to unlock developer options.
2. Open **Developer options** and turn on **USB debugging**.
3. Plug the phone into the computer and tap **Allow** when it asks to trust this computer.

Step 2: Get Artemis

1. Clone it: `git clone https://github.com/google/artemis.git`
2. Go into the folder: `cd artemis`

3. Start it:
    - macOS or Linux: `./start.sh`
    - Windows PowerShell: `.\start.bat` (in CMD: `start.bat`)

Step 3: Add your model key

1. Run `uv run artemis init` for the first-time setup, or copy `.env.example` to `.env`.
2. Put one key in `.env`, for example `GEMINI_API_KEY=` followed by your key. Keep this file private.

Step 4: Run your first task

- In the terminal: `uv run artemis run "Open Settings, find Battery and tell me current level" --profile flash`
- Or in the browser: `uv run artemis ui`, then open **http://localhost:8000**

The first task installs a small **Accessibility Helper** app on the phone. It lets Artemis read the screen, and it listens only on the phone itself.

Pick a speed

- **flash** (the default): a fast loop, about 3 to 5 seconds a step. Good for simple tasks.
- **pro**: plans, acts, then checks its own work, about 15 to 40 seconds a step. Better for long, multi-app jobs.

Set the default with `ARTEMIS_DEFAULT_PROFILE` in `.env`.

Use it from your AI coding tool (optional)

1. Run `uv run artemis mcp --install all` to add it to every supported tool, or `uv run artemis mcp --generate-config <client>` for one.
2. Supported: Antigravity, Codex, Cursor, Claude Code and Claude Desktop, Windsurf, VS Code, Cline and Roo Code, OpenClaw.
3. Your tool then gets five actions: run a task, manage a running task, read the screen, inspect what it did, and diagnose problems.

Try these

Copy one into the web console or after `uv run artemis run`. Keep one small goal per task, and start on a test phone.

- `Open Settings, find Battery and tell me current level`
- `Open Settings, find Battery and report the level. Take a screenshot. Do not change any settings.`
- `Open [your app] and describe the main navigation. Take a screenshot of each main tab. Do not submit forms.`
- `Try these steps in [your app]: [steps]. Report what happened, with screenshots and Logcat.`

Gotchas

- **Using your personal phone?** Set `ARTEMIS_HELPER_AUTO_INSTALL=false` (then install the helper only when you choose, with `uv run artemis helper install`) and `ARTEMIS_KEEP_DEVICE_AWAKE=false` so the screen still times out.
- **Something not working?** Run `uv run artemis doctor` first. `uv run artemis status`, `stop` and `restart` manage the background server.
- **Remove the helper** any time with `uv run artemis helper uninstall`.
- It drives a real phone: start on a test device or emulator before you let it near your banking or chat apps.

Links

- Artemis on GitHub
- The settings file, .env.example
- MCP server guide
- Android: turn on USB debugging