# Package 'rpart.plot'

August 13, 2018

Version 3.0.4

Title Plot 'rpart' Models: An Enhanced Version of 'plot.rpart'
Author Stephen Milborrow
Maintainer Stephen Milborrow <milbo@sonic.net></milbo@sonic.net>
<b>Depends</b> R (>= 3.2.0), rpart (>= 4.1-10)
Suggests earth (>= 4.4.6)
<b>Description</b> Plot 'rpart' models. Extends plot.rpart() and text.rpart() in the 'rpart' package.
License GPL-3
<pre>URL http://www.milbo.org/rpart-plot</pre>
NeedsCompilation no
Repository CRAN
<b>Date/Publication</b> 2018-08-13 21:30:03 UTC
R topics documented:
prp
ptitanic
rpart.plot
rpart.plot.version1
rpart.predict
rpart.rules
show.prp.palettes
Index 20

prp

Plot an rpart model.

#### Description

Plot an rpart model.

This function combines and extends plot.rpart and text.rpart in the rpart package. For an overview, please see the package vignette Plotting rpart trees with the rpart.plot package.

The function rpart.plot provides a simplified interface to this function. First-time users should use rpart.plot rather than this function.

The arguments of this function are a superset of those of rpart.plot and some of the arguments have different defaults. See the rpart.plot help page for a table showing the different defaults.

(The defaults are different for historical reasons: for backwards compatibility the defaults of prp haven't changed, whereas the defaults of rpart.plot were changed when type="auto" and box.palette were introduced in version 2.0.0 of this package.)

#### Usage

```
prp(x=stop("no 'x' arg"),
    type=0, extra=0, under=FALSE, fallen.leaves=FALSE,
    nn=FALSE, ni=FALSE, yesno=TRUE,
    branch=if(fallen.leaves) 1 else .2,
    uniform=TRUE, left=TRUE, xflip=FALSE, yflip=FALSE,
    digits=2, varlen=-8, faclen=3, roundint=TRUE,
    cex=NULL, tweak=1,
    clip.facs=FALSE, clip.right.labs=TRUE,
    compress=TRUE, ycompress=uniform,
    Margin=0, space=1, gap=NULL,
    snip=FALSE, snip.fun=NULL, trace=FALSE,
    box.col=0, box.palette=0,
    pal.thresh=NULL, pal.node.fun=FALSE,
    border.col=col,
    round=NULL, leaf.round=NULL,
    shadow.col=0, prefix="", suffix="", xsep=NULL,
    under.font=font, under.col=1, under.cex=.8,
    split.cex=1, split.font=2, split.family=family, split.col=1,
    split.box.col=0, split.border.col=0,
    split.lty=1, split.lwd=NULL, split.round=0,
    split.shadow.col=0,
    split.prefix="", right.split.prefix=NULL,
    split.suffix="", right.split.suffix=NULL,
    facsep=",", eq=" = ", lt=" < ", ge=" >= ",
```

```
branch.col=if(is.zero(branch.type)) 1 else "gray",
branch.lty=1, branch.lwd=NULL,
branch.type=0, branch.tweak=1,
min.branch.width=.002, branch.fill=branch.col,
nn.cex=NULL, nn.font=3, nn.family="", nn.col=1,
nn.box.col=0, nn.border.col=nn.col,
nn.lty=1, nn.lwd=NULL, nn.round=.3,
yes.text="yes", no.text="no",
node.fun=NULL,
split.fun=NULL,
FUN="text",
nspace=branch, minbranch=.3, do.par=TRUE,
add.labs=TRUE, clip.left.labs=(type == 5), fam.main="",
yshift=0, yspace=space, shadow.offset=.4,
split.adj=NULL, split.yshift=0, split.space=space,
split.yspace=yspace, split.shadow.offset=shadow.offset,
nn.adj=.5, nn.yshift=0, nn.space=.8, nn.yspace=.5,
ygap=gap/2, under.ygap=.5, yesno.yshift=0,
xcompact=TRUE, ycompact=uniform, xcompact.ratio=.8, min.inter.height=4,
max.auto.cex=1, min.auto.cex=.15, ycompress.cex=.7, accept.cex=1.1,
shift.amounts=c(1.5, 2),
Fallen.yspace=.1, boxes.include.gap=FALSE,
legend.x=NULL, legend.y=NULL, legend.cex=1,
...)
```

#### **Arguments**

х

An rpart object. The only required argument.

type

Type of plot. Possible values:

- **0** Default. Draw a split label at each split and a node label at each leaf.
- 1 Label all nodes, not just leaves. Similar to text.rpart's all=TRUE.
- **2** Like 1 but draw the split labels below the node labels. Similar to the plots in the CART book.
- **3** Draw separate split labels for the left and right directions.
- **4** Like 3 but label all nodes, not just leaves. Similar to text.rpart's fancy=TRUE. See also clip.right.labs.

**5 New in version 2.2.0.** Show the split variable name in the interior nodes.

extra

Display extra information at the nodes. Possible values:

"auto" (case insensitive)

Automatically select a value based on the model type, as follows: extra=106 class model with a binary response

extra=104 class model with a response having more than two levels extra=100 other models

**0** Default. No extra information.

- 1 Display the number of observations that fall in the node (per class for class objects; prefixed by the number of events for poisson and exp models). Similar to text.rpart's use.n=TRUE.
- **2** Class models: display the classification rate at the node, expressed as the number of correct classifications and the number of observations in the node. Poisson and exp models: display the number of events.
- **3** Class models: misclassification rate at the node, expressed as the number of incorrect classifications and the number of observations in the node.
- **4** Class models: probability per class of observations in the node (conditioned on the node, sum across a node is 1).
- **5** Class models: like 4 but don't display the fitted class.
- **6** Class models: the probability of the second class only. Useful for binary responses.
- 7 Class models: like 6 but don't display the fitted class.
- **8** Class models: the probability of the fitted class.
- **9** Class models: The probability relative to *all* observations the sum of these probabilities across all leaves is 1. This is in contrast to the options above, which give the probability relative to observations falling *in the node* the sum of the probabilities across the node is 1.
- **10** New in version **2.2.0.** Class models: Like 9 but display the probability of the second class only. Useful for binary responses.
- 11 New in version 2.2.0. Class models: Like 10 but don't display the fitted class.
- +100 Add 100 to any of the above to also display the percentage of observations in the node. For example extra=101 displays the number and percentage of observations in the node. Actually, it's a weighted percentage using the weights passed to rpart.

Note: Unlike text.rpart, by default prp uses its own routine for generating node labels (not the function attached to the object). See the node.fun argument.

under

Applies only if extra > 0. Default FALSE, meaning put the extra text *in* the box. Use TRUE to put the text *under* the box. See also under.cex.

fallen.leaves

Default FALSE. If TRUE, position the leaf nodes at the bottom of the graph.

nn

Display the node numbers. Default FALSE. (In the current implementation some overplotting may occur with nn=TRUE.)

ni

Display the node indices, i.e. the row numbers of the nodes in the object's frame. Default FALSE.

yesno One of

branch

faclen

0 don't write yes and no on the tree

1 (default) write yes and no at the top split

2 write yes and no at all splits. Seems to work best with fallen.leaves=TRUE, split.border.col=1.

(The yesno argument is ignored if type=3 or 4. Use nn.col and the other nn parameters to change the color etc. of the yes and no text. Use yes.text and

no. text to change the actual text displayed.)

Controls the shape of the branch lines. Specify a value between 0 (V shaped

branches) and 1 (square shouldered branches). Default is if(fallen.leaves) 1 else .2.

uniform If TRUE (the default), the vertical spacing of the nodes is uniform. If FALSE,

the nodes are spaced proportionally to the fit (more precisely, to the difference between a node's deviance and the sum of its two children's deviances). Very small vertical spaces are automatically artificially expanded to make room for the labels, see minbranch. Note: uniform=FALSE with cex=NULL (the default)

can sometimes cause very small text.

Default TRUE, meaning the left side of a split is the path taken if the split con-

dition is true. With left=FALSE the split labels are changed so the right side is

true.

xflip Default FALSE. If TRUE, flip the tree horizontally.

yflip Default FALSE. If TRUE, flip the tree vertically, so the root is at the bottom.

digits The number of significant digits in displayed numbers. Default 2.

If 0, use getOption("digits").

If negative, use the standard format function (with the absolute value of digits).

When digits is positive, the following details apply:

Numbers from 0.001 to 9999 are printed without an exponent (and the number of digits is actually only a suggestion, see format for details). Numbers out that

range are printed with an "engineering" exponent (a multiple of 3).

varlen Length of variable names in text at the splits (and, for class responses, the class in the node label). Default -8, meaning truncate to eight characters. Possible

values:

0 use full names.

greater than 0 call abbreviate with the given varlen.

 $less\ than\ 0$  truncate variable names to the shortest length where they are still

unique, but never truncate to shorter than abs(varlen).

Length of factor level names in splits. Default 3, meaning abbreviate to three characters. Possible values are as varlen above, except that for back-compatibility with text.rpart the special value 1 means represent the factor

levels with alphabetic characters (a for the first level, b for the second, etc.).

roundint New in version 3.0.0. If roundint=TRUE (default) and all values of a predictor in the training data are integers, then splits for that predictor are rounded to

integer. For example, display nsiblings < 3 instead of nsiblings < 2.5. If roundint=TRUE and the data used to build the model is no longer available, a warning will be issued.

Using roundint=FALSE is advised if non-integer values are in fact possible for a predictor, even though all values in the training data for that predictor are integral.

cex Default NULL, meaning calculate the text size automatically.

Since font sizes are discrete, the cex you ask for may not be exactly the cex you

get.

Adjust the (possibly automatically calculated) cex. Using tweak is often easier

than specifying cex.

The default tweak is 1, meaning no adjustment. Use say tweak=1.2 to make the text 20% larger.

Since font sizes are discrete, a small change to tweak may not actually change

the type size, or change it more than you want.

clip. facs New in version 3.0.0. Default FALSE. If TRUE, print splits on factors as female

instead of sex = female; the variable name and equals is dropped.

Another example: print survived or died rather than survived = survived or survived = died.

clip.right.labs

tweak

Applies only if type=3 or 4.

Default is TRUE meaning "clip" the right-hand split labels, i.e., don't print variable=.

See also clip.left.labs.

compress If TRUE (the default), make more space by shifting nodes horizontally where

space is available. This often allows larger text. (This is the same as  $\verb"plot"$  .  $\verb"rpart"$ 's

argument of the same name, except that here the default is TRUE.)

ycompress If TRUE (the default unless uniform=FALSE), make more space by shifting labels

vertically where space is available. Actually, this only kicks in if the initial automatically calculated cex is less than 0.7. Use ycompress=FALSE if you feel the resulting display is too messy. In the current implementation, the shifting

algorithm works a little better (allowing larger text) with type=1, 2, or 3.

Margin Extra white space around the tree, as a fraction of the graph width. Default 0,

meaning no extra space. To add say 10% space around the tree use Margin=0.1. (This is the margin argument of plot.rpart. The name was changed to prevent

partial matching with mar, which can be passed in as a ... argument.)

space Horizontal space to the box border on each side of the node label text, in char-

acter widths. Default 1. Use this (and yspace) for bigger boxes. Since this affects the size of the (possibly invisible) boxes, it also affects the graph layout

and hence also the automatic calculation of cex.

gap Minimum horizontal gap between the (possibly invisible) boxes, in character

widths. Default NULL, meaning automatically choose a suitable value (normally 1, but if the graph is very crowded will be set to 0, permitting boxes to touch to

allow a bigger cex). See also space.

snip Default FALSE. Set TRUE to interactively trim the tree with the mouse. See the

package vignette (or just try it).

snip.fun

Function invoked after each mouse click when snip=TRUE. Default NULL, meaning no function. Otherwise set snip.fun to your own function with the prototype function(tree), where tree is the snipped tree. See the package vignette for an example.

#### The following control the node labels.

trace

Default FALSE. Use TRUE to print the automatically calculated cex, xlim, and ylim. Use integer values greater than 1 for more detailed tracing.

box.col

Color of the boxes around the text. Default 0, meaning use the background color. If this argument is used, the box.palette argument is ignored.

box.palette

Palette for coloring the node boxes based on the fitted value. This is a vector of colors, for example box.palette=c("green", "green2", "green4"). Small fitted values are displayed with colors at the start of the vector; large values with colors at the end. Quantiles are used to partition the fitted values.

The special value box.palette=0 (default for prp) uses the background color (typically white).

The special value box.palette="auto" (default for rpart.plot, case insensitive) automatically selects a predefined palette based on the type of model.

Otherwise specify a **predefined palette** e.g. box.palette="Grays" for the predefined gray palette (a range of grays). The predefined palettes are (see the show.prp.palettes function):

Grays Greys Greens Blues Browns Oranges Reds Purples

Gy Gn Bu Bn Or Rd Pu (alternative names for the above palettes)

BuGn GnRd BuOr etc. (two-color diverging palettes: any combination of two of the above palettes)

RdY1Gn GnY1Rd B1GnY1 Y1GnB1 (three color palettes)

Prefix the palette name with "-" to reverse the order of the colors e.g. box.palette="-auto" or box.palette="-Grays".

The box.palette argument is ignored if the box.col palette argument is specified

pal.thresh

Applies when box.palette is a two-color diverging palette (such as BuGn). Specifies the response threshold to split the two sub-palettes (such as Bu and Gn)

For example, to display fitted values less than 90 in shades of blue and values greater than 90 in shades of green, use pal.thresh=90 with box.palette="BuGn". By default pal.thresh is calculated automatically. (For a two-class response the default threshold is 0.5; for a continuous response the default is the median fitted value.)

Node boxes for fitted values less than the threshold are displayed using colors from the first sub-palette; boxes for fitted values greater than the threshold are displayed using colors from the second sub-palette.

This argument is ignored if box.palette isn't a two-color diverging palette, and is ignored for models with multiple-class responses (more than two classes).

pal.node.fun

Specifies how the box.palette argument is handled when the node.fun argument is specified.

Default is FALSE, meaning ignore node. fun and use the fitted value to select the node color from box.palette as usual.

If TRUE, use the label returned by the node function (instead of the fitted value) to select the color. The first number in each label returned by the node function is used, skipping over any non-numeric initial text in the label. An error message will be issued if a label doesn't include a number.

This argument is ignored if node. fun isn't specified, and is ignored for models with multiple-class responses (more than two classes).

border.col Color of the box border around the text. Default col, the color of the text in the box. Use 0 for no border. (Note: par settings like col can be passed in as

... arguments. If not passed in, par("col") is used.)

round Controls the rounding of the corners of the node boxes. Default NULL, meaning calculate automatically. Else specify 0 for sharp edges, and values greater than 0 for rounded edges. Bigger is more round. Values too big for the size of the

box get silently reduced.

leaf.round Controls the rounding of the corners of the leaf node boxes. Default NULL, mean-

ing use round. Else specify a value greater than or equal to 0.

shadow.col Color of the shadow under the boxes. Default 0, no shadow. Try "gray" or

"darkgray". (Note: overlapping shadows look better on devices that support alpha channels. If you get the message "Warning: semi-transparency is not supported" please let me know – it means that a fix is needed to the code that

determines if the device supports alpha channels.)

prefix Default "". Prepend this string to the node labels. So could be the name of the

fitted response, for instance.

Suffix Default "". Append this string to the node labels. Text after a double newline

"\n\n" (if any) will be plotted under the box. (Actually, double newlines can

be used in any of the prefix or suffix arguments for this purpose.)

xsep String which separates the individual counts and probabilities in node labels when extra>0. Default NULL meaning automatically select: usually

" (two spaces), but " / " for rates. Use xsep="/" for compatibility with text.rpart. See also facsep, which separates the factor levels in split labels.

The following control the text under the boxes (apply only if under=TRUE or there is a double newline \n\n in prefix or suffix).

under.font Font of the text under the box. Default font (which can be passed in as a

... argument).

under.col Color of the text under the box. Default 1.

under.cex Size of the text under the box relative to the text in the box. Default .8, smaller

than the text in the box.

The following control the split labels.

split.cex Size of the split text relative to cex (which by default is calculated automati-

cally). Default 1.

split.font Font for the split labels. Default 2, bold. (Note: use font to change the *node* 

label text.)

split.family Font family for the split labels. Default "", or use something like split.family="serif". (Note: use family to change the *node* label text.) split.col Color of the split label text. Default 1. (Note: use col to change the *node* label text.) split.box.col Color of the split boxes. Default 0, meaning use the background color. split.border.col Color of the split box borders. Default 0, invisible. Line type for the split box borders. The default is 1, but the border will be split.lty invisible unless you change the default split.border.col. (Note: use lty to change the *node* box borders.) split.lwd Line width of the split box border relative to cex (which by default is calculated automatically). The border is by default invisible, see codesplit.border.col. Controls the rounding of the corners of the split boxes. Default 0, meaning sharp split.round corners. Else specify a value greater than or equal to 0. The split boxes are by default invisible, see split.box.col and split.border.col). split.shadow.col Color of the shadow under the split boxes. Default 0, no shadow. Default "". Prepend this string to the split labels. split.prefix right.split.prefix Default split.prefix. Prepend this string to the right split labels. Applies only when type=3 or 4. split.suffix Default "". Append this string to the split labels. right.split.suffix Default split. suffix. Append this string to the right split labels. Applies only when type=3 or 4. facsep Default ",". String which separates the factor levels in split labels. See also xsep, which separates the individual counts when extra is used. Default " = ". String which separates the factor name from the levels in split eq labels. The idea is that you can add or remove spaces around the =, or use words if that suits you. Default " < ". String which represents "less than" in split labels. 1t Default " >= ". String which represents "greater than or equal" in split labels. ge The following control the branches. branch.col Color of the branch lines. Default 1, but set to "gray" if branch type is nonzero. branch.lty Branch line type. Default 1. branch.lwd Line width of the branch lines relative to cex (which by default is calculated automatically). (Note: branch.lwd does not control the width of the "wide branches" drawn when branch. type is nonzero.)

branch.type

Default 0. If nonzero draw "wide branches", with branch widths proportional to the parameter selected by branch. type as follows:

**0** The default. The branch lines are drawn conventionally.

1 deviance

2 sqrt(deviance)

3 deviance / nobs

**4** sqrt(deviance / nobs) (the standard deviation when method="anova")

**5** weight (frame\$wt). This is the number of observations at the node, unless rpart's weight argument was used.

6 complexity

7 abs(predicted value)

**8** predicted value - min(predicted value)

**9** constant (for checking visual perception of the relative width of branches).

Otherwise set branch.type to your own function. The function should take a single argument x (the rpart object) and return a numeric vector of non-negative widths corresponding to rows in frame. See get.branch.widths in the source code.

Note: with a nonzero branch.type, in the current implementation the branch argument will be silently changed to 1 (if branch > .5) or 0 (if branch < .5)

branch.tweak

Default 1. Applies only if branch.type is nonzero. Use this argument to scale the widths of the branches, for example, branch.tweak=.5 to halve the width of the branches. (By default, prp normalizes the widths so the widest branch is one-fifth the plot width.)

min.branch.width

Default 0.002. Applies only if branch.type is nonzero. The minimum width of a branch, as a fraction of the page width. The width of branches that would be thinner than min.branch.width is clamped. Increase min.branch.width if the thinnest branches are too skinny on your display device.

branch. fill Color used to fill the wide branch lines. Applies only if branch. type is nonzero.

Default branch. col.

#### The following control the node numbers (with nn=TRUE).

nn.cex Default NULL, meaning calculate the cex of the node numbers automatically.

This and the following arguments apply only when nn=TRUE.

nn. fontFont for the node numbers. Default 3, italic.nn. familyFont family for the node numbers. Default "".

nn.col Color of the node number text. Default 1.

nn.box.col Color of the boxes around the node numbers. Default 0, meaning use the back-

ground color.

nn.border.col Color of the box border around the node numbers. Default nn.col.

nn.lty Line type of the node number box border. Default 1.

nn.lwd Line width of the node box border relative to cex (which by default is calculated

automatically). Default NULL, meaning use 1wd (which can be passed in as a

... argument).

nn.round Controls the rounding of the corners of the node number boxes. Default .3, meaning small corners. Else specify a value greater than or equal to 0.

yes.text, no.text

Text displayed when yesno=TRUE. Default yes. text="yes" and no. text="no".

The following are user definable functions.

node.fun The function that generates the text at the node labels. The default is NULL,

which means use a default function internal to prp. (This is necessary for full

support of extra as described in the section on extra above.)
Otherwise set node. fun to your own function with the prototype

function(x, labs, digits, varlen)

See the package vignette for details. See also the pal. node. fun argument.

split.fun The function that generates the text at the splits. The default is NULL, which

means use a default function internal to prp. Otherwise set split.fun to your own function with the prototype function(x, labs, digits, varlen, faclen)

FUN The function that displays the text on the screen. Default text.

The following are esoteric parameters, mostly for the graph layout engine.

nspace Applies only when compress=TRUE. Default nspace=branch. The size of the

space between a split and a leaf, relative to the space between leaves.

minbranch Applies only when uniform=FALSE. Default .3. The minimum height between

levels is clamped at minbranch times the mean interlevel distance. Needed because sometimes a split gives little or no improvement in deviance, and an interlevel distance strictly proportional to the improvement would leave no room

for the label.

do.par Default TRUE, meaning adjust the mar parameter so the tree fills the figure region.

This also sets xpd=NA. These graphic parameters are restored to their original state before prp exits. If you explicitly set mar or xpd, prp will use your setting

regardless of the setting of do.par.

add.labs Default TRUE, meaning display the labels. If FALSE, gives a bare bones display

similar to plot.rpart.

clip.left.labs Like clip.right.labs but for the left labels. Default is FALSE. Note that

clip.left.labs and clip.right.labs can be vectors, indexed on the split

number.

fam.main Font family for the main text. Default "". The (inconsistent) name was chosen

to minimize partial matching with main and family which can be passed in as

in as ... arguments.

yshift Vertical position of the labels, in character heights relative to their default po-

sition. Default 0. Negative values move the text down; positive up (the box

around the text will follow along).

yspace Vertical space to the box border above and below the node label text, in character

heights. Default space. See the comments for space.

shadow.offset Offset of the shadow from the boxes, in character widths. Default .4 (but the

shadow will be invisible unless the default shadow.col is changed).

Horizontal position of the split text. In string width units, as is the convention for adj arguments. Default NULL, meaning use adj (which defaults to 0.5 but can be passed in as a ... argument). Use values less/more than .5 to shift the text left/right (the box around the text will follow along).

Split.yshift

Vertical position of the split labels, in character heights relative to their default

positions. Default 0. Negative values move the text down; positive up (the box around the text will follow along). This adjusts the positions of the split labels relative to the node labels. (Use yshift if you want to shift *both* the split and node labels.)

Horizontal space between the split label text and the box, in character widths. Default space. Affects the size of the box drawn around the text. The split boxes are by default invisible (see split.box.col and split.border.col), but nevertheless affect the graph layout used in the automatic calculation of cex.

split.yspace Vertical space between the split label text and the box, in character heights. Default yspace.

 ${\sf split.shadow.offset}$ 

split.space

under.ygap

xcompact

Offset of the shadow from the split boxes, in character widths. Default shadow.offset. (but the shadow will be invisible unless the default shadow.col is changed).

nn.adj Horizontal position of the node label text. Default .5.

nn.yshift Vertical position of the node numbers, in character heights relative to their default positions. Default 0.

nn.space Horizontal space to the box border on each side of the node number text, in character widths. Default .8.

nn.yspace Vertical space to the box border above and below the node number text, in character heights. Default .5.

Applies if text is plotted under the box (i.e. if under=TRUE or there is a double newline in prefix or suffix). Vertical gap (in char heights) between the lower edge of the box and the top of the text under the box.

yesno.yshift Vertical position of "yes" and "no" in character heights relative to their default position. Default 0. Applies only when yesno=TRUE.

ygap Minimum vertical gap between boxes, in character heights. Default gap/2.

If TRUE (the default) and there is too much white space, automatically change xlim to compact the entire tree horizontally. This usually only activates for small trees. (The xcompact and ycompact arguments compact the tree as a whole, whereas the compress and ycompress arguments move parts of the tree into available space.)

ycompact If TRUE (the default) and there is too much vertical space, automatically change ylim to compact the entire tree vertically.

xcompact.ratio Default .8. Applies only when xcompact=TRUE. The maximum possible without overplotting is 1, but compacting by .8 usually gives more pleasing spacing (it gives more space).

min.inter.height

Default 4. Applies only when ycompact=TRUE. Minimum height (in units of character height) between the lowest label in a layer and the highest label in the layer below it.

max.auto.cex Clamp the maximum automatically calculated cex at this value Default 1, meaning never expand cex, only contract when necessary.

Default .15. Never downscale to less than this when automatically calculating cex, even if overplotted labels result. (The graph layout algorithm is unstable with cex's below 0.15 – meaning that the automatic type size may be smaller than necessary.)

Default .7. Applies only when ycompress=TRUE. Apply the ycompress algorithm if the initial automatically calculated cex is less than this. The idea is that we don't want to shift if we get an acceptable cex without shifting. Make Inf to always attempt shifting.

Accept shifting only if it causes at least this much improvement in cex (because we don't want to shift if it gives only a small improvement in cex). Default 1.1 i.e. require at least a 10% improvement. Use 0 to always accept shifts and Inf to never accept (or use ycompress=FALSE).

shift.amounts Default c(1.5, 2, 3). For ycompress, choose the best cex yielded by shifting nodes by these amounts, in multiples of the box heights (after initial scaling).

Fallen.yspace Extra space for fallen leaves. Default .1, meaning allow 10% of the vertical space for the fallen leaves. (The name Fallen.yspace uses upper case to avoid partial matching with fallen.leaves.)

boxes.include.gap

legend.x

min.auto.cex

ycompress.cex

accept.cex

Default FALSE. Include gap and ygap when drawing the boxes, for debugging purposes. (To draw the boxes, see box.col, border.col, split.box.col, and split.border.col.) This argument only affects the way the boxes are drawn, not the graph layout algorithm in any way. With the optimum cex at least one pair of boxes displayed in this manner will just touch (but none will overlap).

Applies only to models with a multilevel class response (not binary or anova models, for which no legend is drawn).

Horizontal position of the legend. Typically a value between 0 and 1, although values beyond those limits are often useful.

Default is NULL meaning automatically position the legend (assuming there is enough space). Use NA for no legend.

Use trace=TRUE to see the automatically calculated legend position.

legend. y Like legend. x but for the vertical position of the legend.

legend.cex Like legend.x but for the relative size of the legend text. Default is 1.

Extra par arguments. Only the "important" par arguments are supported. Note that arguments like col apply only to the *node* labels. To affect the split labels or branch lines, use split.col and branch.col instead.

#### Value

A list with the following components. With the default args most of these are calculated automatically.

obj The rpart object. Identical to the x argument passed in unless snip was used. snipped.nodes The snipped nodes, NULL unless snip was used.

```
xlim, ylim
                  The graph limits.
х, у
                  The node coords.
branch.x, branch.y
                  The branch line coords.
labs
                  The node labels.
cex
                  The node label cex.
boxes
                  The coords of the boxes around the nodes.
split.labs
                  The split labels.
                  The split label cex.
split.cex
split.boxes
                  The coords of the boxes around the splits.
```

#### See Also

The package vignette Plotting rpart trees with the rpart.plot package

```
rpart.plot
```

Functions in the rpart package: plot.rpart text.rpart rpart

#### **Examples**

```
data(ptitanic)
tree <- rpart(survived ~ ., data = ptitanic, cp = .02)</pre>
                           # cp = .02 because want small tree for demo
old.par <- par(mfrow = c(2,2))
                           # put 4 figures on one page
prp(tree, main = "default prp\n(type = 0, extra = 0)")
prp(tree, main = "type = 4, extra = 6\nbox.palette = \"auto\"",
    type = 4, extra = 6, # label all nodes, show prob of second class
    box.palette = "auto", # auto color the nodes based on the model type
    faclen = 0)
                          # faclen = 0 to print full factor names
cols <- ifelse(tree$frame$yval == 1, "darkred", "green4")</pre>
                           # green if survived
prp(tree, main = "assorted arguments",
    extra = 106,
                          # display prob of survival and percent of obs
                          # display the node numbers
    nn = TRUE,
    fallen.leaves = TRUE, # put the leaves on the bottom of the page
    shadow.col = "gray", # shadows under the leaves
    branch.lty = 3,
                          # draw branches using dotted lines
    branch = .5,
                          # change angle of branch lines
    faclen = 0,
                          # faclen = 0 to print full factor names
    trace = 1,
                        # print the auto calculated cex, xlim, ylim
                       # make the split text larger than the node text
    split.cex = 1.2,
    split.prefix = "is ", # put "is " before split text
```

ptitanic 15

```
split.suffix = "?",  # put "?" after split text
col = cols, border.col = cols,  # green if survived
split.box.col = "lightgray",  # lightgray split boxes (default is white)
split.border.col = "darkgray",  # darkgray border on split boxes
split.round = .5)  # round the split box corners a tad

# compare to the plotting functions in the rpart package
plot(tree, uniform = TRUE, compress = TRUE, branch = .2)
text(tree, use.n = TRUE, cex = .8, xpd = NA) # cex is a guess, depends on your window size
title("compare to the plotting functions\nin the rpart package", cex.sub = .8)
par(old.par)
```

ptitanic

Titanic data with passenger names and other details removed.

#### Description

Titanic data with passenger names and other details removed.

#### **Format**

A data frame with 1046 observations on 6 variables.

pclass	passenger class, unordered factor: 1st 2nd 3rd
survived	factor: died or survived
sex	unordered factor: male female
age	age in years, min 0.167 max 80.0
sibsp	number of siblings or spouses aboard, integer: 08
parch	number of parents or children aboard, integer: 06

### Source

The dataset was compiled by Frank Harrell and Robert Dawson:

```
http://biostat.mc.vanderbilt.edu/wiki/pub/Main/DataSets/titanic.html.
```

See also:

```
http://biostat.mc.vanderbilt.edu/twiki/pub/Main/DataSets/titanic3info.txt.
```

For this version of the Titanic data, passenger details were deleted, survived was cast as a factor, and the name changed to ptitanic to minimize confusion with other versions.

In this data the crew are conspicuous by their absence.

Contents of ptitanic:

```
pclass survived sex age sibsp parch
1 1st survived female 29.000 0 0
2 1st survived male 0.917 1 2
3 1st died female 2.000 1 2
```

```
4 1st died male 30.000 1 2 5 1st died female 25.000 1 2 ... 1309 3rd died male 29.000 0 0
```

How ptitanic was built:

```
load("titanic3.sav") # from Dr. Harrell's web site
# discard name, ticket, fare, cabin, embarked, body, home.dest
ptitanic <- titanic3[,c(1,2,4,5,6,7)]
# change survived from integer to factor
ptitanic$survived <- factor(ptitanic$survived, labels = c("died", "survived"))
save(ptitanic, file = "ptitanic.rda")</pre>
```

This version of the data differs from etitanic in the earth package in that here survived is a factor (not an integer) and age has some NAs.

#### **Examples**

```
data(ptitanic)
summary(ptitanic)

# survival rate was greater for females
rpart.rules(rpart(survived ~ sex, data = ptitanic))

# survival rate was greater for higher classes
rpart.rules(rpart(survived ~ pclass, data = ptitanic))

# survival rate was greater for children
rpart.rules(rpart(survived ~ age, data = ptitanic))

# main indicator of missing data is 3rd class esp. with many children
obs.with.nas <- rowSums(is.na(ptitanic)) > 0
rpart.rules(rpart(obs.with.nas ~ ., data = ptitanic, method = "class"))
```

rpart.plot

Plot an rpart model. A simplified interface to the prp function.

#### **Description**

Plot an rpart model, automatically tailoring the plot for the model's response type.

For an overview, please see the package vignette Plotting rpart trees with the rpart.plot package.

This function is a simplified front-end to prp, with only the most useful arguments of that function, and with different defaults for some of the arguments.

The different defaults for the extra and col.palette arguments mean that this function automatically creates a colored plot suitable for the type of model (whereas prp by default creates a minimal plot). In detail the different defaults are:

	I	rpart.plot	I	prp	
type	I	2	ı	0	ı
extra		"auto"	-	0	-
fallen.leaves	-	TRUE	-	FALSE	-
varlen		0	-	-8	-
faclen		0	-	3	-
box.palette		"auto"	-	0	-

The function rpart.plot.version1 is compatible with old versions of this function and has the same defaults as prp.

#### Usage

```
rpart.plot(x = stop("no 'x' arg"),
   type = 2, extra = "auto",
   under = FALSE, fallen.leaves = TRUE,
   digits = 2, varlen = 0, faclen = 0, roundint = TRUE,
   cex = NULL, tweak = 1,
   clip.facs = FALSE, clip.right.labs = TRUE,
   snip = FALSE,
   box.palette = "auto", shadow.col = 0,
   ...)
```

#### **Arguments**

To start off, look at the arguments x, type and extra. Just those arguments will suffice for many users. If you don't want a colored plot, use box.palette=0.

An rpart object. The only required argument.

**x**ype

Type of plot. Possible values:

- **0** Draw a split label at each split and a node label at each leaf.
- 1 Label all nodes, not just leaves. Similar to text.rpart's all=TRUE.
- **2** Default. Like 1 but draw the split labels below the node labels. Similar to the plots in the CART book.
- **3** Draw separate split labels for the left and right directions.
- **4** Like 3 but label all nodes, not just leaves. Similar to text.rpart's fancy=TRUE. See also clip.right.labs.
- **5 New in version 2.2.0.** Show the split variable name in the interior nodes.

extra

Display extra information at the nodes. Possible values:

"auto" (case insensitive) Default.

Automatically select a value based on the model type, as follows:

extra=106 class model with a binary response

extra=104 class model with a response having more than two levels

extra=100 other models

**0** No extra information.

- 1 Display the number of observations that fall in the node (per class for class objects; prefixed by the number of events for poisson and exp models). Similar to text.rpart's use.n=TRUE.
- 2 Class models: display the classification rate at the node, expressed as the number of correct classifications and the number of observations in the node. Poisson and exp models: display the number of events.
- 3 Class models: misclassification rate at the node, expressed as the number of incorrect classifications and the number of observations in the node.
- 4 Class models: probability per class of observations in the node (conditioned on the node, sum across a node is 1).
- **5** Class models: like 4 but don't display the fitted class.
- 6 Class models: the probability of the second class only. Useful for binary responses.
- 7 Class models: like 6 but don't display the fitted class.
- **8** Class models: the probability of the fitted class.
- **9** Class models: The probability relative to *all* observations the sum of these probabilities across all leaves is 1. This is in contrast to the options above, which give the probability relative to observations falling in the node – the sum of the probabilities across the node is 1.
- 10 New in version 2.2.0. Class models: Like 9 but display the probability of the second class only. Useful for binary responses.
- 11 New in version 2.2.0. Class models: Like 10 but don't display the fitted class.
- +100 Add 100 to any of the above to also display the percentage of observations in the node. For example extra=101 displays the number and percentage of observations in the node. Actually, it's a weighted percentage using the weights passed to rpart.

Note: Unlike text.rpart, by default prp uses its own routine for generating node labels (not the function attached to the object). See the node. fun argument of prp.

under

Applies only if extra > 0. Default FALSE, meaning put the extra text in the box. Use TRUE to put the text *under* the box.

fallen.leaves

Default TRUE to position the leaf nodes at the bottom of the graph. It can be helpful to use FALSE if the graph is too crowded and the text size is too small.

digits

The number of significant digits in displayed numbers. Default 2. If 0, use getOption("digits").

If negative, use the standard format function (with the absolute value of digits).

When digits is positive, the following details apply:

Numbers from 0.001 to 9999 are printed without an exponent (and the number

of digits is actually only a suggestion, see format for details). Numbers out that range are printed with an "engineering" exponent (a multiple of 3).

varlen

Length of variable names in text at the splits (and, for class responses, the class in the node label). Default 0, meaning display the full variable names. Possible values:

0 use full names (default).

**greater than 0** call abbreviate with the given varlen.

**less than 0** truncate variable names to the shortest length where they are still unique, but never truncate to shorter than abs(varlen).

faclen

Length of factor level names in splits. Default 0, meaning display the full factor names. Possible values are as varlen above, except that for back-compatibility with text.rpart the special value 1 means represent the factor levels with alphabetic characters (a for the first level, b for the second, etc.).

roundint

**New in version 3.0.0.** If roundint=TRUE (default) and all values of a predictor in the training data are integers, then splits for that predictor are rounded to integer. For example, display nsiblings < 3 instead of nsiblings < 2.5. If roundint=TRUE and the data used to build the model is no longer available, a warning will be issued.

Using roundint=FALSE is advised if non-integer values are in fact possible for a predictor, even though all values in the training data for that predictor are integral.

cex

Default NULL, meaning calculate the text size automatically.

Since font sizes are discrete, the cex you ask for may not be exactly the cex you get.

tweak

Adjust the (possibly automatically calculated) cex. Using tweak is often easier than specifying cex.

The default tweak is 1, meaning no adjustment. Use say tweak=1.2 to make the text 20% larger.

Since font sizes are discrete, a small change to tweak may not actually change the type size, or change it more than you want.

clip.facs

**New in version 3.0.0.** Default FALSE. If TRUE, print splits on factors as female instead of sex = female; the variable name and equals is dropped.

Another example: print survived or died rather than survived = survived or survived = died.

clip.right.labs

Applies only if type=3 or 4.

Default is TRUE meaning "clip" the right-hand split labels, i.e., don't print variable=.

snip

Default FALSE. Set TRUE to interactively trim the tree with the mouse. See the package vignette (or just try it).

box.palette

Palette for coloring the node boxes based on the fitted value. This is a vector of colors, for example box.palette=c("green", "green2", "green4").

Small fitted values are displayed with colors at the start of the vector; large values with colors at the end. Quantiles are used to partition the fitted values.

The special value box.palette=0 (default for prp) uses the background color (typically white).

The special value box.palette="auto" (default for rpart.plot, case insensitive) automatically selects a predefined palette based on the type of model.

Otherwise specify a **predefined palette** e.g. box.palette="Grays" for the predefined gray palette (a range of grays). The predefined palettes are (see the show.prp.palettes function):

Grays Greys Greens Blues Browns Oranges Reds Purples

Gy Gn Bu Bn Or Rd Pu (alternative names for the above palettes)

BuGn GnRd BuOr etc. (two-color diverging palettes: any combination of two of the above palettes)

RdYlGn GnYlRd BlGnYl YlGnBl (three color palettes)

Prefix the palette name with "-" to reverse the order of the colors

e.g. box.palette="-auto" or box.palette="-Grays".

shadow.col Color of the shadow under the boxes. Default 0, no shadow. Try "gray" or "darkgray".

Extra arguments passed to prp and the plotting routines. Any of prp's arguments can be used.

#### Value

The returned value is identical to that of prp.

#### Author(s)

Stephen Milborrow, borrowing heavily from the rpart package by Terry M. Therneau and Beth Atkinson, and the R port of that package by Brian Ripley.

#### See Also

```
The package vignette Plotting rpart trees with the rpart.plot package prp rpart.plot.version1 rpart.rules
Functions in the rpart package: plot.rpart text.rpart rpart
```

# Examples

rpart.plot.version1 21

```
rpart.plot(binary.model,
         main = "titanic survived\n(binary response)")
rpart.plot(binary.model, type = 3, clip.right.labs = FALSE,
         branch = .4,
         box.palette = "Grays", # override default GnBu palette
         main = "type = 3, clip.right.labs = FALSE, ...\n")
#-----
anova.model <- rpart(Mileage ~ ., data = cu.summary)</pre>
rpart.plot(anova.model,
          shadow.col = "gray",
                              # add shadows just for kicks
         main = "miles per gallon\n(continuous response)\n")
multi.class.model <- rpart(Reliability ~ ., data = cu.summary)</pre>
rpart.plot(multi.class.model,
         main = "vehicle reliability\n(multi class response)")
par(old.par)
```

rpart.plot.version1 Plot an rpart model (old version).

#### **Description**

This function is provided for backward compatibility with old versions of rpart.plot (prior to version 2.0.0, June 2016).

By default this function creates a minimal unadorned plot, whereas rpart.plot creates a colored plot automatically tailored to the model's type.

Actually, the only difference between the two functions is that some arguments have different defaults. This function has the same defaults as prp. See the rpart.plot help page for a table showing the different defaults.

#### Usage

```
rpart.plot.version1(x = stop("no 'x' arg"),
    type = 0, extra = 0,
    under = FALSE, fallen.leaves = FALSE,
    digits = 2, varlen = -8, faclen = 3,
    cex = NULL, tweak = 1,
    snip = FALSE,
    box.palette = 0, shadow.col = 0,
    ...)
```

22 rpart.plot.version1

#### **Arguments**

x	Same as rpart.plot.		
type	Default 0. Same as rpart.plot.		
extra	Default 0, otherwise the same as rpart.plot (which has a default of "auto").		
under	Default FALSE. Same as rpart.plot.		
fallen.leaves	Default FALSE, otherwise the same as rpart.plot (which has a default of TRUE).		
digits	Default 2. Same as rpart.plot.		
varlen	Default -8, otherwise the same as rpart.plot (which has a default of 0).		
faclen	Default 3, otherwise the same as rpart.plot (which has a default of 0).		
cex	Default NULL. Same as rpart.plot.		
tweak	Default 1. Same as rpart.plot.		
snip	Default FALSE. Same as rpart.plot.		
box.palette	Default 0, otherwise the same as rpart.plot (which has a default of "auto").		
shadow.col	Default 0. Same as rpart.plot.		
	Same as rpart.plot.		

#### Value

The returned value is identical to that of prp.

# **Examples**

```
data(ptitanic)
tree <- rpart(survived ~ ., data = ptitanic, cp = .02)</pre>
                                \# cp = .02 because want small tree for demo
old.par <- par(mfrow = c(2,2))
                                # put 4 figures on one page
rpart.plot.version1(tree, main = "default rpart.plot.version1\n(type = 0, extra = 0)")
rpart.plot.version1(tree, main = "type = 4, extra = 6",
                    type = 4, extra = 6,
                    faclen = 0) # faclen = 0 to print full factor names
rpart.plot.version1(tree, main = "extra = 106, under = TRUE",
                    extra = 106, under = TRUE, faclen = 0)
# compare to the plotting functions in the rpart package
plot(tree, uniform = TRUE, compress = TRUE, branch = .2)
text(tree, use.n = TRUE, cex = .8, xpd = NA) # cex is a guess, depends on your window size
title("compare to the plotting functions\nin the rpart package", cex.sub = .8)
par(old.par)
```

rpart.predict 23

rpart.predict

Extended version of predict.rpart

# Description

Identical to predict.rpart but optionally show the node numbers and rules for the predicted values.

#### Usage

#### **Arguments**

object, newdata, type, na.action

Identical to the same arguments for predict.rpart.

If both nn and rules are FALSE, the returned value is identical to predict.rpart.

If TRUE, return a data.frame with the predictions as usual but with an extra column showing the leaf node number for each prediction.

rules

If TRUE, return a data.frame with the predictions as usual but with an extra column showing the rpart rule (as a string) for each prediction.

It may be helpful to use options (width=1000) before printing this data.frame.

Passed on to rpart.rules, for example clip.facs=TRUE.

#### Value

Same as predict.rpart, but with additional information if nn=TRUE and/or rules=TRUE.

#### See Also

```
predict.rpart
rpart.rules
```

#### **Examples**

```
data(ptitanic)
model <- rpart(survived ~ ., data = ptitanic, cp = .02)
head(rpart.predict(model, rules=TRUE))</pre>
```

24 rpart.rules

rpart.rules

Print an rpart model as a set of rules.

# Description

Print an rpart model as a set of rules.

# Usage

#### **Arguments**

X	An rpart object. The only required argument.
style	One of: "wide" (default) One rule per line. May require a lot of horizontal space. "tall" One split per line. "tallw" Like "tall" but with more horizontal white space for readability.
cover	Default FALSE. If TRUE, also print the percentage of cases covered by each rule.
nn	Default FALSE. If TRUE, also print the leaf node number for each rule.
roundint	If roundint=TRUE (default) and all values of a predictor in the training data are integers, then splits for that predictor are rounded to integer. For example, display nsiblings < 3 instead of nsiblings < 2.5.  Identical to the argument of the same name in rpart.plot, see there for details.
clip.facs	Default FALSE. If TRUE, print splits on factors as female instead of sex = female; the variable name and equals is dropped.  Identical to the argument of the same name in rpart.plot.
varorder	By default, the variables in the rules are ordered left to right on importance, where the "importance" of a variable here is the number of rules it appears in.  Use varorder to force variables to appear first in the rules. For example varorder="sex" or varorder=c("sex", "pclass") will put the specified variables first.  Partial matching of variable names is supported.
• • •	The following can be passed as dot arguments. See prp for details on these arguments.

argument	default	
extra	= "auto"	a subset of the legal values for prp are supported
digits	= 2	default is two digits of accuracy, increase if necessary

show.prp.palettes 25

```
varlen
                 = 0
                                           default displays full variable names
                 = 0
faclen
                                           default displays full factor names
trace
                 = 0
                 = " or "
facsep
                 = " is "
eq
                 = " < "
1t
ge
                 = " & "
and
                 = " when "
when
                 = " because "
because
                                           used only by rpart.predict
null.model
                = "null model"
                                           for root-only models (no splits)
response.name = NULL
                                           the response name printed before the rules (NULL means automatic)
```

#### Value

A data.frame of class c("rpart.rules", "data.frame") with some attached attributes which are passed on to print.rpart.rules. Note that print.rpart.rules temporarily increases options(width).

#### See Also

```
rpart.plot
```

#### **Examples**

```
data(ptitanic)
model <- rpart(survived ~ ., data = ptitanic, cp = .02)
rpart.plot(model)
rpart.rules(model)</pre>
```

show.prp.palettes

Show the built-in prp palettes.

#### **Description**

Display a diagram showing the built-in palettes accepted by prp's box.palette argument.

#### Usage

```
show.prp.palettes()
```

#### **Examples**

```
show.prp.palettes()
```

# **Index**

```
*Topic CART
                                                  ptitanic, 15
    prp, 2
                                                  rpart, 2, 3, 14, 16, 17, 20, 24
    rpart.plot, 16
                                                  rpart.plot, 2, 14, 16, 17, 21, 22, 24, 25
    rpart.plot.version1, 21
*Topic datasets
                                                  rpart.plot.version1, 17, 20, 21
                                                  rpart.predict, 23, 25
    ptitanic, 15
                                                  rpart.rules, 20, 23, 24
*Topic partitioning
    prp, 2
                                                  show.prp.palettes, 7, 20, 25
    rpart.plot, 16
    rpart.plot.version1, 21
                                                  text, 11
*Topic recursive
                                                  text.rpart, 2, 5, 14, 19, 20
    prp, 2
    rpart.plot, 16
    rpart.plot.version1, 21
*Topic rpart
    prp, 2
    rpart.plot, 16
    rpart.plot.version1, 21
*Topic tree
    prp, 2
    rpart.plot, 16
    rpart.plot.version1, 21
abbreviate, 5, 19
alpha, 8
colors, 7, 19
earth, 16
etitanic, 16
format, 5, 18, 19
frame, 4
getOption, 5, 18
par, 13
plot.rpart, 2, 14, 20
predict.rpart, 23
print.rpart.rules(rpart.rules), 24
prp, 2, 2, 16, 17, 20-22, 24
```