


How to delete an incident sequence rule

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Select the *Sequence rules* tab.
3. On the right-hand side of the row for the relevant rule, click  > *Delete rule*.



4. In the *Delete incident rule* dialog box, click *Delete*.

Agent offline warning

The Agent offline warning indicates when nodes are offline for longer than a configurable period of time.

With this warning, nodes that are offline for longer than the defined threshold will be reported as offline in the *Nodes* module's dashboard. For increased visibility, FortiDLP can also generate detections when nodes are offline for longer than the threshold.

The Agent offline warning is configurable within *Admin settings > Agent configuration*. There, you can:

- set the offline threshold
- specify nodes to which the Agent offline warning applies
- enable/disable offline node detections
- specify the risk score and tags to assign to offline node detections.

To learn more, see [Configuring the Agent offline warning on page 207](#).

Configuring the Agent offline warning

To configure the Agent offline warning, follow these steps.

How to configure the Agent offline warning

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Agents*, select the *Agent configuration* tab.

3. In the *Agent offline warning* section, do the following:
 - a. In the *days* field, type or select a number to define the number of days after which a node is considered offline. Only whole numbers are supported.
 - b. Do one of the following:
 - To apply the warning to all nodes, in the *Scope* menu, select *All nodes*.
 - To apply the warning to a subset of nodes that have all of the labels you will choose:
 - a. In the *Scope* menu, select *Nodes with all selected labels*.
 - b. In the label selector box, type a label name and then select it from the list that displays. Repeat as needed.
 - To apply the warning to a subset of nodes that have any of the labels you will choose:
 - a. In the *Scope* menu, select *Nodes with any selected labels*.
 - b. In the label selector box, type a label name and then select it from the list that displays. Repeat as needed.
 - c. *Optionally*, to enable offline node detections:
 - i. Turn the *Raise a detection when Agents go offline* toggle on.
 - ii. In the *Risk score* field, type a number between 0–100 to define the risk score to assign to detections.



The risk score determines the detection's severity level, helping security analysts best allocate their time to threat response:

- A risk score of 0 is classified as no severity.
 - A risk score between 1–39 is classified as low severity.
 - A risk score between 40–69 is classified as medium severity.
 - A risk score between 70–89 is classified as high severity.
 - A risk score between 90–100 is classified as critical severity.
-

- iii. In the *Tags* field, type one or more keywords or terms to describe the detection, separated by a space. A default value of `systemsecurity` is provided.

Agents are considered offline after

14

days

Scope

Nodes with any selected labels ▼

Country | UK x

Country | USA x

Country | France x

Raise a detection when Agents go offline



Risk score

25

Tags

systemsecurity

- d. Click Save.



If you decide to later disable Agent offline warning detections, just turn the *Raise a detection when Agents go offline* toggle off and resave the configuration.

Agent configuration groups

You can streamline configuration by defining groups of Agents that share settings, such as the activities monitored, the target version, and more.

Simply create a group, assign it labels for the nodes you want to include, and set your configuration options as needed. You can then easily switch settings on and off and upgrade to new Agent software without affecting nodes outside of the group.



For example, you could create a group for on-notice employees with email, clipboard, and keystroke monitoring enabled to protect against data loss, but have this functionality disabled for other employees.

You could also create a General Data Protection Regulation (GDPR) compliance group, where web monitoring is disabled for employees in European countries.

Each configuration group you create requires a priority. This determines the configuration that takes precedence if a node belongs to multiple groups. The larger the number, the higher the precedence—so a group with a priority of 4 would prevail over groups 0–3.

A base configuration group is provided, which is assigned a priority of 0. You can use this group to apply general settings to all Agents in your deployment. Any additional configuration groups you create will automatically be assigned a higher priority which you can modify as needed. Unlike other configuration groups, the base configuration group specifies the values applied to all possible options to increase visibility of the applied configuration. For details on viewing your nodes applied settings, see [Testing Agent configurations on page 233](#).



The base configuration group for FortiDLP Cloud tenants contains settings to install the FortiDLP Browser Extension and FortiDLP Email Plugin (Legacy) on supported OS versions out of the box—unless the tenant has been set to explicitly NOT install them.

If you use a fleet management tool for your Agent deployment and you do not want to install the extension and/or plugin, prior to Agent enrollment, in your base configuration group:

- set the *Browser extension installation* option to *Managed with external tool* and/or
- set the *Agent-initiated email plugin installation* option to *Off*.

You should then only apply settings using your fleet management tool.

Creating Agent configuration groups

To create an Agent configuration group, follow the steps below.

When you create an Agent configuration group, bear in mind that the default value applies if an option is set to *Not configured* and is also not configured locally in the Agent's configuration file. Default values are detailed in [Agent configuration default settings on page 219](#).



Let's consider the *GUI Agent uninstallation* configuration option as an example, which controls Windows users' ability to uninstall the Agent via Apps & Features and the Control Panel:

- A value of *Allow* would allow users to uninstall the Agent.
- A value of *Not configured* would make the default value (*Allow*) apply, allowing users to uninstall the Agent.
- A value of *Deny* would deny users from uninstalling the Agent.

It is important to note that if a node belongs to multiple groups, whole configuration groups do not override each other; overrides happen at the individual configuration option level (for example, *Private browsing*). That is, a configuration option in a higher priority group overrides the same configuration option within a lower priority group. Where a node belongs to multiple groups and a configuration option is excluded from some groups but included in others, the highest priority group containing the configuration option applies.



Let's say your base configuration group, which applies to all nodes and has a priority of 0, has the *Private browsing* configuration option set to *Allow*. You then create a configuration group that only applies to on-notice employees and has a priority of 1. If this group has the *Private browsing* configuration option set to *Deny*, nodes within the on-notice group would be prohibited from private browsing. If this group has the *Private browsing* configuration option set to *Not configured*, nodes within the on-notice group would be permitted to privately browse the web, as the base configuration group option applies.

The following instructions provide an overview of the configuration options you can set using Agent configuration groups. For detailed information about this functionality, see the [FortiDLP Agent Deployment Guide](#).



You can speed up this task by duplicating an existing configuration group and modifying it as needed. For details, see [Duplicating Agent configuration groups on page 232](#).

How to create a configuration group



Your configuration will be propagated to each Agent in the group within five minutes of being saved.

Upgrades will occur when nodes are online, either within an upgrade window or immediately if no windows are set. Nodes must be restarted to complete the upgrade.



The following settings may conflict with bulk provisioning tools:

- *Agent-initiated legacy email plugin installation*
- *Automatic upgrades*
- *Browser DNS over HTTPS (DoH)*
- *Private browsing*
- *Browser extension installation*

To manually configure registry keys for the *Browser DNS over HTTPS (DoH)* and *Private browsing* options, see [Bulk deploying the FortiDLP Browser Extension to Windows](#) in the *FortiDLP Agent Deployment Guide*.

If you use such tools for your Agent deployment, consult Fortinet Support.

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Agents*, select the *Agent configuration* tab.
3. In the *Agent configuration* section, click *Create new*.
4. In the *Name* field, type the group name.
5. *Optionally*, in the *Priority* field, type or select a number to determine the group's priority in respect to other groups. The larger the number, the higher the precedence.



The number set by default makes the group the highest priority.

6. *Optionally*, in the *Description* field, type a group description.
7. Do one of the following:
 - To apply the configuration group all entities, in the *Scope* menu, select *All entities*.
 - To apply the configuration group to a subset of entities that have all of the labels you will choose:
 - i. In the *Scope* menu, select *Entities with all selected labels*.
 - ii. In the label selector box, type a label name and then select it from the list that displays. Repeat as needed.
 - To apply the configuration group to a subset of entities that have any of the labels you will choose:
 - i. In the *Scope* menu, select *Entities with any selected labels*.
 - ii. In the label selector box, type a label name and then select it from the list that displays. Repeat as needed.
8. Configure the following options as needed, referring to [Agent configuration default settings on page 219](#) for Agent/OS compatibilities:
 - *Actions >>*
 - *USB file transfer blocking action:*
 - To enable blocking of unauthorized file transfers to USB storage devices, select *On*.



When this setting is applied to Windows devices:

- users will receive a pop-up message upon inserting their first USB storage device that states these devices are monitored
- only predefined applications will be allowed to write to USB storage devices
- files on USB storage devices will only be accessible in read-only mode.

For these reasons, we advise enabling USB policies prior to turning this *On*.

- To disable blocking of unauthorized file transfers to USB storage devices, select *Off*.



Windows devices require a restart for a configuration change to take effect. macOS devices require a restart after this setting is turned *Off* for the change to take effect.

- *Screenshot evidence action:*
 - To enable capturing of screenshot evidence for nodes, select *On*.



On macOS, this action also requires user approval. Selecting *On* will prompt users to grant access the first time this action is executed, if access has not already been permitted. On macOS 15+, users will also be prompted to reapprove access monthly. For details, see [Permitting user-controlled Agent functionality on macOS](#) in the *FortiDLP Agent Deployment Guide*.

- To disable capturing of screenshot evidence for nodes, select *Off*.
- *Screenshot evidence action mode:*
 - To capture a single screenshot when the *Capture screenshot evidence* action is executed, select *Static*.

- To capture an animated GIF when the *Capture screenshot evidence* action is executed, select *Motion*.



On macOS 15+, if users have granted approval to capture screenshot evidence, selecting *Static* will display a momentary notification when a screenshot is captured, and selecting *Motion* will display a persistent notification, even when the screen is not being recorded. A recording is only saved when a policy is violated.

- *Archiving >>*

- *Auto-archive duplicate Agents:*

- To enable auto-archiving for duplicate nodes, select *On*.



A duplicate node is detected using the *Hardware ID* property, which is a unique identifier the Agent generates from the device's SMBIOS ID and boot disk serial number. It can take up to 12 hours for a duplicate node to be auto-archived.

- To disable auto-archiving for duplicate nodes, select *Off*.
 - *Auto-archive inactive Agents:*
 - To enable auto-archiving for inactive nodes after a specified time period:
 - Select *On*.
 - In the *Auto-archive inactive Agents after* field, type the number of days after which an inactive (offline) node is auto-archived.
 - To disable auto-archiving for inactive nodes after a specified time period, select *Off*.
 - *Revoke archived Agents' licenses:*
 - To enable the automatic revocation of archived nodes' licenses after a specified time period:
 - Select *On*.
 - In the *Revoke archived Agents' licenses after* field, type the number of days after which an archived node is unlicensed.



Unlicensed nodes cannot be unarchived.

- To disable the automatic revocation of archived nodes' licenses after a specified time period, select *Off*.
 - *Email >>*
 - *Agent-initiated legacy email plugin installation* (Classic Outlook for Windows):
 - To have the Agent install the FortiDLP Email Plugin (Legacy) on nodes, select *On*.
 - To use an external tool to manage the FortiDLP Email Plugin (Legacy)'s installation on nodes, select *Off*.



The base configuration group for FortiDLP Cloud tenants contains settings to install the FortiDLP Email Plugin (Legacy) on supported OS versions out of the box—unless the tenant has been set to explicitly NOT install it.

Users may be prompted to manually install the plugin upon opening Microsoft Outlook for the first time after installing or upgrading the Agent. To avoid this prompt, read our FAQ [here](#).

- *Email monitoring:*
 - To enable email monitoring on nodes, select *On*.



Installation of the FortiDLP Email Add-in is required before email monitoring can be enabled. For instructions, see [Email monitoring](#) in the *FortiDLP Agent Deployment Guide*.

- To disable email monitoring on nodes, select *Off*.
- *Input >>*
 - *Keystroke monitoring:*
 - To enable keystroke monitoring on nodes, select *On*.



Keystroke monitoring also requires enabling of activity monitoring and keystroke analytics policy templates to detect certain threats. For details, see the [FortiDLP Policies Reference Guide](#). Credential sharing can be detected without policies.

On macOS, approval is also needed for Agents to capture users' keyboard input. For instructions on granting the access required, see [Permitting user-controlled Agent functionality on macOS](#) in the *FortiDLP Agent Deployment Guide*.

- To disable keystroke monitoring on nodes, select *Off*.
- *Clipboard monitoring:*
 - To enable clipboard monitoring on nodes, select *On*.



Clipboard monitoring also requires enabling of clipboard policy templates. For details, see the [FortiDLP Policies Reference Guide](#).

- To disable clipboard monitoring on nodes, select *Off*.
- *Performance >>*
 - *Agent performance monitoring:*
 - To enable the automatic generation of performance reports if CPU or memory usage exceeds a threshold on nodes, select *On*.
 - To disable the automatic generation of performance reports if CPU or memory usage exceeds a threshold on nodes, select *Off*.

- *Printing >>*
 - *Print monitoring:*
 - To enable print monitoring, select *On*.
 - To disable print monitoring, select *Off*.
 - To enable a legacy implementation for Windows only, select *Legacy*.
- *Process exclusion >>*



File and connection events for excluded processes are NOT reported by the Agent and will NOT generate detections or incidents.

[Out-of-box \(OOB\) process exclusion on page 230](#) is provided for trusted endpoint tools for Agent 12.3.2+. For these Agents, process exclusion lists defined via Agent configuration groups are additive to OOB process exclusion.

- *Anti-malware process exclusion:*
 - To exclude [Windows anti-malware processes](#) from monitoring, select *On*. This excludes Windows "protected processes", which you can identify in the [Process Explorer's Protection](#) column.
 - To monitor all Windows anti-malware processes, select *Off (monitor all)*.
- *Process name exclusion:*
 - To list process binary names to exclude from monitoring, select *On*. Then type the process binary names you want to exclude in the entry box. Enter one binary name per line, and do not use commas.



You can use the * wildcard character to match any number of characters.



Entering `google*` would match the processes `googleupdate.exe`, `googlecrashhandler.exe`, and `googledrivesync.exe`—preventing events from being generated when Chrome is updated, when Chrome crashes, and when G Drive is synced.

- To monitor all process names, select *Off (monitor all)*.
- *Process path exclusion:*
 - To list process binary paths to exclude from monitoring, select *On*. Then type the process binary paths you want to exclude in the entry box. Enter one binary path per line, and do not use commas. Paths containing spaces should not be escaped or quoted.



You can use the * wildcard character to match files and directories within a directory or ** to match directories and subdirectories.

You can also type one argument after the path for fine-grained matching of programs in interpreted languages, like Python.



For example, entering `C:\Windows\*` would match the path `C:\Windows\notepad.exe`, but not `C:\Windows\System32\Write.exe`. Further, entering `C:\Windows\**\*.exe` would match the path `C:\Windows\System32\Write.exe`.

Also, entering `C:\Program Files\Python311\python.exe` `C:\Program Files\MyPythonApp\mypythonscript.py` would match the script `C:\Program Files\MyPythonApp\mypythonscript.py` running on the interpreter `C:\Program Files\Python311\python.exe` for Windows. Further, entering `/bin/python` `/bin/mypythonscript` would match the script `/bin/mypythonscript` running on the interpreter `/bin/python` for Linux.

- To monitor all process paths, select *Off (monitor all)*.
- *Process hash (SHA-256) exclusion:*
 - To list process binary hashes to exclude from monitoring, select *On*. Then type the process binary hashes you want to exclude in the entry box. Enter one binary hash per line, and do not use commas.
 - To monitor all process hashes, select *Off (monitor all)*.
- *Security >>*
 - *GUI Agent uninstallation:*
 - To allow users to uninstall the Agent via Windows Apps & Features and the Control Panel, select *Allow*.
 - To deny users from uninstalling the Agent via Windows Apps & Features and the Control Panel, select *Deny*.
 - *Password-protected Agent uninstallation:*
 - To require users to enter a password to uninstall the Agent via Windows Apps & Features, the Control Panel, and the command line, select *On*, then type the password into the entry field.
 - To allow users to uninstall the Agent via Windows Apps & Features, the Control Panel, and the command line without entering a password, select *Off*.



Password protection is enforced by default via the "base configuration" group for tenants created after November 4, 2025. To view a tenant's predefined password, edit its base configuration group and then click the  icon corresponding to this option.

- *Agent anti-tampering:*
 - To prevent local and domain administrators and users from stopping the Windows Agent's service and altering or removing its files and registry keys, select *On*.



To be alerted on tampering attempts—for example, when an administrator tries to stop the FortiDLP Agent service—you must enable this setting and configure policies. For details, see the *FortiDLP Policies Reference Guide (Windows FortiDLP Agent tampered with template)* and out-of-box policies in the FortiDLP Console (*Windows FortiDLP Agent or FortiDLP Browser Extension files tampered with* and *Windows FortiDLP Agent registry data tampered with templates*).

- To allow local and domain administrators to stop the Windows Agent's service and alter or remove its files and registry keys, select *Off*.
- *Upgrades >>*
 - *Automatic upgrades:*
 - To enable automatic upgrades whenever Fortinet releases a new Agent version, select *Latest*.
 - To enable automatic upgrades for a specific Agent version, select the version to upgrade to. (You will need to do this for each future upgrade.)
 - To disable automatic upgrades, select *Off*.
 - *Add time window:*
 - To create an upgrade window during which automatic Agent upgrades can occur:
 - a. Click *Add time window*.
 - b. In the *Select one or more days* list, select the day(s) of the upgrade window.
 - c. In the *Start time* menu, select the start time of the upgrade window. Nodes will be upgraded in local time.
 - d. In the *Duration* menu, select the duration of the upgrade window in hours.
You can create multiple upgrade windows by repeating these steps.
 - To enable automatic upgrades without an upgrade window, skip this step.
 - *Force upgrade after 2 weeks:*
 - To force an upgrade after two weeks if nodes miss upgrade windows, turn the toggle on.



If this is on, and a node misses an upgrade due to being offline, the node will be upgraded two weeks from when it is made aware of the new Agent version, irrespective of upgrade windows.

- To only allow nodes to be upgraded during configured upgrade windows, turn the toggle off.
- *Web >>*
 - *Web monitoring:*
 - To enable web monitoring on nodes, select *On*.
 - To disable web monitoring on nodes, select *Off*.
 - *Browser DNS over HTTPS (DoH):*
 - To use browsers' default DoH settings (either enabling or disabling DoH), select *Browser default*. DNS lookups in a browser that supports DoH are encrypted and may not be monitored by the Agent.
 - To disable browsers' DoH functionality and always allow monitoring by the Agent, select *Off*.
 - *Browser upload notification:*
 - To display a pop-up message to users when uploaded files are verified against policies, select *On*.
 - To disable the display of a pop-up message to users when uploaded files are verified against policies, select *Off*.
 - *Private browsing:*
 - To allow users to privately browse the web and use Chrome Guest mode, which cannot be monitored by the Agent, select *Allow*.
 - To deny users from privately browsing the web and using Chrome Guest mode, select *Deny*.
 - *Safari browser extension monitoring (Agent v12.1.0 or later)*

- To monitor the FortiDLP Browser Extension for Safari, including the events it generates and its Agent health state, select *On*.
- To not monitor the FortiDLP Browser Extension for Safari, including the events it generates and its Agent health state, select *Off*.
- *Browser extension installation:*
 - To use the same configuration for all named browsers:
 - i. Select the *Configure same setting for all browsers* radio button.
 - ii. In the menu, do one of the following:
 - To have the Agent install the FortiDLP Browser Extension in these browsers, select *Agent-managed installation*.
 - To have the Agent uninstall the FortiDLP Browser Extension from these browsers, select *Agent-managed uninstallation*.
 - To use an external tool to install/uninstall the FortiDLP Browser Extension in/from these browsers, select *Managed with external tool*.



For FortiDLP Agent 12.1.3+, setting this option to *Managed with external tool* prevents the Agent from applying Windows Registry changes for the *Browser DNS over HTTPS (DoH)* and *Private browsing* options. To manually configure registry keys for the *Browser DNS over HTTPS (DoH)* and *Private browsing* options, see [Bulk deploying the FortiDLP Browser Extension to Windows](#) in the *FortiDLP Agent Deployment Guide*.

- To use different configurations for named browsers:
 - i. Select the *Configure varied settings for browsers* radio button.
 - ii. In each of the menus, do one of the following:
 - To have the Agent install the FortiDLP Browser Extension in the browser(s), select *Agent-managed installation*.
 - To have the Agent uninstall the FortiDLP Browser Extension from the browser(s), select *Agent-managed uninstallation*.
 - To use an external tool to install/uninstall the FortiDLP Browser Extension in/from the browser(s), select *Managed with external tool*.



For FortiDLP Agent 12.1.3+, setting this option to *Managed with external tool* prevents the Agent from applying Windows Registry changes for the *Private browsing* and *Browser DNS over HTTPS (DoH)* options. To manually configure registry keys for the *Private browsing* and *Browser DNS over HTTPS (DoH)* options, see [Bulk deploying the FortiDLP Browser Extension to Windows](#) in the *FortiDLP Agent Deployment Guide*.



The base configuration group for FortiDLP Cloud tenants contains settings to install the FortiDLP Browser Extension on supported OS versions out of the box—unless the tenant has been set to explicitly NOT install it.

- *WPD device access >>*
 - *Read access for WPD devices:*
 - To block Windows computers from reading WPD devices, select *Deny*.
 - To allow Windows computers to read WPD devices, select *Allow*.

- Write access for WPD devices:
 - To block Windows computers from writing to WPD devices, select *Deny*.
 - To allow Windows computers to write to WPD devices, select *Allow*.
- Custom configuration >>



Custom configuration options are typically used for supportability and debugging purposes. You should only create one under the guidance of Fortinet Support. For more information, see [Advanced Agent configuration settings on page 222](#).

- To create a custom configuration option, do the following:
 - Click *Add custom configuration*.
 - In the *Enter a custom key* field, type the custom key name.
 - In the *Enter a custom value* field, type the custom key value.

9. Click *Save*.

Agent configuration default settings

When considering an Agent's configuration, the order of priority is as follows:

1. Infrastructure configuration (Agent configuration groups)
2. Local configuration (the Agent's configuration file)
3. Agent default.

The following table outlines Agent default settings by Agent version and OS. These default settings will apply if the relevant key is not configured remotely or locally, as stated above.

Agent configuration default settings

Section	Option	Windows	macOS	Linux
Actions	USB file transfer blocking action	Agent 10.0.1+: Off	Agent 10.2.0+: Off	Not supported
	Screenshot evidence action	Agent 12.0.2: On	Agent 12.0.2: On	Not supported
	Screenshot evidence action mode	Agent 3.0.0+: Static	Agent 3.0.0+: Static	Not supported
Archiving	Auto-archive duplicate Agents	All Agents: Off	All Agents: Off	All Agents: Off
	Auto-archive inactive Agents	All Agents: Off	All Agents: Off	All Agents: Off
	Revoke archived Agents' licenses	All Agents: Off	All Agents: Off	All Agents: Off
Email	Agent-initiated legacy email plugin installation	Agent 7.7.0–7.8.1: On Agent 7.9.1+: Off	Not supported	Not supported

Section	Option	Windows	macOS	Linux
	Email monitoring	Agent 7.0.3 & 7.0.4: Off Agent 7.0.0, 7.0.1, & 7.1.2+: On	Agent 7.3.1+: On	Not supported
Input	Keystroke monitoring	Agent 5.1.0+: Off	Agent 5.1.0+: Off	Not supported
	Clipboard monitoring	Agent 6.0.3+: Off	Agent 6.0.3+: Off	Not supported
Performance	Agent performance monitoring	Agent 8.6.0+: Off	Agent 8.6.0+: Off	Agent 8.6.0+: Off
Printing	Print monitoring	Agent 10.4.0+: Legacy	Agent 10.2.0+: On	Agent 10.2.0+: On
Process exclusion	Anti-malware process name exclusion	Agent 7.11.2–12.2.1: Off (monitor all) Agent 12.2.2+: On	Not supported	Not supported
	Process name exclusion	Agent 7.11.2+: Off (monitor all)	Agent 8.0.1+: Off (monitor all)	Agent 7.11.2+: Off (monitor all)
	Process path exclusion	Agent 7.11.2+: Off (monitor all)	Agent 8.0.1+: Off (monitor all)	Agent 7.11.2+: Off (monitor all)
	Process hash (SHA-256) exclusion	Agent 7.11.2+: Off (monitor all)	Agent 8.0.1+: Off (monitor all)	Agent 7.11.2+: Off (monitor all)
Security	GUI Agent uninstallation	Agent 5.1.0+: Allow	Not supported	Not supported
	Password-protected Agent uninstallation	Agent 7.1.2+: Off	Not supported	Not supported
	Agent anti-tampering	Agent 10.2.0–12.2.1: Off Agent 12.2.2+: On	Not supported	Not supported
Upgrades	Automatic upgrades	All Agents: Off	All Agents: Off	All Agents: Off
	Add time window	Agent 8.1.0+: Off	Agent 8.1.0+: Off	Agent 8.1.0+: Off
	Force upgrade after 2 weeks	Agent 8.7.1+: Off	Agent 8.7.1+: Off	Agent 8.7.1+: Off
Web	Web monitoring	Agent 6.0.2+: On	Agent 6.0.2+: On	Agent 7.5.1+: On
	Browser DNS over HTTPS (DoH)	Agent 7.2.3: Off Agent 7.3.1+: Browser default	Not supported (MDM only)*	Agent 7.5.1+: Browser default
	Browser upload notification	Agent 7.7.4+: On	Agent 7.7.4+: On	Agent 7.7.4+: On

Section	Option	Windows	macOS	Linux
	<i>Private browsing</i>	Agent 6.0.2+: <i>Deny</i>	<i>Not supported (MDM only)*</i>	Agent 7.5.1+: <i>Deny</i>
	<i>Browser extension installation</i>	Agent 11.1.1+: <i>Managed with external tool (for all browsers)</i>	<i>Not supported (MDM only)*</i>	Agent 11.1.1+: <i>Managed with external tool (for all browsers)</i>
<i>WPD device access</i>	<i>Read access for WPD devices</i>	Agent 11.1.1+: <i>Off</i>	<i>Not supported</i>	<i>Not supported</i>
	<i>Write access for WPD devices</i>	Agent 11.1.1+: <i>Off</i>	<i>Not supported</i>	<i>Not supported</i>

*For guidance on using MDM profiles to control web functionality for macOS, refer to [Installing the FortiDLP Browser Extension on macOS](#) and [Bulk deploying the FortiDLP Browser Extension to macOS](#).

Advanced Agent configuration settings

FortiDLP supports the following optional advanced Agent configuration settings. These settings must be enabled through *custom configurations*, as described in [Creating Agent configuration groups on page 210](#). Contact Fortinet Support for guidance.



Configuration key names are case-sensitive and must match the exact casing specified below.

Where an advanced Agent configuration setting is not configured in the FortiDLP Console, the Agent default value applies.

Anti-tampering settings

Key	Description	Example value	Agent default value
tamper_process_protection_enable	For use only under the direction of Fortinet Support: Prevents tampering of Agent processes.	true	- Windows: true - macOS: <i>Not supported</i> - Linux: <i>Not supported</i>
tamper_verbose_logging_enable	For use only under the direction of Fortinet Support: Enables verbose debug logging when tamper protection is turned on.	false	- Windows: false - macOS: <i>Not supported</i> - Linux: <i>Not supported</i>
tamper_verbose_logging_all_enable	For use only under the direction of Fortinet Support: Enables an extended version of verbose debug logging when tamper protection is turned on.	false	- Windows: false - macOS: <i>Not supported</i> - Linux: <i>Not supported</i>
tamper_verbose_logging_specific_executables	For use only under the direction of Fortinet Support: Specifies a comma-separated list of canonical file paths for executables verbose debug logging should be enabled for.	c:\dev\my_app.exe, c:\dev\test.exe	- Windows: No default - macOS: <i>Not supported</i> - Linux: <i>Not supported</i>

Browser monitoring exclusion and repair settings

Key	Description	Example value	Agent default value
browser_urls_skip_js_injection_upload	For use only under the direction of Fortinet Support: For specified websites, disables monitoring and blocking of uploads.	*://example1.com/*,*://example2.com/*,*://example3.com/*	All OSes: No default
browser_urls_skip_js_injection	For use only under the direction of Fortinet Support: For specified websites, disables the majority of FortiDLP Browser Extension functionality.	*://example1.com/*,*://example2.com/*,*://example3.com/*	All OSes: No default
browser_urls_skip_js_injection_upload_get_file	For use only under the direction of Fortinet Support: For specified websites, disables monitoring and blocking of uploads that are run using the getFile Web API.	*://example1.com/*,*://example2.com/*,*://example3.com/*	All OSes: No default
browser_urls_skip_js_injection_upload_create_element	For use only under the direction of Fortinet Support: For specified websites, disables monitoring and blocking of uploads that are run using the createElement Web API.	*://example1.com/*,*://example2.com/*,*://example3.com/*	All OSes: No default

Key	Description	Example value	Agent default value
repair_broken_content_script_comms	For use only under the direction of Fortinet Support: Repairs FortiDLP Browser Extension communications for Google Chrome following an extension update that will otherwise halt until a page refresh.	false	All OSes: false



The above settings should only be used until browser monitoring issues are resolved.

Content inspection settings

Key	Description	Example value	Agent default value
content_inspection_next_generation	Enables next-generation content inspection.	true	- Windows: true - macOS: true - Linux: false
content_inspection_next_generation_legacy	Specifies a comma-separated list of file MIME types to enable legacy content inspection for.	application/vnd.openxmlformats-officedocument.wordprocessingml.document	All OSes: No default
enable_content_inspection_metadata_search	Enables legacy or next-generation content inspection of file metadata for Windows.	false	- Windows: false - macOS: <i>Not supported</i> - Linux: <i>Not supported</i>

Key	Description	Example value	Agent default value
content_inspection_next_generation_metadata	Enables next-generation content inspection of file metadata for all OSes.	true	All OSes: true
content_inspection_next_generation_keyword	Enables next-generation content inspection of keywords.	true	All OSes: true
content_inspection_next_generation_exclude	Specifies a comma-separated list of file MIME types to exclude from next-generation content inspection.  This will prevent file content and metadata from being inspected but will not prevent the inspection of Microsoft sensitivity labels. If set, this configuration will take precedence over policy configurations.	application/x-ole-storage, application/x-msi	All OSes: No default
content_inspection_next_generation_search_limit	Defines the maximum size of a file in bytes to perform next-generation content inspection on. If a file is larger than this, content inspection will stop when the limit is reached and any matches made before this will be reported. A value of 0 can be used to place no limit on the number of bytes that can be inspected.	10000	All OSes: 0 (no limit)
content_inspection_next_generation_timeout	Defines the maximum amount of time for next-generation content inspection to run. A time value is a number followed by a unit suffix. Valid units are "s" (seconds), "m" (minutes), and "h" (hours).	30s or 1m10s	All OSes: 60s

Diagnostic settings

Key	Description	Example value	Agent default value
macos_sysex_endpoint_security_notify_events	For use only under the direction of Fortinet Support: Disables the Endpoint Security System Extension's notification events. Certain functionality will be degraded while this key is set to <code>false</code> , such as file access event monitoring, process start event monitoring, and content inspection.	false	- Windows: <i>Not supported</i> - macOS: <code>true</code> - Linux: <i>Not supported</i>
macos_sysex_endpoint_security_auth_events	For use only under the direction of Fortinet Support: Disables the Endpoint Security System Extension's authorization events. Certain functionality will be degraded while this key is set to <code>false</code> , such as copy detection and USB file transfer blocking.	false	- Windows: <i>Not supported</i> - macOS: <code>true</code> - Linux: <i>Not supported</i>



The above settings should only be used until performance issues are resolved.

File evidence capturing settings

Key	Description	Example value	Agent default value
file_shadow_file_size_max	Defines the maximum size of a file for which a file evidence file can be created.	1024GB	All OSes: 100MB

Key	Description	Example value	Agent default value
	A size value is a number followed by a unit suffix, with or without a space between them. Valid units are "B", "KB", "MB", "GB", "TB", "PB", and "EB". You can also use the long format of units, such as "kilobyte" or "kilobytes".  To avoid file evidence capturing failures, ensure the maximum file size here does not exceed the maximum file size configured for your storage bucket.		
file_shadow_storage_size_max	Defines the maximum size of local storage that can be used to store file evidence files if there is an issue connecting to the storage bucket. A size value is a number followed by a unit suffix, with or without a space between them. Valid units are "B", "KB", "MB", "GB", "TB", "PB", and "EB". You can also use the long format of units, such as "kilobyte" or "kilobytes".  File evidence files are removed from local storage when the connection is restored.	2GB	All OSes: 1GB



These settings are typically configured at the tenant level in *Admin settings > Evidence capturing*.

File MIME type identification settings

Key	Description	Example value	Agent default value
mime_enable	Enables file MIME type identification.	true	All OSes: true
mime_cache_size	Defines the maximum number of files that can be stored in the in-memory cache to improve MIME type identification performance.	10000	All OSes: 10240



After configuring file MIME type identification settings, the Agent must be restarted for the change to take effect.

Performance report settings

Key	Description	Example value	Agent default value
cpu_lite_performance_diagnostic_bundle_limit	Defines the CPU percentage that, when exceeded by the Agent, automatically generates a standard performance report.	10	All OSes: 20
cpu_performance_diagnostic_bundle_limit	Defines the CPU percentage that, when exceeded by the Agent, automatically generates an advanced performance report.	30	All OSes: 50
memory_lite_performance_diagnostic_bundle_limit	Defines the memory usage percentage that, when exceeded by the Agent, automatically generates a standard performance report.	10	All OSes: 20
memory_performance_diagnostic_bundle_limit	Defines the memory usage percentage that, when exceeded by the Agent, automatically generates an advanced performance report.	20	All OSes: 40

USB file transfer blocking settings

Key	Description	Example value	Agent default value
usb_blocking_file_size_max	Defines the maximum size of a file that can be blocked from being transferred to a USB storage device when a policy is violated. Files larger than the specified size will not be blocked even if the transfer is deemed unauthorized. A size value is a number followed by a unit suffix, with or without a space between them. Valid units are "B", "KB", "MB", "GB", "TB", "PB", and "EB". You can also use the long format of units, such as "kilobyte" or "kilobytes". A value of 0 can be used to place no size limit on files that can be blocked.	1024GB	• Windows: 0 (no limit) • macOS: <i>Not supported</i> • Linux: <i>Not supported</i>

Out-of-box (OOB) process exclusion

Requirements: FortiDLP Agent 12.3.2+.

To avoid interference with trusted endpoint tools and optimize performance, the FortiDLP Agent provides binary process exclusion by default for all OSes.

The OOB process exclusion list detailed below is combined with custom (operator-configured) process exclusion lists via [Agent configuration groups on page 209](#) to disable monitoring of legitimate software.



For each of the following tools, there is a hard-coded list of binary process names and/or paths for each applicable OS based on software vendor documentation and/or customer feedback/testing. Although we strive to stay current with vendor changes and test this functionality frequently, we cannot guarantee that all excludable processes have been identified.

To ensure interoperability, we also recommend configuring third-party allowlists to include the FortiDLP Agent. You should also follow the guidance in [Excluding FortiDLP Agent processes, directories, and files from antivirus scanning](#) in the *FortiDLP Agent Deployment Guide*.

- Actifile Agent
- Arctic Wolf
- Avast Antivirus
- AWS Patch Manager
- BeyondTrust
- Bitdefender
- Check Point Harmony EDR
- Cisco:
 - Secure Endpoint
 - Umbrella
- Citrix:
 - Telemetry Service
 - Virtual Delivery Agent (VDA)
- ClearSkies
- Code42
- COMODO Endpoint Manager
- CoSoSys Endpoint Protector
- CrowdStrike Falcon
- CyberArk Endpoint Privilege Manager
- CyberReason
- Cynet
- Dell SupportAssist
- ESET Cloud Complete
- ExpressConnect

- Forcepoint:
 - CASB
 - DLP
 - F1E
 - Neo
 - Web Security
- Fortinet:
 - FortiClient
 - FortiEDR
- Huntress
- Ivanti Endpoint Security
- Jamf Protect
- Kaspersky
- Lakeside
- Malwarebytes
- McAfee:
 - On-Access Scanner
 - Trellix
 - Windows Protection Suite
- Microsoft:
 - Defender for Endpoint
 - Monitoring Agent
 - Windows Updater
- N-able Technologies
- Nexthink
- NinjaOne
- Palo Alto:
 - Cortex XDR
 - GlobalProtect
- Panda Security
- Proofpoint
- Qualys Cloud Agent
- Rapid7 Agent
- ReasonLabs
- Riverbed Aternity
- SentinelOne
- Snow Agent
- Sophos Agent
- Symantec Endpoint Protection
- Tanium Client
- Tenable
- Trend Micro
- Wazuh agent

- WithSecure
- XProtect


Duplicating Agent configuration groups

To work more efficiently, you can duplicate an existing Agent configuration group and modify it as needed.

How to duplicate an Agent configuration group

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Agents*, select the *Agent configuration* tab.
3. In the *Agent configuration* section, on the row of the group you want to duplicate, click  > *Duplicate*.

Config settings




4. Update the group properties as needed. For details, see [Creating Agent configuration groups on page 210](#).
5. Click *Save*.

Editing Agent configuration groups

To edit an Agent configuration group, follow these steps.

How to edit an Agent configuration group

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Agents*, select the *Agent configuration* tab.
3. In the *Agent configuration* section, on the row of the group you want to modify, click *Edit*.



4. Update the group properties as needed. For details, see [Creating Agent configuration groups on page 210](#).
5. Click Save.

Deleting Agent configuration groups

To delete an Agent configuration group, follow these steps.

How to delete an agent configuration group

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Agents*, select the *Agent configuration* tab.
3. In the *Agent configuration* section, on the row of the group you want to delete, click  > *Delete*.

Config settings

Process name exclusion = **Exclude 2 entries**

Edit



Duplicate

Delete

Process path exclusion = **Exclude 2 entries**

4. In the *Delete Agent configuration* dialog box, click *Delete*.

Testing Agent configurations

The FortiDLP Console allows you to check the configuration for an Agent with a given set of labels. This is helpful when a node is assigned multiple labels and/or belongs to multiple configuration groups.

How to test an Agent configuration

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Agents*, select the *Agent configuration* tab.
3. In the *Agent configuration* section, click *Test labels*.

4. In the label selector box, type a label name and then select it from the list that displays. Repeat as needed.

Test labels

From here, you can preview the configuration for an agent with a given set of labels.

Check configuration for agents with the following labels

Department | IT x

Country | USA x

Clear selection

The Agent configuration displays.



If a configuration option is set to *Not configured*, this means the Agent default applies, unless it has been configured locally (in the Agent's configuration file). To learn more, see [Agent configuration default settings on page 219](#).

Node archiving

FortiDLP provides archiving functionality to exclude nodes from the FortiDLP Console, so operators can focus only on those that are relevant. When a node is archived, it is hidden from the *Nodes* and *Users* modules. However, for auditing purposes, you can still search for its events, which can be used for searches, investigations, and reports. The operator/rule responsible for archiving a node and the archive reason is also recorded.

The following auto-archiving rules are available:

- *Auto-archive duplicate nodes*: Archive a duplicate node that results from the Agent being re-enrolled on a device.
- *Auto-archive inactive nodes*: Archive a node that is offline for a configurable period of time.
- *Revoke archived Agents' licenses*: Revoke the Agent license of a node after it is archived for a configurable period of time.

For instructions on configuring auto-archiving rules, see [Creating Agent configuration groups on page 210](#).

Manual archiving allows you to exclude nodes from the FortiDLP Console via the *Nodes* module for any reason. This functionality is described in [Manually archiving and unarchiving nodes on page 235](#).



For example, you may want to manually archive a node that has been decommissioned, or you may want to unarchive a node used by an employee who took a long leave of absence.

If needed, you can manually unarchive a licensed node, which will expose it in all parts of the FortiDLP Console again. An archived node will be automatically unarchived if the Agent communicates with the FortiDLP Infrastructure again (see the following table). Unlicensed nodes cannot be unarchived.

Node states

A node is displayed in the *Nodes* module with one of the following states.

Node states

State	Description
Active	The node has not been archived. The node will remain in this state, even if it does not have an active Agent heartbeat, until it is manually or automatically archived.
Archived	The node has been manually or automatically archived. The node can be set to <i>Active</i> upon the Agent sending a heartbeat to the FortiDLP Infrastructure.
Always active	The node has been manually unarchived. The node will remain in this state unless it is manually archived, at which point, it can take on an <i>Active</i> state again (upon the Agent sending a heartbeat to the FortiDLP Infrastructure).
Always archived	The node has been manually set to be always archived via the FortiDLP API, or it has had its Agent license revoked. The node will remain in this state unless it is manually changed using the FortiDLP Console or API. The state of unlicensed nodes cannot be changed.



Node and user states are independent of each other. For information on the different states a user can be set to, see [User states and transitions on page 54](#).

Manually archiving and unarchiving nodes

To manually archive or unarchive one or more nodes, follow these steps.



Unlicensed nodes cannot be unarchived.




You can also automatically archive duplicate and inactive nodes. For details, see [Creating Agent configuration groups on page 210](#).

How to manually archive or unarchive a single node


1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Filter for the relevant node. For guidance on this, see [Nodes](#) in the *FortiDLP Console User Guide*.

3. In the *Table* tab, do one of the following:

- On the relevant node's table row, click  > *Archive node/Unarchive node*.




- On the top-right corner of the page, click  > *Archive nodes/Unarchive nodes*.



When using this method, ensure you have filtered for only the node you want to archive/unarchive. Otherwise, you will archive/unarchive all nodes in view.


- Click the node's table row to go to the *Node profile* page, and then on the top-right corner of the page, click $\vdots$ > *Archive node/Unarchive node*.



- Do one of the following:
 - To archive the node, in the *Archive node* dialog box:
 - In the *Reason* field, type the archiving reason.
 - Click *Archive*.
 - To unarchive the node, in the *Unarchive node* dialog box, click *Unarchive*.

How to manually archive or unarchive multiple nodes

- In the FortiDLP Console, on the left-hand sidebar, click $\square$.
- In either the *Aggregations* or *Table* tab, filter for the relevant nodes. For guidance on this, see [Nodes](#) in the *FortiDLP Console User Guide*.
- On the top-right corner of the page, click $\vdots$ > *Archive nodes/Unarchive nodes*.



4. Do one of the following:

- To archive the nodes, in the *Archive {n} nodes* dialog box:
 - i. In the *Reason* field, type the archiving reason.
 - ii. Click *Archive*.
- To unarchive the nodes, in the *Unarchive {n} nodes* dialog box, click *Unarchive*.

SaaS apps

The *SaaS apps* module offers a holistic view of node and user interactions with Software-as-a-Service (SaaS) apps, that is, cloud-based applications accessed through an internet connection. This feature collates browser activity, classifies it by application, and aggregates it so that you can spot potential risks for web-based data exposure across your organization.

The *SaaS apps* module also integrates with policies, enabling you to detect and block unauthorized web app use, including file uploads and downloads, copied-and-pasted text, and printing. For advanced protection, you can also use our origin-tracking SaaS apps policy capabilities, which allow the FortiDLP Agent to monitor sensitive files downloaded from specified web apps—across file renames, moves, and copies—and block exfiltration attempts.

SaaS apps setup

SaaS apps functionality spans multiple FortiDLP modules, thus configuration is performed from the *Admin settings*, *SaaS apps*, and *Policies modules*. The following table outlines the setup tasks relating to SaaS apps and directs you to the corresponding instructions.

Setup tasks

Task	Description
1. Tracking corporate SaaS app account logins on page 239 .	To get started, you must add your corporate email address domain(s) to the FortiDLP Console. The domain(s) you specify will be compared with the domain of the email addresses used to log in to SaaS apps to determine whether logins are corporate or non-corporate.
2. Preparing the SaaS app inventory: • Manually adding SaaS apps to the inventory • Editing SaaS app verdicts • Editing SaaS app risk scores.	Next, you should set up your SaaS apps inventory. For an app to display in the <i>SaaS apps</i> module and be used in policies, it must be added to the inventory. An app can be added automatically when activity for an app is reported via a browser event. You can also manually add third-party and custom apps to the SaaS apps inventory. After a SaaS app is added, you need to set its verdict to indicate whether it is approved or unapproved for use and review and/or modify its default risk score.
3. Classifying domainless SaaS app account logins (optional) .	Then, you have the option to configure how domainless SaaS app logins are classified. A domainless login, where the username is not an email address, is classified as non-corporate by default. However, you can configure domainless logins to be reported as corporate on a per-app basis if preferred.

Task	Description
4. Creating SaaS app specifier policy assets (optional).	To ease policy configuration, you can create SaaS app specifier assets for reuse across multiple policies. This can be done by defining app conditions and/or selecting apps from your inventory.
5. Enabling SaaS app policies: • Configuring policy templates • SaaS apps • SaaS apps origin.	Lastly, you can configure policies containing the <i>SaaS apps</i> and <i>SaaS apps origin</i> parameters. You can do this by providing custom values or selecting SaaS app specifier assets.

Tracking corporate SaaS app account logins

By adding your corporate domains to the FortiDLP Console, you can identify when users log in to corporate SaaS app accounts via browser login events and web policies. These domains will be compared with the domain of the email address used to log in, and if there is a match, the event will be classified as corporate. If you do not provide any domains or if no domains are matched, the event will be classified as non-corporate.

These classifications will also be used in the *SaaS apps* module to report the number of apps that have been accessed with a corporate or non-corporate account at least once. For more information, see [Dashboard tab](#) in the *FortiDLP Console User Guide*.



Your corporate classifications will only apply to events generated *after* your domains are added or updated.

Subdomains will match. For example, if one of your corporate domains is `company.com` and a user logs in with the account username `mary@sales.company.com`, the login event will be classified as corporate.

Domainless logins, where the username is not an email address, are classified as non-corporate by default. You can classify them as corporate on a per-app basis in the *SaaS apps* module. For more information, see [Classifying domainless SaaS app account logins](#) in the *FortiDLP Console User Guide*.

Password-free logins, where a one-time code, face, fingerprint, pin, or security key is used for authentication, will be reported as unknown logins.

How to add your corporate email address domains

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *General*, select the *SaaS apps* tab.

3. In the *Track corporate SaaS app account logins* section, type a list of your corporate domains, with each domain starting on a new line.

Corporate domain(s)

longcompanyname.com
shortcompanyname.com

Save

4. Click Save.

Auto-archiving SaaS apps

You can automatically archive SaaS apps if they are not reported in browser activity within a configured time frame. Follow the steps below to set this up.

How to auto-archive SaaS apps

1. In the FortiDLP Console, on the sidebar menu, click .
2. Under *General*, select the *SaaS apps* tab.
3. Turn the *Auto-archive unused SaaS apps* toggle on.
4. In the *Days* field, enter a number of days for which an app must be unused for auto-archiving to occur.

Auto-archive SaaS apps

Auto-archive unused SaaS apps



Automatically archive a SaaS app if it is unused for more than:

20



Days

Save

5. Click Save.

Apps archived by this rule will transition to the state *Archived*.

Evidence capturing

Evidence capturing enables the FortiDLP Agent to gather forensic information for investigative analysis. It provides security teams with context and documentation when users violate data loss prevention policies.

The Agent collects evidence through the actions outlined in the following table and then sends it to external object storage or the FortiDLP Infrastructure, depending on the evidence type and configuration.

Evidence type	Action	Description	Storage option(s)
Clipboard	Capture clipboard evidence	The text stored in a user's system or browser clipboard when they violated a policy.	Customer-managed object storage
File	Capture file evidence	A copy of a file a user interacted with when they violated a policy.	Customer-managed object storage
Screenshot	Capture screenshot evidence	An image of a user's computer screen captured either when they violated a policy or when an operator executed a manual action from the FortiDLP Console.	- Customer-managed object storage - FortiDLP-managed storage

External object storage

When evidence is stored externally, you own and manage your data, and evidence is not uploaded to or stored in the FortiDLP Infrastructure. The Agent captures and encrypts evidence and then sends it to your chosen storage vendor through a Transport Layer Security (TLS) connection, protecting your data in motion and at rest. The evidence is then available for decryption either directly from the storage location or through the FortiDLP Console, which redirects the client to the external storage location. Only private key holders can decrypt evidence, and they must do this using a FortiDLP decryption tool. Two decryption tools are available: a browser extension (recommended) and a CLI-based utility.

Evidence can be stored in the cloud with Amazon Web Services (AWS), Google Cloud Storage (GCS), or Microsoft Azure Blob Storage.

To use external object storage for FortiDLP evidence, complete the tasks below.

External object storage setup

Task	Description
1. Depending on your storage vendor, either: Configuring AWS to store evidence on page 242 Configuring Azure Blob Storage to store evidence on page 245	To get started, perform vendor-side setup. This entails creating a secure storage bucket/container and granting the FortiDLP Agent and operators access to it.

Task	Description
or	
Configuring GCS to store evidence on page 247.	
2. Configuring FortiDLP to store evidence in external object storage on page 249.	Then, configure FortiDLP with the details of your storage location along with Agent storage limits, if you want to alter the default settings.
3. Testing external evidence storage configurations on page 250 (optional but recommended).	We recommend testing your configuration. During this stage, you will verify that a test evidence file can be uploaded to and downloaded from your storage bucket/container.
4. Downloading decryption tools on page 251.	Next, download the FortiDLP Decryption Tool Extension or the FortiDLP Decryption CLI Tool.
5. Setting encryption keys and passphrases on page 252.	Then, you will need to generate an encryption key and add its corresponding public key to the FortiDLP Console. You must also create a passphrase to protect your key.
6. Enabling evidence capturing in policies on page 260.	Lastly, configure policy templates to execute evidence capturing actions.

For instructions on decrypting evidence, see [Decrypting evidence on page 260](#).

FortiDLP-managed storage

The FortiDLP Infrastructure is the default storage location for screenshot evidence. When this location is used, the Agent captures and sends screenshots to the FortiDLP Infrastructure, which can then be viewed in the FortiDLP Console by operators with access to the *Action* event stream.

To configure the FortiDLP Infrastructure as your storage location for screenshot evidence, complete the tasks below.

FortiDLP-managed storage setup

Task	Description
1. Configuring FortiDLP to store screenshot evidence on page 269.	First, go to <i>Admin settings > Evidence capturing</i> and turn off the <i>Store screenshot evidence in vendor bucket</i> toggle if this is not the current setting.
2. Enabling evidence capturing in policies on page 260.	Then, configure policy templates to execute the <i>Capture screenshot evidence</i> action.

Configuring AWS to store evidence

When configuring AWS to store FortiDLP evidence, you will need to create the following:

- storage bucket (S3)
- bucket policy

- IAM user policy
- IAM user.

FortiDLP requires HTTPS (TLS) to prevent potential attackers from eavesdropping on or manipulating network traffic using person-in-the-middle or similar attacks. AWS supports HTTP by default, but you should only allow encrypted connections over HTTPS by using the `aws:SecureTransport` condition on your bucket policy.

The bucket policy allows or denies requests based on various elements, including the requester, S3 actions, resources, and aspects or conditions of the request—for example, the IP address used to make the request. When configuring your bucket policy, ensure you enable the bucket to accept `PutObject` and `GetObject` requests and to only accept requests using TLS.

Follow these steps to configure evidence capturing with AWS.

How to configure AWS to store evidence

1. Log in to the AWS Console.
2. Create a storage bucket:
 - a. Go to *Services > Storage > S3*.
 - b. Click *Create bucket*.
 - c. In the *Bucket name* field, type the bucket name.

General configuration

Bucket name

shadow-copies

Bucket name must be unique and must not contain spaces or uppercase letters. [See rules for bucket naming](#) 

- d. In the *AWS Region* menu, select the bucket region. We recommend choosing the region your company is located in.
 - e. Leave the *ACLs disabled* radio button and the *Block all public access* checkbox selected.
 - f. In the *Encryption type* section, leave the *Server-side encryption with Amazon S3 managed keys (SSE-S3)* radio button selected.
 - g. In the *Bucket key* section, leave the *Enable* radio button selected.
 - h. Click *Create bucket*.
3. Create an IAM user policy:
 - a. Go to *Services > Security, Identity, & Compliance > IAM*.
 - b. In the left-hand panel, click *Policies*.
 - c. Click *Create Policy*.
 - d. Click the *JSON* tab.
 - e. Paste the following JSON text, adding your storage bucket ARN. To retrieve this, go to *Services > S3 > Buckets > your storage bucket (from step 2c) > Properties*.

```
{  
  "Version": "2012-10-17",
```

```

    "Statement": [
      {
        "Sid": "FortiDLPBucketPolicy",
        "Effect": "Allow",
        "Action": [
          "s3:PutObject",
          "s3:GetObject"
        ],
        "Resource": "ARN FROM S3 BUCKET PROPERTIES PAGE/*"
      }
    ]
  }
}

```

- f. Click *Next*.
- g. In the *Name* field, type a policy name.
- h. In the *Description* field, type a policy description.
- i. Click *Create policy*.
4. Create an IAM user:
 - a. In the left-hand panel, click *Users*.
 - b. Click *Create user*.
 - c. In the *User name* field, type a username. For example, FortiDLPBucketUser. This name will be included in AWS CloudTrail logs.
 - d. In the *Select AWS access type* section, select the *Access key - Programmatic access* radio button.
 - e. Click *Next*.
 - f. In the *Set permissions* section, click *Attach policies directly*.
 - g. Select the checkbox of your IAM user policy (from step 3).
 - h. Click *Next*.
 - i. Click *Create user*.
5. Create a bucket policy:
 - a. Go to *Services > Storage > S3*.
 - b. Click your storage bucket.
 - c. Click the *Permissions* tab.
 - d. In the *Bucket policy* section, click *Edit*.
 - e. In the entry box, paste the following JSON text, adding your IAM user ARN and storage bucket ARN. To retrieve the IAM user ARN, go to *Services > IAM > Access Management > Users > your IAM user (from step 4) > Summary*. The storage bucket ARN is the ARN used in step 3e.

```

{
  "Version": "2012-10-17",
  "Id": "S3-Console-Auto-Gen-Policy-1643731743161",
  "Statement": [
    {
      "Sid": "BucketPermissions",
      "Principal": {
        "AWS": [
          "ARN FROM IAM USER PAGE"
        ]
      }
    }
  ]
}

```

```

    },
    "Effect": "Allow",
    "Action": [
        "s3:PutObject",
        "s3:GetObject"
    ],
    "Resource": "ARN FROM S3 BUCKET PROPERTIES PAGE/*"
  },
  {
    "Sid": "TLSRequired",
    "Principal": "*",
    "Effect": "Deny",
    "Action": [
        "s3:*"
    ],
    "Resource": [
        "ARN FROM S3 BUCKET PROPERTIES PAGE",
        "ARN FROM S3 BUCKET PROPERTIES PAGE/*"
    ],
    "Condition": {
      "Bool": {
        "aws:SecureTransport": [
          "false"
        ]
      }
    }
  }
]
}

```



To optionally limit bucket access to specific IP addresses, see AWS' documentation [here](#) and [here](#).

f. Click *Save changes*.

Take note of the *Access key ID* and *Secret access key* values, and then proceed to the next task, [Configuring FortiDLP to store evidence in external object storage on page 249](#).

Configuring Azure Blob Storage to store evidence

When configuring Azure Blob Storage to store evidence captured by FortiDLP, you will need to create the following:

- storage account
- storage container.

FortiDLP uses storage account keys to authenticate with the Azure Blob Storage service. These keys grant full permissions to all containers within the storage account. To restrict this scope, we recommend creating a dedicated storage account for FortiDLP.

Follow these steps to configure evidence capturing with Azure Blob Storage.



File evidence is supported with FortiDLP Agent 10.1.3+, and clipboard and screenshot evidence is supported with FortiDLP Agent 12.2.1+. Earlier Agents may successfully upload file evidence to Azure Blob Storage, but the evidence will be unavailable for download from the FortiDLP Console. In this scenario, associated action events will also display with an *Expired* status.

How to configure Azure Blob Storage to store evidence

1. Log in to the Microsoft Azure Portal.
2. Create a storage account:
 - a. Click *Storage accounts*.
 - b. Click *Create*.
 - c. In the *Basics* tab, in the *Storage account name* field, type the account name.
 - d. In the *Region* menu, select the account region. We recommend choosing the region your company is located in.

Instance details

Storage account name ⓘ *

shadowcopies

Region ⓘ *

(US) East US

- e. Click *Next* and configure your account as detailed [here](#).
- f. Click *Create*.
- g. After your account is created, click *Go to resource*.



Your deployment is complete

∨ Deployment details

∧ Next steps

Go to resource

3. Create a storage container:
 - a. In the left-hand panel, click *Containers*.
 - b. Click *Container*.
 - c. In the *New container* panel, in the *Name* field, type the container name.
 - d. Click *Create*.
4. Copy an access key:
 - a. In the left-hand panel, click *Access keys*.
 - b. For either of the access keys shown, click *Show*.
 - c. Copy the key.

Take note of the *Access key*, *Storage account name*, and *Container* values, and then proceed to the next task, [Configuring FortiDLP to store evidence in external object storage on page 249](#).

Configuring GCS to store evidence

When configuring GCS to store FortiDLP evidence, you will need to create the following:

- storage bucket
- bucket policy
- service account
- private key.

FortiDLP requires HTTPS (TLS) to prevent potential attackers from eavesdropping on or manipulating network traffic using person-in-the-middle or similar attacks. GCS enables HTTPS (TLS) by default, so no action is required to configure a secure connection.

Follow these steps to configure evidence capturing with GCS.

How to configure GCS to store evidence

1. Log in to the Google Cloud Platform Console.
2. Create a storage bucket:
 - a. Go to *Cloud Storage > Buckets*.
 - b. Click *Create*.
 - c. In the *Name your bucket* field, type the bucket name. Then click *Continue*.

• Name your bucket

Pick a globally unique, permanent name. [Naming guidelines](#)

shadow-copies

Tip: Don't include any sensitive information

- d. In the *Choose where to store your data* section, select the appropriate *Location type* radio button and location for the bucket. We recommend choosing a single region that is the same region your company is located in. Then click *Continue*.
- e. In the *Choose a storage class for your data* section, select the radio button for the appropriate storage class option. Then click *Continue*.
- f. In the *Choose how to control access to objects* section, leave the *Enforce public access prevention on this bucket* checkbox selected and select the *Uniform* radio button. Then click *Continue*.
- g. In the *Choose how to protect object data* section:
 - i. Select the radio button for the appropriate protection tools option.
 - ii. *Optionally*, to enable data encryption using a customer-managed encryption key, click *Data encryption* and then select the *Cloud KMS key* checkbox. To use this feature, you must also create a new key in your Cloud Key Management Console, as described [here](#). Google Cloud provides

default encryption at rest using AES-256 encryption standards, which applies if a Cloud KMS key is not configured.

iii. Click *Create*.

h. In the *Public access will be prevented* dialog box, click *Confirm*.

3. Create a service account key:

a. Go to *IAM and admin > Service accounts*.

b. Click *Create service account*.

c. In the *Service account details* section:

i. In the *Service account name* field, type a service account display name.



Your *Service account ID* is created as you type your *Service account name* and is displayed in the field below in the format `serviceaccountname@projectid.iam.gserviceaccount.com`. Take note of this value, as you will need it during step 4.

ii. In the *Service account description* field, type a service account description.

i. Click *Done*.

d. On the row of your service account, click  > *Manage keys*.

e. Click *Add key > Create new key*.

f. In the *Create private key* dialog box, leave the *JSON* radio button selected and click *Create*.

The service account JSON file will then download to your computer. You will need this to complete the next task, [Configuring FortiDLP to store evidence in external object storage on page 249](#).

4. Create a bucket policy:

a. Go to *Cloud Storage > Buckets*.

b. On the row of your storage bucket, click  > *Edit access*.

c. In the right-hand panel, click *Add principal*.

d. In the *New principals* field, enter the *Service account ID* (generated at step 3c).

e. In the *Select a role* menu, click *Cloud Storage > Storage Object Creator*.

f. Click *Add another role*.

- g. In the *Select a role* menu, click *Cloud Storage > Storage Object Viewer*.

Add principals

Principals are users, groups, domains or service accounts. [Learn more about principals in IAM](#)

New principals

revealbucketuser@test-123456.iam.gserviceaccount.com
 ✕
?

Assign Roles

Roles are composed of sets of permissions and determine what the principal can do with this resource. [Learn more](#)

Role * Storage Object Creator Access to create objects in GCS.	IAM condition (optional) ? + ADD IAM CONDITION
Role Storage Object Viewer Read access to GCS objects.	IAM condition (optional) ? + ADD IAM CONDITION

- h. Click **Save**.

You can then proceed to the next task, [Configuring FortiDLP to store evidence in external object storage on page 249](#).

Configuring FortiDLP to store evidence in external object storage

After completing vendor-side setup, you can configure FortiDLP to use your external storage location.

If the Agent cannot connect to the storage bucket or container, it temporarily stores evidence locally. Once the connection is restored, the Agent removes the evidence from local storage and uploads it to your configured storage location. FortiDLP provides settings to limit local storage for evidence associated with the *Capture file evidence* action locally. If needed, you can also change the default limits for this during configuration.

How to configure FortiDLP to store evidence in external object storage

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Integrations*, select the *Evidence capturing* tab.

3. In the *Storage vendor* section:**a.** Do one of the following:

- To use AWS:
 - i. In the *Vendor* menu, select *AWS*.
 - ii. In the *Region* field, type the name of the region the S3 bucket is in.
 - iii. In the *Bucket* field, type the name of your S3 bucket.
 - iv. In the *Access key ID* field, paste your access key ID.
 - v. In the *Secret key* field, paste your secret key.
- To use Azure Blob Storage:
 - i. In the *Vendor* menu, select *Azure*.
 - ii. In the *Storage account name* field, type the name of your storage account.
 - iii. In the *Storage container* field, type the name of your container.
 - iv. In the *Access key* field, paste your access key.
- To use GCS:
 - i. In the *Vendor* menu, select *GCS*.
 - ii. In the *Bucket* field, type the name of your storage bucket.
 - iii. In the *Service account JSON* field, paste the contents of the service account JSON file you generated.

b. Turn the *Store screenshot evidence in vendor bucket* toggle on.

If you would prefer to store screenshot evidence in the FortiDLP Infrastructure but store all other evidence externally, you can turn this toggle off. For more information, see [Configuring FortiDLP to store screenshot evidence on page 269](#).

- 4.** Optionally, in the *Agent local storage limits* section, in the *Maximum local storage on Agent (MB)* field, type a number to limit the local storage of file evidence by, in megabytes. The default value is 1 GB, and a value of 0 places no limit on local storage.
- 5.** Optionally, in the *Maximum single file size* field, type a number to limit the single file size by which a file evidence file can be created, in megabytes. The default value is 100 MB, and value of 0 places no limit on single file size.



Agent storage limits for file evidence can also be modified via [Advanced Agent configuration settings on page 222](#).

6. Click *Save*.

When you complete this task, proceed to [Testing external evidence storage configurations on page 250](#).

Testing external evidence storage configurations

FortiDLP lets you test your external storage configuration so you can confirm evidence capturing is set up correctly.

When you test your configuration, you verify that the FortiDLP Agent can upload evidence to your storage bucket/container and that you can download it. For simplicity, this is done with an unencrypted TXT file.

How to test your external evidence storage configuration

1. In the FortiDLP Console, on the left-hand sidebar, click ⚙️.
2. Under *Integrations*, select the *Evidence capturing* tab.
3. In the *Storage vendor* section, click *Test configuration*.
4. In the *Test file storage configuration* dialog box, click *Copy* beside the command supported for your OS.
5. Open a command-line interface and run the command you copied.



If this results in an error message, check your configuration. Otherwise, allow time for the file to be uploaded to your bucket/container before proceeding to the next step.

6. In the *Test file storage configuration* dialog box, click *Download test file*.
The test file is downloaded to your computer.

If the test file was successfully uploaded and downloaded, proceed to [Setting encryption keys and passphrases on page 252](#).

Downloading decryption tools

Fortinet provides two tools, compatible with all OSes, for decrypting FortiDLP evidence files:

- The FortiDLP Decryption Tool Extension is a GUI version of the tool that is available as a browser extension for Google Chrome, Microsoft Edge, and Firefox. It allows you to seamlessly decrypt evidence from the FortiDLP Console's *Detection details* and *Action details* panels. Alternatively, you can download evidence from these panels or your storage bucket/container and then upload it to the extension for decryption. Evidence files can be decrypted individually or in bulk.
- The FortiDLP Decryption CLI Tool is a command-line interface version of the tool. It allows you to decrypt evidence after downloading it from the FortiDLP Console's *Detection details* and *Action details* panels or your storage bucket/container. Evidence files can be decrypted individually, and bulk decryption can be scripted. For details on scripting this, contact Fortinet Support.

How to download the FortiDLP Decryption Tool Extension

1. Using Google Chrome, Microsoft Edge, or Firefox, log in to the FortiDLP Console.
2. On the left-hand sidebar, click ⚙️.
3. Under *Integrations*, select the *Evidence capturing* tab.

4. In the *FortiDLP Decryption Tool Extension* section, click the link for the browser you want to install the extension on.



5. In the installation dialog box, follow the steps to add the extension to your browser.
6. Refresh the page.



The page must be refreshed to enable the *Decrypt* button to display within the *Detection details* and *Action details* panels.

How to download the FortiDLP Decryption CLI Tool

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Integrations*, select the *Evidence capturing* tab.
3. In the *FortiDLP Decryption CLI Tool* section, select the binary file format for your OS.
4. Click *Download*.

Setting encryption keys and passphrases

Before the FortiDLP Agent transfers evidence files to an external storage location, it encrypts them to add an additional layer of protection. To do this, the Agent requires an encryption key.

You will need to generate at least one encryption key using the FortiDLP Decryption Tool Extension or the FortiDLP Decryption CLI Tool. An encryption key has a *public* component and a *private* component:

- The *public* key must be pasted into the FortiDLP Console so that the Agent can use it to encrypt files.
- The *private* key must be kept in a safe location, only accessible to operators who decrypt evidence:
 - When you generate an encryption key using the FortiDLP Decryption Tool Extension, the private key is automatically encrypted and stored within the extension's passphrase-protected vault.
 - When you generate an encryption key using the FortiDLP Decryption CLI Tool, the private key is saved in your home directory by default (as detailed below). We advise implementing internal security measures like access control and logging to protect it.



If evidence must be accessible by multiple people, we recommend setting up a distinct key for each person, rather than sharing a single common key.

You will create a passphrase during the initial setup process to secure access to these tools and their corresponding encryption keys. This passphrase will then be required each time you launch the extension to "unlock" it or run a command using the CLI tool. After the passphrase is validated, encryption keys can be generated, evidence files can be decrypted, and so on.

You can change your FortiDLP Decryption Tool Extension passphrase at any time from within the extension UI's settings. FortiDLP Decryption CLI Tool passphrase resets are not supported. See [Changing decryption tool passphrases on page 259](#) for details.

Refer to the instructions corresponding to your tool of choice when setting encryption keys.

How to set an encryption key using the FortiDLP Decryption Tool Extension

1. On your browser's menu bar, click the  icon and launch the FortiDLP Decryption Tool Extension.
2. In the *New passphrase* field, type a passphrase of at least 12 characters.



We recommend that your passphrase:

- contains a mixture of uppercase and lowercase letters, numbers, and special characters
- is complex (avoid strings of repeated characters)
- is unique (avoid reusing passphrases).

3. In the *Confirm passphrase* field, type your passphrase again.

New passphrase

Confirm passphrase

4. Click *OK*.
5. Do one of the following:
 - To generate a new key:
 - i. Click *Generate a new key*.
Your key pair is generated.
 - ii. Click *Copy* to copy the public key.



From this screen, you can optionally export the private key as a PEM file for backup by clicking *Export*. If you do this, choose a complex passphrase to protect the key file and make a note of it, as this will be needed to re-import it.

- iii. Log in to the FortiDLP Console.
- iv. On the left-hand sidebar, click .
- v. Under *Integrations*, select the *Evidence capturing* tab.
- vi. In the *Encryption keys* section, click *Add key*.
- vii. In the *Add new encryption key* dialog box:
 - i. In the *Name* field, type a key name that will help you associate your private key with the public key.
 - ii. In the *Public key* field, paste your public key.
 - iii. Click *Save*.

- To import an existing key (generated by the extension or the CLI tool):
 - i. Click *Import an existing key*.
 - ii. Select your private key file.



Key files generated by the FortiDLP Decryption CLI Tool are saved in the following locations by default:

- Windows: C:/Users/<user>/ .fortidlp-decryption-tool/key
- macOS and Linux: ~/.fortidlp-decryption-tool/key.

-
- iii. In the *Passphrase* field, type the private key file's passphrase (not your extension passphrase) and then click *OK*.
 - iv. If you have not already added the public key to the FortiDLP Console, do the following:
 - i. Click *Copy* to copy the public key.
 - ii. Log in to the FortiDLP Console.
 - iii. On the left-hand sidebar, click .
 - iv. Under *Integrations*, select the *Evidence capturing* tab.
 - v. In the *Encryption keys* section, click *Add key*.
 - vi. In the *Add new encryption key* dialog box:
 - i. In the *Name* field, type a key name that will help you associate your private key with the public key.
 - ii. In the *Public key* field, paste your public key.
 - iii. Click *Save*.



If you forget your FortiDLP Decryption Tool Extension passphrase, you will lose access to all private keys stored in the extension and files that were encrypted using such keys. Fortinet cannot recover passphrases and private keys. If needed, you can view an existing public key in the FortiDLP Console and export a private key from the extension UI for backup (as described above).

After you configure at least one encryption key, proceed to [Enabling evidence capturing in policies on page 260](#). For details on managing keys, see [Rotating encryption keys on page 255](#) and [Deleting encryption keys on page 258](#).

How to set an encryption key using the FortiDLP Decryption CLI Tool

1. Open a CLI.
2. Go to the directory containing the FortiDLP Decryption CLI Tool binary.
3. Do one of the following:
 - On Windows, run the command `fortidlp-decryption-tool.exe keygen`.
 - On macOS or Linux, run the command `./fortidlp-decryption-tool keygen`.
4. Type a passphrase of at least 15 characters and then press *Enter*.



Your passphrase must:

- contain a mixture of uppercase and lowercase letters, numbers, and special characters
- be complex (avoid strings of repeated characters)
- be unique (avoid reusing passphrases).

Remember this passphrase, as you will need it every time you use the FortiDLP Decryption CLI Tool and if you later import your key file into the FortiDLP Decryption Tool Extension.

Your key pair is generated.

5. Store the private key in a safe location and copy the public key.
6. Log in to the FortiDLP Console.
7. On the left-hand sidebar, click .
8. Under *Integrations*, select the *Evidence capturing* tab.
9. In the *Encryption keys* section, click *Add key*.
10. In the *Add encryption key* dialog box, do the following:
 - a. In the *Name* field, type a key name that will help you associate your private key with the public key.
 - b. In the *Public key* field, paste your public key.
 - c. Click *Save*.



Key files generated by the FortiDLP Decryption CLI Tool are saved in the following locations by default:

- Windows: C:/Users/<user>/fortidlp-decryption-tool/key
- macOS and Linux: ~/.fortidlp-decryption-tool/key.



If you lose your private key or forget your FortiDLP Decryption CLI Tool passphrase, you will lose access to all files that were encrypted using that key. Fortinet cannot recover private keys and passphrases. If needed, you can view an existing public key in the FortiDLP Console or by running the export command when using the FortiDLP Decryption CLI Tool.

After you configure at least one encryption key, proceed to [Enabling evidence capturing in policies on page 260](#).

For details on deleting unwanted keys, see [Deleting encryption keys on page 258](#).

Rotating encryption keys

As a best practice for data security, we recommend regularly rotating encryption keys.


Follow these instructions when rotating keys using your decryption tool of choice.



If you delete an encryption key from the FortiDLP Console, the Agent can no longer use its public key to encrypt new evidence, and operators cannot use the corresponding private key to decrypt new evidence. However, operators can still use the private key to decrypt existing evidence. For this reason, you should keep your private key protected if you need continued access to previously encrypted evidence, or delete it if you do not.


How to rotate an encryption key using the FortiDLP Decryption Tool Extension

1. Create a new key:
 - a. On your browser's menu bar, click the  icon and launch the FortiDLP Decryption Tool Extension.
 - b. In the *Passphrase* field, type your passphrase and then click *Unlock*.
 - c. On the top-right corner of the extension UI, click  > *Manage keys*.
 - d. Click  > *Rotate key*.



Your new key pair is generated, replacing the previous pair.

- e. Click *Copy* to copy the public key.
2. Configure the new key:
 - a. Log in to the FortiDLP Console.
 - b. On the left-hand sidebar, click .
 - c. Under *Integrations*, select the *Evidence capturing* tab.
 - d. In the *Encryption keys* section, click *Add key*.
 - e. In the *Add new encryption key* dialog box:
 - i. In the *Name* field, type a key name that will help you associate your private key with the public key.
 - ii. In the *Public key* field, paste your public key.
 - iii. Click *Save*.
3. Delete the former key:
 - a. In the *Encryption keys* table, on the row of the old key, click  > *Delete key*.



- b. In the dialog box, click *Delete key*.

How to rotate an encryption key using the FortiDLP Decryption CLI Tool

1. Create a new key:
 - a. Open a CLI.
 - b. Go to the directory containing the FortiDLP Decryption CLI Tool binary.
 - c. Do one of the following:
 - To create the new key file at the default location:
 - i. Remove the existing key file from the default location:
 - Windows: C:/Users/<user>/fortidlp-decryption-tool/key
 - macOS and Linux: ~/.fortidlp-decryption-tool/key.
 - ii. Do one of the following:
 - On Windows, run the command `fortidlp-decryption-tool.exe keygen`.
 - On macOS or Linux, run the command `./fortidlp-decryption-tool keygen`.
 - To create the new key file at a custom location:
 - i. Do one of the following, replacing <path> with the file path where you want to store the new file:
 - On Windows, run the command `fortidlp-decryption-tool.exe keygen -k "<path>"`.
 - On macOS or Linux, run the command `./fortidlp-decryption-tool keygen -k "<path>"`.
 - d. Type a passphrase of at least 15 characters and then press *Enter*.



Your passphrase must:

- contain a mixture of uppercase and lowercase letters, numbers, and special characters
- be complex (avoid strings of repeated characters)
- be unique (avoid reusing passphrases).


Remember this passphrase, as you will need it every time you use the FortiDLP Decryption CLI Tool and if you later import your key file into the FortiDLP Decryption Tool Extension.

Your key pair is generated.

- e. Store the private key in a safe location and copy the public key.
2. Configure the new key:
 - a. Log in to the FortiDLP Console.
 - b. On the left-hand sidebar, click .
 - c. Under *Integrations*, select the *Evidence capturing* tab.
 - d. In the *Encryption keys* section, click *Add key*.
 - e. In the *Add encryption key* dialog box, do the following:
 - i. In the *Name* field, type a key name that will help you associate your private key with the public key.
 - ii. In the *Public key* field, paste your public key.
 - iii. Click *Save*.

3. Delete the former key:

- a. In the *Encryption keys* table, on the row of the old key, click ⋮ > *Delete key*.



- b. In the dialog box, click *Delete key*.

Deleting encryption keys

If you no longer need an encryption key, you can delete it from the FortiDLP Console and/or FortiDLP Decryption Tool Extension.


Note the following behavior:



- If you delete an encryption key from the FortiDLP Console, the Agent can no longer use its public key to encrypt new evidence, and operators cannot use the corresponding private key to decrypt new evidence. However, operators can still use the private key to decrypt existing evidence. For this reason, you should keep your private key protected if you need continued access to previously encrypted evidence, or delete it if you do not.
- If you delete an encryption key from the FortiDLP Decryption Tool Extension, the Agent can still use its public key to encrypt new evidence, but operators cannot use its corresponding private key to decrypt *any* evidence—neither new nor existing. For this reason, use caution when deleting keys from the extension, as doing so permanently removes your ability to decrypt evidence encrypted with that public key.

How to delete an encryption key from the FortiDLP Console

1. In the FortiDLP Console, on the left-hand sidebar, click ⚙️.
2. Under *Integrations*, select the *Evidence capturing* tab.
3. In the *Encryption keys* table, on the row of the relevant key, click ⋮ > *Delete*.



4. In the dialog box, click *Delete*.

How to delete an encryption key from the FortiDLP Decryption Tool Extension

1. On your browser's menu bar, click the  icon and launch the FortiDLP Decryption Tool Extension.
2. In the *Passphrase* field, type your passphrase and then click *Unlock*.
3. On the top-right corner of the extension UI, click  > *Manage keys*.
4. In the *Previous keys* section, below the key you want to delete, click *Delete*.
AUKxCTcgKAF7u6ZVozyUN8XfN5S1UhsA17hex0r7JypweS0fX1TsWBD-id0f18NyP4
ZWC4cIkkb0TPBpmR2vbYbCU_UH_s9mnMVkPZstie52n-WSmi_GkwxPUKJjYNBcNZYg
qB66HVdYRIw4jwuPNJiYLWbQmUa-6JhWmMvmwxwzhwE1ZMA4ZGX6aH3qj6N-VUnfM1
h3Ja84J4kCAwEAAQ

Delete

Export

Copy

5. In the dialog box, click *Delete*.

Changing decryption tool passphrases

You can change your FortiDLP Decryption Tool Extension passphrase at any time from within the extension UI's settings, as detailed below. FortiDLP Decryption CLI Tool passphrase resets are not supported.



If you forget your passphrase and cannot unlock the extension, you will need to remove and re-install the extension and then follow the steps in [Setting encryption keys and passphrases on page 252](#) to configure a new encryption key.

How to change your FortiDLP Decryption Tool Extension passphrase

1. On your browser's menu bar, click the  icon and launch the FortiDLP Decryption Tool Extension.
2. In the *Passphrase* field, type your passphrase and then click *Unlock*.
3. On the top-right corner of the extension UI, click  > *Change passphrase*.
4. In the *Current passphrase* field, type the passphrase you are changing.
5. In the *New passphrase* field, type a new passphrase of at least 12 characters.



We recommend that your passphrase:

- contains a mixture of uppercase and lowercase letters, numbers, and special characters
- is complex (avoid strings of repeated characters)
- is unique (avoid reusing passphrases).

6. In the *Confirm passphrase* field, type your passphrase again.

New passphrase

Confirm passphrase

7. Click *OK*.

Enabling evidence capturing in policies

Various data loss prevention policy templates support evidence capturing actions.

For example, you can create policies that enable the FortiDLP Agent to capture file and screenshot evidence when a user:

- uploads or downloads a sensitive file
- copies a sensitive file to a USB storage device
- sends an email containing a sensitive file.

For details about our policy templates, see the [FortiDLP Policies Reference Guide](#).

For instructions on creating policies, see [Policies on page 158](#).

Decrypting evidence

See the following sections to learn how to decrypt evidence:

- [Decrypting clipboard evidence on page 260](#)
- [Decrypting file evidence on page 263](#)
- [Decrypting screenshot evidence on page 266](#).

Decrypting clipboard evidence

Clipboard evidence files are packaged in encrypted ZIP files that are downloadable from the storage bucket as well as from the FortiDLP Console via pre-signed URLs. A pre-signed URL is a temporary secure URL that grants limited access to the specific encrypted ZIP file. They are dynamically generated and only displayed to operators who are permitted to download clipboard evidence. Further, if these files are stored on-premises, operators can only access them if they have the appropriate server permissions.



A pre-signed URL is valid for one hour. After one hour, you will need to obtain a new URL to view the evidence file by revisiting the relevant *Detection details/Action details* panel.

For identification purposes, the filename given to a clipboard evidence ZIP file contains the corresponding action UUID assigned in the FortiDLP Console, and its file path is structured as `/<tenant_uuid>/<agent_uuid>/evidence/<action_uuid>/clipboard_<action_uuid>.evidence`.

Within the decrypted ZIP file, one or more evidence files will be provided depending on the clipboard type. Each will be structured as `evidence/<text_type>/<index>`, where `text_type` will either be string, formatted string, or URL, and index counts files of the same type.



When you delete a user from FortiDLP, you remove all references to them. Before doing this, make a note of the user's Agent UUID so that you can manage their associated evidence files.

Follow these instructions to decrypt evidence using the FortiDLP Decryption Tool Extension or FortiDLP Decryption CLI Tool.


How to decrypt clipboard evidence using the FortiDLP Decryption Tool Extension



You can only decrypt evidence files that were generated after your encryption key was created and added to the *Evidence capturing* tab in *Admin settings*.

1. Do one of the following:

- To decrypt a clipboard evidence file from the FortiDLP Console's *Detection details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `detection:requested_actions = clipboard_evidence` search query.
 - iii. Click the *Detection* event stream.
 - iv. In the *Events* section, select the table row of the relevant detection.
 - v. In the *Detection details* panel's *Associated actions* section, click  in the action widget.



The FortiDLP Decryption Tool Extension opens.

- vi. In the *Passphrase* field, type your passphrase and then click *Unlock*.
 - vii. Click *Download* to download the decrypted file to your device.
- To decrypt a clipboard evidence file from the FortiDLP Console's *Action details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `action:action = clipboard_evidence` search query.
 - iii. Click the *Action (New)* event stream.
 - iv. In the *Events* section, select the table row of the relevant action event.
 - v. In the *Action details* panel's *Key information & content* section, click *Decrypt* in the action widget.

The FortiDLP Decryption Tool Extension opens.

- vi. In the *Passphrase* field, type your passphrase and then click *Unlock*.

- vii. Click *Download* to download the decrypted file to your device.
- To download an *encrypted* clipboard evidence file from the FortiDLP Console or your storage bucket and then decrypt it:
 - i. Do one of the following:
 - In the FortiDLP Console, follow the steps above to open the relevant *Detection details* panel , and in the *Associated actions* section, click  in the action widget.
 - In the FortiDLP Console, follow the steps above to open the relevant *Action details* panel, and in the *Key information & content* section, click *Download* in the action widget.
 - Download the file from your storage bucket.
 - ii. On your browser's menu bar, click the  icon and launch the FortiDLP Decryption Tool Extension..
 - iii. In the *Passphrase* field, type your passphrase and then click *Unlock*.
 - iv. Drag and drop one or more files or click *Select files to decrypt* and select them from your device.
 - v. Click *Download* to download the decrypted file(s) to your device.

How to decrypt clipboard evidence using the FortiDLP Decryption CLI Tool



You can only decrypt evidence files that were generated after your encryption key was created and added to the *Evidence capturing* tab in *Admin settings*.

1. Do one of the following:
 - Download the clipboard evidence file from the FortiDLP Console's *Detection details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `detection:requested_actions = clipboard_evidence` search query.
 - iii. Click the *Detection* event stream.
 - iv. In the *Events* section, select the table row of the relevant detection.
 - v. In the *Detection details* panel's *Associated actions* section, click  in the action widget.
 - Download the clipboard evidence file from the FortiDLP Console's *Action details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `action:action = clipboard_evidence` search query.
 - iii. Click the *Action (New)* event stream.
 - iv. In the *Events* section, select the table row of the relevant action event.
 - v. In the *Action details* panel's *Key information & content* section, click *Download* in the action widget.
 - Download the file from your storage bucket.
2. Open a command-line interface.
3. Go to the directory containing the FortiDLP Decryption CLI Tool binary.
4. Run one of the following commands, where `<path>` is the path to the encrypted file:
 - On Windows, run the command `fortidlp-decryption-tool.exe decrypt <path>`.
 - On macOS or Linux, run the command `./fortidlp-decryption-tool decrypt <path>`.



If your private key file is not in the default directory (see [Setting encryption keys](#)), you must use the `-k` flag to specify the path to the key file.

For example:

```
fortidlp-decryption-tool.exe decrypt <evidence file path> -k <private key path>.
```

5. Type your passphrase and then press *Enter*.

The decrypted file will be saved in the same directory as the encrypted version.



If preferred, you can save the decrypted file to a different location by specifying a destination path. For example:

```
fortidlp-decryption-tool.exe decrypt <encrypted evidence file path>  
<decrypted evidence file path>.
```

Decrypting file evidence

File evidence files are packaged in encrypted ZIP files that are downloadable from the storage bucket as well as from the FortiDLP Console via pre-signed URLs. A pre-signed URL is a temporary secure URL that grants limited access to the specific encrypted ZIP file. They are dynamically generated and only displayed to operators who are permitted to download file evidence. Further, if these files are stored on-premises, operators can only access them if they have the appropriate server permissions.



A pre-signed URL is valid for one hour. After one hour, you will need to obtain a new URL to view the evidence file by revisiting the relevant *Detection details/Action details* panel.

For identification purposes, the filename given to a file evidence ZIP file contains the corresponding action UUID assigned in the FortiDLP Console. However, its file path will vary by the Agent version:

- For nodes running Agent 12.2.1+, the path will be:
/`<tenant_uuid>`/`<agent_uuid>`/`evidence/<action_uuid>/fileshadow_<action_uuid>.evidence`.
- For nodes running Agent 11.0.1+, the path will be:
/`<tenant_uuid>`/`<agent_uuid>`/`<action_uuid>/<action_uuid>.evidence`.
- For nodes running Agents earlier than 11.0.1, the path will be:
/`<tenant_uuid>`/`evidence/<first two characters of action_uuid>/<rest of action_uuid>/<action_uuid>.evidence`.

Within the decrypted ZIP file, the file path for the evidence file will be structured as `/evidence/C:/<original file path>`, identifying the original file path associated with the policy violation.



For example, if a violation occurred for a file located at `C:/Users/Brian/Desktop/secret.txt`, the decrypted evidence file would be extracted as `evidence/C:/Users/Brian/Desktop/secret.txt`.



For macOS print job file evidence, information about the file path from which the document was printed is generally unavailable. In this case, the file evidence file path will be unrelated to the printed document's location, but if present, the print job name or document name will be included in the path.



When you delete a user from FortiDLP, you remove all references to them. Before doing this, make a note of the user's Agent UUID so that you can manage their associated evidence files.

Follow these instructions to decrypt evidence using the FortiDLP Decryption Tool Extension or FortiDLP Decryption CLI Tool.


How to decrypt file evidence using the FortiDLP Decryption Tool Extension



You can only decrypt evidence files that were generated after your encryption key was created and added to the *Evidence capturing* tab in *Admin settings*.

1. Do one of the following:


- To decrypt a file evidence file from the FortiDLP Console's *Detection details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `detection:requested_actions = file_evidence` search query.
 - iii. Click the *Detection* event stream.
 - iv. In the *Events* section, select the table row of the relevant detection.
 - v. In the *Detection details* panel's *Associated actions* section, click  in the action widget.



The FortiDLP Decryption Tool Extension opens.

- vi. In the *Passphrase* field, type your passphrase and then click *Unlock*.
 - vii. Click *Download* to download the decrypted file to your device.
- To decrypt a file evidence file from the FortiDLP Console's *Action details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `action:action = file_evidence/legacy_action:action = file_evidence` search query.
 - iii. Click the *Action (New)/Action (Legacy)* event stream.
 - iv. In the *Events* section, select the table row of the relevant action event.

- v. In the *Action details* panel's *Key information & content* section, click *Decrypt* in the action widget.



The FortiDLP Decryption Tool Extension opens.

- vi. In the *Passphrase* field, type your passphrase and then click *Unlock*.
- vii. Click *Download* to download the decrypted file to your device.
- To download an *encrypted* file evidence file from the FortiDLP Console or your storage bucket and then decrypt it:
 - i. Do one of the following:
 - In the FortiDLP Console, follow the steps above to open the relevant *Detection details* panel , and in the *Associated actions* section, click  in the action widget.
 - In the FortiDLP Console, follow the steps above to open the relevant *Action details* panel, and in the *Key information & content* section, click *Download* in the action widget.
 - Download the file from your storage bucket.
 - ii. On your browser's menu bar, click the  icon and launch the FortiDLP Decryption Tool Extension..
 - iii. In the *Passphrase* field, type your passphrase and then click *Unlock*.
 - iv. Drag and drop one or more files or click *Select files to decrypt* and select them from your device.
 - v. Click *Download* to download the decrypted file(s) to your device.

How to decrypt file evidence using the FortiDLP Decryption CLI Tool



You can only decrypt evidence files that were generated after your encryption key was created and added to the *Evidence capturing* tab in *Admin settings*.

1. Do one of the following:
 - Download the file evidence file from the FortiDLP Console's *Detection details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `detection:requested_actions = file_shadow` search query.
 - iii. Click the *Detection* event stream.
 - iv. In the *Events* section, select the table row of the relevant detection.
 - v. In the *Detection details* panel's *Associated actions* section, click  in the action widget.
 - Download the file evidence file from the FortiDLP Console's *Action details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `action:action = file_evidence/legacy_action:action = file_evidence` search query.
 - iii. Click the *Action (New)/Action (Legacy)* event stream.
 - iv. In the *Events* section, select the table row of the relevant action event.
 - v. In the *Action details* panel's *Key information & content* section, click *Download* in the action widget.
 - Download the file from your storage bucket.
2. Open a command-line interface.

3. Go to the directory containing the FortiDLP Decryption CLI Tool binary.
4. Run one of the following commands, where <path> is the path to the encrypted file:
 - On Windows, run the command `fortidlp-decryption-tool.exe decrypt <path>`.
 - On macOS or Linux, run the command `./fortidlp-decryption-tool decrypt <path>`.



If your private key file is not in the default directory (see [Setting encryption keys](#)), you must use the `-k` flag to specify the path to the key file.

For example:

```
fortidlp-decryption-tool.exe decrypt <evidence file path> -k <private key path>.
```

5. Type your passphrase and then press *Enter*.

The decrypted file will be saved in the same directory as the encrypted version.



If preferred, you can save the decrypted file to a different location by specifying a destination path. For example:

```
fortidlp-decryption-tool.exe decrypt <encrypted evidence file path>  
<decrypted evidence file path>.
```

Decrypting screenshot evidence

This section provides an overview of the process for decrypting screenshot evidence files if you choose to store them in external storage.

Screenshot evidence files stored externally are encrypted JPEG (for Windows) files or PNG (for macOS) files that are downloadable from the storage bucket as well as from the FortiDLP Console via pre-signed URLs. A pre-signed URL is a temporary secure URL that grants limited access to the specific encrypted ZIP file. They are dynamically generated and only displayed to operators who are permitted to download screenshot evidence. Further, if these files are stored on-premises, operators can only access them if they have the appropriate server permissions.



A pre-signed URL is valid for one hour. After one hour, you will need to obtain a new URL to view the evidence file by revisiting the relevant *Detection details/Action details* panel.

For identification purposes, the filename given to a screenshot evidence file contains the corresponding action UUID assigned in the FortiDLP Console, and its file path is structured as `/<tenant_uuid>/<agent_uuid>/evidence/<action_uuid>/screenshot_<action_uuid>.evidence`.



When you delete a user from FortiDLP, you remove all references to them. Before doing this, make a note of the user's Agent UUID so that you can manage their associated evidence files.

Follow these instructions to decrypt evidence using the FortiDLP Decryption Tool Extension or FortiDLP Decryption CLI Tool.


How to decrypt screenshot evidence using the FortiDLP Decryption Tool Extension



You can only decrypt evidence files that were generated after your encryption key was created and added to the *Evidence capturing* tab in *Admin settings*.

1. Do one of the following:

- To decrypt a screenshot evidence file from the FortiDLP Console's *Detection details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `detection:requested_actions = screenshot_evidence` search query.
 - iii. Click the *Detection* event stream.
 - iv. In the *Events* section, select the table row of the relevant detection.
 - v. In the *Detection details* panel's *Associated actions* section, click  in the action widget.



The FortiDLP Decryption Tool Extension opens.

- vi. In the *Passphrase* field, type your passphrase and then click *Unlock*.
 - vii. Click *Download* to download the decrypted file to your device.
- To decrypt a screenshot evidence file from the FortiDLP Console's *Action details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `action:action = screenshot_evidence` search query.
 - iii. Click the *Action (New)* event stream.
 - iv. In the *Events* section, select the table row of the relevant action event.
 - v. In the *Action details* panel's *Key information & content* section, click *Decrypt* in the action widget.

The FortiDLP Decryption Tool Extension opens.

- vi. In the *Passphrase* field, type your passphrase and then click *Unlock*.
 - vii. Click *Download* to download the decrypted file to your device.
- To download an *encrypted* screenshot evidence file from the FortiDLP Console or your storage bucket and then decrypt it:
 - i. Do one of the following:
 - In the FortiDLP Console, follow the steps above to open the relevant *Detection details* panel, and in the *Associated actions* section, click  in the action widget.
 - In the FortiDLP Console, follow the steps above to open the relevant *Action details* panel, and in the *Key information & content* section, click *Download* in the action widget.
 - Download the file from your storage bucket.
 - ii. On your browser's menu bar, click the  icon and launch the FortiDLP Decryption Tool Extension..
 - iii. In the *Passphrase* field, type your passphrase and then click *Unlock*.
 - iv. Drag and drop one or more files or click *Select files to decrypt* and select them from your device.
 - v. Click *Download* to download the decrypted file(s) to your device.

How to decrypt screenshot evidence using the FortiDLP Decryption CLI Tool



You can only decrypt evidence files that were generated after your encryption key was created and added to the *Evidence capturing* tab in *Admin settings*.

1. Do one of the following:

- Download the screenshot evidence file from the FortiDLP Console's *Detection details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `detection:requested_actions = screenshot_evidence` search query.
 - iii. Click the *Detection* event stream.
 - iv. In the *Events* section, select the table row of the relevant detection.
 - v. In the *Detection details* panel's *Associated actions* section, click  in the action widget.
- Download the screenshot evidence file from the FortiDLP Console's *Action details* panel:
 - i. On the left-hand sidebar, click .
 - ii. In the search bar, enter the `action:action = screenshot_evidence` search query.
 - iii. Click the *Action (New)* event stream.
 - iv. In the *Events* section, select the table row of the relevant action event.
 - v. In the *Action details* panel's *Key information & content* section, click *Download* in the action widget.
- Download the file from your storage bucket.

2. Open a command-line interface.

3. Go to the directory containing the FortiDLP Decryption CLI Tool binary.

4. Run one of the following commands, where <path> is the path to the encrypted file:

- On Windows, run the command `fortidlp-decryption-tool.exe decrypt <path>`.
- On macOS or Linux, run the command `./fortidlp-decryption-tool decrypt <path>`.



If your private key file is not in the default directory (see [Setting encryption keys](#)), you must use the `-k` flag to specify the path to the key file.

For example:

```
fortidlp-decryption-tool.exe decrypt <evidence file path> -k <private key path>
```

5. Type your passphrase and then press *Enter*.

The decrypted file will be saved in the same directory as the encrypted version.



If preferred, you can save the decrypted file to a different location by specifying a destination path. For example:

```
fortidlp-decryption-tool.exe decrypt <encrypted evidence file path> <decrypted evidence file path>
```

Configuring FortiDLP to store screenshot evidence

With FortiDLP Agent 12.2.1+, you can either store screenshot evidence in the FortiDLP Infrastructure, which is the default, or in external object storage.

Follow these instructions to store future captures in the FortiDLP Infrastructure. For instructions on using an external storage vendor, see [Configuring FortiDLP to store evidence in external object storage on page 249](#).



For Agents earlier than 12.2.1, screenshot evidence is always stored in the FortiDLP Infrastructure.

How to configure FortiDLP to store screenshot evidence

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Integrations*, select the *Evidence capturing* tab.
3. In the *Storage vendor* section, turn the *Store screenshot evidence in vendor bucket* toggle off.
4. Click *Save*.

Login banner message

You can optionally present a customizable banner message on the FortiDLP Console login page. When a banner message is enabled, it displays every time an operator visits the login page.



For example, you can use a banner message to display terms and conditions and privacy and security notices to operators which they must consent to before accessing the FortiDLP Console.

Configuring a login banner message

To enable or disable a login banner message for the FortiDLP Console, follow the instructions below.

How to enable a login banner message

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Authentication*, select the *Login banner* tab.
3. Turn the *Enabled* toggle on.
4. In the *Title* field, type the message title.
5. In the *Body* field, type the message body.



You can use Markdown syntax to format and structure your message. For example, surrounding text with double asterisks (**bold text**) would bold it, and prefixing text with one or more hash symbols followed by a space (# level 1 heading) would create heading levels.

6. In the *Button text* field, type the message button text.

Title

Terms and conditions

Body

Markdown supported

General site usage

Last revised: MM/DD/YYYY

Welcome to www.example.com.

Button text

Accept and continue

7. Click **Save**.

How to disable a login banner message

1. In the FortiDLP Console, on the left-hand sidebar, click .
2. Under *Authentication*, select the *Login banner* tab.
3. Turn the *Enabled* toggle off.

Enabled



Title

Terms and conditions

4. *Optionally*, delete the *Title*, *Body*, and *Button text* values.

5. Click *Save*.