LAB 2: IP Addresses and Host-to-Host Communication

Contents

| Introduction to LAB 2 | 2 |
|---|----|
| Exercise 1: Converting between the numeral systems | 2 |
| Task 1: Binary numbers to decimal | 2 |
| Task 2: Converting decimal numbers to binary | 2 |
| Task 3: Converting hexadecimal numbers to binary and decimal | 3 |
| Exercise 2: IP Addresses and Masks | 4 |
| Exercise 3: Explore the traffic flow and the message exchange between two directly connected hosts | 5 |
| Exercise 4: Explore the traffic flow and the message exchange between hosts connected with a Hub | 17 |
| Exercise 5: Explore the traffic flow and the message exchange between hosts connected with a Switch | 19 |

Introduction to LAB 2

In Lecture 2, you have learned about the different numeral systems, the subnet masks and their usage. You also learned what are the ARP and MAC address tables and how the computers and the networking devices use them. In this lab, you will make some conversions between the numeral systems and will determine some valid IP addresses and ranges based on network masks. Then, using Cisco Packet Tracer, you will monitor Host-to-Host communication at Layer 2 in different scenarios.

Exercise 1: Converting between the numeral systems

Task 1: Binary numbers to decimal

Convert the following binary numbers to decimal and write down the results in the table

| Binary | Decimal |
|----------|---------|
| 00001111 | 15 |
| 11110000 | 240 |
| 1111111 | 255 |
| 10101010 | 170 |
| 11111110 | 254 |

Task 2: Converting decimal numbers to binary

Now, let us do the opposite - convert the decimal numbers in binary and fill in the table the results

| Decimal | Binary |
|---------|----------|
| 192 | 11000000 |

| 168 | 10101000 |
|-----|----------|
| 5 | 00000101 |
| 240 | 11110000 |
| 256 | 10000000 |

Task 3: Converting hexadecimal numbers to binary and decimal

Why do we need the hexadecimal numbering system? Well, one reason is that the MAC addresses are represented in this format. In this task, you are asked to convert some MAC addresses into binary and decimal numbers. Please fill in the table respectively.

<u>Note</u>: When converting the HEX numbers from the table below to Decimal, do this in groups and not the whole number. As an example, for the first address, first take the HEX **10** and convert it to decimal, then take **1F** and convert it to decimal, etc. This is so because otherwise, if you convert the whole HEX number to Decimal, you will need to work with very large numbers.

| Hexadecimal (MAC Address) | Binary | Decimal |
|---------------------------|--|----------------------------|
| 10-1F-74-E2-2D-12 | 00010000-00011111-0 1110100-11100010-00 101101-00010010 | 16-31-116-226-45-18 |
| B0-05-94-F4-A8-0D | 10110000-00000101-1 0010100-11110100-10 101000-0000-1101 | 176-5-148-244-168-13 |
| 70-18-8B-C6-86-DC | 01110000-00011000-1 0001011-11000110-10 000110-11011100 | 112-24-139-198-134-2 20 |
| 00-1F-3B-99-34-7D | 00000000-00011111-0 0111011-10011001-00 110100-01111101 | 0-31-59-153-52-125 |

| E8-11-32-4E-07-DB | 11101000-00010001-0 | 232-17-50-78-7-219 |
|-------------------|---------------------|--------------------|
| | 0110010-01001110-00 | |
| | 000111-11011011 | |

Who is the vendor of the network adapter that has the first in the table MAC address (10-1F-74-E2-2D-12)? How do you know it?

Exercise 2: IP Addresses and Masks

Given some IP networks and subnet masks, determine:

- The network address
- The broadcast address
- The first usable host address
- The last usable host address


| IP Network and Mask | Network Address | Broadcast Address | First host Address | Last Host Address |
|------------------------|--------------------|----------------------|-----------------------|----------------------|
| 192.168.1.0/24 | 192.168.1.0 | 192.168.1.255 | 192.168.1.1 | 192.168.1.254 |
| 192.168.0.0/24 | 192.168.0.0 | 192.168.0.255 | 192.168.0.1 | 192.168.0.254 |
| 10.0.0.0/23 | 10.0.0.0 | 10.0.1.255 | 10.0.0.1 | 10.0.1.254 |
| 15.137.14.128/2 5 | 15.137.14.12 8 | 15.137.14.255 | 15.137.14.12 9 | 15.137.14.254 |
| 213.0.0.0/8 | 213.0.0.0 | 213.255.255.25 | 213.0.0.1 | 213.255.255.25 4 |

Exercise 3: Explore the traffic flow and the message exchange between two directly connected hosts


In this exercise, you are going to connect two PCs directly to each other with a cable (without using any networking device between them). You will setup IP addresses on their NICs (Network Interface Cards) from the **10.0.0.0/24** IP network in order to be able to ping between them. As you already know, **ping** is Layer 3 protocol, which uses ICMP echo requests, and ICMP echo replies to check the IP connectivity between two hosts. You will closely monitor the network packet flow between the devices.

Note: In the following exercises, you will be asked to change the topology or part of it (for example change the Hub with a Switch). If this leads to unexpected behavior (like generating multiple ARP packets, or missing ARP), please create a brand-new topology for each exercise (delete all the devices and add them again) – this should be very fast process.


- 1. Open <u>Cisco Packet Tracer</u>. Move two end devices to the topology (select "PC" type) and connect them directly. For the connection, you can use either the automatic connection or the crossover cable.
 - Why crossover should be used? Because it connects devices from the same type (in this case, pc-to-pc)




2. Click on the first pc (PC0), go to the config tab and select <u>FastEthernet0</u> to setup an IP address. This will be the first address in the selected network: **10.0.0.1/24** (as you know, /24 is another representation of 255.255.255.0)




3. Use the same steps to setup the second IP address, **10.0.0.2/24**, on the second pc (PC1)



4. Back in PCO, go to the <u>Desktop</u> tab and the open a <u>Command Prompt</u> (We will sometimes refer to it as CLI – Command Line Interface)



5. Since this is the beginning of our tests, PCO should have empty ARP table. Make sure this is true by typing **arp -a** in the CLI



6. Check that you have the correct IP address and subnet mask on PC0 (10.0.0.1, 255.255.255.0) with the **ipconfig** command. Make sure that you do not have a default gateway in the configuration.


Why a default gateway is not needed? In this exercise (and all other exercises below in Lab 2), you have connections that do not require routing. Instead, you connect devices, which belong to the same IP subnet – that is why there is no need for default gateway in these scenarios

```
PC0
Physical Config Desktop Attributes Software/Services
 Command Prompt
                                                      Χ
 Packet Tracer PC Command Line 1.0
 C:\>arp -a
 No ARP Entries Found
 C:\>
 C:\>arp -a
 No ARP Entries Found
 C:\>ipconfig
 FastEthernet0 Connection:(default port)
    Link-local IPv6 Address....:
 FE80::260:47FF:FE65:29A5
    IP Address.....: 10.0.0.1
Subnet Mask.....: 255.255.255.0
    C:\>
□ Тор
```


7. Open the second pc (PC1), go to the Desktop tab -> Command Prompt and check that you have the correct IP address and subnet mask (10.0.0.2, 255.255.255.0) with the **ipconfig** command

```
PC1
                                                    Physical Config Desktop Attributes Software/Services
 Command Prompt
                                                       X
 Packet Tracer PC Command Line 1.0
 C:\>ipconfig
 FastEthernet0 Connection:(default port)
    Link-local IPv6 Address....:
 FE80::20A:F3FF:FE0D:E190
                                     10.0.0.2
    IP Address.....
    Subnet Mask.....
                                   .: 255.255.255.0
    Default Gateway.....
                                     0.0.0.0
 C:\>
□ Тор
```

8. In the lower-right corner of Packet Tracer, click the icon to change to Simulation Mode (or press Shift + S). Now you can monitor each step in the communication and the packet exchange process. Before this, make sure that you do not monitor all the events since this can be distractive. For the purposes of this Lab, you will monitor ICMP (ping) and ARP packets. Click on Show All/None to deselect all the events and then click Edit Filters




9. In the Edit Filters window, make sure to select only ARP and ICMP under the IPv4 section. All other protocols in this and the other sections (IPv6 and Misc) should be un-checked




10. Open again the command prompt of PCO and start ping to 10.0.0.2 (PC1). Note that since you are in Simulation Mode, you will not see any results from this command at the moment. Just type **ping 10.0.0.2** and hit **Enter**

```
PC0
                                                  Physical Config Desktop Attributes Software/Services
Command Prompt
                                                     Х
 Packet Tracer PC Command Line 1.0
 C:\>arp -a
 No ARP Entries Found
 C:\>
 C:\>arp -a
 No ARP Entries Found
 C:\>ipconfig
 FastEthernet0 Connection:(default port)
    Link-local IPv6 Address....:
 FE80::260:47FF:FE65:29A5
    IP Address..... 10.0.0.1
    Subnet Mask..... 255.255.255.0
    Default Gateway..... 0.0.0.0
 C:\>ping 10.0.0.2
____ Тор
```


11.To start the packet exchange process, click on <u>Capture / Forward</u> button in the Simulation Panel. Note the two packets that PCO is generating – ARP request and ICMP echo request. Continue to click on the <u>Capture / Forward</u> button to see each step of the packets



12. You can click on a packet to open more details about it, read additional information or take a quick test in the Challenge me section



13.Check your <u>Event List</u> – you should have an ARP packet exchange at the beginning and then, when PCO knows the MAC address of PC1, all the other packets are ICMP




14.Go back to the command prompt of PCO and check that ping succeeded - all the four ICMP packets should have been sent and received successfully

```
PC0
                                                   X
 Physical Config
          Desktop
               Attributes
                     Software/Services
 Command Prompt
                                                      Χ
    Link-local IPv6 Address....:
 FE80::260:47FF:FE65:29A5
    IP Address..... 10.0.0.1
    Subnet Mask..... 255.255.255.0
    Default Gateway..... 0.0.0.0
 C: \ping 10.0.0.2
 Pinging 10.0.0.2 with 32 bytes of data:
 Reply from 10.0.0.2: bytes=32 time=4ms TTL=128
 Reply from 10.0.0.2: bytes=32 time=2ms TTL=128
 Reply from 10.0.0.2: bytes=32 time=2ms TTL=128
 Reply from 10.0.0.2: bytes=32 time=2ms TTL=128
 Ping statistics for 10.0.0.2:
     Packets: Sent = 4, Received = 4, Lost = 0 (0%
 loss),
 Approximate round trip times in milli-seconds:
     Minimum = 2ms, Maximum = 4ms, Average = 2ms
 C:\>
Тор
```

15. Check the ARP table of PCO by typing **arp -a**. Now you can see an entry which shows the MAC address of PC1 (remember that before the ping, this table was empty)

```
Attributes
                       Software/Services
                                                           Χ
 Command Prompt
 Pinging 10.0.0.2 with 32 bytes of data:
 Reply from 10.0.0.2: bytes=32 time=4ms TTL=128
 Reply from 10.0.0.2: bytes=32 time=2ms TTL=128
 Reply from 10.0.0.2: bytes=32 time=2ms TTL=128
 Reply from 10.0.0.2: bytes=32 time=2ms TTL=128
 Ping statistics for 10.0.0.2:
     Packets: Sent = 4, Received = 4, Lost = 0 (0%
 loss),
 Approximate round trip times in milli-seconds:
     Minimum = 2ms, Maximum = 4ms, Average = 2ms
 C:\>
 C:\>
 C:\>arp -a
   Internet Address
                          Physical Address
                                                  Type
   10.0.0.2
                          000c.cf97.0e18
                                                  dynamic
 C:\>
 C:\>
Тор
```


16.Click on <u>Realtime</u> to reset the clear the simulation mode (you will go back to in in the next exercises)




Exercise 4: Explore the traffic flow and the message exchange between hosts connected with a Hub

In this exercise, you will use network Hub to establish connection between the networking devices. You will observe the Hub behavior by monitoring the ICMP packet exchange. A Hub is a Layer 1 device, which simply retransmits each received packet to all other ports.


1. Delete the connection between the end devices, drag a Hub (Use PT-Hub, the first one) in the topology, drag one more generic end device (PC2) and connect them as shown in the screenshot (again, as noted before, you can start a new topology from zero – sometimes it can eliminate errors)



2. Open the configuration of PC2 and setup static IP address in the same IP network – 10.0.0.3/24





3. Initiate ping to 10.0.0.2 (PC1) from the command line of PC0 and while clicking the <u>Capture / Forward</u> button, observe the packet exchange between the two hosts



<u>Note</u>: PCO now has the MAC address of the destination, PC1, in its ARP table. You can (optionally) clear the ARP table of PCO by typing **arp -d** in the command line if you want to see the ARP message exchange again. In either case, the Hub will broadcast each message (either ARP or ICMP) to all ports except the port on which the packet is received.

4. For example, have a look at the ICMP echo reply packet (this is the ping response) from PC1 – it goes to both PC0 and PC2






5. Reset the simulation to prepare for the next exercise

Exercise 5: Explore the traffic flow and the message exchange between hosts connected with a Switch

In this exercise, you will observe the ICMP and ARP message exchange when we have our hosts connected with a Switch. As you know, a Switch is a Layer 2 device, which is more intelligent than a Hub. One reason is that it has a MAC address table. This table keeps records about the switch ports and the connected to them MAC addresses. This way, the forwarding decisions are more efficient and secure (instead of sending the packet out of each single port like the Hubs do). Again, you will use the 10.0.0.0/24 IP network with three end devices belonging to it (we still do not have routing here).


1. Delete the Hub and move a Switch to the topology (use 2960 as a Switch model). Connect the end devices to it as per the picture below




2. Consult the help about the Windows ARP command by typing **arp /?** and clear the ARP table of PCO by typing **arp -d**. Then, check that it is deleted, and no entries exist by typing **arp -a**

```
PC0
 Physical Config
            Desktop
                Attributes
                         Software/Services
 Command Prompt
                                                              Х
 C:\>
 C:\arp -d
 C:\>arp /?
 Packet Tracer PC ARP
 Display ARP entries: arp -a
 Clear ARP table: arp -d
 C:\>arp -d
 C:\>arp -a
 No ARP Entries Found
Тор
```


3. Login to the CLI of your Switch and type **show mac address-table** to see that no entries exist before a communication is initiated. Sometimes, it may happen that you see entries in the MAC address table and this can happen because some of the hosts initiate [hidden] messages in the background and because of this the switch learns the connected MAC addresses. If this is the case, you can clear the table with the **clear mac address-table** command (from the privileged access mode)



4. Initiate ping 10.0.0.2 (this is PC1) from PC0. By clicking the <u>Capture / Forward</u> button, monitor the packet exchange. Observe that the ARP request will reach ALL connected devices (PC1 and PC2) although the client computers are connected through a Switch. This is so because the ARP destination is a Layer 2 broadcast address and in this particular situation, the switch will act like a Hub. Observe that after the initial ARP message exchange, all other ICMP packets are unicast (because the source now knows the destination MAC address) and also the switch will forward each subsequent packet to a single port – the one which is connected to the corresponding MAC address. This is because the MAC address table is built dynamically



5. Connect to the switch and type again **show mac address-table**. Observe the new entries in the MAC address table



You have completed LAB 2.