Regression with Two Independent Variables

Objectives

Write a raw score regression equation with 2 ivs in it.

What is the difference in interpretation of b weights in simple regression vs. multiple regression?

Describe R-square in two different ways, that is, using two distinct formulas. Explain the formulas.

What happens to b weights if we add new variables to the regression equation that are highly correlated with ones already in the equation?

Why do we report beta weights (standardized b weights)?

Write a regression equation with beta weights in it.

What are the three factors that influence the standard error of the b weight?

How is it possible to have a significant R-square and non-significant b weights?

Materials

The Regression Line

With one independent variable, we may write the regression equation as:

$$Y = a + bX + e$$

Where Y is an observed score on the dependent variable, a is the intercept, b is the slope, X is the observed score on the independent variable, and e is an error or residual.

We can extend this to any number of independent variables:

$$Y = a + b_1 X_1 + b_2 X_2 + ... + b_k X_k + e_{(3.1)}$$

Note that we have *k* independent variables and a slope for each. We still have one error and one intercept. Again we want to choose the estimates of *a* and *b* so as to minimize the sum of squared errors of prediction. The prediction equation is:

$$Y' = a + b_1 X_1 + b_2 X_2 + ... + b_k X_k$$
(3.2)

Finding the values of b is tricky for k>2 independent variables, and will be developed after some matrix algebra. It's simpler for k=2 IVs, which we will discuss here.

For the one variable case, the calculation of b and a was:

$$b = \frac{\sum xy}{\sum x^2}$$

$$a = \overline{Y} - b\overline{X}$$

For the two variable case:

$$b_1 = \frac{(\sum x_2^2)(\sum x_1 y) - (\sum x_1 x_2)(\sum x_2 y)}{(\sum x_1^2)(\sum x_2^2) - (\sum x_1 x_2)^2}$$

and

$$b_2 = \frac{(\sum x_1^2)(\sum x_2 y) - (\sum x_1 x_2)(\sum x_1 y)}{(\sum x_1^2)(\sum x_2^2) - (\sum x_1 x_2)^2}$$

At this point, you should notice that all the terms from the one variable case appear in the two variable case. In the two variable case, the other X variable also appears in the equation. For example, X_2 appears in the equation for b_1 . Note that terms corresponding to the variance of both X variables occur in the slopes. Also note that a term corresponding to the covariance of X1 and X2 (sum of deviation cross-products) also appears in the formula for the slope.

The equation for *a* with two independent variables is:

$$a = \overline{Y} - b_1 \overline{X}_1 - b_2 \overline{X}_2$$

This equation is a straight-forward generalization of the case for one independent variable.

A Numerical Example

Suppose we want to predict job performance of Chevy mechanics based on mechanical aptitude test scores and test scores from personality test that measures conscientiousness.

Job Perf Med Apt	h Consc					
------------------------	---------	--	--	--	--	--

Y	X1	X2	X1*Y	X2*Y	X1*X2	
1	40	25	40	25	1000	
2	45	20	90	40	900	
1	38	30	38	30	1140	
3	50	30	150	90	1500	
2	48	28	96	56	1344	
3	55	30	165	90	1650	
3	53	34	159	102	1802	
4	55	36	220	144	1980	
4	58	32	232	128	1856	
3	40	34	120	102	1360	
5	55	38	275	190	2090	
3	48	28	144	84	1344	

3	45	30	135	90	1350	
2	55	36	110	72	1980	
4	60	34	240	136	2040	
5	60	38	300	190	2280	
5	60	42	300	210	2520	
5	65	38	325	190	2470	
4	50	34	200	136	1700	
3	58	38	174	114	2204	
Y	X1	X2	X1*Y	X2*Y	X1*X2	
65	1038	655	3513	2219	34510	Sum
20	20	20	20	20	20	N
3.25	51.9	32.75	175.65	110.95	1725.5	M
1.25	7.58	5.24	84.33	54.73	474.60	SD

00.75	4004.0	F04 7F		1100
29.75	1091.8	521.75		088

$$\sum x_{1}y = \sum X_{1}Y - \frac{(\sum X_{1})(\sum Y)}{N}$$

$$\sum x_{2}y = \sum X_{2}Y - \frac{(\sum X_{2})(\sum Y)}{N}$$

$$\sum x_{1}x_{2} = \sum X_{1}X_{2} - \frac{(\sum X_{1})(\sum X_{2})}{N}$$

We can collect the data into a matrix like this:

	у	X ₁	X ₂
Υ	29.75	139.5	90.25
X ₁	0.77	1091.8	515.5

X_2	0.72	0.68	521.75

The numbers in the table above correspond to the following sums of squares, cross products, and correlations:

	у	x1	X ₂
Υ	$\sum y^2$	$\sum x_1 y$	$\sum x_2 y$
X ₁	r_{yx1}	$\sum x_1^2$	$\sum x_1x_2$
X ₂	r_{yx2}	r_{x1x2}	$\sum x_2^2$

We can now compute the regression coefficients:

$$b_{1} = \frac{(\sum x_{2}^{2})(\sum x_{1}y) - (\sum x_{1}x_{2})(\sum x_{2}y)}{(\sum x_{1}^{2})(\sum x_{2}^{2}) - (\sum x_{1}x_{2})^{2}}$$

$$b_1 = \frac{(521.75)(139.5) - (515.5)(90.25)}{(1091.8)(521.75) - (515.5)(515.5)}$$

$$b_1 = \frac{(72784.13) - (46523.88)}{(569646.7) - (265740.3)}$$

$$b_1 = \frac{26260.25}{303906.4} = .086409 = .09$$

9 of 36

$$b_2 = \frac{(\sum x_1^2)(\sum x_2 y) - (\sum x_1 x_2)(\sum x_1 y)}{(\sum x_1^2)(\sum x_2^2) - (\sum x_1 x_2)^2}$$

$$b_2 = \frac{(1091.8)(90.25) - (515.5)(139.5)}{(1091.8)(521.75) - (515.5)(515.5)}$$

$$b_2 = \frac{26622.7}{303906.4} = .087602 = .09$$

To find the intercept, we have:

$$a = \overline{Y} - b_1 \overline{X}_1 - b_2 \overline{X}_2$$

$$a = 3.25 - .086409(51.9) - .087602(32.75) = -4.10$$

Therefore, our regression equation is:


$$Y = -4.10 + .09X1 + .09X2$$
 or

Job Perf' = -4.10 +.09MechApt +.09Coscientiousness.


Visual Representations of the Regression

We have 3 variables, so we have 3 scatterplots that show their relations.


Scatterplot



Scatterplot




Scatterplot




Because we have computed the regression equation, we can also view a plot of Y' vs. Y, or actual vs. predicted Y.

Scatterplot of Predicted vs. Actual Values



We can (sort of) view the plot in 3D space, where the two predictors are the X and Y axes, and the Z axis is the criterion, thus:

3D Plot of Regression



This graph doesn't show it very well, but the regression problem can be thought of as a sort of response surface problem. What is the expected height (Z) at each value of X and Y? The linear regression solution to this problem in this dimensionality is a plane.

R-square (R²)

Just as in simple regression, the dependent variable is thought of as a linear part and an error. In multiple regression, the linear part has more than one X variable associated with it. When we do multiple regression, we can compute the

proportion of variance due to regression. This proportion is called R-square. We use a capital R to show that it's a multiple R instead of a single variable r. We can also compute the correlation between Y and Y' and square that. If we do, we will also find R-square.

Y	X1	X2	Y'	Resid
2	45	20	1.54	0.46
1	38	30	1.81	-0.81
3	50	30	2.84	0.16
2	48	28	2.50	-0.50
3	55	30	3.28	-0.28
3	53	34	3.45	-0.45
4	55	36	3.80	0.20
4	58	32	3.71	0.29
3	40	34	2.33	0.67
5	55	38	3.98	1.02

48	28	2.50	0.50
45	30	2.41	0.59
55	36	3.80	-1.80
60	34	4.06	-0.06
60	38	4.41	0.59
60	42	4.76	0.24
65	38	4.84	0.16
50	34	3.19	0.80
		4.24	-1.24
51.9	32.75	3.25	0
57.46	27.46	1.05	0.52
		19.95	9.88
	45 55 60 60 65 50 58	45 30 55 36 60 34 60 42 65 38 50 34 58 38 51.9 32.75	45 30 2.41 55 36 3.80 60 34 4.06 60 38 4.41 60 42 4.76 65 38 4.84 50 34 3.19 58 38 4.24 51.9 32.75 3.25 57.46 27.46 1.05

The mean of Y is 3.25 and so is the mean of Y'. The mean of the residuals is 0. The variance of Y is 1.57. The variance of Y' is 1.05, and the variance of the residuals is .52. Together, the variance of regression (Y') and the variance of error (e) add up to the variance of Y (1.57 = 1.05 + .52). R-square is 1.05/1.57 or .67. If we compute the correlation between Y and Y' we find that R=.82, which when squared is also an R-square of .67. (Recall the scatterplot of Y and Y'). R-square is the proportion of variance in Y due to the multiple regression.

Testing the Significance of R²

You have already seen this once, but here it is again in a new context:

$$F = \frac{R^2 / k}{(1 - R^2) / (N - k - 1)}$$

which is distributed as F with k and (N-k-1) degrees of freedom when the null is true. Now R^2 is for the multiple correlation rather than the simple correlation that we saw last time. For our most recent example, we have 2 independent variables, an R^2 of .67, and 20 people, so

$$F_{(2,17)} = \frac{.67/2}{(1-.67)/(20-2-1)} = \frac{.335}{.33/17} = 17.23$$

p < .01. (F_{crit} for p < .01 is about 6).

Because SStot=SSreg+SSres, we can compute an equivalent F using sums of squares and associated df.


$$F = \frac{SS_{reg} / df_{reg}}{SS_{res} / df_{res}} = \frac{19.95 / 2}{9.88 / 17} = \frac{9.975}{.5811} = 17.17$$

which agrees with our earlier result within rounding error.

Relative Importance of the Independent Variables

In simple regression, we have one IV that accounts for a proportion of variance in Y. The influence of this variable (how important it is in predicting or explaining Y) is described by r^2 . If r^2 is 1.0, we know that the DV can be predicted perfectly from the IV; all of the variance in the DV is accounted for. If the r^2 is 0, we know that there is no linear association; the IV is not important in predicting or explaining Y. With 2 or more IVs, we also get a total R^2 . This R^2 tells us how much variance in Y is accounted for by the set of IVs, that is, the importance of the linear combination of IVs ($b_1X_1+b_2X_2+...+b_kX_k$). Often we would like to know the importance of each of the IVs in predicting or explaining Y. In our example, we know that mechanical aptitude and conscientiousness together predict about 2/3 of the variance in job performance ratings. But how important are mech apt and consc in relation to each other? Correlation and regression provide answers to this question. Unfortunately, the answers do not always agree. It is important to understand why they sometimes agree and sometimes disagree. You must understand this potential disagreement to make appropriate interpretations of regression weights.

I am going to introduce Venn diagrams first to describe what happens. You should know that **Venn diagrams are not an accurate representation of how regression actually works. Venn diagrams can mislead you in your reasoning**. However, most people find them much easier to grasp than the related equations, so here goes. We are going to predict Y from 2 independent variables, X1 and X2. Let's suppose that both X1 and X2 are correlated with Y, but X1 and X2 are not correlated with each other. Our diagram might look like Figure 5.1:



In Figure 5.1, we have three circles, one for each variable. Each circle represents the variance of the variable. The size of the (squared) correlation between two variables is indicated by the overlap in circles. Recall that the squared correlation is the proportion of shared variance between two variables. In Figure 5.1, X_1 and X_2 are not correlated. This is indicated by the lack of overlap in the two variables. We can compute the correlation between each X variable and Y. These correlations and their squares will indicate the relative importance of the independent variables. Figure 5.1 might correspond to a correlation matrix like this:

R	Y	X_1	X_2
Y	1		
X_1	.50	1	


X_2	.60	.00	1
-------	-----	-----	---

In the case that X_1 and X_2 are uncorrelated, we can estimate the shared variance between the two X variables and Y by summing the squared correlations. In our example, the shared variance would be $.50^2 + .60^2 = .25 + .36 = .61$. This turns out to be 61 percent shared variance, and if we calculated a regression equation, we would find that R^2 was .61 (The calculations will be more fully developed later. For now, concentrate on the figures.) If X_1 and X_2 are uncorrelated, then they don't share any variance with each other. If they do share variance with Y, then whatever variance is shared with Y is must be unique to that X because the X variables don't overlap.

On the other hand, it is usually the case that the X variables are correlated and do share some variance, as shown in Figure 5.2, where X_1 and X_2 overlap somewhat. Note that X_1 and X_2 overlap both with each other and with Y. There is a section where X_1 and X_2 overlap with each other but not with Y (labeled 'shared X' in Figure 5.2). There are sections where each overlaps with Y but not with the other X (labeled 'UY:X1' and 'UY:X2'). The portion on the left is the part of Y that is accounted for uniquely by X_1 (UY:X1). The similar portion on the right is the part of Y accounted for uniquely by X_2 (UY:X2). The last overlapping part shows that part of Y that is accounted for by both of the Y variables ('shared Y').

Just as in Figure 5.1, we could compute the correlations between each X and Y. For X_1 , the correlation would include the areas UY:X1 and shared Y. For X_2 , the correlation would contain UY:X2 and shared Y. Note that shared Y would be counted twice, once for each X variable. We could also compute a regression equation and then compute R^2 based on that equation. If we did, we would find that R^2 corresponds to UY:X1 plus UY:X2 plus shared Y. Note that R^2 due to regression of Y on both X variables at once will give us the proper variance accounted for, with shared

Y only being counted once. Now we want to assign or divide up R^2 to the appropriate X variables in accordance with their importance. We can do this a couple of ways. Any way we do this, we will assign the unique part of Y to the appropriate X (UY:X1 goes to X1, UY:X2 goes to X2). But what to do with shared Y? The most common solution to this problem is to ignore it. If we assign regression sums of squares according the magnitudes of the *b* weights, we will be assigning sums of squares to the unique portions only. The shared portion will assigned to the overall R^2 , but not to any of the variables that share it. (There are other ways that divvy up the shared part. We'll visit them later.). In multiple regression, we are typically interested in predicting or explaining all the variance in Y. To do this, we need independent variables that are correlated with Y, but not with X. It's hard to find such variables, however. It is more typical to find new X variables that are correlated with old X variables and shared Y instead of unique Y. The desired vs. typical state of affairs in multiple regression can be illustrated with another Venn diagram:



Notice that in Figure 5.3, the desired state of affairs, each X variable is minimally correlated with the other X variables, but is substantially correlated with Y. In such a case, R^2 will be large, and the influence of each X will be unambiguous. The typical state of affairs is shown in Figure 5.4. Note how variable X_3 is substantially correlated with Y, but also with X_1 and X_2 . This means that X_3 contributes nothing new or unique to the prediction of Y. It also

muddies the interpretation of the importance of the X variables as it is difficult to assign shared variance in Y to any X.

Standardized & Unstandardized Weights (b vs. b)

Each X variable will have associated with it one slope or regression weight. Each weight is interpreted to mean the unit change in Y given a unit change in X, so the slope can tell us something about the importance of the X variables. (Strictly speaking, the statement about the interpretation slope isn't true without mentioning the other X variables. But it's close enough untill we get to partial correlations). Variables with large b weights ought to tell us that they are more important because Y changes more rapidly for some of them than for others. The problem with unstandardized or raw score b weights in this regard is that they have different units of measurement, and thus different standard deviations and different meanings. If we measured X = height in feet rather than X = height in inches, the b weight for feet would be 12 times larger than the b for inches (12 inches in a foot; in both cases we interpret b as the unit change in Y when X changes 1 unit). So when we measure different X variables in different units, part of the size of b is attributable to units rather than importance per se. So what we can do is to standardize all the variables (both X and Y, each X in turn). If we do that, then the importance of the X variables will be readily apparent by the size of the b weights -- all will be interpreted as the number of standard deviations that Y changes when each X changes 1 standard deviation. The standardized slopes are called beta (b) weights. This is an extremely poor choice of symbols, because we have already used b to mean the population value of b (don't blame me; this is part of the literature). From here out, b will refer to standardized b weights, that is, to estimates of parameters, unless otherwise noted.

Regression Equations with b weights

Because we are using standardized scores, we are back into the z-score situation. As you recall from the comparison of correlation and regression:

$$z_y' = r_{xy} z_x$$

But b means a b weight when X and Y are in standard scores, so for the simple regression case, r = b, and we have:

$$z_y' = \beta z_x$$

The earlier formulas I gave for b were composed of sums of square and cross products ($\sum x^2, \sum xy, \sum x_1x_2$). But with z scores, we will be dealing with standardized sums of squares and cross products. A standardized averaged sum of squares is 1 ($\sum x^2 / NS_xS_x$) and a standardized averaged sum of cross products is a correlation

coefficient ($\sum xy/NS_xS_y$). Bottom line on this is we can estimate beta weights (b s) using a correlation matrix. With simple regression, as you have already seen, r=b. With two independent variables,

$$\beta_1 = \frac{r_{y1} - r_{y2} r_{12}}{1 - r_{12}^2}$$

and

$$\beta_2 = \frac{r_{y2} - r_{y1}r_{12}}{1 - r_{12}^2}$$

where r_{y1} is the correlation of y with X1, r_{y2} is the correlation of y with X2, and r_{12} is the correlation of X1 with X2. Note that the two formulas are nearly identical, the exception is the ordering of the first two symbols in the numerator.

Our correlation matrix looks like this:

	Y	X_1	X_2
Y	1		
X_1	0.77	1	
X_2	0.72	0.68	1

$$\beta_1 = \frac{.77 - (.72)(.68)}{1 - .68^2} = .521577$$

$$\beta_2 = \frac{.72 - (.77)(.68)}{1 - .68^2} = .365327$$

Note that there is a surprisingly large difference in beta weights given the magnitude of correlations.

Let's look at this for a minute, first at the equation for b_1 . The numerator says that b_1 is the correlation (of X_1 and Y) minus the correlation (of X_2 and Y) times the correlation (of X_1 and X_2). The denominator says boost the numerator a bit depending on the size of the correlation between X_1 and X_2 . Suppose r_{12} is zero. Then $r_{y2}r_{12}$ is zero, and the numerator is r_{y1} . The denominator is 1, so the result is r_{y1} , the simple correlation between X_1 and Y_2 . If the correlation between Y_1 and Y_2 is zero, the beta weight is the simple correlation. On the other hand, if the correlation between Y_1 and Y_2 is 1.0, the beta is undefined, because we would be dividing by zero. So our life is less complicated if the correlation between the Y_1 variables is zero. Suppose that Y_1 is somewhere between 0 and 1. Then we will be in the situation depicted in Figure 5.2, where all three circles overlap. The beta weight for Y_1 (b 1) will be essentially that part of the picture labeled Y_1 . We start with Y_2 , which has both Y_1 and shared Y_2 in it. (When Y_1 is zero, we stop here, because we don't have to worry about the shared part). We subtract Y_2 times Y_1 , which means subtracting only that pat of Y_2 that corresponds to the shared part of Y_2 . But the shared part of Y_3 contains both shared Y_1 with Y_2 we will take out too much. To correct for this, we divide by Y_1 to boost Y_2 back up to where it should be.

Calculating R²

As I already mentioned, one way to compute R^2 is to compute the correlation between Y and Y', and square that. There are some other ways to calculate R^2 , however, and these are important for a conceptual understanding of what is happening in multiple regression. If the independent variables are uncorrelated, then

$$R^2 = r_{v1}^2 + r_{v2}^2$$
 (only if $r_{12} = 0$)

This says that R², the proportion of variance in the dependent variable accounted for by both the independent variables, is equal to the sum of the squared correlations of the independent variables with Y. This is only true when the IVs are orthogonal.

[Review Venn diagrams, Figure 5.1.]

In our example, R^2 is .67. The correlations are r_{y1} =.77 and r_{y2} = .72. If we square and add, we get .77²+.72² = .5929+.5184 = 1.11, which is clearly too large a value for R^2 .

If the IVs are correlated, then we have some shared X and possibly shared Y as well, and we have to take that into account. Two general formulas can be used to calculate R² when the IVs are correlated.

$$R^2 = \beta_1 r_{v1} + \beta_2 r_{v2}$$

This says to multiply the standardized slope (beta weight) by the correlation for each independent variable and add to calculate R^2 . What this does is to include both the correlation, (which will overestimate the total R^2 because of shared Y) and the beta weight (which underestimates R^2 because it only includes the unique Y and discounts the shared Y). Appropriately combined, they yield the correct R^2 . Note that when r_{12} is zero, then $b_1 = r_{y1}$ and $b_2 = r_{y2}$, so that $(b_1)(r_{y1}) = r^2_{y1}$ and we have the earlier formula where R^2 is the sum of the squared correlations between the Xs and Y. For our example, the relevant numbers are (.52).77+(.37).72 = .40+.27 = .67, which agrees with our earlier value of R^2 .

A second formula using only correlation coefficients is

$$R^{2} = \frac{r_{y1}^{2} + r_{y2}^{2} - 2r_{y1}r_{y2}r_{12}}{1 - r_{12}^{2}}$$

This formula says that R^2 is the sum of the squared correlations between the Xs and Y adjusted for the shared X and shared Y. Note that the term on the right in the numerator and the variable in the denominator both contain r_{12} , which is the correlation between X1 and X2. Note that this equation also simplifies the simple sum of the squared correlations when $r_{12} = 0$, that is, when the IVs are orthogonal. For our example, we have

$$R^2 = \frac{.77^2 + .72^2 - 2(.77)(.72)(.68)}{1 - .68^2}$$

$$R^2 = \frac{.5929 + .5184 - .753984}{.5376} = .66$$

which is the same as our earlier value within rounding error.

Tests of Regression Coefficients

Each regression coefficient is a slope estimate. With more than one independent variable, the slopes refer to the expected change in Y when X changes 1 unit, CONTROLLING FOR THE OTHER X VARIABLES. That is, b_1 is the change in Y given a unit change in X_1 while holding X_2 constant, and b_2 is the change in Y given a unit change in X_2 while holding X_1 constant. We will develop this more formally after we introduce partial correlation.

For now, consider Figure 5.2 and what happens if we hold one X constant. The amount change in Y due to X_1 while holding X_2 constant is a function of the unique contribution of X_1 . If X_1 overlaps considerably with X_2 , then the change in Y due to X_1 while holding the X_2 constant will be small.

The standard error of the b weight for the two variable problem:

$$S_{b_1} = \sqrt{\frac{S_{y.12}^2}{\sum x_1^2 (1 - r_{12}^2)}}$$

$$s_{b_2} = \sqrt{\frac{s_{y.12}^2}{\sum x_2^2 (1 - r_{12}^2)}}$$

where $s^2_{y,12}$ is the variance of estimate (the variance of the residuals). We use the standard error of the b weight in testing t for significance. (Is the regression weight zero in the population? Is the regression weight equal to some other value in the population?) The standard error of the b weight depends upon three things. The variance of estimate tells us about how far the points fall from the regression line (the average squared distance). Large errors in prediction mean a larger standard error. The sum of squares of the IV also matter. The larger the sum of squares (variance) of X, the smaller the standard error. Restriction of range not only reduces the size of the correlation, but also increases the standard error of the b weight. The correlation between the independent variables also matters. The larger the correlation, the larger the standard error of the b weight. So to find significant b weights, we want to minimize the correlation between the predictors, maximize the variance of the predictors, and minimize the errors of prediction.

The variance of prediction is

$$s_{y.12}^2 = \frac{ss_{res}}{N - k - 1}$$

and the test of the *b* weight is a *t*-test with *N-k*-1 degrees of freedom.

In our example, the sum of squared errors is 9.79, and the df are 20-2-1 or 17. Therefore, our variance of estimate is .575871 or .58 after rounding. Our standard errors are:

$$S_{b_1} = \sqrt{\frac{S_{y.12}^2}{\sum x_1^2 (1 - r_{12}^2)}}$$

$$s_{b_1} = \sqrt{\frac{.57587}{1091.8(1-.68^2)}} = \sqrt{\frac{.57587}{1091.8(.5376)}} = .0313$$

and $S_{b2} = .0455$, which follows from calculations that are identical except for the value of the sum of squares for X_2 instead of X_1 .

To test the b weights for significance, we compute a t statistic

$$t_{b_1} = \frac{b_1}{S_{b_1}}$$

in our case t = .0864/.0313 or 2.75. If we compare this to the t distribution with 17 df, we find that it is significant (from a lookup function, we find that p = .0137, which is less than .05).

For b_2 , we compute t = .0876/.0455 = 1.926, which has a p value of .0710, which is not significant. Note that the correlation r_{y2} is .72, which is highly significant (p < .01) but b_2 is not significant.

Tests of \mathbb{R}^2 vs. Tests of b

Because the b-weights are slopes for the unique parts of Y and because correlations among the independent variables increase the standard errors of the b weights, it is possible to have a large, significant R^2 , but at the same time to have nonsignificant b weights (as in our example). Consider Figure 5.4, where there are many IVs accounting for essentially the same variance in Y. Although R^2 will be fairly large, when we hold the other X variables constant to test for b, there will be little change in Y for a given X, and it will be difficult to find a significant b weight. It is also possible to find a significant b weight without a significant R^2 . This can happen when we have lots of independent variables (usually more than 2), all or most of which have rather low correlations with Y. If one of these variables has a large correlation with Y, R^2 may not be significant because with such a large number of IVs we would expect to see as large an R^2 just by chance. If R^2 is not significant, you should usually avoid interpreting b weights that are significant. In such cases, it is likely that the significant b weight is a type I error.

Testing Incremental R²

We can test the change in R^2 that occurs when we add a new variable to a regression equation. We can start with 1 variable and compute an R^2 (or r^2) for that variable. We can then add a second variable and compute R^2 with both variables in it. The second R^2 will always be equal to or greater than the first R^2 . If it is greater, we can ask whether it is significantly greater. To do so, we compute

$$F = \frac{(R_L^2 - R_S^2)/(k_L - k_S)}{(1 - R_L^2)/(N - K_L - 1)}$$

where R^2_L is the larger R^2 (with more predictors), k_L is the number of predictors in the larger equation and k_S is the number of predictors in the smaller equation. When the null is true, the result is distributed as F with degrees of freedom equal to $(k_L - k_S)$ and $(N - k_L - 1)$. In our example, we know that $R^2_{y.12} = .67$ (from earlier calculations) and also that $r_{y1} = .77$ and $r_{y2} = .72$. $r^2_{y1} = .59$ and $r^2_{y2} = .52$. Now we can see if the increase of adding either X1 or X2 to the equation containing the other increases R^2 to significant extent. To see if X1 adds variance we start with X2 in the equation:

$$F = \frac{(.67 - .52)/(2 - 1)}{(1 - .67)/(20 - 2 - 1)} = \frac{.15}{.33/17} = 7.73$$

Our critical value of F(1,17) is 4.45, so our F for the increment of X1 over X2 is significant.

For the increment of X2 over X1, we have

$$F = \frac{(.67 - .59)/(2 - 1)}{(1 - .67)/(20 - 2 - 1)} = \frac{.08}{.33/17} = 4.12$$

Our critical value of F has not changed, so the increment to \mathbb{R}^2 by $\mathbb{X}2$ is not (quite) significant.