


Integer Casting in C

Computer Engineering 1

Motivation



<http://www.instructables.com>

Agenda

- Type conversion
 - signed $\leftrightarrow$ unsigned
 - Extension
 - Truncation

Learning Objectives

At the end of this lesson you will be able

- to explain the casting of integer types in C
- to apply the assembly instructions associated with casting
- to say how a given memory content is interpreted for different integer types in C
- to give the memory content after storing different C integer types

Integer Casting in C

Integer ranges based on word sizes

8-bit	hex	unsigned	signed
	0x00	0	0
	...	...	...
	0x7F	127	127
	0x80	128	-128
	...	...	...
	0xFF	255	-1

16-bit	hex	unsigned	signed
	0x0000	0	0
	...	...	...
	0x7FFF	32'767	32'767
	0x8000	32'768	-32'768
	...	...	...
	0xFFFF	65'535	-1

32-bit	hex	unsigned	signed
	0x0000 0000	0	0
	...	...	...
	0x7FFF'FFFF	2'147'483'647	2'147'483'647
	0x8000'0000	2'147'483'648	-2'147'483'648
	...	...	...
	0xFFFF'FFFF	4'294'967'295	-1

Integer Casting in C

Type conversion

- signed $\leftrightarrow$ unsigned

<code>int8_t</code>	$\leftrightarrow$	<code>uint8_t</code>
<code>int16_t</code>	$\leftrightarrow$	<code>uint16_t</code>
<code>int32_t</code>	$\leftrightarrow$	<code>uint32_t</code>
<code>int64_t</code>	$\leftrightarrow$	<code>uint64_t</code>

- Extension

<code>int_8_t</code>	$\rightarrow$	<code>int16_t</code>	$\rightarrow$	<code>int32_t</code>	$\rightarrow$	<code>int64_t</code>	signed
<code>uint_8_t</code>	$\rightarrow$	<code>uint16_t</code>	$\rightarrow$	<code>uint32_t</code>	$\rightarrow$	<code>uint64_t</code>	unsigned

- Truncation

<code>int64_t</code>	$\rightarrow$	<code>int32_t</code>	$\rightarrow$	<code>int16_t</code>	$\rightarrow$	<code>int_8</code>	signed
<code>uint64_t</code>	$\rightarrow$	<code>uint32_t</code>	$\rightarrow$	<code>uint16_t</code>	$\rightarrow$	<code>uint_8</code>	unsigned

Integer Casting in C

signed $\leftrightarrow$ unsigned

signed $-b_3 \cdot 2^3 + b_2 \cdot 2^2 + b_1 \cdot 2^1 + b_0 \cdot 2^0$

unsigned $+b_3 \cdot 2^3 + b_2 \cdot 2^2 + b_1 \cdot 2^1 + b_0 \cdot 2^0$

Casts in **red** area

→ Small negative numbers turn into large positive numbers

→ Large positive numbers turn into small negative numbers

binary	unsigned	signed 2' compl.
0000	0	0
0001	1	1
0010	2	2
0011	3	3
0100	4	4
0101	5	5
0110	6	6
0111	7	7
1000	8	-8
1001	9	-7
1010	10	-6
1011	11	-5
1100	12	-4
1101	13	-3
1110	14	-2
1111	15	-1

Integer Casting in C

signed $\leftrightarrow$ unsigned

- **Casting**
 - unsigned $\rightarrow$ signed
 - signed $\rightarrow$ unsigned

Bit representation stays the same,
but interpretation changes

- **Example 4-Bit**
 - 1011b $\rightarrow$ Interpretation as unsigned 11d
 - $\rightarrow$ Interpretation as signed -5d

Integer Casting in C

signed $\leftrightarrow$ unsigned

- **Example 1: signed 8-bit $\rightarrow$ unsigned 8-bit**
 - Bit representation stays the same, interpretation changes

dec	hex	OC	TC = OC + 1
10d	0x0A	0xF5	0xF6

```
int8_t c = -10;  
uint8_t uc = (uint8_t) c;
```

c contains 0xF6,
interpreted as -10d


uc also contains 0xF6,
but interpreted as 246d

Integer Casting in C

signed $\leftrightarrow$ unsigned

- **Example 2: signed 32-bit $\rightarrow$ unsigned 32-bit**
 - Bit representation stays the same, interpretation changes

dec	hex	OC	TC = OC + 1
9133d	0x0000'23AD	0xFFFF'DC52	0xFFFF'DC53



Explicit cast is not even required

```
uint32_t ui2 = i; // implicit cast
```

Integer Casting in C

signed $\leftrightarrow$ unsigned

- **Example 3: Cast unsigned 32-bit $\rightarrow$ signed 32-bit**
 - Bit representation stays the same, interpretation changes

dec	hex
4'294'964'632d	0xFFFF'F598

uix contains 0xFFFF'F598,
interpreted as 4'294'964'632

```
uint32_t uix = 4294964632;  
int32_t ix = uix;    // implicit cast
```

ix also contains 0xFFFF'F598,
but interpreted as -2664d

Integer Casting in C

Implicit Casts


- If one of the operands is unsigned, C performs an **implicit cast for the signed values to unsigned**
 - Example n = 32: signed [-2'147'483'648 , 2'147'483'647]
 - Can lead to strange results (red lines)

Expression	Type	Evaluation
0 == 0U	unsigned	1
-1 < 0	signed	1
-1 < 0U	unsigned	0
2'147'483'647 > -2'147'483'647 - 1	signed	1
2'147'483'647U > -2'147'483'647 - 1	unsigned	0
2'147'483'647 > (int) 2'147'483'648U	signed	1
-1 > -2	signed	1
(unsigned) -1 > -2	unsigned	1



Integer Casting

Extension: 4 Bit → 8 Bit

- Unsigned → Zero Extension



- Signed → Sign Extension



Integer Casting

Sign Extension

- **Sign Extension Cortex-M0 (signed values)**
 - Extend word-length without changing value
 - **SXTB** Extends an 8-bit value to a 32-bit value
 - **SXTH** Extends a 16-bit value to a 32-bit value
- **Zero Extension Cortex-M0 (unsigned values)**
 - Extend word-length, fill with zeroes
 - **UXTB** Extends an 8-bit value to a 32-bit value
 - **UXTH** Extends a 16-bit value to a 32-bit value

Examples

```
SXTB  R3, R4    ; Extract lowest byte of the value in R4,  
                ; sign extend it and write the result to R3  
UXTH  R2, R3    ; Extract lower two bytes of the value in R3,  
                ; zero extend it and write the result to R2
```

Integer Casting

Sign Extension

– Example Sign Extension

```
int16_t sx = 15213;  
int32_t ix = (int32_t) sx;  
  
int16_t sy = -15213;  
int32_t iy = (int32_t) sy;
```

	dec	hex	bin			
sx	15213	0x3B6D	00111011 01101101			
ix	15213	0x0000'3B6D	00000000	00000000	00111011	01101101
sy	-15213	0xC493	11000100 10010011			
iy	-15213	0xFFFF'C493	11111111	11111111	11000100	10010011

signed Integer Types: from small to large

→ **Sign bit is copied to the left**

Integer Casting Truncation

- **Truncation: Reduce number of digits**
 - Cast cuts the left most digits
- **Unsigned** → modulo Operation

```
uint32_t x = 287962;  
uint16_t sx = (uint16_t)x;  
uint32_t y = (uint32_t)sx;
```

```
0x000464DA → 287'962  
      0x64DA → 25'818  
0x000064DA → 25'818
```

- **Signed** → possible change of sign!

```
int32_t x = 53191;  
int16_t sx = (int16_t) x;  
int32_t y = (int32_t) sx;
```

```
0x0000CFC7 → 53'191  
      0xCFC7 → -12'345  
0xFFFFCFC7 → -12'345
```

Conclusion

- **Integer Casts**
 - Type Conversions
- **signed – unsigned**
 - Small negative numbers correspond to large positive numbers
- **Extensions**
 - Add additional bits
 - signed sign extension copy sign bit to the left
 - unsigned zero extension fill left bits with zero
- **Truncations**
 - Cut left most digits
 - signed possible change of sign
 - unsigned results in modulo operation