CMP(N)302: Design and Analysis of Algorithms



Lecture 09: Flow Networks

Ahmed Hamdy

Computer Engineering Department


Cairo University

Fall 2019

Real life application


 Find max water rate flowing from source (Vancouver) to sink (Winnipeg) in the shown pipe network based on the shown capacities.

- Can you guess an upper-bound for what we can get from just looking?
- Iteratively how do you come up with the best solution?
- Between iterations, how to simplify and prepare the network for the next iteration?



What is a flow network?

- Flow network is a directed graph G(V, E)
- Each edge $(u, v) \in E$ has a nonnegative capacity $c(u, v) \ge 0$. No self-loops.
- If there is $(u, v) \in E$, then there is no edge (v, u) in reverse direction, and c(v, u) = 0
- Typically, there is source s and sink t



What is a flow?

- Flow is a real-valued function $f: V \times V \to \mathbb{R}$ that satisfies:
 - Capacity constraint: For all $u, v \in E$, we require

$$0 \le f(u, v) \le c(u, v)$$

- For all $u, v \in V - \{s, t\}$, we require

$$\sum_{v \in V} f(v, u) = \sum_{v \in V} f(u, v)$$


Modeling with antiparallel edges

Antiparallel edge:


Edges (v_1, v_2) and (v_2, v_1) are called antiparallel

Workaround:

Split one of the edges using a new vertex



Modeling with multiple sources/sinks



Ford-Fulkerson method

- Method not algorithm because it has several implementations with different complexities
- Greedy, greedy, greedy!!!
- Main ideas
 - Residual networks
 - Augmenting paths
 - Cuts FORD-FULKERSON-METHOD (G, s, t)1 initialize flow f to 0

 2 while there exists an augmenting path p in the residual network G_f 3 augment flow f along p4 return f

Residual network

- Residual network G_f contains the residual capacities from G
- It may contain extra edges
 - To allow for decreasing previously-allocated flows
 - Reversed edges for previously-allocated flows
- Kind of similar to a flow network, except it allows for reversed edges
- Now, why there is no reversed edges in flow networks??

$$c_f(u, v) = \begin{cases} c(u, v) - f(u, v) & \text{if } (u, v) \in E, \\ f(v, u) & \text{if } (v, u) \in E, \\ 0 & \text{otherwise}. \end{cases}$$

A path is simple if all the vertices on the path are distinct.

Augmenting paths

• Augmenting path p is a simple path from s to t in the residual network G_f





Figure 26.4 (a) The flow network G and flow f of Figure 26.1(b). (b) The residual network G_f with augmenting path p shaded; its residual capacity is $c_f(p) = c_f(v_2, v_3) = 4$. Edges with residual capacity equal to 0, such as (v_1, v_3) , are not shown, a convention we follow in the remainder of this section. (c) The flow in G that results from augmenting along path p by its residual capacity 4. Edges carrying no flow, such as (v_3, v_2) , are labeled only by their capacity, another convention we follow throughout. (d) The residual network induced by the flow in (c).

Cuts of flow networks

- How to know when the algorithm terminates??
- A cut (S, T) of flow network G(V, E) is a partition of V into S and T= V - S
- Net flow f(S,T) across the cut (S,T) is defined as

$$f(S,T) = \sum_{u \in S} \sum_{v \in T} f(u,v) - \sum_{u \in S} \sum_{v \in T} f(v,u)$$



Cuts of flow networks

The capacity of the cut (S, T) is

$$c(S,T) = \sum_{u \in S} \sum_{v \in T} c(u,v)$$

 A minimum cut of a network is a cut whose capacity is minimum over all cuts of the network

Max-flow min-cut

Theorem 26.6 (Max-flow min-cut theorem)

If f is a flow in a flow network G = (V, E) with source s and sink t, then the following conditions are equivalent:

- 1. f is a maximum flow in G.
- 2. The residual network G_f contains no augmenting paths.
- 3. |f| = c(S, T) for some cut (S, T) of G.

Basic Ford-Fulkerson algorithm

```
FORD-FULKERSON(G, s, t)

1 for each edge (u, v) \in G.E

2 (u, v).f = 0

3 while there exists a path p from s to t in the residual network G_f

4 c_f(p) = \min\{c_f(u, v) : (u, v) \text{ is in } p\}

5 for each edge (u, v) in p

6 if (u, v) \in E

7 (u, v).f = (u, v).f + c_f(p)

8 else (v, u).f = (v, u).f - c_f(p)
```

- Path-finding is performed using either BFS or DFS, thus O(V + E) = O(E)
- The while loop is executed $|f^*|$ (if every iteration just adds on unit value), where f^* is the maximum flow
- Overall complexity is $O(E | f^*|)$

FFA







Figure 26.6 The execution of the basic Ford-Fulkerson algorithm. (a)–(e) Successive iterations of the **while** loop. The left side of each part shows the residual network G_f from line 3 with a shaded augmenting path p. The right side of each part shows the new flow f that results from augmenting f by f_p . The residual network in (a) is the input network G.

FFA








Worst case for FFA

• | f * | in this case is 2,000,000



Edmonds-Karp algorithm

Uses BFS for augmenting path (shortest path)

• Total number of flow augmentations is O(VE), thus overall complexity $O(VE^2)$

How does it perform with the worst case for FFA?