MASAR MCE ASSETS

User Guide &Testing Checklist

IT Asset Role Matrix

Asset Submission

Location Quantity Limits

Document details	Value
Audience	MCE ERP Team, IT Warehouse, Finance (Fixed Assets), System Managers and administrators
Prepared by	KCSC Development Team
Application	Masar MCE Assets
Purpose	Explain the new behavior, guide configuration and provide a practical test checklist

Please complete the relevant checks in a test environment before applying changes to production.

1. Overview

This guide explains the new features in the Masar MCE Assets app and how relevant users should configure, use and test them.

- IT Asset Role Matrix: applies a controlled workflow to configured IT roles for Purchase Receipt, Stock Entry and Asset Movement.
- IT asset serial numbers: qualifying IT Purchase Receipts require one serial number per asset unit, and the generated Asset stores that serial number.
- Auto Submit Assets: an optional Purchase Receipt checkbox submits generated Assets in the background and uses depreciation settings from the Asset Category.
- Location Asset Quantity Limit: each Location can set a maximum number of asset units per Asset Category.

The documented rules are enforced on the server, including for forms, REST API requests, integrations, data imports and background jobs. Standard ERPNext permissions and validations continue to apply.

2. Understand the role matrix

A System Manager configures the two role lists in IT Asset Role Matrix Settings.

Role list	Purpose	Initial configuration
IT Asset Roles	Users with any listed role follow the IT asset workflow.	IT Warehouse
Ignore IT Asset Role Matrix Roles	Users with any listed role are exempt from these IT-specific restrictions, even if they also have an IT asset role.	Empty by default

User group	Condition	Expected behavior
IT user	Has an IT Asset Role and no ignore role.	IT-specific restrictions apply.
Exempt user	Has any ignore role.	IT-specific restrictions do not apply; IT fields and IT naming series remain available where described below.
Other user	Has neither configured role.	Existing standard behavior remains; IT naming series are unavailable.

- The ignore list always takes precedence over the IT Asset Roles list.
- The ignore list does not bypass normal ERPNext permissions or validations.
- The roles All and Guest cannot be added, and the same role cannot appear in both lists.
- After a user's roles change, refresh the form to update the UI. The server applies role changes immediately.

3. Purchase Receipt

3.1 Naming series and fields

Setting	IT user	Exempt user	Other user
Naming series: IT-PRE-.YYYY.-	Required; field is read-only.	Optional.	Not available.
Normal Cycle	Checked by default; can be unchecked.	Existing behavior.	Existing behavior.
Warranty Expiry, Invoice Date, Invoice No, Referral Decision No, Approval Letter Date and Approval Letter No	Shown.	Shown.	Existing behavior.
Auto Submit Assets checkbox	Available.	Available.	Available.

3.2 Serial numbers for IT assets

When a Purchase Receipt using naming series IT-PRE-.YYYY.- is submitted, serial numbers are required for each qualifying fixed-asset row where Auto Create Assets is enabled and Is Grouped Asset is disabled.

- Enter one serial number per asset unit in the Serial Numbers IT field. Use one serial number per line; comma-separated values are also accepted.
- The received quantity must be a whole number.
- The number of serial numbers must match the received quantity.
- A serial number must not be repeated in the same receipt or already belong to another Asset of the same item.
- If validation fails, correct the row identified in the error message.

After submission, each generated Asset should show its corresponding value in the Serial No field. Grouped asset items, ordinary items and receipts using other naming series are not affected.

3.3 Optional Auto Submit Assets checkbox

The checkbox is off by default. When selected, the system schedules background processing for Assets created by the submitted Purchase Receipt.

1. The job reads the first Finance Book row of the Asset Category.
2. It sets Available for Use Date to Purchase Date and enables Calculate Depreciation.
3. It fills the depreciation method, number of depreciations, frequency and depreciation start date using the category's Finance Book settings and the Purchase Date.
4. It saves and submits each eligible Asset.

Important operating notes:

- Each Asset is processed independently. One failure should not prevent other Assets from being submitted.
- A comment on the Purchase Receipt reports submitted, failed and skipped counts. Failure details are recorded in Error Log.
- Already-submitted Assets are skipped on a retry, and duplicate depreciation rows should not be added.
- The background job runs as the user who submitted the Purchase Receipt. That user must have permission to submit Assets.
- Before enabling this feature, Finance must confirm that every applicable Asset Category has at least one Finance Book row.

4. Stock Entry

Setting	IT user	Exempt user	Other user
Naming series: IT-STE-.YYYY.-	Required; field is read-only.	Optional.	Not available.
Stock Entry Type	Only سند اخراج.	Any valid type.	Any valid type.

If an IT user attempts to use another Stock Entry Type, the server should reject the transaction. Exempt users retain the normal available types.

5. Asset Movement

Setting	IT user	Exempt user	Other user
Purpose	Only Transfer or Issue.	Any valid purpose.	Any valid purpose.
Approval Letter No, Approval Letter Date and Default Target Location	Visible and mandatory.	Optional.	Optional.
Target Location in movement rows	Read-only; copied from Default Target Location.	Existing behavior.	Existing behavior.

For IT users, Default Target Location controls the destination of all applicable movement rows.

- Changing Default Target Location updates all existing rows.
- New rows automatically receive the selected Default Target Location.
- The server synchronizes the target location on each applicable row before saving and submitting.
- Source locations are not changed by this feature.
- ERPNext's automatically created Receipt movement when an Asset is submitted is not affected by these rules.

Default Target Location is mandatory only for IT users under this role matrix.

6. Location Asset Quantity Limit

Each Location can have an Asset Category Limits table. For each listed Asset Category, configure the maximum number of asset units allowed at that Location.

- A maximum quantity of 0 means no units of that category are allowed at the Location.
- An Asset Category not listed in the table has no configured limit.
- The limit counts asset units (Asset Quantity), not the number of Asset documents.
- Cancelled, sold, scrapped and capitalized Assets are excluded from the count.

The limit is checked when assets arrive at a Location, including:

- Purchase Receipt submission.
- Purchase Invoice submission with Update Stock.
- Asset save.
- Asset Movement submission.
- Asset Movement cancellation, when Assets return to their previous Location.

Moving assets out of a Location is allowed even if the Location is already over its configured limit. When an incoming transaction exceeds a limit, the error should show the maximum, current, incoming and available quantities.

7. Configuration and rollout steps

For System Managers

5. Open IT Asset Role Matrix Settings.
6. Confirm that IT Warehouse is included in IT Asset Roles.
7. Add the roles that should be exempt to Ignore IT Asset Role Matrix Roles (for example, System Manager if that is the intended policy).
8. Confirm that no role appears in both lists and that All and Guest are not included.
9. For each Location that requires a cap, configure the Asset Category Limits table and maximum quantity.

For Finance / Fixed Assets

10. Check that each Asset Category used with Auto Submit Assets has at least one Finance Book row.
11. Confirm the category's depreciation method, number of depreciations and frequency before enabling automatic submission.

For IT Warehouse staff

12. Use the IT Purchase Receipt naming series for qualifying IT fixed-asset receipts.
13. Enter one serial number per received unit in Serial Numbers IT.
14. Review the receipt details before submission.
15. Enable Auto Submit Assets only when automatic Asset submission is intended and the category configuration has been checked.
16. For Asset Movement, use Default Target Location and verify the destination before submission.

8. User Acceptance Test Checklist

Run these checks in a test site or an approved test transaction set. Record Pass/Fail and attach the document name or screenshot for any failure.

8.1 Role matrix

- ☐ A user with IT Warehouse and no ignore role receives the IT workflow restrictions.
- ☐ A user with an ignore role is exempt, even when that user also has IT Warehouse.
- ☐ A user with neither configured role retains the existing standard behavior.
- ☐ After changing a user's roles, refreshing the form reflects the applicable UI behavior.
- ☐ Normal ERPNext permissions still apply to exempt users.

8.2 Purchase Receipt

- ☐ For an IT user, the naming series defaults to IT-PRE-.YYYY.- and cannot be changed in the form.
- ☐ For an exempt user, the IT naming series is available but optional.
- ☐ For an ordinary user, the IT naming series is unavailable.
- ☐ The six IT receipt custom fields are visible for IT and exempt users.
- ☐ A qualifying fixed-asset row with missing serial numbers is rejected on submission.
- ☐ A receipt with fewer or more serial numbers than the received whole-unit quantity is rejected.
- ☐ Duplicate serial numbers within the receipt are rejected.
- ☐ A serial number already assigned to another Asset of the same item is rejected.
- ☐ After successful submission, each generated Asset displays the correct serial number.
- ☐ With Auto Submit Assets unchecked, this feature does not automatically submit generated Assets.
- ☐ With Auto Submit Assets checked and a valid Asset Category Finance Book, eligible Assets are submitted in the background.
- ☐ If one Asset fails, other eligible Assets continue processing and the failure is logged.
- ☐ Retrying the job does not submit already-submitted Assets again or duplicate depreciation rows.

8.3 Stock Entry

- ☐ For an IT user, the naming series defaults to IT-STE-.YYYY.- and is read-only.
- ☐ For an exempt user, the IT naming series is available but optional.
- ☐ For an ordinary user, the IT naming series is unavailable.
- ☐ An IT user can select سند اخراج and submit a valid transaction.
- ☐ An IT user cannot save or submit a transaction with another Stock Entry Type.
- ☐ Exempt and ordinary users retain the expected standard Stock Entry type choices.

8.4 Asset Movement

- ☐ An IT user can select Transfer or Issue, but cannot use another purpose.
- ☐ Approval Letter No, Approval Letter Date and Default Target Location are visible and mandatory for an IT user.
- ☐ The same fields are optional for an exempt user.
- ☐ Changing Default Target Location updates all applicable existing rows.
- ☐ Adding a new row copies Default Target Location into that row.
- ☐ The target-location field in rows is read-only for an IT user.
- ☐ Saving or submitting through the API also synchronizes target locations for an IT user.
- ☐ Source locations remain unchanged.
- ☐ The automatically created Receipt movement for Asset submission is not blocked by these rules.

8.5 Location asset quantity limit

- ☐ A Location with a configured category limit accepts incoming units when the resulting quantity is within the maximum.
- ☐ A Location rejects incoming units when the resulting quantity would exceed the maximum.
- ☐ A configured maximum of zero rejects incoming units of that category.
- ☐ An Asset Category not listed in the limits table remains unlimited.
- ☐ The limit counts asset units rather than Asset documents.
- ☐ Cancelled, sold, scrapped and capitalized Assets are excluded from the count.
- ☐ Moving assets out of a Location is allowed even when that Location is already over its limit.
- ☐ Purchase Receipt, Purchase Invoice with Update Stock, Asset save, Asset Movement submit and Asset Movement cancel are checked as documented.
- ☐ The validation error shows maximum, current, incoming and available quantities.

8.6 API and regression checks

- ☐ The relevant server-side validations apply when documents are created or updated through the REST API.
- ☐ Data imports and background jobs do not bypass the role-matrix or Location limit validations.
- ☐ Standard Purchase Receipt, Stock Entry, Asset creation/depreciation and Asset Movement workflows still work for unaffected users.

10. Support and issue reporting

If a check fails, report the DocType, document ID, user role configuration, steps to reproduce, expected result, actual result, and any error message or screenshot to the KCSC Development Team.