#### Lecture 4b - Advanced Fortran 95/03

- There are different data types used in Fortran 95/03
  - Some compilers will delineate REAL variables into KINDS
  - KINDS are described in Chapman
  - Most of the time, you do not have to worry about the KINDS but will instead decide in advance if you wish to work in *single* or double precision and then declare variables accordingly
  - REAL\*4 (single precision), REAL\*8 (double precision)
- Most modern scientific Fortran programs use derived data type variables to better describe their meaning
  - Convenient way to group together all information regarding a particular item and their relationships
  - Used extensively in object-oriented programming (OOP)

## **Derived Data Types**

Usage:

TYPE :: type\_name component definitions

..

END TYPE type\_name

• EXAMPLE:

TYPE:: PERSON

CHARACTER (LEN=14) :: first\_name

CHARACTER :: middle\_initial

CHARACTER (LEN=14) :: last\_name CHARACTER (LEN=14) :: phone

INTEGER :: age CHARACTER :: sex

CHARACTER (LEN=11) :: ssn

**END TYPE PERSON** 

2

## **Derived Data Types**

We could initialize variables or arrays as data types

EXAMPLE: TYPE (PERSON) :: JOHN, JANE

TYPE (PERSON) :: DIMENSION(100) PEOPLE

....

JOHN = PERSON('John', 'R', 'Jones', '323-6439', '21', 'M', '123-45-6789') JANE = PERSON('Jane', 'C', 'Doe', '332-3060', '19', 'F', 999-99-9999') PEOPLE(1) = PERSON('Sam', 'L', 'Van', '666-2354', '33', 'M', '987-65-4321')

 We can refer to individual parameters of a derived data type (such as first\_name, age, or ssn in the above example) by simply referring to type%parameter

EXAMPLE: JOHN%age = 21

JANE%last\_name = 'Doe'

- You can now begin to see how all of the parameters (or characteristics) of a variable can be linked together by using derived data types
  - Working with the parameters of derived data types is easy but working with the data types as a whole is not!

# **Derived Data Types in Modules**

- Derived data types can be defined in Modules and then "used" in different routines
  - Input into Modules is the same as previously described
- You can see how derived data types might be very useful in
  - Data bases
  - Data structures used for scientific simulations
    - Unstructured-grids for instance:

TYPE GRID CELL

REAL :: cell number

CHARACTER(LEN=4) :: cell\_type

REAL :: number\_of\_faces

**END TYPE GRID** 

Object oriented programming (OOP)

### **Dynamic Memory Allocation**

- One reason that the C computer language became so popular was its ability to dimension arrays dynamically.
  - This eliminates the need to re-compile codes in order to handle different problem sizes
- Fortran did not allow for dynamic memory allocation until the 90/95 versions (several years after C was able to)
- An array can be declared with variable dimensions through use of the ALLOCATABLE statement

REAL, ALLOCATABLE, DIMENSION (:,:) :: ARRAY1
This declares ARRAY1 with a variable dimension to be defined with an ALLOCATE statement

#### **ALLOCATE and DEALLOCATE**

 Once an array is declared ALLOCATABLE, the dimensions can be defined and the array created

EXAMPLE: INTEGER, PARAMETER :: IDIM=200 INTEGER, PARAMETER :: JDIM=100

REAL, ALLOCATABLE DIMENSION (:,:) :: ARRAY1

...

ALLOCATE(ARRAY1(IDIM,JDIM),STAT=STATUS)

...use in computation

DEALLOCATE(ARRAY1,STAT=STATUS)

Where STATUS = 0 for successful allocation and a positive number if the allocation fails

5

6

# **Checking Allocated Arrays**

- Arrays can not be re-allocated once they have been allocated. They must first be deallocated and the allocated with new parameters.
- A way to check to see if an array has be allocated is to use the logical intrinsic function ALLOCATED

EXAMPLE: REAL, ALLOCATEABLE, DIMENSION (:) :: INPUT
...

IF(ALLOCATED(INPUT)) THEN

READ(8,\*) INPUT

ELSE

WRITE(\*,\*) 'Warning: INPUT not allocated'
END IF

### **Pointers**

- Pointers are primarily used when variables and arrays are created and destroyed dynamically and we do not know in advance the number of each that will be needed
- A pointer is a variable that contains the address in memory of another variable where data is stored
  - Pointer → address of variable
  - Variable → data value

7

#### **Pointers**

 A Fortran variable is declared to be a pointer by including the POINTER attribute in its declaration statement

EXAMPLE: REAL, POINTER :: P1

- A pointer is only allowed to point to variables of its declared type
- Pointers may also be used for derived data types
   EXAMPLE: TYPE(VECTOR), POINTER :: VECTOR P1
- Pointers may also point to arrays

EXAMPLE: INTEGER, DIMENSION(:), POINTER :: P1
REAL, DIMENSION(:,:), POINTER :: P2

9

11

 A target is a data object whose address has been made available for use with pointers

**Targets** 

• A pointer can point to any variable or array of the

pointer's type as long as the variable has been

 A Fortran variable or array may be declared to be a target by including the TARGET attribute in its declaration

EXAMPLE: REAL, TARGET :: A1 = 7
INTEGER, DIMENSION(10), TARGET :: INT\_ARRAY

declared to be a target

# **Pointers** → **Targets**

 Pointers may be associated with a given target by using a pointer assignment statement

EXAMPLE: pointer => target

This stores the memory address of target in the pointer

 We can also assign the value of one pointer to another pointer by using the assignment statement

EXAMPLE: pointer2 => pointer

 Even though the address is stored in a pointer, reference to the pointer (say with a read or write statement) will result in the variable value that it is pointing to

#### **Disassociation and Status of Pointers**

 Pointers can be disassociated from their targets by using the *nullify* statement

EXAMPLE: NULLIFY(pointer1, pointer2,...)

• The status of the association of a pointer can be determined using the associated statement

EXAMPLE: status = ASSOCIATED(pointer1)

where status is TRUE if the pointer is associated with any target

or status = ASSOCIATED(pointer1,target1)

 where status is TRUE if the pointer is associated with the particular target included in the ASSOCIATED statement 10

#### **Pointers and Arrays**

 Pointers can also point to a targeted array. The pointer must declare the type and the rank of the array that it will point to:

EXAMPLE: REAL, DIMENSION(50,50), TARGET :: MYDATA

REAL, DIMENSION(:,:), POINTER :: POINTER1

POINTER1 => MYDATA

Pointers can also point to a subset of an array

EXAMPLE: REAL, DIMENSION(50,50), TARGET :: MYDATA

REAL, DIMENSION(:,:), POINTER:: POINTER1

POINTER1 => MYDATA(1:20,10:50)

13

#### **Dynamic Memory Allocation of Array Pointers**

 A powerful feature of pointers is that they can be used to dynamically create variables or arrays (similar to what we did before but without the need for ALLOCATABLE statements)

**EXAMPLE:** 

PROGRAM MEM IMPLICIT NONE

INTEGER :: I, ISTAT

INTEGER, DIMENSION(:) POINTER :: PTR1,PTR2

ALLOCATE(PTR1(1:10),STAT=ISTAT)
ALLOCATE(PTR2(1:10),STAT=ISTAT)

! NOTE THAT WE DID NOT HAVE TO DECLARE PTR1 OR PTR2

! AS ALLOCATABLE ARRAYS

PTR1 = (/ I,I=1,10) /)PTR2 = (/ I,I=11,20) /)

14

## **Pointers with Derived Data Types**

- Another powerful use of pointers is with components of derived data types.
  - Pointers in derived data types may even point to the derived data type being defined (circular!)
  - This feature allows us to construct types of dynamic data structures linked together by successive pointers during program execution. Such a structure is called a *linked list*
  - A linked list is a series of variables of a derived data type with the pointer from each variable pointing to the next variable in the list

EXAMPLE: TYPE :: REAL\_VALUE

REAL :: VALUE

TYPE(REAL\_VALUE), POINTER :: PNTR

**END TYPE** 

Contains a real number and a pointer to another variable of the same type

#### **Uses of Link Lists**

- Link lists are useful when the size of the data set is dynamic and it is unknown at the start of the program what the final size will be
  - Grid embedding adaptation is an example
  - Convergence histories is another example
- Link lists allow us to add elements to an array, one at a time

#### **Pointers in Procedures**

- Pointers can also be used as dummy arguments in procedures or passed as arguments to procedures
  - If a procedure has dummy arguments with either the POINTER or TARGET attributes, then the procedure must have an explicit interface
  - If a dummy argument is a pointer, then the actual argument passed to the procedure must be a pointer of the same type, kind, and rank
  - A pointer dummy argument cannot have an INTENT attribute
- · A function result can also be a pointer.

17

# **Data Types**

- We've mentioned some data types used in programming
  - Intrinsic types: character, logical, floating point, complex, real
  - User defined data types: derived data types
- Now let's discuss data types and some definitions in the context of OOP
- Abstract Data Types
  - Coupling or encapsulation of the data with a select group of functions defining everything that can be done with the data → abstract data type
  - Abstraction (generalization):
    - pertains to only the essential features of the data
    - Features are defined in a manner that is independent of any specific programming language
    - Instances are defined by their behavior and the implementation is secondary

## **Object Oriented Programming (OOP)**

- Modern programming methods include object oriented styles that include:
  - Modular program design (intensive use of subroutines)
  - Use of re-usable programming "objects"
  - Abstract data types
  - General data structures
  - Pointers and targets
- OOP methods have been used in the C language for several years and are now fully-functional in Fortran
  - Object-based modular structure
  - Data abstraction
  - Automatic memory management
  - Classes
  - Inheritance

Polymorphism (generic functionality) and dynamic binding

18

### Classes

- Class: an extension of an abstract data type by providing additional member routines to serve as constructors
- The constructor ensures that the class is created with acceptable values assigned to all its data attributes.

- Example a type: type (face\_information) :: face

integer :: face\_index

integer :: face\_idim, face\_idim

real\*8, allocatable, dimension(:,:) :: xface,yface

end type face\_information

when combined with a constructor to create the information contained in the type and all included in a module, it becomes a class

## Object, Instance, Encapsulation, and Data Hiding

- Object: combines various classical data types into a set that defines a new variable type or structure.
- Instance: every object from a class, by providing the necessary data, is called an instance of the class.
- Encapsulation: the coupling or encapsulation of data and its functions into a unified entity. This is performed by including the class in a module.
- Data hiding: the protection of information in one part of a program from access and from being changed in other parts of the program. In the module, the "contains" statement couples the data, specifications, and operators before it to the functions and subroutines that follow it in the module.

#### **Inheritance and Polymorphism**

- Inheritance: we can employ one or more previously defined classes (of data and functionality) to organize additional classes.
   Functionality programmed into the earlier classes may not need to be recoded to be usable in the later class.
  - This is performed in Fortran with "use" followed by the name of the module statement block that defined the class.

22

 Polymorphism: ability of a function to respond differently when supplied with arguments that are objects of different types

21

# **Example**

- In this class (and likely during your careers) you will develop (or use) a differential equation solver for modeling some physical phenomena.
  - Heat conduction, stress/strain, flow
- In such solvers, there are several kernels that make up the algorithms and several algorithms that make up the code
  - Grid cell face area
  - Grid cell volume
  - i-face, j-face, k-face fluxes
  - Integration of fluxes
  - Timestep size
  - Update of variables, etc.

### Procedural vs OOP

- Most people learn how to program codes start off learning the procedural programming style
- Let's say you wanted to start programming your project-1 code
- The pseudo-code for a procedural program to solve the heat conduction equation might look something like the following:

## **Procedural Programming Example-1**

program heat

- this program solves the 2D heat conduction equation on a structured grid create global computational grid
  - define computational and physical dimensions allocate memory for grid and temperature variables initialize temperature on computational grid
  - set the boundary conditions on temperature
  - solve the heat conduction equation
  - calculate constant-i face primary projected lengths calculate constant-j face primary projected lengths calculate primary cell volume calculate primary cell-centered time-step size calculate constant-i face temperature fluxes calculate constant-j face temperature fluxes

calculate primary cell center temperature first-derivatives

## **Procedural Programming Example-1**

calculate constant-i face secondary projected lengths
calculate constant-j face secondary projected lengths
calculate secondary cell volume
calculate secondary node-centered time-step size
calculate constant-i face temperature derivative fluxes
calculate constant-j face temperature derivative fluxes
calculate secondary node-center temperature second-derivatives
calculate right-hand side of heat conduction equation
sum second derivatives and multiply by time-step size
these are the changes in temperature
apply boundary conditions
update temperature and test for convergence
— if (notconverged) iterate
else write out final solution in standard (plot3d) format

end program

# **Procedural Programming Example-1**

- Each line of the pseudo-code could be either programmed directly in the main program (that I do not recommend), or written as a subroutine that is called from the main program.
- When subroutines are used, you need to get information exchanged between the subroutine and the main program
  - This can be done using arguments in the subroutine call OR a module that can be "used" in both the subroutine and the main program
  - Also note that subroutines that pertain to the calculation of geometry variables do not need to be placed inside of the iteration loop

# **Procedural Programming Example-2**

program heat

use variable module

! this program solves the 2D heat conduction equation on a structured grid call computational grid creation

define computational and physical dimensions

allocate memory for grid and temperature variables and store in variable\_module

call temperature initialization

call boundary condition initialization

call constant-i face primary projected lengths

call constant-j face primary projected lengths

calculate primary cell volume

calculate constant-i face secondary projected lengths

calculate constant-j face secondary projected lengths

calculate secondary cell volume

26

## **Procedural Programming Example-2**

solve the heat conduction equation

- → call primary cell-centered time-step size
- call constant-i face temperature fluxes
- call constant-j face temperature fluxes
- call primary cell center temperature first-derivatives
- call secondary node-centered time-step size
- call constant-i face temperature derivative fluxes
- call constant-i face temperature derivative fluxes
- call secondary node-center temperature second-derivatives
- call right-hand side of heat conduction equation
- sum second derivatives and multiply by time-step size
  - these are the changes in temperature
- call boundary conditions
- call update temperature and test for convergence
- -if (notconverged) iterate
- else write out final solution in standard (plot3d) format
- end program

## **Procedural Programming Example-2**

- Then the subroutines are linked to the main program during the linking step, after compilation of all subroutines, in the creation of the code
- The subroutines can be included in the same file as the main program or in separate files
- Procedural programming is the most straightforward method for engineers. However, it lacks the generality (abstractions) and organization that OOP offers.

# **OOP Example-3**

29

31

program heat

this program solves the 2D heat conduction equation on a structured grid

use grid\_module

use face\_module

use cellvolume module

use facefluxes\_module

use secondaryface\_module

use secondarycellvolume\_module

use secondaryfacefluxes\_module

use boundarycondition\_module

create global computational grid (class)

define computational and physical dimensions

allocate memory for grid and temperature variables and store in module

call temperature initialization (subroutine)

call boundary condition initialization (subroutine)

call constant-i face primary projected lengths (class)

call constant-j face primary projected lengths (class)

## **OOP Example-3**

calculate primary cell volume (class)

calculate constant-i face secondary projected lengths (class)

calculate constant-j face secondary projected lengths (class)

calculate secondary cell volume (class)

solve the heat conduction equation

call primary cell-centered time-step size

call constant-i face temperature fluxes (class)

call constant-j face temperature fluxes (class)

call primary cell center temperature first-derivatives (class)

call secondary node-centered time-step size (class)

call constant-i face temperature derivative fluxes (class)

call constant-i face temperature derivative fluxes (class)

call secondary node-center temperature second-derivatives (class)

32

### **OOP Example-3**

call right-hand side of heat conduction equation (class)
sum second derivatives and multiply by time-step size
these are the changes in temperature
call boundary conditions (class)
call update temperature and test for convergence
if (notconverged) iterate
else write out final solution in standard (plot3d) format
end program

### **OOP Example-3**

Each class consists of a module of the allocatable array(s)
pertaining to that particular class and contains the subroutine
that creates the data. For instance, constant-i face lengths
class would be:

```
module constant-i_face_lengths real*8, allocatable, dimension(:,:) :: dx_i, dy_i contains use dimensions_module (contains imax, jmax) do j = 1, jmax-1 do i = 1, imax dx_i(i,j) = x(i,j+1)-x(i,j) dy_i(i,j) = y(i,j+1)-y(i,j) enddo enddo end module constant-i_face_lengths
```

# **Projects**

33

- During the creation of your projects, I would like for you to start by using procedural programming until you are comfortable with programming techniques.
- However, I would like for you to move toward OOP as soon as possible and incorporate abstract programming techniques with classes to make your codes more elegant and general.

## Homework 2 (cont)

• Read Chapters 11-15 in Fortran95/03 (Chapman)

35