### **Lecture 20 – Multi-Processor Performance**

- CPU scalability
- Memory scalability
- Interconnection network
- Bandwidth and latency issues
- Problem size and granularity
- · How many processors can we use efficiently?
- In the last class, we discussed Amdahl's law for single and multiple processors. Let's first go back and review the multiple-processor model.

## **Amdahl's Law - Parallel Processing**

• The *computational efficiency* using *p* processors is defined as

$$E_p = \frac{S_p}{p} \qquad 0 \le E_p \le 1$$

• Then, the *total execution time* using *p* processors is given by

$$t_p = \frac{ft_1}{p} + (1 - f)t_1 = \frac{t_1(f + (1 - f)p)}{p} \ge (1 - f)t_1$$

### **Amdahl's Law - Parallel Processing**

- Ideally, if a computation can be carried out in p equal parts, the total execution time will be nearly 1/p of the time required by a single processor
- Suppose  $t_j$  denotes the wall clock time required to execute a task with j processors
- Speedup,  $S_{\scriptscriptstyle p}$  , for p processors is defined as

$$S_p = \frac{t_1}{t_p}$$

• Where  $t_1$  is the time required for the most-efficient sequential algorithm to complete the calculation, and  $t_p$  is the time required for the most efficient parallel implementation of the same algorithm, from beginning to end, using p processors.

## **Amdahl's Law - Parallel Processing**

• Therefore, the speedup on p processors is then

$$S_p = \frac{p}{(f + (1 - f)p)} \le \frac{1}{1 - f}$$

(Ware's Law)

• This shows that the speedup is considerable reduced even for pretty large values of f (close to 95%)

### **Amdahl's Law - Parallel Processing**


- Parallel overhead is the additional amount of work that is required on the parallel implementation of a sequential algorithm arising from the use of a parallel computer:
  - Inter-processor communication
  - Load imbalance
  - Additional computation resulting from the algorithm that is being parallelized not being as efficient as the most efficient serial algorithm.
- If the total time spent in solving a problem over all processing elements is  $pT_p$  and  $T_s$  is the time spent doing useful work (consider this the time for a single processor), then  $T_o$  is the overhead time:

$$T_o = pT_p - T_s$$

• This is the overhead time spent in communication

5

### Amdahl's Law - Parallel Processing



6

## **Amdahl's Law - Parallel Processing**


- Amdahl's law is a simplistic, yet powerful way of looking at the problem of scalability.
- In a naïve way, it points out that a large number of processors cannot be used on any computational task, since f needs to be very close to 1. For example, f=0.999 would allow the use of a maximum number of processors equal to 1000.

### **Example - Adding on a Hypercube**

- Consider adding n numbers using n processors of a hypercube (n is a power of two)
- Initially, each processor gets one number, and at the end, one processor has the sum of all of them
- Addition and communication take each 1 unit of time.
  - The addition can be performed in some constant time,  $\mathbf{t}_{\mathrm{c}}.$
  - The communication of a single word can be performed in time  $t_s$ + $t_w$  where
    - t<sub>s</sub> is the start-up time to handle message at the sending and receiving nodes
    - t<sub>w</sub> is the per-word transfer time

# **Example - Adding on a Hypercube**

(sum 16 numbers on 16 processors)



## **Example - Adding on a Hypercube**

$$T_p = \Theta(\log n)$$
  $S_p = \Theta\left(\frac{n}{\log n}\right)$   $E_p = \frac{S_p}{n} = \Theta\left(\frac{1}{\log n}\right)$ 

- Performance not impressive:
  - For 16 numbers and 16 processors, E<sub>p</sub> = 25% (Note that all log functions in <u>Introduction to Parallel Computing</u> by Grama et al are in base 2. See Appendix A)

$$\log_2 x = \frac{\log_{10} x}{\log_{10} 2} = \frac{\log_{10} x}{.301}$$

- Maybe we are using too many processors for this problem? Maybe the problem size is too small?
- · Let's try again.

10

## **Example - Adding on a Hypercube**

- Assign larger pieces of data to each processor (more than one number per processor). We are increasing the work-load of each processor by doing this.
- Consider adding n numbers using p processors of a hypercube, p < n, both p and n are powers of two.</li>
   Using fewer processors than the maximum number of elements is called scaling down.
- Initially, each processor gets *n/p* numbers, and at the end, one processor has the sum of all of them
- Addition and communication take each 1 unit of time

# **Example - Adding on a Hypercube (Non-optimal Algorithm)**

(Sum 16 numbers on 4 processors – mimic operations of 16 processors)

	sub-	step 1				sub-	step 2	
12	13	14	15		12	13	14	15
8	9	10	11	:	8	9	10	11
4	5	6	7		4	5	6	7
0	1	2	3	,	Σ		Σ	
0	1	2	3			1	2	3


### Step 1

8 communications and 8 adds

sub-step 3				sub-step 4			
12	13	14	15	12	13	14	15
8	9	10	11	Σ		Σ	
Σ		Σ		$oldsymbol{\Sigma}$		Σ	
Σ		Σ		Σ		Σ	
0	1	2	3	0	1	2	3


# **Example - Adding on a Hypercube (Non-optimal Algorithm)**

(sum 16 numbers on 4 processors (non-optimally))



**Example - Adding on a Hypercube (Non-optimal Algorithm)** 


(sum 16 numbers on 4 processors (non-optimally))



14

# **Example - Adding on a Hypercube (Non-optimal Algorithm)**

(sum 16 numbers on 4 processors (non-optimally))



- First log p steps (until only one processor left) of the log n steps are done in
  - (n/p) log p steps on p processors
- Remaining steps require no communication, therefore, adding n/p numbers takes n/p time

### **Example - Adding on a Hypercube**

(sum 16 numbers on 4 processors (non-optimally))

 Expected computational time from our previous example of n-processor hypercube:

$$T_p = \Theta\left(\frac{n}{p}\log n\right)$$

 However what we find in this analysis for a p-processor hypercube and n-words:

$$T_p = \Theta\left(\frac{n}{p}\log p\right)$$

and the speedup and efficiency would be

$$S_{p} = \Theta\left(\frac{n}{\frac{n}{p}\log p}\right) = \Theta\left(\frac{p}{\log p}\right) \qquad E_{p} = \frac{S_{p}}{n} = \Theta\left(\frac{p}{n\log p}\right)$$

• For 16 words on 4 processors, E<sub>p</sub> =12% (worse – because it is non-optimal). Increasing work-load doesn't help!!

## **Example - Adding on a Hypercube**

(sum 16 numbers on 4 processors (non-optimally))

- This example shows that if you have a bad parallel algorithm, increasing work-load will not necessarily help
- We must go back and change the algorithm to make it more optimal

**Example - Adding on a Hypercube (Optimal)** 

(Sum 16 numbers on 4 processors optimally)

step 1 step 2 12 adds 2 communications step 3 step 4 2 adds 1 communication and 1 add

3 communications

and 15 adds







18

# **Example - Adding on a Hypercube**

(sum 16 numbers on 4 processors optimally)

• Total computation time, assuming it takes one unit of time to add two numbers and one unit of time to transfer a number between neighboring processors

$$T_p = \left(\frac{n}{p} - 1\right) + 2\log p \approx \frac{n}{p} + 2\log p$$

Speedup

$$S_p = \frac{n}{\frac{n}{p} + 2\log p} = \frac{np}{n + 2p\log p}$$

### **Example - Adding on a Hypercube**

(sum 16 numbers on 4 processors optimally)
• Efficiency:  $E_p = \frac{S_p}{p} = \frac{n}{n+2p\log p}$ 


- For 16 numbers on 4 processors,  $E_n = 50\%$  (much better!!!)

-	<u> </u>						
	Р	Sp	Ep				
	2	1.6	0.8				
	4	2.0	0.5				
	8	2.0	0.25				
	16	1.78	0.11				

### Note that:

- Speedup does not increase linearly with the number of processors
- Speedup increases with larger vector sizes (for fixed p)
- If we scale the problem at the same time we increase the number of processors, and efficiency remains constant, we have a scalable system and algorithm


## **Example - Adding on a Hypercube**



21


23

### **Example - Adding on a Hypercube**




### **Realistic Test Case**

### • A multi-block flow solver. Not very different!!!



### A Scalable Version of Another Multi-Block Flow Solver



### **Granularity**

- Often, the concept of *granularity* is what matters most.
- Granularity: Ratio of amount of communication that a processor requires to the amount of computation that it performs
- Coarse grain parallelism (low granularity): typical MPI applications. Decrease communication overhead. Most suitable for low performance networks (but also for high performance, of course).

### **Granularity**

- Fine grain parallelism (high granularity): most typical in OpenMP and GPU applications where small portions of computation (such as operations inside a loop) are divided among multiple processors.
- Fine grain parallelism requires high performance network/memory subsystems.

25

## **Granularity**

- Note the inherent benefit in scaling up the problem size for a block of typical dimension, *L*:
  - Amount of communication is proportional to the surface area of the block  $\approx L^2$
  - Amount of computation is proportional to the volume of the block  $\approx L^3$
- Therefore, as the problem gets larger, the granularity decreases  $\approx \frac{1}{L}$

### **Bandwidth**

- Bandwidth is the rate of information transfer that a communication subsystem can maintain (Mb/sec)
  - Bandwidth that matters is software bandwidth (using MPI, for example)
  - More is better (... and much more expensive)
  - To minimize communication overhead, send only necessary information
  - Typical number: 60 Mb/sec for Origin2000, 85 Mb/sec for Matrx, 775 Mb/sec for Davistron, 440 Mb/sec for Vortex or Wopr

### Latency

- Latency is defined as the time it takes to send a zerolength message from one processor to another (measured in microseconds, typically)
  - Less is better (... and more expensive)
  - Software latency (MPI, for example) matters
  - Impacts short messages mostly (and algorithms that rely heavily on short messages, i.e. multigrid)
  - Try to agglomerate messages if possible to decrease communication cost.
  - Typical number: 15 microseconds for SGI Origin2000, 50 microseconds for Matrx, 1.3 microseconds for Davistron, 2 microseconds for Vortex

29

### Homework 7

- Read Chapter 7 of <u>Introduction to Parallel</u> <u>Computing</u> by Grama et al
  - Read about shared-memory parallel computing and OpenMP
  - A good tutorial and users' manual on OpenMP is: https://computing.llnl.gov/tutorials/openMP/