




```
MLS1_503610(config)#int vl 60
MLS1_503610(config-if)#no ip add
MLS1_503610(config-if)#no vl 60
```

```
MLS2_503610(config)#no vl 60
MLS2_503610(config)#
```

```
MLS2_503610(config)#no vl 60
```

```
Router(config)#hostname ServerSite_503610
ServerSite_503610(config)#line console 0
ServerSite_503610(config-line)#password 123
ServerSite_503610(config-line)#login
ServerSite_503610(config-line)#exit
ServerSite_503610(config)#enable pass 123
ServerSite_503610(config)#no ip domain-lookup
ServerSite_503610(config)#banner motd #Server Site, No Unauthorized Access!!#
ServerSite_503610(config)#service password-encryption
ServerSite_503610(config)#do wr
Building configuration...
[OK]
ServerSite_503610(config)#ip domain-name nagoya.net
ServerSite_503610(config)#username nagoyaserver password 123
ServerSite_503610(config)#crypto key generate rsa
The name for the keys will be: ServerSite_503610.nagoya.net
Choose the size of the key modulus in the range of 360 to 2048 for your
General Purpose Keys. Choosing a key modulus greater than 512 may take
a few minutes.
```

```
How many bits in the modulus [512]: 1024
% Generating 1024 bit RSA keys, keys will be non-exportable...[OK]
```

```
ServerSite_503610(config)#line vty 0 15
*Mar 1 0:4:27.262: %SSH-5-ENABLED: SSH 1.99 has been enabled
ServerSite_503610(config-line)#login local
ServerSite_503610(config-line)#transport input ssh
ServerSite_503610(config-line)#exit
ServerSite_503610(config)#line vty 0 15
ServerSite_503610(config-line)#ip ssh version 2
ServerSite_503610(config)#do wr
Building configuration...
[OK]
```

```

ServerSite_503610(config)#int se0/0/0
ServerSite_503610(config-if)#cl ra 64000
This command applies only to DCE interfaces
ServerSite_503610(config-if)#no sh

ServerSite_503610(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

ServerSite_503610(config-if)#int se0/0/0
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0,
changed state to up

ServerSite_503610(config-if)#int se0/0/1
ServerSite_503610(config-if)#cl ra 64000
This command applies only to DCE interfaces
ServerSite_503610(config-if)#no sh

Enter configuration commands, one per line. End with CTRL-Z
Switch(config)#hostname Switch_ServerSite_503610
Switch_ServerSite_503610(config)#line console 0
Switch_ServerSite_503610(config-line)#password 123
Switch_ServerSite_503610(config-line)#login
Switch_ServerSite_503610(config-line)#exit
Switch_ServerSite_503610(config)#enable pass 123
Switch_ServerSite_503610(config)#no ip domain-lookup
Switch_ServerSite_503610(config)#banner motd #Serve Site, No
Unauthorized Access!!#
Switch_ServerSite_503610(config)#service password-encryption
Switch_ServerSite_503610(config)#do wr
Building configuration...
[OK]

Switch_ServerSite_503610(config)#int range fa0/2-5
Switch_ServerSite_503610(config-if-range)#sw mo acc
Switch_ServerSite_503610(config-if-range)#sw po max 1
Switch_ServerSite_503610(config-if-range)#sw po mac stick
Switch_ServerSite_503610(config-if-range)#sw po vi sh
Switch_ServerSite_503610(config-if-range)#int range
fa0/6-24,g0/1-2
Switch_ServerSite_503610(config-if-range)#sw mo acc
Switch_ServerSite_503610(config-if-range)#sw acc vl 99
% Access VLAN does not exist. Creating vlan 99

ISP1_503610(config)#int se0/0/1
ISP1_503610(config-if)#ip add 195.136.17.17 255.255.255.252

ISP2_503610(config)#int se0/0/0
ISP2_503610(config-if)#ip add 195.136.17.21 255.255.255.252

ServerSite_503610(config)#int se0/0/0
ServerSite_503610(config-if)#ip add 195.136.17.22
255.255.255.252
ServerSite_503610(config-if)#int se0/0/1
ServerSite_503610(config-if)#ip add 195.136.17.18
255.255.255.252

ServerSite_503610(config-if)#int g0/1
ServerSite_503610(config-if)#ip add 172.16.3.129
255.255.255.240

ServerSite_503610(config)#router ospf 10
ServerSite_503610(config-router)#router-id 7.7.7.7
ServerSite_503610(config-router)#network 172.16.3.128
0.0.0.15 area 0
ServerSite_503610(config-router)#network 195.136.17.16
0.0.0.3 area 0
ServerSite_503610(config-router)#network 195.136.17.20
0.0.0.3 area 0

ISP1_503610(config)#router ospf 10
ISP1_503610(config-router)#network 195.136.17.16 0.0.0.3 area
0

```

```
ISP2_503610(config)#router ospf 20
ISP2_503610(config-router)#network 195.136.17.20 0.0.0.3 area
0
```

ServerSite_DHCPServer_503610

Physical Config Services Desktop Programming

IP Configuration

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 172.16.3.133

Subnet Mask 255.255.255.240

Default Gateway 172.16.3.129

DNS Server 172.16.3.131

ServerSite_DNSServer_503610

Physical Config Services Desktop Programming

IP Configuration

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 172.16.3.131

Subnet Mask 255.255.255.240

Default Gateway 172.16.3.129

DNS Server 172.16.3.131

ServerSite_MailServer_503610

Physical Config Services Desktop Programming

IP Configuration

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 172.16.3.136

Subnet Mask 255.255.255.240

Default Gateway 172.16.3.129

DNS Server 172.16.3.131

ServerSite_WebServer_503610

Physical Config Services Desktop Programming

IP Configuration

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 172.16.3.137

Subnet Mask 255.255.255.240

Default Gateway 172.16.3.129

DNS Server 172.16.3.131

```

ISP1_503610(config)#access-list 10 permit 172.16.3.0
0.0.0.127
ISP1_503610(config)#access-list 10 deny any
ISP1_503610(config)#line vty 0 15
ISP1_503610(config-line)#access-class 10 in

ServerSite_503610(config)#access-list 10 permit 172.16.3.0
0.0.0.127
ServerSite_503610(config)#access-list 10 deny any
ServerSite_503610(config)#line vty 0 15
ServerSite_503610(config-line)#access-class 10 in

ISP2_503610(config)#access-list 10 permit 172.16.3.0
0.0.0.127
ISP2_503610(config)#access-list 10 deny any
ISP2_503610(config)#line vty 0 15
ISP2_503610(config-line)#access-class 10 in

RTR1_503610(config)#access-list 10 permit 172.16.3.0
0.0.0.127
RTR1_503610(config)#access-list 10 deny any
RTR1_503610(config)#line vty 0 15
RTR1_503610(config-line)#access-class 10 in

RTR2_503610(config)#access-list 10 permit 172.16.3.0
0.0.0.127
RTR2_503610(config)#access-list 10 deny any
RTR2_503610(config)#line vty 0 15
RTR2_503610(config-line)#access-class 10 in

MLS1_503610(config)#access-list 10 permit 172.16.3.0
0.0.0.127
MLS1_503610(config)#access-list 10 deny any
MLS1_503610(config)#line vty 0 15
MLS1_503610(config-line)#access-class 10 in

MLS2_503610(config)#access-list 10 permit 172.16.3.0
0.0.0.127
MLS2_503610(config)#access-list 10 deny any
MLS2_503610(config)#line vty 0 15
MLS2_503610(config-line)#access-class 10 in

RTR1_503610(config)#license boot module c2900 technology-
package securityk9

RTR1_503610(config)#do reload
Proceed with reload? [confirm]
System Bootstrap, Version 15.1(4)M4, RELEASE SOFTWARE (fc1)
Technical Support: http://www.cisco.com/techsupport

RTR1_503610(config)#access-list 110 permit ip 172.16.1.0
0.0.0.255 172.16.3.128 0.0.0.15
RTR1_503610(config)#crypto isakmp policy 110

RTR1_503610(config-isakmp)#encryption aes 256
RTR1_503610(config-isakmp)#authentication pre-share
RTR1_503610(config-isakmp)#group 5
RTR1_503610(config-isakmp)#exit
RTR1_503610(config)#crypto isakmp key vpnpa55 address
195.136.17.18
RTR1_503610(config)#crypto ipsec transform-set VPN-SET esp-
aes esp-sha-hmac
RTR1_503610(config)#crypto map VPN-MAP 10 ipsec-isakmp
% NOTE: This new crypto map will remain disabled until a peer
and a valid access list have been configured.
RTR1_503610(config-crypto-map)#description VPN Connection to
Main-Site
RTR1_503610(config-crypto-map)#set peer 195.136.17.18
RTR1_503610(config-crypto-map)#set transform-set VPN-SET
RTR1_503610(config-crypto-map)#match address 110
RTR1_503610(config-crypto-map)#exit
RTR1_503610(config)#int se0/3/0
RTR1_503610(config-if)#crypto map VPN-MAP
*Jan 3 07:16:26.785: %CRYPTO-6-ISAKMP_ON_OFF: ISAKMP is ON
RTR1_503610(config-if)#do wr

```

```
ServerSite_503610(config)#license boot module c2900  
technology-package securityk9
```

```
ServerSite_503610(config)#do reload
```

```
ServerSite_503610(config)#access-list 110 permit ip 172.16.3.128 0.0.0.15 172.16.1.0 0.0.0.255  
ServerSite_503610(config)#crypto isakmp policy 110  
ServerSite_503610(config-isakmp)#encryption aes 256  
ServerSite_503610(config-isakmp)#authentication pre-share  
ServerSite_503610(config-isakmp)#group 5  
ServerSite_503610(config-isakmp)#exit  
ServerSite_503610(config)#crypto isakmp key vpnpa55 address 195.136.17.1  
ServerSite_503610(config)#crypto ipsec transform-set VPN-SET esp-aes esp-sha-hmac  
ServerSite_503610(config)#crypto map VPN-MAP 10 ipsec-isakmp  
% NOTE: This new crypto map will remain disabled until a peer  
and a valid access list have been configured.  
ServerSite_503610(config-crypto-map)#description VPN Connection to Main-Site  
ServerSite_503610(config-crypto-map)#set peer 195.136.17.1  
ServerSite_503610(config-crypto-map)#set transform-set VPN-SET  
ServerSite_503610(config-crypto-map)#match address 110  
ServerSite_503610(config-crypto-map)#exit
```

```
ServerSite_503610(config)#int se0/0/0  
ServerSite_503610(config-if)#crypto map VPN-MAP  
*Jan 3 07:16:26.785: %CRYPTO-6-ISAKMP_ON_OFF: ISAKMP is ON  
ServerSite_503610(config-if)#do wr  
Building configuration...  
[OK]
```