

# **Building Root filesystem**

The organization of sub-directories and files in **linux root filesystem** (/) is well-defined by the Filesystem Hierarchy Standard, and is as follows:

/bin Basic programs

**/boot** Kernel image

**/dev** Device files

**/etc** System-wide configuration

**/home** Directory for the users home directories

/lib Basic libraries

/media Mount points for removable media

**/mnt** Mount points for static media

/proc Mount point for the proc virtual filesystem

**/root** Home directory of the root user

/sbin Basic system programs

/sys Mount point of the sysfs virtual filesystem

**/tmp** Temporary files

/usr

/usr/bin Non-basic programs
/usr/lib Non-basic libraries

/usr/sbin Non-basic system programs

**/var** Variable data files. This includes spool directories

and files, administrative and logging data, and

transient and temporary files



Creating root filesystem for a target machine is, creating required directories and populating them with appropriate files.

## Creating minimal Root filesystem

Create a work space for root filesystem to be built:

# mkdir roofs

# cd rootfs

Now create the root filesystem structure for target machine:

# mkdir dev proc sys etc bin sbin lib mnt usr usr/bin usr/sbin

#### Populate bin, sbin, usr/bin, usr/sbin

- Binaries for target machine is created using busybox.
- A Linux system needs a basic set of programs to work
  - An init program
  - A shell
  - Various basic utilities for file manipulation and system configuration
- Busybox is an alternative solution, extremely common on embedded systems
  - Rewrite of many useful Unix command line utilities
  - Integrated into a single project, which makes it easy to work with
  - Designed with embedded systems in mind: highly configurable, no unnecessary features
- All the utilities are compiled into a single executable, /bin/busybox, symbolic links to /bin/busybox are created for each application integrated into Busybox



# Configure Busybox Download busybox source from <a href="http://busybox.net">http://busybox.net</a> and extract it: # tar -xvf <archived-busybox-source-file> Configure busybox, # make menuconfig as follows: Busybox Settings ---> Build Options ---> [\*] Build BusyBox as a static binary (no shared libs) Coreutils--> [\*] sync [] syncfs Linux System Utilities ---> [\*] mdev [] nsenter Compile busybox using cross-compiler: # make CROSS\_COMPILE=\$(PREFIX-CROSSCOMPILER) Example: # make CROSS\_COMPILE=arm-linux-Install the commands in target root filesystem: # make CROSS\_COMPILE=arm-linux- CONFIG\_PREFIX=<path-to-rootfs> install



Example:

# make CROSS\_COMPILE=arm-linux-

CONFIG\_PREFIX=/root/elinux/workspace/rootfs install

#### Populate etc

#### <u>init:</u>

- Init is the first process started during booting, and is typically assigned PID number 1.
- Its primary role is to create processes from a scriptstored in the file /etc/inittab file.
- It is started by the kernel, and if the kernel is unable to start it, a kernel panic will result.
- All System V init scripts are stored in /etc/rc.d/init.d/ or /etc/init.d directory. These scripts are used to control system startup and shutdown.
- BusyBox can handle the system's startup. BusyBox /sbin/init is particularly well adapted to embedded systems, because it provides most of the init functionality an embedded system typically needs without dragging the weight of the extra features found in System V init.
  - BusyBox init does not provide runlevel support.
  - The **init** routine of BusyBox carries out the following main tasks in order:
    - 1. Sets up signal handlers for init.
    - 2. Initializes the console(s).
    - 3. Parses the inittab file, /etc/inittab.
    - 4. Runs the system initialization script. /etc/init.d/rcS is the default for BusyBox.
    - 5. Runs all the inittab commands that block (action type: wait).
    - 6. Runs all the inittab commands that run only once (action type: once).
- Once it has done this, the init routine loops forever carrying out the following tasks:



- 1. Runs all the inittab commands that have to be respawned (action type: respawn).
- 2. Runs all the inittab commands that have to be asked for first (action type: askfirst).

#### Create inittab file in etc

Each line in the inittab file follows this format:

#### id:runlevel:action:process

id - specify the tty for the process to be started.
 runleven - completely ignores the runlevel field
 action - can be any of the following:

Action	Effect
1. sysinit	Provide init with the path to the initialization
	script.
2. respawn	Restart the process every time it terminates.
3. askfirst	Similar to respawn, but It prompts init to display
	"Please press Enter to activate this console."
4. wait	Tell init that it has to wait for the process to
	complete before continuing.
5. once	Run process only once without waiting for them.
6. ctrlaltdel	Run process when the Ctrl-Alt-Delete key
	combination is pressed.
7. shutdown	Run process when the system is shutting down.
8. restart	Run process when init restarts. Usually, the
X Y	process to be run here is init itself.

Sample inittab file for beaglebone:

# cd <path-to-rootfs>/etc



#### # vim inittab

Copy following commands into inittab file and save it:

# Startup the system

null::sysinit:/etc/init.d/rcS

# Start getty on serial for login

ttyO0::respawn:/sbin/getty -L ttyO0 115200 vt100

# Stuff to do before rebooting

null::shutdown:/bin/umount -a -r

#### This inittab file does the following:

- 1. Sets /etc/init.d/rcS as the system initialization file.
- 2. Starts getty on serial port.
- 3. Tells init to run the umount command to unmount all filesystems it can at system shutdown

# Create profile file in etc

profile file has environment variables.

# vim profile

Copy the following into profile file and save it:

# Used for prompt format

PS1='[\u@\h:\W]\#'

PATH=\$PATH

HOSTNAME='/bin/hostname'

export HOSTNAME PS1 PATH

## Create passwd file

passwd file has user's password information.



#### # vim passwd

Copy following command for veda user and save it:

veda::0:0:root:/root:/bin/sh

#### - Create rcS file under /etc/init.d

- This script can be quite elaborate and can actually call other scripts.
- Use this script to set all the basic settings and initialize the various components of the system like Mount additional filesystems, Initialize and start networking interfaces.
- Start system daemons.

Sample rcS file for beaglebone:

# mkdir init.d
# vim init.d/rcS

Copy follwing commands into the rcS file and save it:
#!/bin/sh
# -----# Mounting procfs
# -----mount -n -t proc null /proc
# -----# Mounting sysfs
# -----mount -n -t sysfs null /sys
# -----# Mounting ramfs to /dev
# -----mount -n -t ramfs null /dev
# -----# Create /dev/shm directory and mount tmpfs to /dev/shm



```
# -----
mkdir -p /dev/shm
/bin/mount -n -t tmpfs tmpfs /dev/shm
# -----
# Enabling hot-plug
# -----
echo "/sbin/mdev" > /proc/sys/kernel/hotplug
# -----
# Start mdev
# -----
mdev -s
# -----
# Set PATH
# -----
export PATH=/bin:/sbin:/usr/bin:/usr/sbin:/usr/local/bin
# -----
# Set ip address
# -----
/sbin/ifconfig lo 127.0.0.1 up
/sbin/ifconfig eth0 10.0.0.111 up
# -----
sleep 3
# -----
# Assigning hostname
# -----
/bin/hostname boneblack
Give executable permissions to rcS script file:
# chmod +x init.d/rcS
```



#### Populate dev

As part of inittab & rcs files as we are using "null & ttyO0" device nodes we need to create them manually.

Create device nodes for beagle bone:

```
# cd <path-to-rootfs>/dev
```

# mknod console c 5 1

# mknod null c 1 3

# mknod tty00 c 204 64

#### Populate lib

As we used buildroot for building cross-compiler copy all libs created by buildroot for target machine.

# cp -Rfp <path-to-buildroot-source>/output/host/usr/arm-buildroot-linux-uclibcgnueabi/lib/\* <path-to-rootfs>/lib

# cp -Rfp <path-to-buildroot-source>/output/host/usr/arm-buildroot-linux-uclibcgnueabi/sysroot/lib/\* <path-to-rootfs>/lib

# cp -Rfp <path-to-buildroot-source>/output/host/usr/arm-buildroot-linux-uclibcgnueabi/sysroot/usr/lib/\* <path-to-rootfs>/lib

# cp -Rfp <path-to-buildroot-source>/output/host/usr/lib/\* <path-to-rootfs>/lib

- And copy other libraries cross-compiled for target machine.

# Install kernel modules



- At the time of building kernel if ant service is selected as modules, than we neet to install those modules as part of target root file system.
- The following command will install kernel modules in target root file system
- Change directory to cross-compiled linux kernel and give following command:

# cd <path-to-linux-source>

# make ARCH=arm CROSS\_COMPILE=arm-linux- modules

# make ARCH=arm CROSS\_COMPILE=arm-linux-INSTALL\_MOD\_PATH=<path-to-rootfs> modules\_install

