Chapter 1. Components of the EchoMix mixnet

Table of Contents

Directory authorities
Configuring directory authorities
Mix, gateway, and service nodes
Configuring mix nodes
Configuring gateway nodes
Configuring service nodes

Directory authorities

Directory authorities, or *dirauths*, are nodes in EchoMix's decentralized public key infrastructure (PKI), which forms the security root of the entire EchoMix system. Clients and mixnet nodes rely on the PKI to maintain and sign an up-to-date *consensus* document, providing a view of the entire network including connection information and public cryptographic key materials and signatures.

Every 20 minutes (the current value for an *epoch*), each mix node signs a descriptor and uploads it to the dirauth nodes. The dirauths then vote on a new consensus document. If consensus is reached, each dirauth signs the document. Clients and nodes download the document as needed and verify the signatures. Consensus fails when 1/2 + 1 nodes fail, which yields greater fault tolerance than, for example, Byzantine Fault Tolerance, which fails when 1/3 + 1 of the nodes fail.

The PKI signature scheme is fully configurable by the dirauth nodes. Our recommendation is to use a hybrid signature scheme consisting of the classical Ed25519 and the post-quantum, stateless, hash-based signature scheme known as Sphincs+ (with the parameters: "sphincs-shake-256f"), which is designated in EchoMix configurations as "Ed25519 Sphincs+". Examples are provided below.

Configuring directory authorities

The following configuration is drawn from the reference implementation in katzenpost/dock-er/voting_mixnet/auth1/authority.toml. In a real-world mixnet, the component hosts would not be sharing a single IP address. For more information about the test mixnet, see Using the EchoMix test network.

Server section

```
[Server]
   Identifier = "auth1"
   WireKEMScheme = "xwing"
   PKISignatureScheme = "Ed25519 Sphincs+"
   Addresses = ["tcp://127.0.0.1:30001"]
   DataDir = "/voting_mixnet/auth1"
```

Identifier

Identifier is the human-readable identifier for a node, and should be unique per mixnet. It can be an FQDN but does not have to be.

Type: string

Required:

WireKEMScheme

WireKEMScheme specifies the key encapsulation mechanism (KEM) scheme for the PQ Noise [https://eprint.iacr.org/2022/539]-based wire protocol (link layer) that nodes use to communicate with each other. PQ Noise is a post-quantum variation of the Noise protocol framework [https://noiseprotocol.org/], which algebraically transforms ECDH handshake patterns into KEM encapsulate/decapsulate operations.

This configuration option supports the optional use of post-quantum cryptography to strengthen security. The following KEM schemes are supported:

• Classical: "x25519", "x448"

"sntrup4591761", "mceliece348864", Post-quantum: "mlkem768", "frodo640shake", "mceliece348864f", "mceliece460896", "mceliece460896f". "mceliece6688128". "mceliece6960119", "mceliece6960119f", "mceliece6688128f", "mceliece8192128", "mceliece8192128f", "xwing", "Kyber768-X25519", "MLKEM768-X25519", "MLKEM768-X448", "CTIDH511", "CTIDH512", "CTIDH1024", "CTIDH2048", "CTIDH512-X25519", "CTIDH512-X25519"

Type: string Required: Yes

• PKISignatureScheme

PKISignatureScheme specifies the cryptographic signature scheme which will be used by all components of the mix network when interacting with the PKI system. Mix nodes will sign their descriptors using this signature scheme. Likewise PKI documents will be signed by the dir auth nodes using this signature scheme.

The following signature schemes are supported: "ed25519", "ed448", "Ed25519 Sphincs+", "Ed448-Sphincs+", "Ed25519-Dilithium2", "Ed448-Dilithium3"

Type: string

Required:

Addresses

Addresses specifies a list of one or more Address URLs in a format that contains the transport protocol, IP address and port number that the server will bind to for incoming connections. Currently EchoMix supports URLs with that start with either "tcp://" or "quic://" such as: ["tcp://192.168.1.1:30001"] and ["quic://192.168.1.1:40001"]

Type: []string

Required:

DataDir

DataDir is the absolute path to the directory authority server's state directory where the persistence.db will be written to disk AND where the server's cryptographic key materials will be written to disk when started with the "-g" commmandline option.

Type: string

Required:

Authorities section

An Authorities section is configured for each peer authority. We recommend using TOML's muli-line quotes for key materials.

```
[[Authorities]]
    Identifier = "auth1"
    IdentityPublicKey = """
----BEGIN ED25519 PUBLIC KEY----
dYpXpbozjFfqhR45ZC2q97SOOSXMANdHaEdXrP42CJk=
----END ED25519 PUBLIC KEY----
"""
    PKISignatureScheme = "Ed25519"
    LinkPublicKey = """
----BEGIN XWING PUBLIC KEY----
ooQBPYNdmfwnxXmvnljPA2mG5gWgurfHhbY87DMRY2tbNQqxcS9o36IS62SVMlOUkw+XEZGVvc9wJqHpgEgVJRAs1ESPKDCtZ3GiSIOZMuaglo2tarIPEv1AY7r9B0xXOgSKMkC
```

ooQBPYNdmfwnxXmvnljPA2mG5gWgurfHhbY87DMRY2tbMeZpinJ5BlSiIecprnmm QqxcS9o36IS62SVMlOUkw+XEZGVvc9wJqHpgEgVJRAs1PCR8cUAdM6QIYLWt/lkf SPKDCtZ3GiSIOzMuaglo2tarIPEv1AY7r9B0xXOgSKMkGyBkCfw1VBZf46MM26NL opKx+rAKBzjKBJgGg9AHt9rNQsBbCVFBO+KKbpHHXFCBztK1Hhei3LeeYxcqL4bC Rzi2kfBvQLPNzIuHOktKX7m39CxMByMNm4qL6dSVbtZaMOenpUlsIHOR5vyF2bgX syRS3WnPRaIOarkMXUwJpzasNzuPUSAmJyaAQVwgrTSJyXp91usF6wBHKApq1DVY dldqH7O90EI1tYNiOYpBCgwGBIK+xOkjoVNY91B/PVbA5ngcXgt8xQp02WXF11VN +ixu2XF8ndJXtLmlTIMUb0YwHsEo9UqdN7yLMPqcVScqR+ZKyCpaIPS+dpF20AAu fvVVlxKVLqonUkJLCMgR/4morUOXVHwRgkKr0mIuw9RTWwSlSGxasFiVFZM5p6kS EligPlCX94xV52BjcerPQ1R2TJdlVdWgLUAO7UNhyETCGrdxjxZSYmxNjfsOLHk7 qFNNDhUqHBjJmYOSDis0qHNXW8oZ9SF6pFN9NlctH8Uq10c/fNltykEbTkgLdMJP phWWVOWD1YIU+/kt05ZNVIVK/CHOqdc41+mRyxh/OmbEWMaaicuijLNR3KV9OoHG 9JWw9RtrPeE+jbgUX0g0asFf0nibfWqdV5QfAfwV/shYuIJR4nZMb6B4R9t8wYd0 gCSZg1M7gJW1J5B17cPM6+OCz2JaYhgAHfvJhSYK3zGzWWvGWvKTJrSTjiIhX8wM H/KiX5U8+nkWPDiu/nqyRVej8/ELYvg7T2R7tKJzB0Gr5GUFd3B1TzvAcIRBl+yd 9ma5tRE44culy0Nuc1N8ITp8xqezSjwdavoMeuphryd6xbacZCVCcnM2R5mGOAhI xzQWA5teHxoBTnliRQq1HriKX8N8Ogq3GPYu0Lue+MwEkkRkxSJdNpSLE/yzOQkf DrlBbbURIfelT6aeAlSuXeacTzqd6lfPWvjCgXMYriwhAazKwgS+WwcXd5RKbWEN PIISgRavtoahEdOVSJJbVMUYptA3+CcY9eEi/rWOc1RgTWGNtWW0FYnFyiq6UdPM NiO/z7S9uJJI/2wWMlJi+OoTx9cf3mjIMOPLkzEOhpVRhCZvcSvFIoF6ItcETnda HmmOFwFg2req1PioBORUufk7zdhs0MuuMY1aG+E0OqxTOKiZg0qbgMZqtOlsXkp8 QdY8R/W4ePiVAI2iZnMzEqMl3LLEDlRdMOkBYzOkR2GSvpYv6tetgoNAu8vFkpc6 Rma3y7KnihWaYhwEFbEqV2kD2GO9cMV+AcFvuCE9dVGVSatdxsSNX6ZXaFGlmHCp gHtNyQJnXski52003JpZRIhR40pFOhAAcMMAZDpMTVoxlcdR6WA4SlBiSceeJBgY Yp9PlGhCimx9am99TrdLoLCdTHB6oowt8tss3POpIOxaSlguyeym/sBhkUrnXOgN ldMtDsvvc9KUfE4I0+c+XQ==

```
----END XWING PUBLIC KEY----
"""

WireKEMScheme = "xwing"

Addresses = ["tcp://127.0.0.1:30001"]
```

Identifier

Identifier is the human readable identifier for the node which should be unique per mixnet. It can be an FQDN but certainly doesn't have to be.

Type: string

Required:

IdentityPublicKey

String in PEM format containing the public identity key. The node's public identity key is the node's permanent identifier and is used to verify cryptographic signatures produce by node's private identity key.

Type: string

Required:

• PKISignatureScheme

PKISignatureScheme specifies the cryptographic signature scheme used by all of the directory authority nodes. This PKISignatureScheme must match the scheme specified in the Server section of the configuration.

Type: string

Required:

LinkPublicKey

LinkPublicKeyPem is string containing the PEM format of the peer's public link layer key. The EchoMix "link layer" protocol is the PQ Noise based protocol which is sometimes also referred to as the "wire protocol". The type of this link public key must match the specified WireKEMScheme. Our wire protocol is used to secure the transport between nodes only and in this case it's used between directory authority nodes when they communicate with each other for the voting rounds and it's also the protocol that clients use to retrieve published PKI documents from the dir auth nodes.

Type: string

Required:

WireKEMScheme

WireKEMScheme specifies the key encapsulation mechanism (KEM) scheme for the PQ Noise [https://eprint.iacr.org/2022/539]-based wire protocol (link layer) that nodes use to communicate with each other. PQ Noise is a post-quantum variation of the Noise protocol framework [https://noiseprotocol.org/], which algebraically transforms ECDH handshake patterns into KEM encapsulate/decapsulate operations.

This configuration option supports the optional use of post-quantum cryptography to strengthen security. The following KEM schemes are supported:

```
• Classical: "x25519", "x448"
```

```
• Post-quantum: "mlkem768", "sntrup4591761", "frodo640shake", "mceliece348864", "mceliece460896", "mceliece460896f", "mceliece6688128f", "mceliece6960119", "mceliece6960119f", "mceliece8192128",
```

"mceliece8192128f", "xwing", "Kyber768-X25519", "MLKEM768-X25519", "MLKEM768-X448", "CTIDH511", "CTIDH512", "CTIDH1024", "CTIDH2048", "CTIDH512-X25519", "CTIDH512-X25519"

Type: string Required: Yes

Addresses

Addresses specifies a list of one or more Address URLs in a format that contains the transport protocol, IP address and port number that the server will bind to for incoming connections. Currently EchoMix supports URLs with that start with either "tcp://" or "quic://" such as: ["tcp://192.168.1.1:30001"] and ["quic://192.168.1.1:40001"]

Type: []string Required:

Logging section

The logging configuration section controls logging.

```
[Logging]
  Disable = false
  File = "katzenpost.log"
  Level = "INFO"
```

• Disable

Disables logging if set to true.

Type: bool

Required:

• File

Specifies the log file. If omitted, stdout is used.

An absolute or relative file path can be specified. A relative path is relative to the DataDir specified in the Server section of the configuration.

Type: string

Required:

Level

Supported values are ERROR | WARNING | NOTICE | INFO | DEBUG.

Type: string Required:



Warning

The DEBUG log level is unsafe for production use.

Parameters section

The Parameters section holds the network parameters, for example:

```
[Parameters]

SendRatePerMinute = 0

Mu = 0.005

MuMaxDelay = 1000

LambdaP = 0.001

LambdaPMaxDelay = 1000

LambdaL = 0.0005

LambdaLMaxDelay = 1000

LambdaD = 0.0005

LambdaDMaxDelay = 3000

LambdaM = 0.0005

LambdaG = 0.0

LambdaGMaxDelay = 100

LambdaGMaxDelay = 100

LambdaGMaxDelay = 100
```

• SendRatePerMinute

SendRatePerMinute is the maximum allowed rate of packets per client per gateway node. Rate limiting is done on the gateway nodes.

SendRatePerMinute is the rate per minute.

Type: uint64

Required:

• Mu

Mu is the inverse of the mean of the exponential distribution that the Sphinx packet per-hop mixing delay will be sampled from. Mu is the inverse of the mean of the exponential distribution that is used to select the delay for each hop.

Type: float64

Required:

MuMaxDelay

MuMaxDelay is the maximum Sphinx packet per-hop mixing delay in milliseconds. MuMaxDelay sets the maximum delay for Mu.

Type: uint64

Required:

LambdaP

LambdaP is the inverse of the mean of the exponential distribution that clients will sample to determine the time interval between sending messages from it's FIFO egress queue or drop decoy messages if the queue is empty. LambdaP is the inverse of the mean of the exponential distribution that is used to select the delay between clients sending from their egress FIFO queue or drop decoy message.

Type: float64

LambdaPMaxDelay

LambdaPMaxDelay is the maximum send interval for LambdaP in milliseconds

LambdaPMaxDelay sets the maximum delay for LambdaP.

Type: uint64

Required:

LambdaL

LambdaL is the inverse of the mean of the exponential distribution that is used to select the delay between clients sending loop decoys.

Type: float64

Required:

LambdaLMaxDelay

sets the maximum send interval for LambdaL in milliseconds.

LambdaLMaxDelay sets the maximum delay for LambdaP.

Type: uint64

Required:

LambdaD

LambdaD is the inverse of the mean of the exponential distribution that clients will sample to determine the time interval between sending decoy drop messages. LambdaD is the inverse of the mean of the exponential distribution that is used to select the delay between clients sending deop decoys.

Type: float64

Required:

LambdaDMaxDelay

LambdaDMaxDelay is the maximum send interval in milliseconds. LambdaDMaxDelay sets the maximum delay for LambdaP.

Type: uint64

Required:

• LambdaM

LambdaM is the inverse of the mean of the exponential distribution that mixes will sample to determine send timing of mix loop decoy traffic. LambdaM is the inverse of the mean of the exponential distribution that is used to select the delay between sending mix node decoys.

Type: float64

LambdaG

LambdaG is the inverse of the mean of the exponential distribution that is used to select the delay between sending gateway node decoys. WARNING: DO NOT SET THIS VALUE. This is not used via the TOML config file; this field is used internally by the dirauth server state machine.

Type: float64 Required:

· LambdaMMaxDelay

LambdaMMaxDelay sets the maximum delay for LambdaM LambdaMMaxDelay sets the maximum delay for LambdaP.

Type: uint64

Required:

LambdaGMaxDelay

LambdaGMaxDelay sets the maximum delay for LambdaG.

Type: uint64

Required:

Debug section

```
[Debug]
  Layers = 3
  MinNodesPerLayer = 1
  GenerateOnly = false
```

Layers

Number of non-provider layers in the network topology.

Type: int

Required:

MinNodesrPerLayer

Minimum number of nodes per layer required to form a valid document.

Type: int

Required:

GenerateOnly

If set to true, the server halts and cleans up the data directory immediately after long-term key generation.

Type: bool

Mixes sections

The Mixes configuration section lists mix nodes that are known to the authority.

```
[[Mixes]]
    Identifier = "mix1"
    IdentityPublicKeyPem = "../mix1/identity.public.pem"

[[Mixes]]
    Identifier = "mix2"
    IdentityPublicKeyPem = "../mix2/identity.public.pem"

[[Mixes]]
    Identifier = "mix3"
    IdentityPublicKeyPem = "../mix3/identity.public.pem"
```

Identifier

A human readable mix node identifier.

Type: string

Required:

• IdentityPublicKeyPem

Path and file name of a mix node's public identity signing key, also known as the identity key, in PEM format.

Type: string

Required:

GatewayNodes sections

The GatewayNodes configuration section lists gateway nodes that are known to the authority.

```
[[GatewayNodes]]
    Identifier = "gateway1"
    IdentityPublicKeyPem = "../gateway1/identity.public.pem"
```

• Identifier

A human readable gateway node identifier.

Type: string

Required:

· IdentityPublicKeyPem

Path and file name of a gateway node's public identity signing key, also known as the identity key, in PEM format.

Type: string

Required:

ServiceNodes sections

The ServiceNodes configuration section lists service nodes that are known to the authority.

```
[[ServiceNodes]]
    Identifier = "servicenode1"
    IdentityPublicKeyPem = "../servicenode1/identity.public.pem"
```

• Identifier

A human readable service node identifier.

Type: string

Required:

· IdentityPublicKeyPem

Path and file name of a service node's public identity signing key, also known as the identity key, in PEM format.

Type: string

Required:

Topology section

The Topology configuration section defines the layers of the mix network and the mix nodes in each layer.

• Identifier

A human readable mix node identifier.

Type: string

· IdentityPublicKeyPem

Path and file name of a mix node's public identity signing key, also known as the identity key, in PEM format.

Type: string

Required:

SphinxGeometry section

WARNING: The Sphinx Geometry section of the configuration MUST be programmatically generated. Do NOT modify the geometry by hand.

The original Sphinx paper introduces the Sphinx nested encrypted packet format using a NIKE (NIKE: non-interactive key exchange). NIKE Sphinx can be a hybrid post quantum construction simply by using a hybrid NIKE. Our Sphinx implementation also can optionally use a KEM (KEM: key encapsulation mechanism) instead of a NIKE, however the trade-off is that the packet's header will take up a lot of overhead because it must store a KEM ciphertext for each hop. EchoMix has a completely configurable Sphinx geometry which allows for any KEM or NIKE to be used.

The Sphinx cryptographic packet format also uses these additional cryptographic primitives, the current EchoMix selection is:

• stream cipher: CTR-AES256

• MAC: HMAC-SHA256

• KDF: HKDF-SHA256

• SPRP: AEZv5

In EchoMix the dirauths select the Sphinx geometry, each dirauth must agree with the other dirauths. They publish the hash of the Sphinx Geometry in the PKI document so that the rest of the network entities can validate their Sphinx Geometry.

```
[SphinxGeometry]
  PacketLength = 3082
  NrHops = 5
  HeaderLength = 476
  RoutingInfoLength = 410
  PerHopRoutingInfoLength = 82
  SURBLength = 572
  SphinxPlaintextHeaderLength = 2
  PayloadTagLength = 32
  ForwardPayloadLength = 2574
  UserForwardPayloadLength = 2000
  NextNodeHopLength = 65
  SPRPKeyMaterialLength = 64
  NIKEName = "x25519"
```

```
KEMName = ""
· PacketLength
  PacketLength is the length of a packet.
  Type: int
  Required:
• NrHops
  NrHops is the number of hops through the mixnet, which determines the size
  of the Sphinx packet header.
  Type: int
  Required:
• HeaderLength
  HeaderLength is the length of the Sphinx packet header in bytes.
  Type: int
  Required:
· RoutingInfoLength
  RoutingInfoLength is the length of the routing info portion of the header.
  Type: int
  Required:
• PerHopRoutingInfoLength
  PerHopRoutingInfoLength is the length of the per hop routing info.
  Type: int
  Required:
• SURBLength
  SURBLength is the length of SURB.
  Type: int
  Required:
• SphinxPlaintextHeaderLength
  SphinxPlaintextHeaderLength is the length of the plaintext header.
  Type: int
```

· PayloadTagLength

 $Payload Tag Length \ is \ the \ length \ of \ the \ payload \ tag.$

Type: int

Required:

· ForwardPayloadLength

ForwardPayloadLength is the size of the payload.

Type: int

Required:

· UserForwardPayloadLength

the size of the usable payload.

Type: int

Required:

• NextNodeHopLength

NextNodeHopLength is derived off the largest routing info

block that we expect to encounter. Everything else just has a NextNodeHop + NodeDelay, or a Recipient, both cases which are shorter.

Type: int

Required:

SPRPKeyMaterialLength

SPRPKeyMaterialLength is the length of the SPRP key.

Type: int

Required:

NIKEName

NIKEName is the name of the NIKE (non-interactive key exchange) scheme used by the mixnet's Sphinx packets. NIKEName and KEMName are mutually exclusive.

Type: string

Required:

KEMName

KEMName is the name of the KEM scheme used by the mixnet's Sphinx packet. NIKEName and KEM-Name are mutually exclusive.

Type: string

Mix, gateway, and service nodes

Configuring mix nodes

The following configuration is drawn from the reference implementation in katzenpost/dock-er/voting_mixnet/mix1/katzenpost.toml. In a real-world mixnet, the component hosts would not be sharing a single IP address. For more information about the test mixnet, see Using the EchoMix test network.

Server section

```
[Server]
  Identifier = "mix1"
  WireKEM = "xwing"
  PKISignatureScheme = "Ed25519"
  Addresses = ["127.0.0.1:30008"]
  OnlyAdvertiseAltAddresses = false
  MetricsAddress = "127.0.0.1:30009"
  DataDir = "/voting_mixnet/mix1"
  IsGatewayNode = false
  IsServiceNode = false
  [Server.AltAddresses]
```

• Identifier

Identifier is the human-readable identifier for a node (for example, the FQDN) and must be unique for a given mixnet.

Type: string
Required: Yes

WireKEM

WireKEM is the wire protocol KEM (key encapsulation mechanism) scheme to use.

This configuration option supports the use of post-quantum cryptography to strengthen security. In this case the "Wire" protocol refers to our PQ Noise based protocol which is how all the dir auth nodes talk to one another. PQ Noise is a variation of the Noise protocol framework where the handshake patterns are algebraically transformed to replace ECDH operations with KEM encapsulate/decapsulate operations.

```
"x448".
                                                                    "x25519",
The
        following
                      KEM
                                schemes
                                                     supported:
                                             are
              "sntrup4591761",
                                 "frodo640shake",
                                                   "mceliece348864",
                                                                       "mceliece348864f".
"mceliece460896", "mceliece460896f", "mceliece6688128", "mceliece6688128f", "mceliece6960119",
"mceliece6960119f", "mceliece8192128", "mceliece8192128f", "xwing", "Kyber768-X25519",
"MLKEM768-X25519",
                       "MLKEM768-X448", "CTIDH511",
                                                            "CTIDH512",
                                                                           "CTIDH1024",
"CTIDH2048", "CTIDH512-X25519", "CTIDH512-X25519"
```

Type: string Required: Yes

• PKISignatureScheme

PKISignatureScheme specifies the cryptographic signature scheme used by all components of the mix network when interacting with the PKI system. Mix nodes sign their descriptors using this signature scheme. Likewise, PKI documents are signed by directory authority nodes using this signature scheme.

The following signature schemes are supported: "ed25519", "ed448", "Ed25519 Sphincs+", "Ed448-Sphincs+", "Ed25519-Dilithium2", "Ed448-Dilithium3"

Type: string

Required: Yes

Addresses

Addresses specifies a list of one or more address URLs in a format that includes the transport protocol, IP address, and port number that the server will bind to for incoming connections. Currently EchoMix supports URLs with that start with either "tcp://" or "quic://" such as: ["tcp://192.168.1.1:30001"] and ["quic://192.168.1.1:40001"]

Type: []string

Required:

BindAddresses

BindAddresses are listener addresses that the server will bind to and accept connections on. These addresses are not advertised in the PKI.

Type: bool

Required:

MetricsAddress

MetricsAddress is the address/port to bind the Prometheus metrics endpoint to.

Type: string

Required:

DataDir

DataDir is the absolute path to the directory authority server state directory where persistence.db will be written to disk and where the servers' cryptographic key materials will be written to disk when the server is started with the "-g" command-line option.

Type: string

Required:

IsGatewayNode

IsGatewayNode specifies if the server is a gateway or not.

Type: bool

Required:

IsServiceNode

IsServiceNode specifies if the server is a service node or not.

Type: bool

Required:

Logging section

The logging configuration section controls logging.

```
[Logging]
  Disable = false
  File = "katzenpost.log"
  Level = "INFO"
```

Disable

Disables logging if set to true.

Type: bool

Required:

File

Specifies the log file. If omitted, stdout is used.

An absolute or relative file path can be specified. A relative path is relative to the DataDir specified in the Server section of the configuration.

Type: string

Required:

Level

Supported values are ERROR | WARNING | NOTICE | INFO | DEBUG.

Type: string

Required:



Warning

The DEBUG log level is unsafe for production use.

PKI section

The PKI section contains the directory authority configuration for a mix, gateway, or service node.

```
IdentityPublicKey = "----BEGIN ED25519 PUBLIC KEY----\n/v3qYgh2TvV5Z
    PKISignatureScheme = "Ed25519"
   LinkPublicKey = "----BEGIN XWING PUBLIC KEY----\nJeFaZoYQEOO71zPFFWj
   WireKEMScheme = "xwing"
   Addresses = ["127.0.0.1:30001"]
[[PKI.Voting.Authorities]]
    Identifier = "auth2"
   IdentityPublicKey = "----BEGIN ED25519 PUBLIC KEY----\n60KQRhG7njt+k
   PKISignatureScheme = "Ed25519"
   LinkPublicKey = "----BEGIN XWING PUBLIC KEY----\nHVR2m7i6G6cf1qxUvyE
   WireKEMScheme = "xwing"
    Addresses = ["127.0.0.1:30002"]
[[PKI.Voting.Authorities]]
    Identifier = "auth3"
    IdentityPublicKey = "----BEGIN ED25519 PUBLIC KEY----\naZUXqznyLO2mK
   PKISignatureScheme = "Ed25519"
   LinkPublicKey = "----BEGIN XWING PUBLIC KEY----\nEZukXtZwHTjGj7tCI0k
   WireKEMScheme = "xwing"
   Addresses = ["127.0.0.1:30003"]
```

Identifier

Identifier is the human readable identifier for the node (eg: FQDN).

Type: string

Required:

IdentityPublicKey

IdentityPublicKeyPem is a string in PEM format containing the public identity key.

Type: string

Required:

• PKISignatureScheme

PKISignatureScheme specifies the cryptographic signature scheme

Type: string

Required:

LinkPublicKey

LinkPublicKeyPem is string containing the PEM format of the peer's public link layer key.

Type: string

Required:

• WireKEMScheme

WireKEMScheme is the wire protocol KEM scheme to use.

```
Type: string
```

Addresses

```
// Addresses are the IP address/port combinations that the peer authority
// uses for the Directory Authority service.

Type: []string

Required:
```

Management section

Management is the EchoMix management interface configuration. The management section specifies connectivity information for the EchoMix control protocol which can be used to make configuration changes during run-time. An example configuration looks like this:

```
[Management]
    Enable = false
    Path = "/voting_mixnet/mix1/management_sock"
```

Enable

Enables the management interface if set to true.

Type: bool Required:

Path

Specifies the path to the management interface socket. If left empty, then management_sock will be used under the DataDir.

Type: string Required:

SphinxGeometry section

```
[SphinxGeometry]
   PacketLength = 3082
   NrHops = 5
   HeaderLength = 476
   RoutingInfoLength = 410
   PerHopRoutingInfoLength = 82
   SURBLength = 572
   SphinxPlaintextHeaderLength = 2
   PayloadTagLength = 32
   ForwardPayloadLength = 2574
   UserForwardPayloadLength = 2000
   NextNodeHopLength = 65
```

```
SPRPKeyMaterialLength = 64
NIKEName = "x25519"
KEMName = ""
```

• PacketLength

PacketLength is the length of a packet.

Type: int

Required:

• NrHops

NrHops is the number of hops through the mixnet, which determines the size

of the Sphinx packet header.

Type: int

Required:

· HeaderLength

HeaderLength is the length of the Sphinx packet header in bytes.

Type: int

Required:

• RoutingInfoLength

RoutingInfoLength is the length of the routing info portion of the header.

Type: int

Required:

• PerHopRoutingInfoLength

PerHopRoutingInfoLength is the length of the per hop routing info.

Type: int

Required:

• SURBLength

SURBLength is the length of SURB.

Type: int

Required:

• SphinxPlaintextHeaderLength

SphinxPlaintextHeaderLength is the length of the plaintext header.

Type: int

· PayloadTagLength

PayloadTagLength is the length of the payload tag.

Type: int

Required:

· ForwardPayloadLength

ForwardPayloadLength is the size of the payload.

Type: int

Required:

· UserForwardPayloadLength

the size of the usable payload.

Type: int

Required:

NextNodeHopLength

NextNodeHopLength is derived off the largest routing info

block that we expect to encounter. Everything else just has a NextNodeHop + NodeDelay, or a Recipient, both cases which are shorter.

Type: int

Required:

· SPRPKeyMaterialLength

SPRPKeyMaterialLength is the length of the SPRP key.

Type: int

Required:

• NIKEName

NIKEName is the name of the NIKE (non-interactive key exchange) scheme used by the mixnet's Sphinx packets. NIKEName and KEMName are mutually exclusive.

Type: string

Required:

KEMName

KEMName is the name of the KEM scheme used by the mixnet's Sphinx packet. NIKEName and KEM-Name are mutually exclusive.

Type: string

Required:

Debug section

Debug is the EchoMix server debug configuration for advanced tuning.

[Debug]

```
NumSphinxWorkers = 16
NumServiceWorkers = 3
NumGatewayWorkers = 3
NumKaetzchenWorkers = 3
SchedulerExternalMemoryQueue = false
SchedulerQueueSize = 0
SchedulerMaxBurst = 16
UnwrapDelay = 250
GatewayDelay = 500
ServiceDelay = 500
KaetzchenDelay = 750
SchedulerSlack = 150
SendSlack = 50
DecoySlack = 15000
ConnectTimeout = 60000
HandshakeTimeout = 30000
ReauthInterval = 30000
SendDecoyTraffic = false
DisableRateLimit = false
GenerateOnly = false
```

• NumSphinxWorkers

specifies the number of worker instances to use for inbound Sphinx packet processing.

Type: int

Required:

• NumProviderWorkers

specifies the number of worker instances to use for provider specific packet processing.

Type: int

Required:

• NumKaetzchenWorkers

specifies the number of worker instances to use for Kaetzchen specific packet processing.

Type: int

Required:

• SchedulerExternalMemoryQueue

	will enable the experimental external memory queue that is backed by disk.
	Type: bool
	Required:
•	SchedulerQueueSize
	is the maximum allowed scheduler queue size before random entries will start getting dropped. A value ≤ 0 is treated as unlimited.
	Type: int
	Required:
•	SchedulerMaxBurst
	is the maximum number of packets that will be dispatched per scheduler wakeup event.
	Type:
	Required:
•	UnwrapDelay
	is the maximum allowed unwrap delay due to queueing in milliseconds.
	Type: int
	Required:
•	GatewayDelay
	the maximum allowed gateway node worker delay due to queueing
	in milliseconds.
	Type: int
	Required:
•	ServiceDelay
	is the maximum allowed provider delay due to queueing in milliseconds.
	Type: int
	Required:
•	KaetzchenDelay
	is the maximum allowed kaetzchen delay due to queueing in milliseconds.
	Type: int
	Required:
•	SchedulerSlack

: - 41	:			-111	4		:11:
is the	maximum	anowed	scheduler	stack due	to queueing and	or processing in	miniseconas.

Type: int

Required:

SendSlack

is the maximum allowed send queue slack due to queueing and or congestion in milliseconds.

Type: int

Required:

DecoySlack

is the maximum allowed decoy sweep slack due to various external delays such as latency before a loop decoy packet will be considered lost.

Type: int

Required:

ConnectTimeout

specifies the maximum time a connection can take to establish a TCP/IP connection in milliseconds.

Type: int

Required:

• HandshakeTimeout

specifies the maximum time a connection can take for a link protocol handshake in milliseconds.

Type: int

Required:

ReauthInterval

specifies the interval at which a connection will be reauthenticated in milliseconds.

Type: int

Required:

SendDecoyTraffic

enables sending decoy traffic. This is still experimental and untuned and thus is disabled by default. WARNING: This option will go away once decoy traffic is more concrete.

Type: bool

Required:

• DisableRateLimit

disables the per-client rate limiter. This option should only be used for testing.

Type: bool

Required:

GenerateOnly

halts and cleans up the server right after long term key generation.

Type: bool

Required:

Configuring gateway nodes

The following configuration is drawn from the reference implementation in katzenpost/dock-er/voting_mixnet/gateway1/katzenpost.toml. In a real-world mixnet, the component hosts would not be sharing a single IP address. For more information about the test mixnet, see Using the EchoMix test network.

Server section

Identifier

Identifier is the human-readable identifier for a node (for example, the FQDN) and must be unique for a given mixnet.

```
Type: string
Required: Yes
```

WireKEM

WireKEM is the wire protocol KEM (key encapsulation mechanism) scheme to use.

This configuration option supports the use of post-quantum cryptography to strengthen security. In this case the "Wire" protocol refers to our PQ Noise based protocol which is how all the dir auth nodes talk to one another. PQ Noise is a variation of the Noise protocol framework where the handshake patterns are algebraically transformed to replace ECDH operations with KEM encapsulate/decapsulate operations.

```
The following KEM schemes are supported: "x25519", "x448", "mlkem768", "sntrup4591761", "frodo640shake", "mceliece348864", "mceliece348864",
```

"mceliece460896", "mceliece460896f", "mceliece6688128", "mceliece6688128f", "mceliece6960119", "mceliece6960119f", "mceliece8192128f", "xwing", "Kyber768-X25519", "MLKEM768-X25519", "CTIDH511", "CTIDH512", "CTIDH1024", "CTIDH2048", "CTIDH512-X25519", "CTIDH512-X25519"

Type: string

Required: Yes

PKISignatureScheme

PKISignatureScheme specifies the cryptographic signature scheme used by all components of the mix network when interacting with the PKI system. Mix nodes sign their descriptors using this signature scheme. Likewise, PKI documents are signed by directory authority nodes using this signature scheme.

The following signature schemes are supported: "ed25519", "ed448", "Ed25519 Sphincs+", "Ed448-Sphincs+", "Ed25519-Dilithium2", "Ed448-Dilithium3"

Type: string

Required: Yes

Addresses

Addresses specifies a list of one or more address URLs in a format that includes the transport protocol, IP address, and port number that the server will bind to for incoming connections. Currently EchoMix supports URLs with that start with either "tcp://" or "quic://" such as: ["tcp://192.168.1.1:30001"] and ["quic://192.168.1.1:40001"]

Type: []string

Required:

BindAddresses

BindAddresses are listener addresses that the server will bind to and accept connections on. These addresses are not advertised in the PKI.

Type: bool

Required:

MetricsAddress

MetricsAddress is the address/port to bind the Prometheus metrics endpoint to.

Type: string

Required:

• DataDir

DataDir is the absolute path to the directory authority server state directory where persistence.db will be written to disk and where the servers' cryptographic key materials will be written to disk when the server is started with the "-g" command-line option.

· IsGatewayNode

IsGatewayNode specifies if the server is a gateway or not.

Type: bool

Required:

• IsServiceNode

IsServiceNode specifies if the server is a service node or not.

Type: bool

Required:

Logging section

The logging configuration section controls logging.

```
[Logging]
  Disable = false
  File = "katzenpost.log"
  Level = "INFO"
```

Disable

Disables logging if set to true.

Type: bool

Required:

• File

Specifies the log file. If omitted, stdout is used.

An absolute or relative file path can be specified. A relative path is relative to the DataDir specified in the Server section of the configuration.

Type: string

Required:

Level

Supported values are ERROR | WARNING | NOTICE | INFO | DEBUG.

Type: string

Required:



Warning

The DEBUG log level is unsafe for production use.

Gateway section

PKI section

The PKI section contains the directory authority configuration for a mix, gateway, or service node.

```
WireKEMScheme = "xwing"
Addresses = ["127.0.0.1:30002"]

[[PKI.Voting.Authorities]]
   Identifier = "auth3"
   IdentityPublicKey = "----BEGIN ED25519 PUBLIC KEY----\naZUXqznyLO2mK
   PKISignatureScheme = "Ed25519"
   LinkPublicKey = "----BEGIN XWING PUBLIC KEY----\nEZukXtZwHTjGj7tCI0k
   WireKEMScheme = "xwing"
   Addresses = ["127.0.0.1:30003"]
```

• Identifier

Identifier is the human readable identifier for the node (eg: FQDN).

Type: string

Required:

IdentityPublicKey

IdentityPublicKeyPem is a string in PEM format containing the public identity key.

Type: string

Required:

• PKISignatureScheme

PKISignatureScheme specifies the cryptographic signature scheme

Type: string

Required:

LinkPublicKey

LinkPublicKeyPem is string containing the PEM format of the peer's public link layer key.

Type: string

Required:

• WireKEMScheme

WireKEMScheme is the wire protocol KEM scheme to use.

Type: string

Required:

Addresses

```
// Addresses are the IP address/port combinations that the peer authority
```

// uses for the Directory Authority service.

Type: []string

Management section

Management is the EchoMix management interface configuration. The management section specifies connectivity information for the EchoMix control protocol which can be used to make configuration changes during run-time. An example configuration looks like this:

```
[Management]
    Enable = false
    Path = "/voting_mixnet/mix1/management_sock"
```

• Enable

Enables the management interface if set to true.

Type: bool

Required:

Path

Specifies the path to the management interface socket. If left empty, then management_sock will be used under the DataDir.

Type: string

Required:

SphinxGeometry section

```
[SphinxGeometry]
   PacketLength = 3082
   NrHops = 5
   HeaderLength = 476
   RoutingInfoLength = 410
   PerHopRoutingInfoLength = 82
   SURBLength = 572
   SphinxPlaintextHeaderLength = 2
   PayloadTagLength = 32
   ForwardPayloadLength = 2574
   UserForwardPayloadLength = 2000
   NextNodeHopLength = 65
   SPRPKeyMaterialLength = 64
   NIKEName = "x25519"
   KEMName = ""
```

· PacketLength

PacketLength is the length of a packet.

Type: int

Required:

• NrHops

NrHops is the number of hops through the mixnet, which determines the size of the Sphinx packet header.

Type: int

Required:

HeaderLength

HeaderLength is the length of the Sphinx packet header in bytes.

Type: int

Required:

RoutingInfoLength

RoutingInfoLength is the length of the routing info portion of the header.

Type: int

Required:

• PerHopRoutingInfoLength

PerHopRoutingInfoLength is the length of the per hop routing info.

Type: int

Required:

SURBLength

SURBLength is the length of SURB.

Type: int

Required:

• SphinxPlaintextHeaderLength

SphinxPlaintextHeaderLength is the length of the plaintext header.

Type: int

Required:

• PayloadTagLength

PayloadTagLength is the length of the payload tag.

Type: int

Required:

ForwardPayloadLength

ForwardPayloadLength is the size of the payload.
Type: int
Required:
• UserForwardPayloadLength
the size of the usable payload.
Type: int
Required:
• NextNodeHopLength
NextNodeHopLength is derived off the largest routing info
block that we expect to encounter. Everything else just has a NextNodeHop + NodeDelay, or a Recipie both cases which are shorter.
Type: int
Required:
• SPRPKeyMaterialLength
SPRPKeyMaterialLength is the length of the SPRP key.
Type: int
Required:
• NIKEName
NIKEName is the name of the NIKE (non-interactive key exchange) scheme used by the mixnet's Sphipackets. NIKEName and KEMName are mutually exclusive.
Type: string
Required:
• KEMName
KEMName is the name of the KEM scheme used by the mixnet's Sphinx packet. NIKEName and KE Name are mutually exclusive.
Type: string
Required:
section
Debug is the EchoMix server debug configuration for advanced tuning.

Debug

[Debug]

```
NumSphinxWorkers = 16
NumServiceWorkers = 3
NumGatewayWorkers = 3
NumKaetzchenWorkers = 3
SchedulerExternalMemoryQueue = false
SchedulerQueueSize = 0
SchedulerMaxBurst = 16
UnwrapDelay = 250
GatewayDelay = 500
ServiceDelay = 500
KaetzchenDelay = 750
SchedulerSlack = 150
SendSlack = 50
DecoySlack = 15000
ConnectTimeout = 60000
HandshakeTimeout = 30000
ReauthInterval = 30000
SendDecoyTraffic = false
DisableRateLimit = false
GenerateOnly = false
```

· NumSphinxWorkers

specifies the number of worker instances to use for inbound Sphinx packet processing.

Type: int

Required:

NumProviderWorkers

specifies the number of worker instances to use for provider specific packet processing.

Type: int

Required:

• NumKaetzchenWorkers

specifies the number of worker instances to use for Kaetzchen specific packet processing.

Type: int

Required:

• SchedulerExternalMemoryQueue

will enable the experimental external memory queue that is backed by disk.

Type: bool

Required:

• SchedulerQueueSize

is the maximum allowed scheduler queue size before random entries will start getting dropped. A value <= 0 is treated as unlimited.

	Type: int
	Required:
•	SchedulerMaxBurst
	is the maximum number of packets that will be dispatched per scheduler wakeup event.
	Type:
	Required:
•	UnwrapDelay
	is the maximum allowed unwrap delay due to queueing in milliseconds.
	Type: int
	Required:
•	GatewayDelay
	the maximum allowed gateway node worker delay due to queueing
	in milliseconds.
	Type: int
	Required:
•	ServiceDelay
	is the maximum allowed provider delay due to queueing in milliseconds.
	Type: int
	Required:
•	KaetzchenDelay
	is the maximum allowed kaetzchen delay due to queueing in milliseconds.
	Type: int
	Required:
•	SchedulerSlack
	is the maximum allowed scheduler slack due to queueing and or processing in milliseconds.
	Type: int
	Required:
•	SendSlack

is the maximum allowed send queue slack due to queueing and or congestion in milliseconds.

	Type: int
	Required:
•	DecoySlack
	is the maximum allowed decoy sweep slack due to various external delays such as latency before a loo decoy packet will be considered lost.
	Type: int
	Required:
•	ConnectTimeout
	specifies the maximum time a connection can take to establish a TCP/IP connection in milliseconds.
	Type: int
	Required:
•	HandshakeTimeout
	specifies the maximum time a connection can take for a link protocol handshake in milliseconds.
	Type: int
	Required:
•	ReauthInterval
	specifies the interval at which a connection will be reauthenticated in milliseconds.
	Type: int
	Required:
•	SendDecoyTraffic
	enables sending decoy traffic. This is still experimental and untuned and thus is disabled by defaul WARNING: This option will go away once decoy traffic is more concrete.
	Type: bool
	Required:
•	DisableRateLimit
	disables the per-client rate limiter. This option should only be used for testing.
	Type: bool
	Required:
•	GenerateOnly

halts and cleans up the server right after long term key generation.

Type: bool

Required:

Configuring service nodes

The following configuration is drawn from the reference implementation in katzenpost/dock-er/voting_mixnet/servicenodel/authority.toml. In a real-world mixnet, the component hosts would not be sharing a single IP address. For more information about the test mixnet, see Using the Katzenpost test network.

Server section

The Server section contains mandatory information common to all nodes, for example:

```
[Server]
    Identifier = "servicenodel"
    WireKEM = "xwing"
    PKISignatureScheme = "Ed25519"
    Addresses = ["127.0.0.1:30006"]
    OnlyAdvertiseAltAddresses = false
    MetricsAddress = "127.0.0.1:30007"
    DataDir = "/voting_mixnet/servicenodel"
    IsGatewayNode = false
    IsServiceNode = true
    [Server.AltAddresses]
```

Identifier

Identifier is the human-readable identifier for a node (for example, the FQDN) and must be unique for a given mixnet.

Type: string
Required: Yes

WireKEM

WireKEM is the wire protocol KEM (key encapsulation mechanism) scheme to use.

This configuration option supports the use of post-quantum cryptography to strengthen security. In this case the "Wire" protocol refers to our PQ Noise based protocol which is how all the dir auth nodes talk to one another. PQ Noise is a variation of the Noise protocol framework where the handshake patterns are algebraically transformed to replace ECDH operations with KEM encapsulate/decapsulate operations.

```
The
                                                                    "x25519".
        following
                      KEM
                                schemes
                                                     supported:
                                                                                  "x448".
                                             are
                                 "frodo640shake",
              "sntrup4591761",
                                                   "mceliece348864".
                                                                       "mceliece348864f".
"mceliece460896", "mceliece460896f", "mceliece6688128", "mceliece6688128f", "mceliece6960119",
"mceliece6960119f", "mceliece8192128", "mceliece8192128f", "xwing", "Kyber768-X25519",
"MLKEM768-X25519",
                       "MLKEM768-X448",
                                            "CTIDH511",
                                                            "CTIDH512",
                                                                           "CTIDH1024",
"CTIDH2048", "CTIDH512-X25519", "CTIDH512-X25519"
```

Type: string Required: Yes

• PKISignatureScheme

PKISignatureScheme specifies the cryptographic signature scheme used by all components of the mix network when interacting with the PKI system. Mix nodes sign their descriptors using this signature scheme. Likewise, PKI documents are signed by directory authority nodes using this signature scheme.

The following signature schemes are supported: "ed25519", "ed448", "Ed25519 Sphincs+", "Ed448-Sphincs+", "Ed25519-Dilithium2", "Ed448-Dilithium3"

Type: string

Required: Yes

Addresses

Addresses specifies a list of one or more address URLs in a format that includes the transport protocol, IP address, and port number that the server will bind to for incoming connections. Currently EchoMix supports URLs with that start with either "tcp://" or "quic://" such as: ["tcp://192.168.1.1:30001"] and ["quic://192.168.1.1:40001"]

Type: []string

Required:

BindAddresses

BindAddresses are listener addresses that the server will bind to and accept connections on. These addresses are not advertised in the PKI.

Type: bool

Required:

MetricsAddress

MetricsAddress is the address/port to bind the Prometheus metrics endpoint to.

Type: string

Required:

DataDir

DataDir is the absolute path to the directory authority server state directory where persistence.db will be written to disk and where the servers' cryptographic key materials will be written to disk when the server is started with the "-g" command-line option.

Type: string

Required:

IsGatewayNode

IsGatewayNode specifies if the server is a gateway or not.

Type: bool

Required:

IsServiceNode

IsServiceNode specifies if the server is a service node or not.

Type: bool

Required:

Logging section

The logging configuration section controls logging.

```
[Logging]
  Disable = false
  File = "katzenpost.log"
  Level = "INFO"
```

Disable

Disables logging if set to true.

Type: bool

Required:

• File

Specifies the log file. If omitted, stdout is used.

An absolute or relative file path can be specified. A relative path is relative to the DataDir specified in the Server section of the configuration.

Type: string

Required:

Level

Supported values are ERROR | WARNING | NOTICE | INFO | DEBUG.

Type: string

Required:



Warning

The DEBUG log level is unsafe for production use.

ServiceNode section

The service node configuration section contains subsections with settings for each service that Katzenpost supports. In a production network, the various services would be hosted on dedicated systems.

```
[ServiceNode]
```

[[ServiceNode.Kaetzchen]]

```
Capability = "echo"
   Endpoint = "+echo"
   Disable = false
[[ServiceNode.CBORPluginKaetzchen]]
   Capability = "spool"
   Endpoint = "+spool"
   Command = "/voting_mixnet/memspool.alpine"
   MaxConcurrency = 1
   Disable = false
   [ServiceNode.CBORPluginKaetzchen.Config]
       data_store = "/voting_mixnet/servicenode1/memspool.storage"
        log_dir = "/voting_mixnet/servicenodel"
[[ServiceNode.CBORPluginKaetzchen]]
   Capability = "pigeonhole"
   Endpoint = "+pigeonhole"
   Command = "/voting_mixnet/pigeonhole.alpine"
   MaxConcurrency = 1
   Disable = false
   [ServiceNode.CBORPluginKaetzchen.Config]
       db = "/voting_mixnet/servicenode1/map.storage"
       log_dir = "/voting_mixnet/servicenode1"
[[ServiceNode.CBORPluginKaetzchen]]
   Capability = "panda"
   Endpoint = "+panda"
   Command = "/voting_mixnet/panda_server.alpine"
   MaxConcurrency = 1
   Disable = false
   [ServiceNode.CBORPluginKaetzchen.Config]
        fileStore = "/voting_mixnet/servicenodel/panda.storage"
        log_dir = "/voting_mixnet/servicenodel"
        log_level = "INFO"
[[ServiceNode.CBORPluginKaetzchen]]
   Capability = "http"
   Endpoint = "+http"
   Command = "/voting_mixnet/proxy_server.alpine"
   MaxConcurrency = 1
   Disable = false
   [ServiceNode.CBORPluginKaetzchen.Config]
       host = "localhost:4242"
        log_dir = "/voting_mixnet/servicenodel"
       log_level = "DEBUG"
```

Common parameters:

Capability

The capability exposed by the agent.

Type: string

• Endpoint

	Endpoint is the provider side endpoint that the agent will accept requests at. While not required by the spec, this server only supports Endpoints that are lower-case local-parts of an e-mail address.
	Type: string
	Required:
	Command
	Command is the full file path to the external plugin program that implements this Kaetzchen service.
	Type: string
	Required:
	MaxConcurrency
	MaxConcurrency is the number of worker goroutines to start for this service.
	Type: int
	Required:
	Config
	The extra per agent arguments to be passed to the agent's initialization routine.
	Type: map[string]interface{}
	Required:
	Disable
	disabled a configured agent.
	Type: bool
	Required:
•	er-service parameters:
	Kaetzchen
	spool
	• data store

Type:

• log_dir

Type:

•	pigeonhole								
	•	db							
		Type:							
		Required:							
	•	log_dir							
		log_un							
		Type:							
		Required:							
•	pa	anda							
	•	fileStore							
		Type:							
	Required: • log_dir								
		log_un							
		Type:							
		Required:							
	•								
Supported values are ERROR WARNING NOTICE INFO DEBU									
			Warning						
		W	The DEBUG log level is unsafe for production use.						
		Type: string							
		Required:							
		Required:							
•	h	ttp							
	•	host							
		Type:							
	•	log_dir							

Type:

Required:

log_level

Supported values are ERROR | WARNING | NOTICE | INFO | DEBUG.

Type: string Required:

Required:



Warning

The DEBUG log level is unsafe for production use.

Type: string

Required:

Required:

PKI section

The PKI section contains the directory authority configuration for a mix, gateway, or service node.

```
[PKI]
    [PKI.Voting]
        [[PKI.Voting.Authorities]]
            Identifier = "auth1"
            IdentityPublicKey = "----BEGIN ED25519 PUBLIC KEY----\n/v3qYgh2TvV5Z
            PKISignatureScheme = "Ed25519"
           LinkPublicKey = "----BEGIN XWING PUBLIC KEY----\nJeFaZoYQEOO71zPFFWj
           WireKEMScheme = "xwing"
           Addresses = ["127.0.0.1:30001"]
        [[PKI.Voting.Authorities]]
            Identifier = "auth2"
            IdentityPublicKey = "----BEGIN ED25519 PUBLIC KEY----\n60KQRhG7njt+k
           PKISignatureScheme = "Ed25519"
           LinkPublicKey = "----BEGIN XWING PUBLIC KEY----\nHVR2m7i6G6cf1qxUvyE
           WireKEMScheme = "xwing"
           Addresses = ["127.0.0.1:30002"]
        [[PKI.Voting.Authorities]]
            Identifier = "auth3"
            IdentityPublicKey = "----BEGIN ED25519 PUBLIC KEY----\naZUXqznyLO2mK
           PKISignatureScheme = "Ed25519"
           LinkPublicKey = "----BEGIN XWING PUBLIC KEY----\nEZukXtZwHTjGj7tCI0k
```

WireKEMScheme = "xwing"

Addresses = ["127.0.0.1:30003"]

• Identifier

Identifier is the human readable identifier for the node (eg: FQDN).

Type: string

Required:

IdentityPublicKey

IdentityPublicKeyPem is a string in PEM format containing the public identity key.

Type: string

Required:

• PKISignatureScheme

PKISignatureScheme specifies the cryptographic signature scheme

Type: string

Required:

· LinkPublicKey

LinkPublicKeyPem is string containing the PEM format of the peer's public link layer key.

Type: string

Required:

• WireKEMScheme

WireKEMScheme is the wire protocol KEM scheme to use.

Type: string

Required:

Addresses

```
// Addresses are the IP address/port combinations that the peer authority
```

// uses for the Directory Authority service.

Type: []string

Required:

Management section

Management is the EchoMix management interface configuration. The management section specifies connectivity information for the EchoMix control protocol which can be used to make configuration changes during run-time. An example configuration looks like this:

```
[Management]
    Enable = false
```

```
Path = "/voting_mixnet/mix1/management_sock"
```

• Enable

Enables the management interface if set to true.

Type: bool

Required:

Path

Specifies the path to the management interface socket. If left empty, then management_sock will be used under the DataDir.

Type: string

Required:

SphinxGeometry section

```
[SphinxGeometry]
   PacketLength = 3082
   NrHops = 5
   HeaderLength = 476
   RoutingInfoLength = 410
   PerHopRoutingInfoLength = 82
   SURBLength = 572
   SphinxPlaintextHeaderLength = 2
   PayloadTagLength = 32
   ForwardPayloadLength = 2574
   UserForwardPayloadLength = 2574
   UserForwardPayloadLength = 65
   SPRPKeyMaterialLength = 64
   NIKEName = "x25519"
   KEMName = ""
```

• PacketLength

PacketLength is the length of a packet.

Type: int

Required:

NrHops

NrHops is the number of hops through the mixnet, which determines the size

of the Sphinx packet header.

Type: int

Required:

HeaderLength

	HeaderLength is the length of the Sphinx packet header in bytes.						
	Type: int						
	Required:						
•	RoutingInfoLength						
	RoutingInfoLength is the length of the routing info portion of the header.						
	Type: int						
	Required:						
•	PerHopRoutingInfoLength						
	PerHopRoutingInfoLength is the length of the per hop routing info.						
	Type: int						
	Required:						
•	SURBLength						
	SURBLength is the length of SURB.						
	Type: int						
	Required:						
•	SphinxPlaintextHeaderLength						
	SphinxPlaintextHeaderLength is the length of the plaintext header.						
	Type: int						
	Required:						
•	PayloadTagLength						
	PayloadTagLength is the length of the payload tag.						
	Type: int						
	Required:						
• ForwardPayloadLength							
	ForwardPayloadLength is the size of the payload.						
	Type: int						
	Required:						
•	UserForwardPayloadLength						

the size of the usable payload.

Type: int

Required:

NextNodeHopLength

NextNodeHopLength is derived off the largest routing info

block that we expect to encounter. Everything else just has a NextNodeHop + NodeDelay, or a Recipient, both cases which are shorter.

Type: int

Required:

• SPRPKeyMaterialLength

SPRPKeyMaterialLength is the length of the SPRP key.

Type: int

Required:

NIKEName

NIKEName is the name of the NIKE (non-interactive key exchange) scheme used by the mixnet's Sphinx packets. NIKEName and KEMName are mutually exclusive.

Type: string

Required:

KEMName

KEMName is the name of the KEM scheme used by the mixnet's Sphinx packet. NIKEName and KEM-Name are mutually exclusive.

Type: string

Required:

Debug section

Debug is the EchoMix server debug configuration for advanced tuning.

[Debug]

```
NumSphinxWorkers = 16

NumServiceWorkers = 3

NumGatewayWorkers = 3

NumKaetzchenWorkers = 3

SchedulerExternalMemoryQueue = false

SchedulerQueueSize = 0

SchedulerMaxBurst = 16

UnwrapDelay = 250

GatewayDelay = 500

ServiceDelay = 500

KaetzchenDelay = 750
```

```
SchedulerSlack = 150
SendSlack = 50
DecoySlack = 15000
ConnectTimeout = 60000
HandshakeTimeout = 30000
ReauthInterval = 30000
SendDecoyTraffic = false
DisableRateLimit = false
GenerateOnly = false
```

• NumSphinxWorkers

specifies the number of worker instances to use for inbound Sphinx packet processing.

Type: int

Required:

• NumProviderWorkers

specifies the number of worker instances to use for provider specific packet processing.

Type: int

Required:

• NumKaetzchenWorkers

specifies the number of worker instances to use for Kaetzchen specific packet processing.

Type: int

Required:

• SchedulerExternalMemoryQueue

will enable the experimental external memory queue that is backed by disk.

Type: bool

Required:

• SchedulerQueueSize

is the maximum allowed scheduler queue size before random entries will start getting dropped. A value <= 0 is treated as unlimited.

Type: int

Required:

SchedulerMaxBurst

is the maximum number of packets that will be dispatched per scheduler wakeup event.

Type:

• UnwrapDelay is the maximum allowed unwrap delay due to queueing in milliseconds. Type: int Required: · GatewayDelay the maximum allowed gateway node worker delay due to queueing in milliseconds. Type: int Required: · ServiceDelay is the maximum allowed provider delay due to queueing in milliseconds. Type: int Required: KaetzchenDelay is the maximum allowed kaetzchen delay due to queueing in milliseconds. Type: int Required: SchedulerSlack is the maximum allowed scheduler slack due to queueing and or processing in milliseconds. Type: int Required: SendSlack is the maximum allowed send queue slack due to queueing and or congestion in milliseconds. Type: int Required:

DecoySlack

is the maximum allowed decoy sweep slack due to various external delays such as latency before a loop decoy packet will be considered lost.

Type: int

• ConnectTimeout

specifies the maximum	time a connection	can take to establish	TCD/ID connecti	on in millicacande
Specifies the maximum	гиние а соппесион	Call take to establish a	a TCE/TE CONNECH	OH III HIIIHISECONAS.

Type: int

Required:

HandshakeTimeout

specifies the maximum time a connection can take for a link protocol handshake in milliseconds.

Type: int

Required:

ReauthInterval

specifies the interval at which a connection will be reauthenticated in milliseconds.

Type: int

Required:

• SendDecoyTraffic

enables sending decoy traffic. This is still experimental and untuned and thus is disabled by default. WARNING: This option will go away once decoy traffic is more concrete.

Type: bool

Required:

• DisableRateLimit

disables the per-client rate limiter. This option should only be used for testing.

Type: bool

Required:

• GenerateOnly

halts and cleans up the server right after long term key generation.

Type: bool