# FKPhy1

Es ist dabei mo glich, folgende Klassifizierung vorzunehmen:

- einkristalline Festk orper: periodisch angeordnete Atome im idealen Kristall (Nah- und Fernordnung vorhanden), zum Beispiel Diamant, Salzkristalle, etc.
- polykristalline Festk orper: eine Anordnung von kleinen Einkristallen, die u ber Ver- setzungen oder Fehlstellen miteinander verbunden sind (Nah- und Fernordnung pro Kristallit vorhanden, keine Fernordnung u ber Kristallitgrenzen hinweg), zum Beispiel Metalle, Quarze, etc.
- amorphe Festk"orper: statistische Anordnung (nur eingeschra nkte Nahordnung, keine Fernordnung), zum Beispiel Gla ser, bestimmte Legierungen, etc.

r=0.52 A Bohrradius

Lyman-Serie: U"berga"nge von n2 nach n1 = 1

- Balmer-Serie: U"berga"nge von n2 nach n1 = 2
- Paschen-Serie: U'berga nge von n2 nach n1 = 3
- Bracket-Serie: U"berga"nge von n2 nach n1 = 4
- Pfund-Serie: U'berga nge von n2 nach n1 = 5
- Humphreys-Serie: U"berga"nge von n2 nach n1 = 6

Struktur = Gitter + Basis.

Kristallgitter werden aufgrund ihrer Symmetrien unterschieden.

- 1-Drehung
- 2-Spiegelung an einer Ebene
- 3-Inversion
- 4-Drehinversion
  - Es gibt sieben verschiedene Kristallsysteme:

Kristallsystem	Gitterkonstanten	Winkel
kubisch	a = b = c	$\alpha=\beta=\gamma=90^{\circ}$
trigonal (rhomboedrisch)	a = b = c	$\alpha=\beta=\gamma\neq90^\circ$
hexagonal	$a = b \neq c$	$\alpha=\beta=90^{\circ}~\gamma=120^{\circ}$
tetragonal	$a = b \neq c$	$lpha=eta=\gamma=90^\circ$
orthorhombisch	$a \neq b \neq c$	$lpha=eta=\gamma=90^\circ$
mono $k$ lin	$a \neq b \neq c$	$\alpha=\gamma=90^\circ,\ \beta\neq90^\circ$
triklin	$a \neq b \neq c$	$\alpha \neq \beta \neq \gamma$

Lasse mehrere Gitterpunkte je Einheitszelle auf **raumzentrierten**, **fl** "achenzentrier- ten oder basiszentrierten Positionen zu, um Anzahl der Symmetrien zu maximieren. Dies ergibt die **14 Bravais-Gitter**.

<del>-----</del>>

In zwei Dimensionen existieren fu'nf Bravais Gitter, wovon vier primitiv sind und eins ist zentriert. Die fu'nf Bravais Gitter sind in Abb. 1.13 dargestellt.

<del>-----</del>>

Van der Waals Kräfte sind Wechselwirkungen, die zwischen verschiedenen Atomen und/oder Molekülen auftreten. Sie sind relativ **schwache**, nichtkovalente Wechselwirkungen.

<del>-----</del>>

Die **Bindung** entsteht durch die elektrostatische Anziehung entgegengesetzt geladener Teilchen. Die Ionen sind regelmäßig in einem Ionengitter angeordnet und sie bilden häufig Kristalle. Ihr Aufbau ist abhängig von der Ladung und den Größenverhältnissen der Ionen.

\_\_\_\_<

**kovalente Bindung** Bei den Elementverbindungen der Gruppen III bis V des Periodensystems (z.B. C, Si, Ge) treten Hybridisierungen der p- und s-Orbitale auf.

metallische Bindung Das freie Elektronengas sorgt allgemein fur eine Gleichverteilung der Elektronen im Festkorper. Die Randbedingungen einer Oberflache sorgen allerdings dafur, dass die Elektronen sich mehr im Rumpf des Festkorpers aufhalten als an der Oberflache. Diese Elektronenumlagerung sorgt fur ein Dipolfeld, das eine Kraft ausurbt und so den Abstand der ersten zur zweiten Atomlage verringert. Dieser Effekt sorgt also nicht fur eine Rekonstruktion (Neuanordnung der Atome in der ersten Lage), sondern fur eine Relaxation (verringerter Atomlagenabstand an der Oberflache).

\_\_\_\_

Viele Elemente ko"nnen in verschiedenen Strukturen vorkommen: **Allotropie**. Umwandlung durch A"nderung der Temperatur oder des Drucks.

\_\_\_\_\_

The critical temperature of a ferromagnetic material is called the Curie temperature (Tc) and that of an anti-ferromagnetic material, the Ne<sup>\*</sup>el temperature (TN).

pin-valve structure was NiFe(15 nm)/Cu(2.6 nm)/NiFe(15 nm)/FeMn(10 nm). There are two ferromagnetic NiFe layers and an anti-ferromagnetic FeMn layer is attached to one of the NiFe layers to increase the required coercive force via the exchange anisotropy. The other NiFe layer behaves freely as a soft magnet. Therefore, the two NiFe layers are called the "pinned" and "free" layers, respectively.

The z-component of spin sz takes one of two values 1/2 and is not necessarily conserved, that is, it is time dependent due to such effects as the spin-orbit interaction (SOI) and interactions between electrons. Therefore, the length for which the spin of an electron is conserved is finite. This length is called the spin-flip mean free path and typically takes values in the range 102 nm–101 mm.

Due to scattering of electrons, the length an electron travels with a fixed spin direction is much shorter than the spin-flip mean free path. This length is called the spin-diffusion length lspin.

Another important length scale is the Fermi wave length IF, which characterizes the electronic states.

TMR is a phenomenon in which the overlap of wave functions of electrons in two separated ferromagnetic metals becomes small.

anomalous Hall effect (AHE) and spin Hall effect (SHE)

Since SOI is a coupling of spin and orbital motion of electrons, current control of spin and magnetic control of charge via SOI are possible. This is the reason that SOI attracts much interests in the technological aspect.

One of the most important requirements for magnetoresistance (MR) in nanoscale ferromagnets is spin dependence of the electrical resistivity. In this section, we review spin-dependent resistivity (or conductivity) in ferromagnetic bulk metals and alloys, emphasizing the role of the electronic states on the resistivity at low temperatures.

The resistivity decreases with increasing magnetic field due to a change in the align- ment of the magnetization of the Fe layers

The magnitude of the MR is expressed by the so-called MR ratio, defined as MR 1/4 rAP rP;

## Spin valve

Technological applications of GMR, for example, sensors, require a sharp response of the magnetization direction to the external magnetic field within a few Oe

To achieve such sensitivity, a trilayer structure with an attached antiferromagnetic has been designed. The magnetization of the magnetic layer adjacent to the antiferromagnetic layer is pinned by the antiferromagnetism and only the other magnetic layer responds to the external magnetic field. This kind of trilayer is called a spin valve

Simple picture of GMR

#### **TUNNEL MAGNETORESISTANCE**

TMR in ferromagnetic tunnel junctions (FTJs) was reported prior to the discovery of GMR [112, 113]. The observed MR ratios, however, were rather small at the time. A large TMR at room temperature was reported for Fe/Al–O/Fe in 1995 [114–116], and it has attracted considerable attention due to its wide potential application in sensors and memory storage devices in the near future. In the same year, tunnel-type MR was reported for metal-oxide ferromagnetic granular films [117, 118].

Many theoretical studies have so far investigated tunnel resistance and TMR [11, 119–123]. Since TMR is caused by tunnelling current through an insulating barrier, it is sensitive to physical factors such as temperature, voltage and the thickness and energy height of the barrier; it is also affected by scattering mechan- isms. It is therefore vital to clarify the effects of each factor on TMR in order to develop technological applications of TMR.

In this section, we first overview the experimental results of TMR together with a phenomenological theory, and then describe the results obtained using microscopic theories. We also touch upon some recent experiments.

#### 5.1. Ferromagnetic tunnel junctions

One of the characteristics of TMR is that the external magnetic field required to rotate the magnetization is sufficiently low.

where PL(R) is the spin polarization of L(R) electrodes a

An intuitive picture of the tunnelling process explained above is shown in

Ingredients for TMR

Tunnel junctions are usually composed of an insulating barrier sandwiched between two different ferromagnetic metals. Therefore, the Fermi surfaces of the L and R electrodes are generally different. Since kk is conserved in specular tunnelling, only states on the Fermi surface with the same kk may contribute to tunnelling.

When a semiconductor (e.g. GaAs) is used as the barrier, interfacial states, called Shockley states, appear within the energy band gap.

## Spin-flip tunnelling

The results presented thus far were obtained by assuming that the spin of tunnel- ling electrons is conserved. When there exist impurity spins within the barrier or near the interfaces, the tunnelling electrons may interact with these impurity spins and reverse their spins in the tunnelling process. This kind of spin-flip tunnelling may reduce the MR ratio. Interaction between conduction electrons and localized spins in electrodes may also produce similar effects.

Summing up these results, theory predicts that more than two periods appear in TMR oscillations and that the MR ratio oscillates about a finite value. These theoretical results do not agree with experimental observations. These results, however, are modified when roughness is present, and become [159]:

The DOS of metallic ferromagnets is usually spin dependent. When the DOS of either a " or # spin state is zero at the Fermi level, and one of two spin states is metallic and the other is insulating, the metals are referred to as half-metals. The spin polarization P of these half-metals is 100%, and therefore half-metals have potential applicability as magnetoresistive devices

Recently, it has been shown using the first- principles method that diluted magnetic semiconductors, such as (GaMn)As, may also be half-metallic. In experiments in which point contacts and tunnel junctions were used to measure spin polarization, lower values than 100% were obtained for P (e.g. 90% for CrO2, 70–85% for LaSrMnO3 and 60% for Heusler alloys) [164–166]. Recently, relatively high MR ratios have been observed in FTJs with Heusler alloys, suggesting that the value of P is about 86% [167, 168].

In the following, we briefly review the electronic states of half-metals, and give some experimental results for TMR in FTJs with half-metals.

We have shown that the SOI gives rise to the magnetoresistance known as AMR. Since SOI is a coupling of spin and orbital motion of electrons, it also gives rise to other interesting transport properties called as anomalous Hall effect (AHE) and spin Hall effect (SHE) as well as electric field-induced spin accumulation in 2DEG.

• Since the first three types of SOI are called intrinsic SOI since they reside uni- formly in the system, the last one is called an extrinsic SOI as it is caused by impurity potentials.

when he was studying the force acting on the charged particles under an external electric field Eext and a magnetic field Hext

• This is the so-called "ordinary" Hall effect in which the electrons are deflected into the direction of Eext Hext due to the Lorentz force

the extrinsic AHE appears due to spin-dependent scattering. The up- and down-spin electrons are scattered into opposite directions, resulting in spin-up and spin-down charge Hall currents along the perpendicular direction of Eext

called spin Hall effect (SHE). A schematic view of SHE is shown in Fig. 54. When the spin Hall current is originated from scattering of electrons by impurity potentials with SO interaction,

\_\_\_\_

Teo FKPhy1

• Der Widerstand nimmt mit steigender Temperatur stetig zu und hat auch bei Raumtemperatur noch einen relativ geringen Wert von etwa  $10-4~\Omega cm$ .

entweder ist total antisymmetrisch oder ist total symmetrisch bezüglich Vertau-

schung. In der Natur nehmen Fermionen die erste und Bosonen die zweite Art Zustände ein.

Im Gegensatz zu den Bose- Operatoren vertauschen die fermionischen Operatoren aber nicht, denn wegen der Anti- symmetrisierung der Wellenfunktion macht es einen Unterschied, ob man erst ein Teil- chen im Zustand  $|-\!\!\!\!/$ 1 erzeugt und dann eines im Zustand  $|-\!\!\!\!$ 4 oder umgekehrt.

Tabelle 6.2: Einige thermodynamische Begriffe.

Begriff	Definition
isobar	P = const.
isochor	V=const.
isotherm	T=const.
isentrop	S=const.
adiabatisch	$\delta Q=0$
extensiv	proportional zur Größe des Systems
intensiv	unabhängig von der Größe des Systems

Als ein weiteres Beispiel für einen Phasenübergang wollen wir im Folgenden den ferro- magnetischen Phasenübergang besprechen. Einen Ferromagneten kann man sich durch viele atomare magnetische Momente ('Spins') zusammengesetzt denken. Bei sehr hohen Temperaturen sind die Spins ungeordnet und die Magnetisierung ist im Mittel Null. Unterhalb einer kritischen Temperatur, der sogenannten Curie-Temperatur, können sich die Spins spontan ordnen und die mittlere Magnetisierung wird dann ungleich Null.

Theo FKpy

----<

Translationsinvarianz, d. h. die gleiche Atomgruppe wird periodisch wiederholt.

Die Grundidee der Tight-binding-Methode ist es, die Blochfunktionen aus an den Atomrümpfen lokalisierten Zuständen zu konstruieren
Supraleitung
Meissner-Effekt
die Änderung der inneren Energiedich- te im normalleitenden und supraleitenden Zustand in Anwesenheit eines magnetischen Feldes.
schwachen Pauli-Paramagnetismus
Streng bedeutet; das Elektron muss sein K Vektor und seine Energie ändern.
_
Die anisotrope Magnetiserung kann sozugen mit D-Orbetalen zu tun. ( <b>Anisotropie</b> (von altgriechisch ἀν- an- "un-" [ <i>Alpha privativum</i> ], ἴσος <i>isos</i> "gleich" und τρόπος <i>tropos</i> "Drehung, Richtung") ist die Richtungsabhängigkeit einer Eigenschaft oder eines Vorgangs.)
Halbwegs , doch das ist so. hahaah
Mit Hohe Magnetfeld ——>

Das war damals eine große Aufregung in der Physik
Die Arbeitsscjicht (free )(Richtung ändern )
Fixierte schichte (Referenz)

Die Born-Oppenheimer-Näherung oder Born-Oppenheimer-Approximation (nach Max Born und J. Robert Oppenheimer) oder adiabatische Näherung ist eine Näherung zur Vereinfachung der Schrödingergleichung von Systemen aus mehreren Teilchen. Sie nutzt aus, dass schwere und leichte Teilchen in einem System ihre Bewegungsrichtung auf sehr unterschiedlichen Zeitskalen ändern, und dass die Bewegungsgleichungen der schnellen, leichten daher ohne Berücksichtigung der Bewegung der langsamen, schweren sinnvoll gelöst werden kann.

Die Born-Oppenheimer-Approximation wird bei der quantenmechanischen Behandlung von Molekülen und Festkörpern angewendet, da diese aus mindestens zwei Atomkernen und einer Vielzahl sehr viel leichterer Elektronen bestehen. Auch in der physikalischen Chemie findet die Näherung breite Anwendung, da hier lediglich für die einfachsten Systeme, z. B. das Wasserstoffatom, eine analytisch exakte Lösung der Schrödinger-Gleichung bekannt ist. [1] Die Born-Oppenheimer-Approximation wurde erstmals 1927 in den Annalen der Physik veröffentlicht. [2]

Als **Magnon** bzw. Magnon-Quasiteilchen bezeichnet man einen kollektiven Anregungszustand eines magnetischen Systems mit Eigenschaften eines bosonischen Quasiteilchens. Dieser Anregungszustand entspricht in Festkörpern der quantisierten Form einer magnetischen Spinwelle, analog zu den Phononen als quantisierten Schallwellen.

Einfacher ausgedrückt handelt es sich um eine Störung in Form einer Abweichung des Spins einzelner Teilchen, welche sich wie eine Schallwelle durch den Festkörper ausbreitet.

Unter einem **Quasiteilchen** versteht man eine Anregung eines Vielteilchensystems, die eine Energie-Impuls-Beziehung (Dispersionsrelation) wie ein Teilchen aufweist. Bei einem Quasiteilchen handelt es sich meist um einen kollektiven Zustand vieler Teilchen, eine elementare Anregung oder manchmal auch um den gebundenen Zustand eines Teilchenpaars. Charakteristisch für Quasiteilchen ist jedoch, dass sie außerhalb ihres Vielteilchensystems nicht auftreten können.

Ein bekanntes Beispiel sind die Defektelektronen ("Löcher") in einem Halbleiter, in dem sich die negativ geladenen Valenzelektronen kollektiv so in eine Richtung bewegen, als würde sich ein positiv geladenes Teilchen in die entgegengesetzte Richtung bewegen. Andere Beispiele sind Phononen, Magnonen, Cooper-Paare und Exzitonen.

Ein **Exziton** (engl. *exciton* von *excitation*, Anregung) ist ein gebundenes Elektron-Loch-Paar in einem Isolator bzw. einem Halbleiter. Es ist somit eine elementare Anregung des Festkörpers und außerdem wie ein Phonon oder ein Polaron ein Quasiteilchen. Ein Exziton kann sich durch den Kristall bewegen und transportiert dabei seine Anregungsenergie durch diesen hindurch, ohne dass ein Ladungstransport stattfindet, da das Exziton elektrisch neutral ist. Exzitonen haben einen ganzzahligen Spin.

Ein Exziton spielt eine große Rolle bei der Absorption von Licht in Halbleitern. Es kann z. B. entstehen, wenn ein Photon in einen Halbleiter eindringt und ein Elektron zum Übergang aus dem Valenzband in das Leitungsband anregt. Das Elektron und das im Valenzband entstandene, entgegengesetzt geladene Loch ziehen sich durch die Coulomb-Kraft gegenseitig an. Diese Situation ähnelt einem Wasserstoffatom und lässt sich auch quantenmechanisch analog beschreiben. Das gebundene Elektron/Loch-Paar hat eine etwas geringere Energie als der ungebundene Zustand. Allerdings ist die Bindungsenergie in der Regel viel kleiner und die räumliche Ausdehnung viel größer als beim Wasserstoffatom, da die Coulomb-Wechselwirkung zwischen Elektron und Loch teilweise abgeschirmt ist ("Screening").

https://www.uni-muenster.de/Physik.AP/Demokritov/Forschen/Forschungsschwerpunkte/mBECwasw.html

https://www.uni-muenster.de/Physik.AP/Demokritov/Forschen/Forschungsschwerpunkte/mBECwasw.html

https://qnap.e3.physik.tu-dortmund.de/suter/Vorlesung/ Festkoerperphysik\_WS01\_02/3\_Bindungen.pdf https://www.uni-muenster.de/Physik.AP/Demokritov/Forschen/ Forschungsschwerpunkte/mBECwam.html https://www.xtal.iqfr.csic.es/Cristalografia/indexen.html https://demonstrations.wolfram.com/ MillerIndicesForASimpleCubicLattice/ https://www.researchgate.net/figure/Rocking-curves-of-theasymmetric-1-0-5-reflection-peaks-in-AIN-epilayers-grown-withand\_fig4\_258260784 https://www.researchgate.net/post/peak\_position\_of\_AIN https://www.xtal.igfr.csic.es/Cristalografia/index-en.html https://ieeexplore.ieee.org/stamp/stamp.jsp?tp=&arnumber=7886528 https://www.rigaku.com/newsletters/mabu/april2015/thin.film.training.book.pdf

https://www.freiberginstruments.com/x-ray-diffraction/omegatheta-x-ray-

diffractometer/omegatheta-rocking-curve-measurement.html

### https://wiki.anton-paar.com/en/x-ray-diffraction-xrd/

\_

### X-Ray Analysis

<del>----></del>

X-ray diffraction results when an monochromatic, collimated X-Ray beam strikes a crystalline sample and the lattice spacings between atomic planes produce constructive interference with the incident beam at specified angles, in accordance with Bragg's Law.

The XRD system scans over a range of diffraction angles, yielding diffraction peaks that can be correlated to distinct families of atomic planes in crystalline specimens.

By analyzing the XRD peak pattern, one can: identify and quantify crystalline phases, calculate residual stress (macrostrain) in the material from measured lattice parameters, characterize the crystallite size and microstrain from peak broadening effects, and map the measured lattice parameters in reciprocal space to analyze pseudo-morphic growth of epitaxial films.

Additionally, advanced modeling can be performed from high-resolution XRD data to obtain layer composition and thickness information for epitaxial films, and rocking-curves procedures can be used to show the quality of the films.


# **Rocking Curve**

RC measurement reveals broadening of the diffraction peaks. The increase in the peak widths can be caused by:


Mosaicity (misorientation of crystallites)

Strain

Limited layer thickness



Typically XRD peak width is quantitatively described by Full-Width-at Half-Maximum (FWHM). From RC measurement it is impossible to separate mosaicity (variation in w) and lattice strain (variation in w/2q). These effects can be separated by analyzing Reciprocal Space Maps (RSM).



Empirically, mosaicities can be determined by measuring *rocking curves*.

Rocking Curve(Omega Scan) is an useful way to study perfection when the planes are not parallel. It's done by fixing the detector at the center of the expected Bragg reflection and the sample is tilted.

Defects like mosaicity, dislocations, and curvature create disruptions in the perfect parallelism of the atomic planes.

Rocking Curve(Omega Scan) is an useful way to study perfection when the planes are not parallel. It's done by fixing the detector at the center of the expected Bragg reflection and the sample is tilted.

The rocking curve is a way to explore a small region of reciprocal space at a constant Q-value. This is the only way to get information about the missorientation of different domains or zones of the film/crystal.

I try to explain this with an example. If you collect a theta/2theta scan you will find diffraction peaks corresponding to the family of planes parallel to the surface. This scan corresponds to a travel in the reciprocal space in the direction perpendicular to the surface. For example, in a cubic/tetragonal/ orthorhombic cell, and a (001) surface, the travel will be along (001)\*. For every point in the scan the modulus of Q will be 2sin theta/lambda. In general peaks will be thin (for very thin films, they will be wide due to the finite size effect). With this technique one can detect only interplanar distances, and that there are regions of the crystal with the right orientation (parallel to sample surface). To detect different orientations of those planes it is mandatory to make scans conserving the value of the Q modulus. There are different ways to perform that and one of those is a rocking curve. Moving omega keeping 2theta fix makes a travel in the reciprocal space that is a circumference around the ideal position of the diffraction peak. How quickly it disappears the intensity around this ideal position of the peak inform you about how disperse is the orientation of the corresponding planes: a rapid drop of the intensity means small dispersion, and a slow drop a large dispersion. To compare, if you have a polycrystalline sample (every possible orientation of the planes is present), there will be no variation of the intensity along the curve (the only variation will be due to geometrical reasons).