## ns-2 for the impatient

Imad Aad and Jean-Pierre Hubaux

### EPFL Lausanne, Switzerland

#### 1. INTRODUCTION

This document is a quick tutorial on ns-2 [4]. It introduces the basic simulation aspects of wireless networking. Other detailed tutorials and documentation can be found in [4, 2, 3]. We assume the reader is using a Linux machine (on which *ns* is already installed) and is familiar with common Linux basics.

Here are some conventions used throughout this document:

- ~ns/ is the *ns* directory (.../ns-allinone-2.27/)
- Templates for the examples in this tutorial, can be found in ~ns/quick-tutorial/.
- This document can be found in ~ns/quick-tutorial/quick-tutorial.html
- If you need to go into more details, you can find the complete ns Manual in

~ns/quick-tutorial/ns-manual.html

ns is written in tcl and in C++. We use tcl to configure the topology, the nodes, the channel, to schedule the events, etc. C++ is used to implement the protocols (have a look at the 802.11 implementation in  $ns/ns-2.27/mac/802_11.[cc,h]$ ). We will be using tcl scripts in this tutorial, without having to use the C++ implementations (to modify the protocols for example). Other independent tools will be needed to filter, compute and display the results.

Before starting, you should reinstall the tutorial scripts: go to ~ns/ and run: ./tutorial-install.sh.

# 2. A VERY SIMPLE SCENARIO: A "PURE" AD HOC NETWORK OF 6 NODES

Let us first start by showing the result of this example scenario, then we will explain the way to go there. Go to ~ns/quick-tutorial/ and run: ns ex6sta.tcl.

You will see a graph popping up, with 3 curves on it (Figure 1): the throughputs of 3 nodes when they contend to access the channel to send UDP packets to 3 others. They start at  $t_1=20s$ ,  $t_2=60s$  and  $t_3=100s$  respectively. Simulation stops at  $t_4=150$ .

Let us have a close look at ex6sta.tcl. The nodes (WT(1) ... WT(6)) are created then positioned as follows (Figure 2):




Figure 1: Throughputs of nodes WT(1), WT(3) and WT(5)

```
for {set i 1} {$i <= $opt(nn)} {incr i} {
    set WT($i) [ $ns_ node $i ]
}

proc coord_proc {a} {
    return [expr 10 * $a ]
}

for {set i 1} {$i <= $opt(nn)} {incr i} {
    $WT($i) set X_ [coord_proc $i]
    $WT($i) set Y_ [coord_proc $i]
    $WT($i) set Z_ 0.0
}</pre>
```




Figure 2: The ad hoc network topology

Like all the array variables opt () used throughout the script, opt (nn)

is defined (=6) at the beginning of ex6sta.tcl. coord\_proc is a procedure we define to compute the values to be assigned to X\_, Y\_(coordinates) of each node WT(i). *ns-2* does not take the Z\_elevation into consideration (flat 2-D topologies only).

We use CBR (constant bit rate) sources, over UDP layers, that we attach to nodes WT(1),WT(3) and WT(5):

```
for {set i 1} {$i < $opt(nn)} {incr i 2} {
    set udp($i) [new Agent/UDP]
    $ns_ attach-agent $WT($i) $udp($i)

    set sink($i) [new Agent/Null]
    $ns_ attach-agent $WT([expr $i +1]) $sink($i)
    $ns_ connect $udp($i) $sink($i)

    set cbr($i) [new Application/Traffic/CBR]
    $cbr($i) set packetSize_ 1000
    $cbr($i) set interval_ 0.005
    $cbr($i) attach-agent $udp($i)

    $ns_ at [expr 20.0 * $i] "$cbr($i) start"
    $ns_ at $opt(stop) "$cbr($i) stop"
}</pre>
```

For a UDP source in WT(i) we place a "sink" at WT(i+1) to receive the packets. Each CBR source sends 1000-Bytes packets each 5ms, therefore it can occupy alone the total the channel capacity (2 Mbits/s in this example). We schedule the sources to start at  $t_1=20s$ ,  $t_2=60s$  and  $t_3=100s$  respectively, and to stop at  $t_4=150s$ .

Lower layers of Mobile nodes are configured as follows:

```
$ns_ node-config -adhocRouting DumbAgent \
   -llType
                  LL \
   -macType
                  Mac/802_11 \
                  Queue/DropTail/PriQueue \
   -ifqType
   -ifqLen
   -antType
                  Antenna/OmniAntenna \
   -propType
                  Propagation/FreeSpace \
   -phyType
                  Phy/WirelessPhy \
   -channelType
                  Channel/WirelessChannel \
   -topoInstance
                  $topo \
```

adhocRouting specifies which ad hoc routing protocol to use (DSR, DSDV, AODV). Since all nodes are in the same collision domain, no ad hoc routing protocol is needed. ifqLen is the interface queue size. It has large influence on packet delays and drop rate. We use FreeSpace as a propagation model, which assumes there is a a single line of sight between senders and receivers (no radio wave reflections). More complex propagation models include TwoRayGround and Shadowing.

We consider a  $100m \times 100m$  topology

(\$topo load\_flatgrid \$opt(x) \$opt(y)). The default communication range of 802.11 nodes in ns-2 is 240m. Therefore all 6 (=opt(nn)) nodes considered here are within receive range of each other.

We define what traces should be put in the trace file (out.tr):

```
-agentTrace ON \
-routerTrace OFF \
-macTrace OFF \
-movementTrace OFF
```

agent traces are the ones written by traffic sources/destinations. Router traces are written by packet forwarders. MAC traces are written by each node's MAC. Nodes' movements can be traced by switching movementTrace ON (we don't need it for the moment).

We use the basic mode (no RTS/CTS, i.e. Mac/802\_11 set RTSThreshold\_ 3000), and the channel capacity is set to 2Mbps (Mac/802\_11 set dataRate\_ 2.0e6)

A god (General Operations Director) needs to be created:

```
create-god $opt(nn)
```

god is an object that is used to store global information about the state of the environment, network and nodes that an omniscient observer would have (without being available to any participant in the simulation). It accelerates the computation of the network routing/connectivity prior to the simulation run. We still need to create it even though we use no routing in our simulations.

Finally, at the end of the simulation (at t=opt(stop)), we reset all the wireless nodes and we call a procedure finish. In this procedure we call some external tools to filter, compute and display the throughput graphs. Everything is based on the trace file out.tr. Have it open and displayed while you follow the explanation. out.tr looks like this:

```
s 20.050000000 _0_ AGT --- 10 cbr 1000 ...
r 20.051231990 _1_ AGT --- 9 cbr 1000 ...
```

That is, at second 20.05 the agent in WT(1)  $(_0)^1$  sent (s) cbr packet number 10 of size 1000 (bytes). And at second 20.05123199, agent in WT(2) received cbr packet number 9, and so on.

Our goal is to compute the throughput of a given node  $_i$ \_along the simulation time. That is, we need to sum up all packets sizes (column 8) of the rows starting with r, between second t and t+1. The "array of seconds" will contain the throughput curve of node  $_i$ .

To do this computation, the tcl script (ex6sta.tcl) calls an external command, awk [1].

```
exec awk -f fil$i.awk out.tr > out$i.xgr
```

awk filters the trace file out.tr using filter fil2.awk and directs the output to out2.xgr (to be displayed with xgraph later on). Same with fil4.awk and fil6.awk.

Have a look at fil2.awk. BEGIN $\{\}$  initializes an array sec[i], which will contain the throughput at second i. This is done in the

<sup>&</sup>lt;sup>1</sup>Note that node numbering starts from 0 in the trace file

following lines (between  $\{\}$ ) which are applied to each line of the trace file.

```
if ($1=="r" && $7=="cbr" && $3=="_1_") {
sec[int($2)]+=$8;
};
```

It indicates that if the value in column 1 (\$1) is r (packet received) and the value in column 7 (\$7) is cbr (packet type) and the value in column 3 (\$3) is  $_1$  (WT(2)), then add the packet size (\$8) to the throughput in sec[int(\$2)].

at the end of the trace file, awk will display (output directed to out1.xgr) the array values as:

```
X Y
sec[i] throughput[i]
```

in bits/s.

Last, the output files (out2.xgr, out4.xgr and out6.xgr) are displayed calling:

```
exec xgraph out2.xgr out4.xgr out6.xgr &
```

from the ex6sta.tcl script.

#### **Exercises:**

With this basic information, you are (able and) asked to do the following:




Figure 3: The hidden node scenario

- Simulate a scenario with 3 nodes, A,B and C, where A is hidden to C<sup>2</sup>, and vice versa, see Figure 3. A and C send full rate CBR/UDP packets to B (situated in their receive ranges). A and C use the basic mode (no RTS/CTS) and start transmissions at different times. Show the throughputs.
- Same as 1, using RTS/CTS. Show both results on a single graph.
- 3. In a topology with no hidden nodes, show the total system throughput when the number of flows increases from 1 to 50 (i.e. 100 nodes). Consider both basic and RTS/CTS modes.
- 4. Simulate the scenarios in Table 1 of *Demo1* shown in the classroom (Figure 5). Merge the *Sink* and the AP into a single wireless node. You can have a look at infra.tcl to see how to create and configure TCP agents.

5. Simulate a multihop scenario (using AODV) and show the throughput vs. number of hops.

#### 3. ADDING AN INFRASTRUCTURE

As in the previous section, we will first start by checking the result of the example. Go to "ns/quick-tutorial/ and run ns infra.tcl. Simulations will start, then *xgraph* pops up showing a graph. *Nam* (Network AniMator) pops up two windows, one of which shows a network topology (you should zoom-in to see it properly). Figure 4 shows it more clearly.




Figure 4: W(1) routes packets from W(0) to the Mobile Host (MH), associated with his Home Agent (HA) or with a Foreign Agent (FA)

A wired node W(0), with address 0.0.0 is sending TCP packets to a Mobile Host (MH: 1.0.0) associated to its Home Agent (HA: 1.0.0). MH starts moving towards the Foreign Agent (FA: 2.0.0), gets disconnected from the HA (around t=113s), then connects to the FA later on (at t=174s). While moving back towards the HA, the MH gets disconnected again (at t=213s) then reconnects to the HA's network (at t=239s). This can be observed in the xgraph output curve.

Wired node W(1) (0.1.0) routes the packets from W(0) to the HA and FA. All wired links are 5Mbps and have 2ms delays (cf. infra.tcl):

```
$ns_ duplex-link $W(0) $W(1) 5Mb 2ms DropTail
$ns_ duplex-link $W(1) $HA 5Mb 2ms DropTail
$ns_ duplex-link $W(1) $FA 5Mb 2ms DropTail
```

We can control how these wired links look like in NAM by setting:

 $<sup>^2\</sup>mathrm{You}$  will have to reduce the carrier sense range (to 252m) using: Phy/WirelessPhy set CSThresh. 3.5e-10

```
$ns_ duplex-link-op $W(0) $W(1) orient down
```

How do we tell the HA to forward the MH's packets to its new location (FA)? MobileIP takes care of this:

```
$ns_ node-config -mobileIP ON
```

And we have to register the MH at the corresponding Home Agent (HA):

```
set MH [$ns_ node 1.0.1]
set MH [$ns_ node 1.0.1]
set HAaddress [AddrParams addr2id [$HA node-addr]]
Exercises:
[$MH set regagent_] set home_agent_ $HAaddress
```

Therefore, when the MH moves towards the FA (starting at second 100)

```
$ns_ at 100.00 "$MH setdest 640.00 610.00 20.00"
```

at a speed of 20m/s (640 and 610 are the coordinates of the FA), the home agent (HA) will take care of tunneling MH's packets to the FA.

In this topology we are using hierarchical addresses:

```
$ns_ node-config -addressType hierarchical
```

composed of 3 domains (0.x.x to which the wired nodes belong, 1.x.x where HA and MH belong, and 2.x.x where the FA belongs), therefore:

```
AddrParams set domain_num_ 3
```

The first of the 3 domains has  $\boxed{2}$  clusters: 0.0.x and 0.1.x. The second domain (1.x.x) has only 1 cluster (i.e. 1.0.x), and the last domain also has 1 cluster (i.e. 2.0.x), therefore:

```
lappend cluster_num 2 1 1
```

Finally, cluster 0.0.x has 1 node; cluster 0.1.x has 1 node; cluster 1.0.x has 2 nodes; and cluster 2.0.x has 1 node. Therefore:

lappend eilastlevel 1 1 2 1

The rest of the tcl script is similar to the previous example (in Section 2).

Note that in this example we have 2 trace files:

```
set tracefd [open $opt(tr-ns) w]
set namtrace [open $opt(tr-nam) w]
$ns_ trace-all $tracefd
$ns_ namtrace-all-wireless $namtrace ...
```

One of these files is used by NAM. We will let you discover NAM's GUI intuitively, and watch the packet runs on the wired links. Mobile nodes can be seen moving in NAM. However, packets are not shown on the wireless channel.

As for the ns trace file, the structure differs slightly from the one seen before since it combines wireless (similar to the previous one) and wired traces. Since we are only interested in the throughput of the MH (wireless), we only had to adapt the awk filter fil-tcp.awk to count tcp packets instead of cbr ones:

```
if ($1=="r" && $7=="tcp" && $3=="_4_") {...
```

Now that you are familiar with wireless and wired networking simulations, you are (able and) asked to simulate all scenarios of *Demo1* done in the classroom. Refer to Figure 5 and to Table 1.




Figure 5: The topology considered in Demo1

Scenario #	S1
1	7 Mbps UDP, pkt_size= 1448 B
2	7 Mbps UDP, pkt_size= 1448 B
3	7 Mbps UDP, pkt_size= 1448 B
4	7 Mbps UDP, pkt_size= 724 B
5	7 Mbps UDP, pkt_size= 2000 B
Scenario #	S2
Scenario #	S2 7 Mbps UDP, pkt_size= 1448 B
Scenario #	2
Scenario #  1 2 3	7 Mbps UDP, pkt_size= 1448 B
1 2	7 Mbps UDP, pkt_size= 1448 B 7 Mbps UDP, pkt_size= 724 B

Table 1: Scenarios of Demo1

### **4. FAQ**

Q: Compilation problem... what's wrong?
A: Make sure there are no spaces after
\$ns\_ node-config -adhocRouting DumbAgent \
and all \s of the following lines.

Q: Even though the hidden nodes are far enough from each other, it seems they still can sense each other (no decrease in throughput). Why?

A: A common problem is to miss one of the "h"s in: Phy/WirelessPhy set CSThresh\\_

#### 5. REFERENCES

- [1] http://www.cs.hmc.edu/qref/awk.html.
- [2] Kevin Fall and Kannan Varadhan. The *ns* manual. http://www.isi.edu/nsnam/ns/ns-documentation.html.
- [3] M. Greis. Marc Greis' Tutorial for the UCB/LBNL/VINT Network Simulator "ns". http://www.isi.edu/nsnam/ns/tutorial/index.html.
- [4] The VINT Project. Network Simulator. http://www.isi.edu/nsnam/ns/.