

MŌNANDÆG

EIGHT TAKES, ONE FOLD

USER GUIDE · VERSION 1.0 · MAC

K.ODK

Eight takes, one fold

Mōnandæg plays sound files through a **wave folder**. Up to eight takes stand in a row, A to H. At any moment one or two of them are heard, and one or two others are only listened to.

The takes that are heard are **PLAY**: they run through three fold stages, four times oversampled, and come out bent and bright. The takes that are listened to are **FOLLOW**: their loudness pushes the fold. Every take has a gate of its own, the gates are wired into a small net, and when one fires the roles change hands — so the piece keeps rearranging itself out of the sound itself.

Around the fold sit the rooms: FREEZE, BREAK, LOOP, TEXTURE, SEND, SPEAK, and PRESET — where the settings and the files are kept and a WAV is written. On the Mac there is one more: FILES, a list of A … H.

Too much to read? Skip it. Drop a few sound files on the window (they go into A, B, C …), press BASIC (the metronome key) and move the three pads. Press it again to go back to where you were.

In your DAW

The app, the AU (AUv3) and the VST3 are the same instrument. In your DAW you'll find **Mōnandæg** under *k.odk*: put it on an instrument track and it plays by itself — MIDI notes are not needed. As an audio effect, **Mōnandæg FX** folds what comes in (see page 12).


Installing

1. Open **Mōnandæg.pkg** and follow the installer. You can choose: **Standalone + AU**, and/or **VST3**.
2. Open **Mōnandæg** once from Applications — this registers the AUv3.
3. In your DAW, rescan plug-ins. Mōnandæg is under **k.odk**.

Standalone + AU	The Mōnandæg app in /Applications, with its Audio Unit (AUv3) inside — the instrument and the effect (Mōnandæg FX). Logic, GarageBand, Live and other AU hosts list them under *k.odk*.
VST3	In /Library/Audio/Plug-Ins/VST3 — Live, Bitwig, Reaper, Cubase …
The app	Plays on its own through the output chosen in the Mac’s Sound settings.

Requires macOS 12 or later · Apple silicon and Intel.

Keys, takes, pads




FREEZE BREAK LOOP TEXTURE SEND SPEAK	The rooms, as icons along the top left: snowflake, hammer, arrows, tape, dial, speech bubble. A key stays lit while its room is doing something. Esc or **CLOSE ✕** closes a room.
PRESET FILES	The tray: PRESET — twelve slots, the WAV, RING · FM · FADE. The folder: FILES, A … H in a list.
Fold · scope	The curve is the shape of the fold right now; the line beside it is the output.
REC→A	The take the record key writes into — click to step A to H. The record key starts and stops: what goes out becomes that take.
Freeze · swap · run	The snowflake freezes: once the first seat, twice the second, a third time lets both go. ⇄ swaps the roles now. Pause / play runs the takes.
Drift · basic	The wind is DRIFT — the pads and knobs on the front move by themselves. The metronome is BASIC: four takes, one heard, one listening.

Who plays, who steers


A … H	Click the name row of a cell to open a file into it; hold it to empty the take. A letter printed white is PLAY, in a white outline FOLLOW. The small square flashes when the gate opens. Drag either edge of the strip to choose the part that is read; the slider is the take's level.
I · II · III	Three fold stages in series. X is how hard the stage folds (at the left edge: OFF), Y the bias — where the folds land.
SOFT · SPREAD · TONE	How rounded the folds are · the two channels pulled apart · a low-pass on the way out.
FOLD · SPEED · LEVEL	Folded against the take as it was · how fast the takes are read, ×0.25 to ×4 · the output.
THRESH · HOLD	Where a gate opens · with CLOCK how often the roles change, with GATE the shortest time before they may change again.
RANDOM · CV · SHIFT · FOLLOW	Chance in who comes next · how far the FOLLOW takes push the fold and the bias · how quickly the listening follows.
FILES	4, 6 or 8 takes in one net; 2·2 and 4·4 run two nets side by side.
ROLE · READ	One or two PLAY and FOLLOW; POP drops in short pieces. Forward, backward, both ways, JUMP or STEADY.
NET · SWAP · LOCK	RING, CROSS, STAR or ALL · CLOCK, GATE, STAY or NOW · LOCK returns to a passage every 1–16 s.
SCALE · PITCH · GLIDE	The folded sound turned into a pitch movement on the takes, snapped to FREE, 12, PENTA or 8+5.
SCATTER · FOL VOL	How far a JUMP may land · a little of the FOLLOW takes heard as they are.

One moment, held



1ST · 2ND	Two seats. FREEZE catches what is playing as a chord, STACK lays another moment on top (LAY counts them). Choose the chord, then OCT −, TUNE, OCT +.
LEVEL · CHORD · KEEP	Its volume · how much of the upper voices · how bright it stays.
HARM · TILT · SHIM	An octave above · the height of the whole · a slow shimmer.
FREEZE BOTH · ROLL · GATED	Both at once · roll the knobs of both seats · roll again whenever the sound crosses OVER.
DRIFT · HALT ALL · ALL OFF	The knobs wander · the takes stop while frozen · everything let go.
1 … 4	Four slow movers. The arrows choose the knob, ALT moves the other seat’s the opposite way; SINE, TRI, STEP or DRIFT; SYNC ties a cycle to a turn of the take; RATE, DEPTH, MID. ROLL MOD rolls all four.


Cutting the files



BREAK rewrites the file itself, not the way it is played. UNDO keeps the last steps of each take.

WHICH FILE	A … H. DICE does something at random, REVERSE turns it round, CROP TO RANGE keeps only the part the strip reads.
SHATTER	GRAIN (the size of the pieces), MESS, FLIP, SPRAY; then SHATTER, SCATTER, STUTTER, or SPLICE — pieces borrowed from the other takes.
FREEZE CHORD	One moment — POINT, or HERE for where it plays — written back as a held chord. LENGTH, BLUR; MAKE CHORD writes it.
HOLES · TIME	MANY and LONG, then MAKE HOLES · STRETCH without the pitch · PITCH as tape speed · CRUSH. Each is written when its key is pressed.

Tape and disc




An insert on the output: nothing is written, it wears what you hear.

TAPE	WOW, FLUTTER, SAT, HISS, DROPOUT, HEAD (a worn head that takes the top off).
NEEDLE	SKIP, GRIP, CLOSE, GAP, SEEK — a player that sticks, repeats and jumps.
DISC	OFF · STUCK · OPEN, then DEPTH, SLIP, TURN, WIDE.
VOID	Where the sound goes missing: STARVE, DROP, LENGTH, CHOKE, FADE, LOSS. LOSS ON switches the column; HEAL fills it back.
GLITCH	Choose the takes (A … H or ALL) and the kinds — STUTTER, REVERSE, TAPE STOP, CRUSH, GATE, FREEZE; OFTEN is how often.
The bottom row	WORN TAPE and CLEAN TAPE set the tape at once · CLEAR DIGITAL · DRIFT and WANDER let the knobs move.

07 · SEND

Echo, room, sweep



Three boxes side by side. On each, FILES and SPEAK choose what goes in: the folded takes, the spoken voice, or both.


ECHO	MIX, TIME, FEED, WIDTH, BITS — each repeat comes back with fewer bits. SYNC: one turn of the first PLAY take. SLAP, TAPE, STEP.
ROOM	MIX, SIZE, TAIL, DAMP, BITS, WIDTH. PLATE, HALL, GATE, 12-BIT.
SWEEP	A comb that steps through 2 … 32 places: MIX, DEPTH, RATE, WIDTH. STRAY lets a take spill in, OFTEN how often. DRIFT · ALL OFF.

08 · LOOP

One loop from many takes


The arrows key. One waveform cut into STEPS (4 … 32); click or drag across steps to choose where to write. FROM chooses the take, TAKE which part (START, MIDDLE, END, LOUD, QUIET, ATTACK, TAIL, TONAL, NOISY, RANDOM, HERE), SHAPE how it changes on the way in. EXTRACT writes it; OVERDUB adds; LOOP ON plays the loop instead of the net; INTO copies it into a take.

A voice and a harmoniser



TEXT	Type what it will say; ADD A LINE, CLEAR, DONE. READ ALL, FROM ANY, LINES or PIECES. The language and the voice below — the voices installed on the Mac (more in System Settings › Accessibility › Spoken Content).
SPEAK · PLAY · HEAD · LINK	Speak the text into the voice track · run it · back to the start · its start lined up with the takes.
AUTO · CHORD	Speaks again by itself (TIMED or GATED) · rolls the chord too.
OFF · GATE · OVER	The voice opens only when the fold sounds; OVER is how loud.
HARMONISER	Up to twelve voices, −12 … +12; ONE, OCT, 5TH, MIN7, MAJ7, SUS, DIM, WHOLE, WIDE, CLUST set a chord, ROLL picks one.
HOW IT READS	RATE, DETUNE, RES, RELEASE, FREEZE. DRIFT moves them, LIGHT · SOME · ALL.
The voice track	LEVEL, PAN, SPEED, SWAY, WEAR, VOX, EVERY, THROW, AUTO.

Keeping a whole session



PRESETS 1 … 12	Hold a slot to keep it: every setting and the files in A … H. Click a kept slot to bring it all back. CLEAR SLOT, then a slot, empties it. They live in ~/Library/Application Support/Monandaeg.
WAV	A name, ● REC, ■ STOP: what goes out as a 24-bit WAV in Music › Monandaeg. Without a name, the date.
CLEAR ALL FILES	Empties A … H at once.
RING · FM	RING multiplies each take by the others sounding · FM bends each take’s speed with the others’ sound.
FADE · AT END → NEXT · NEXT NOW	How long one take gives way to the next · move on at the end of the range · move on now.

A … H in a list



OPEN FILES	Several at once, into the empty takes from A on. Files dropped on the window go the same way.
OPEN · CLEAR	Each line opens a file into its own take, or empties it.
▲▼	Two takes change places.
CLEAR ALL	Every take empty.
The files	Any sound file the Mac can read, taken in mono at 44.1 kHz — up to two minutes each. The song keeps them with it.

Mōnandæg FX, and a few ways in

On an audio track, **Mōnandæg FX** reads no file: one sound — what comes in — in eight places. It is written round a ring of sixteen seconds, and A … H all read that ring: A as it comes, B … H each from a place of its own. The roles, READ, the net, SPEED, SCATTER, PITCH, FREEZE, TEXTURE, BREAK, LOOP and SEND all work on it. In place of REC: DRIFT and WANDER. Not there: FILES, SPEAK, REC, the WAV. With nothing coming in, nothing goes out (unless something is frozen).

A first fold	Three or four field recordings into A … D, BASIC on, then move pad I to the right.
Hold it	When something good happens, press the snowflake: the chord stays while the takes go on.
Rough it up	TEXTURE · WORN TAPE, then a little GLITCH on ALL.
Keep it	Hold a PRESET slot; ● REC a WAV while you play.
In a DAW	Put it on its own track and record the output; the host sees Volume and eight knobs for automation.
It screams	Several rooms feed back by design. Pull SEND down first, then the take levels.

Credits

Mōnandæg — k.odk (Kei Odaka)
Support · keiodak.github.io/privacy/monandaeg-support.html · kodk.dev@gmail.com

Requires macOS 12 or later · Apple silicon and Intel.