Install STAF on macOS

By qzh.anny@gmail.com

 Download latest STAF binary for macOS from http://staf.sourceforge.net/getcurrent.php.

In my PC, I installed with STAF3426-setup-macosx-universal.bin

2. Start staf installation wizard by running


\$ sudo ./STAF3426-setup-macosx-universal.bin
Preparing to install


Extracting the installation resources from the installer archive...


Configuring the installer for this system's environment...


Launching installer...


Properties file for authenticator not read as user is truly "root"




















3. Create a symbolic link to /Library/staf/lib

\$ sudo mkdir -p /Library/staf/lib
/opt/dev/autobuild/build/rel/macosx/staf/retail
\$ sudo ln -s /Library/staf/lib
/opt/dev/autobuild/build/rel/macosx/staf/retail/lib

4. Edit /Library/staf/startSTAFProc.sh

\$ sudo vim startSTAFProc.sh

#!/bin/sh

Sets up the STAF environment variables and starts STAFProc

in the background, logging STAFProc output to nohup.out
ipconfig waitall

. /Library/staf/STAFEnv.sh

cd /Library/staf/lib

nohup /Library/staf/bin/STAFProc &

5. Add your ip/hostname to /etc/hosts

your_PC_ip your_PC_hostname.domain your_PC_hostname

6. Create a data diretory

- \$ sudo mkdir /Library/staf/data
- \$ sudo chmod -R a+w data

7. Change "trust machine local://local level 5" to "trust machine
 :// level 5" in /Library/staf/bin/STAF.cfg

```
$ sudo sed -i -e 's/local:\/\/local /*:\/\* /'
/Library/staf/bin/STAF.cfg
```

- 8. Start STAFProc
 - \$ /Library/staf/startSTAFProc.sh
- 9. Start STAFProc during boot (not tested)

```
$ sudo vim /Library/LaunchDaemons/com.ibm.staf.plist
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE plist PUBLIC "-//Apple Computer//DTD PLIST 1.0//EN"</pre>
 "http://www.apple.com/DTDs/PropertyList-1.0.dtd">
<pli><pli><pli><pli>version="1.0">
<dict>
 <key>Label</key>
 <string>com.ibm.staf</string>
 <key>Program</key>
 <string>/Library/staf/startSTAFProc.sh</string>
 <key>RunAtLoad</key>
<true/>
 <key>StandardOutPath</key>
 <string>/Library/staf/com.ibm.staf.out</string>
 <key>StandardErrorPath/key>
 <string>/Library/staf/com.ibm.staf.out</string>
</dict>
</plist>
```

Notes: By default, staf is installed under /Library/staf. If you changed the target installation folder, please make sure you also change /Library/staf in above commands to your staf's installation folder.

Reference:

http://staf.sourceforge.net/current/STAFInstall.pdf