# How to configure the snapshot directory

Last updated by | Vitor Tomaz | Feb 24, 2023 at 3:31 AM PST

#### **Contents**

- Create storage account and file share
- Configure a new Distributor
- · Change an existing Distributor
- Public Doc Reference

### How to configure the snapshot directory for an Managed Instance Distributor

This is a "How To" TSG to show you how the snapshot directory can be (re-)configured for a Distributor hosted on Managed Instance.

Note that you need to replace logins, passwords, account names etc. with your own configuration.

The snapshot directory is configured through a property of the Distributor. The steps below demonstrate how to set up the snapshot storage and how to set the Distributor properties pointing to the storage.

### Create storage account and file share

- Create an Azure storage account ☐ for the working directory
- Create a file share 12 within the storage account
- Copy the file share path in the format of:

\\storage-account-name.file.core.windows.net\file-share-name.

Example: \\replstorage.file.core.windows.net\snapshots

- View the storage account access keys [2]
- Copy the storage acount access keys in the format of:

DefaultEndpointsProtocol=https;AccountName=<Storage-Account-Name>;AccountKey=\*\*\*\*;EndpointSuffix=core.windows.net
Example:

DefaultEndpointsProtocol=https;AccountName=replstorage;AccountKey=dYT5hHZVu9aTgIteGfpYE64cfis0mpKTmmc8+EP53GxuRg6TCwe5eTYWrQM4AmQSG5lb3OBskhg==;EndpointSuffix=core.windows.net

# Configure a new Distributor

```
-- enable distribution

EXEC sp_adddistributor @distributor = @@ServerName, @password = N'$trongPa11word';

-- create distribution database

EXEC sp_adddistributiondb @database = N'Distribution';

GO

-- Configure the Publisher at the Distributor

-- CRITICAL: Port 445 (TCP outbound) needs to be open in the security rules of the Managed Instance subnet to

-- set the name of the publisher here:

EXEC sp_adddistrublisher @publisher = @@ServerName,

    @distribution_db = N'Distribution',
    @security_mode = 0,
    @login = N'TRANREPLADMIN',
    @password = N'$trongPa11word',
    @working_directory = N'\\replstorage.file.core.windows.net\snapshots',
    @storage_connection_string = N'DefaultEndpointsProtocol=https;AccountName=replstorage;AccountKey=dYT5hHZV
```

## Change an existing Distributor

```
exec sp_changedistpublisher @publisher = @@ServerName,
    @property = N'working_directory',
    @value = N'\\replstorage.file.core.windows.net\snapshots';

exec sp_changedistpublisher @publisher = @@ServerName,
    @property = N'storage_connection_string',
    @value = N'DefaultEndpointsProtocol=https;AccountName=replstorage;AccountKey=dYT5hHZVu9aTgIteGfpYE64cfis0m
```

### **Public Doc Reference**

- <u>Mount SMB Azure file share on Windows</u> ☑ (this is helpful if you need to view and manage snapshot files manually)
- Tutorial: Configure replication between two managed instances

### How good have you found this content?

