USER MANUAL · WEB SYSTEM AND WINDOWS TILL

Pockets POS User Manual

Step-by-step guide for cashiers, supervisors, managers and administrators.

Pockets POS is a point of sale and back office for shops, bars, hardware stores and other retailers in Zimbabwe. It sells, keeps stock, manages cash and customers, and issues ZIMRA fiscal receipts. This manual walks every user through the system, one role at a time.

Web system

Runs in any browser. The back office for managers and admins, plus the **Web POS** selling screen.

Windows desktop till

Pockets POS for Windows. Sells with or without internet and sends its sales to the web system when it is online.

ZIMRA fiscalisation

Every sale is a signed fiscal invoice and every refund a credit note, sent to ZIMRA automatically.

Who does what


ROLE	WHO IT IS FOR	WHAT THEY CAN DO
Till	Cashiers	Sell, print receipts, request refunds, cash in / out, count the till and close it. Own branch only.
Supervisor	Shift leaders	Everything a Till user can do, plus approve refunds and run the ZIMRA fiscal day.
Management	Shop managers, owners	Everything a Supervisor can do, plus dashboards, sales, stock, cash and tax reports, ZIMRA receipts and refund checks.

ROLE	WHO IT IS FOR	WHAT THEY CAN DO
Admin	The business administrator	Everything: products, stock, purchasing, customers, users, tax rates, ZIMRA devices, backups and desktop tills, for all branches.
Super Admin	Pocket Solutions (the provider)	Sets up companies and publishes desktop till updates. Never sells or refunds.

01 Getting started EVERYONE

Signing in

1. Open the web address your administrator gave you in Chrome, Edge or any modern browser.
2. Enter your **email or username** and your **password**, then press **Login Now**.
3. Till users go straight to the selling screen. Everyone else lands on **Admin Home**.



The sign-in page. Use Light or Dark at the top right to change the colours.


Security. After 5 wrong passwords the account is paused for 15 minutes. You are signed out after 10 minutes without activity. Change your password any time from **Password** at the bottom of the menu.

Finding your way around

The menu on the left groups the pages: **Sell**, **Reports**, **Till & Cash**, **Products & Stock**, **Purchasing**, **Customers & Accounts**, **Finance** and **Admin**. You only see the pages your role allows.

- **Search menu** at the top finds any page by name. Type a product name and press Enter to search products.

- **Switch branch** changes the branch you are working in, for users allowed more than one branch.
- The tiles on **Admin Home** are shortcuts to the most used pages.




Admin Home with the shortcut tiles and the menu on the left. (Company details blurred.)

02 Selling at the till TILL

This chapter is for cashiers. The same steps work on the **Web POS** and on the **Windows desktop till**.

1. Open the till


1. Open **Web POS** from the menu.
2. Tap **Till** at the bottom of the screen.
3. Count the cash in the drawer and enter it as the **Opening float**, then tap **Open Session**.



The Till menu: open a session with the opening float, check its status, reconcile and close.


> The daily routine is always: **Open → Sell → Reconcile → Close**. If a till is left open overnight the screen reminds you to reconcile and close it.

2. Ring up a sale




The selling screen: product tiles on the left, the order on the right. Group buttons at the top filter the tiles.

- **Tap +** on a product tile to add one. **Tap −** to take one away.
- **Tap the number** between − and + to **type a quantity**, e.g. 12. Enter 0 to remove the item.
- **Search or scan**: type a name, product ID or barcode in the box at the top, or scan the barcode.
- Items sold by weight or length (kg, m, litres) always ask for the amount, e.g. 1.25 kg.
- Items with sizes or colours open a picker so you can choose the right one.



Four items in the order. The totals update as you add items.



Tap the quantity to type it. "Set quantity" saves it; 0 removes the item.


3. Choose the customer (optional)

Sales go to **Cash Customer** unless you pick someone. Tap **Customer**, search by name, phone or code, and choose them. To sell on account (credit), the customer needs an active customer account.

4. Take payment

1. Tap **Print / Submit** or **Place Order**. The payment screen opens.


2. Choose the **payment method**: Cash, Card, EcoCash, Bank transfer, Account (credit) or Other.
3. Enter the **amount paid**, or tap **Exact** or a quick amount such as $100. The change is shown.
4. Tap **Confirm Payment**. The receipt prints, with the ZIMRA QR code and verification code when the branch is fiscalised.



The payment screen. Card, EcoCash and bank payments can carry a reference number.

5. Reprint a receipt


Open **Receipts**, search by customer or date, and tap **Print** next to the invoice.



Past receipts for the branch. (Staff details blurred.)

6. Cash in and cash out


Use **Cash In / Out** for money added to or taken out of the drawer that is not a sale: float top-ups, cash drops to the safe, small payments. Choose Cash in or Cash out, enter the amount and reason, and save. Movements cannot be edited afterwards, so check before saving.



Cash In / Out shows the expected cash in the drawer and the session's history. (Names blurred.)

7. Count the till (reconciliation)


Before closing, count the cash and enter it on **Cash Reconciliation**. The system compares your count with the expected cash: opening float + cash sales + cash in − cash refunds − cash out. Any shortage or surplus is recorded.



Cash Reconciliation for the open till. (Names blurred.)

8. Close the till


Open **Close Till** and confirm. Closing needs a current reconciliation, and it cannot be undone. The next cashier opens a new session.



Close Till with the closed-till history on the right. (Names blurred.)

9. Ask for a refund

1. Open **Refunds** and enter the **receipt number**.
2. Choose the items and quantities being returned and send the request.
3. A Supervisor, Manager or Admin approves it and processes the refund. Cash refunds come out of the till; stock goes back on the shelf; a ZIMRA credit note is issued.



Refunds: look up the receipt to start a request.

03 Supervisor tasks SUPERVISOR


Approving refunds

Every refund goes **Request → Approve → Process**. Open **Refunds**, open the waiting request, check the items, and choose **Approve** (with a note) or **Reject**. Then **Process** it to pay the customer and return the stock. Quantities are locked once approved; to change them, reject and ask for a new request.

The ZIMRA fiscal day

ZIMRA requires every fiscal device to work in **fiscal days**. Pockets POS handles most of this for you:

- The fiscal day **opens automatically** with the first sale. Nobody has to open it.
- **Close the fiscal day at the end of trading**, every day, from **ZIMRA Fiscal Day** › **Close fiscal day**.
- The page shows the day number, when it opened and the **hours left** before ZIMRA's limit (usually 24 hours). The status bar warns in the last 3 hours.
- If the day reaches the limit, sales stop until it is closed. ZIMRA does not allow signing past the limit.
- **Send waiting receipts now** pushes any receipts that could not reach ZIMRA earlier.



ZIMRA Fiscal Day: status, hours left, the day's receipts and any that need attention.


If ZIMRA cannot be reached, keep selling. Receipts are signed on the spot, printed with their QR code, and sent automatically when ZIMRA answers again. Only closing the day has to wait until ZIMRA is reachable.

04 Reports for managers MANAGEMENT

Managers see live figures for the branches they are allowed. Reports can be filtered by date and branch, and most export to CSV or PDF.

Management Dashboard


Sales, stock, cash and refunds for a period at a glance, with operational alerts such as tills left open or receipts waiting for ZIMRA.



Management Dashboard with period filters and quick links to the detailed reports.

Sales Reports


Every sale by date, branch, cashier, product and payment method, plus refunds and cancelled sales. Click an invoice to open it.



Sales Reports: switch between Transactions, By branch, By cashier, By product, Payment methods, Refunds and Cancelled. (Names blurred.)

Z Report


Sales by cashier for a day or date range: the end-of-day summary. Print it or save it as a PDF.



Z Report for the working branch.

Inventory Reports


Stock on hand, low stock, out of stock and stock movements, with stock value at cost.



Inventory Reports with the stock value summary.

Cash Management


Expected cash in every open till, cash sales, cash in and out, shortages and surpluses, by cashier, till and branch. From here you also reach the Cash Movements, Reconciliation and Till Closure reports and the **Cash Audit** history.



Cash Management dashboard.

ZIMRA Fiscal Receipts

Every fiscal invoice and credit note with its fiscal day, receipt number, status at ZIMRA and verification code.



ZIMRA Fiscal Receipts for a date range.

Refund Reconciliation


Checks that every processed refund has the matching stock return and cash refund, and lists anything that does not add up so it can be reviewed. It only reads; it never changes your records.

05 Running the business (Admin) ADMIN

Admins set the system up and keep it running. This chapter follows the order you would set up a new shop.

Users


Open **Users** › **Create user**. Enter the person's name and phone, an email address or a simple username (e.g. *tendai.m*), a password, their **role** (Till, Supervisor, Management or Admin) and their **branch**. Accounts can be locked when someone leaves; history is never deleted.




Create User. Staff without an email can sign in with a username.

Products


- **Items** lists products for the working branch. Search, filter by button group and edit prices in place. Inactive items stay for history but are hidden from the till.
- **Create item**: name, optional barcode, selling and cost price, tax code, category and button group. The product ID is given automatically.
- **Import Items** loads many products at once from the Excel template.
- **Bulk Price Change** raises or lowers many prices together. **Barcode Labels** prints shelf labels.
- **Categories & Groups**: categories group products in reports; **button groups** are the coloured buttons cashiers tap on the till. Set their colour and order here.



Items: search, edit prices, print barcode labels, import and export.




Create Item. New items start with zero stock.




Categories and till button groups.

Stock


- **Opening Stock** sets the starting quantity for each product.
- **Goods Receipt** (GRV) books in deliveries from suppliers, with or without a purchase order. Stock goes up when goods are received.
- **Stock Adjustment** corrects quantities (damage, expiry, theft, count differences) with a reason.
- **Stock Transfers** move stock between branches.
- **Stock Take** prints a count sheet and records counted quantities against the system quantity.
- **Stock Movements** and **Product History** show every change to a product.



Goods Receipt: new receipts, receiving against a purchase order, and purchase returns.




Stock Adjustment needs a reason for every change.



Stock Take: enter counted quantities and save.

Purchasing


Keep **Suppliers**, raise **Purchase Orders** and receive them through Goods Receipt. Purchase orders do not change stock until the goods arrive. **Purchase Returns** send goods back. **Purchasing Reports** summarise spend by supplier and product.



Purchase Orders.

Customers and accounts


Customers keeps your customer list. To sell on credit, open a **Customer Account** for the customer and set a limit. Record payments in **Account Payments**, print statements, and follow up debtors with **Receivables Ageing**, **Credit Control** and **Collection Activity**.



Customer Accounts for credit sales.

Finance


- **Expenses** records business costs.
- **Tax Rates** holds VAT and other rates (e.g. VAT 15.5%, prices inclusive). Each product gets a tax code; it decides the VAT on receipts and ZIMRA invoices.
- **Tax Reports** and **Accounting Export** give your accountant what they need.



Tax Rates and sales tax enforcement.

ZIMRA device setup


Each branch has one ZIMRA fiscal device. Copy the device ID, serial number and activation key from the ZIMRA portal, choose **Test** or **Production**, and register. When the status shows **Fiscalising**, every sale on that branch is a fiscal invoice.



ZIMRA Device Setup. (Taxpayer and device details blurred.)

Desktop tills


To add a Windows till: open **Desktop Tills**, choose the branch, give the till a name (e.g. Front counter) and press **Add till**. Press **Pairing code** and enter that code on the PC (see the Desktop till chapter). The list shows when each till was last seen and how many sales it has synced. **Revoke** disconnects a lost or replaced PC. **Sync Differences** lists offline sales that differed from the server, such as an old price.



Desktop Tills: add a till, get its pairing code, revoke. (Names blurred.)

Backup & Recovery

The web system backs up its database automatically and keeps a set number of copies. **Run database backup now** takes one on demand. Health checks show the last backup and storage status.



Backup & Recovery for the web system.

06 Selling and paying in other currencies EVERYONE

A company can sell in more than one currency, for example US dollars and ZiG. Every company has one **base currency**. Prices are kept in the base and totals and reports are shown in it. Other currencies are converted with the exchange rate your manager enters.

Selling in another currency (cashiers)

1. On the selling screen, choose the currency in the **currency box** under the till line *before* adding items. It only appears when your company uses more than one currency.
2. Prices on screen change to that currency. The rate in use is shown next to the box, for example **1 USD = 26.50 ZWG**.
3. Take payment in the same currency. Change is given in that currency too.
4. The receipt shows the amounts in that currency (the exchange rate is kept with the sale but not printed). On fiscal branches the ZIMRA receipt is issued in the same currency.

Rate changed? If a manager changes the rate while you are serving, the till tells you and updates the prices. Check the new total with the customer, then pay again.

Counting and closing the till

- Each currency has its own drawer total. **Cash Reconciliation** shows one tab per currency in your drawer: count each one.
- **Close Till** lists every currency. The till closes only when every currency has a count that is still current.
- **Cash in / out**: choose the currency before the amount.

Refunds

There is nothing to choose. A refund is always paid back in the currency the customer paid in, at the rate of the original sale.

Customer accounts

- When opening an account, pick its **Account currency**. It cannot be changed later. Credit sales must be made in it.

- When a customer pays in another currency, choose **Received in** on the payment page. The amount is converted at today's rate and the balance stays in the account currency.

Purchasing and expenses

Purchase orders, goods received without an order, and expenses each have a **Currency** box. Choose the currency the supplier invoiced in. Goods received against an order use the order's currency.

Exchange rates (Management and Admin)

1. Open **Finance** › **Exchange Rates**.
2. Add a rate as **1 [base] = x [currency]** and the date and time it starts. You can enter future rates in advance.
3. A rate is never edited. To fix a mistake, **Retire** the wrong rate with a reason and add the correct one. Sales already made keep the rate they used.
4. Use **Check a conversion** to see what an amount converts to at any time.

The list of currencies, each company's base currency and which currencies a company may use are set by Pocket Solutions (Super Admin), under **Platform** › **Currencies**. Desktop tills receive currencies and rates when they sync.

07 Platform (Super Admin) SUPER ADMIN

Super Admin accounts belong to Pocket Solutions, the provider. They work across all client companies and cannot sell or refund on any till.

- **Companies**: create a client company and its first Admin, or open a company to support it.
- **Super Admins**: manage provider staff accounts.
- **Units of Measure**: the shared list of units (kg, g, litres, metres…).
- **Desktop Releases**: upload a new version of the Windows till. Tills update themselves.
- **Platform Activity**: a log of provider actions.

08 The Windows desktop till EVERYONE

Pockets POS for Windows is a full till that runs on the shop PC. It keeps its own copy of products, users and customers, so it **keeps selling when the internet is down**, and it sends its sales to the web system as soon as it is back online.

Installing

1. Run **PocketsPOS-Setup.exe** on the till PC (Windows 10 or 11, 64-bit).
2. Start **Pockets POS**. The first screen is **Set up this PC**.
3. In the web system, an Admin opens **Desktop Tills**, adds a till for the branch and presses **Pairing code**.
4. On the PC, enter the **server address** and the **pairing code**, and connect. The till downloads the company once: users, products and prices, customers and stock.

Daily use

- **Sign in** with the same username and password as the web system. Signing in works offline.
- **Open the till** with the opening float, then sell exactly as on the Web POS: tap tiles, +/−, tap the number to type a quantity, search or scan, choose a customer, take payment.
- The status line at the top shows the connection, sales waiting to sync, and the ZIMRA fiscal day.
- Reports, refunds, cash in / out, reconciliation and closing the till are in the back office, by role, just like the web.

Till Settings (Admin)

- **Printing**: print through the Windows printer driver, send ESC/POS commands straight to a receipt printer, or print to a network printer by IP address. Choose 58 mm or 80 mm paper, copies and automatic paper cut. **Test print** checks it.
- **Cash drawer**: drawers plugged into the receipt printer open automatically for cash sales and refunds. Choose pin 2 or pin 5. Every opening is logged.
- **Appearance**: pick the primary and secondary colours of the till screens.
- **Updates**: the till checks for new versions on the web server, or in a shared folder or USB stick, and installs them with one click. The previous version is kept in case you need to roll back.
- **Shop network**: several tills in one shop can share sales and stock over the local network. One PC is the main till; the others join it with a code. Each till still works

on its own if the network drops.

Your data on the till

- Everything is saved on the PC's hard drive the moment a sale completes. Switching the PC off, or a power cut, does not lose completed sales.
- A **backup** is made automatically each time a till is closed and once a day. The last 30 are kept. Set the backup folder to a USB drive or network folder to protect against a failed or stolen PC.
- An Admin can **restore** a backup from **Backup & Recovery**; the app restarts to complete it.

A small UPS (battery backup) on the till PC is recommended. It is not needed to protect data, but it stops a power cut from interrupting a sale or the close of a ZIMRA fiscal day.

09 Questions and fixes EVERYONE

ZIMRA could not be reached. Can we still sell?

Yes. Receipts are signed and printed straight away and sent to ZIMRA automatically when it answers. Close the fiscal day once ZIMRA is reachable again.

Sales have stopped: "The ZIMRA fiscal day has reached its time limit."

A Supervisor, Manager or Admin must close the fiscal day on **ZIMRA Fiscal Day**. The next sale opens a new day. Close the day every evening to avoid this.

A product does not show on the till.

Check in **Items** that it is Active, has a price and belongs to a button group. On a desktop till, wait for the next sync or download the company again.

The cash count does not match.

Check Cash In / Out for missing entries and card or EcoCash payments recorded as cash. Card, EcoCash and account payments are not counted as till cash.

I forgot my password.

Ask your Admin to set a new one in **Users**. Change it yourself afterwards from **Password**.

The desktop till was offline all day.

Nothing to do. The sales are kept on the PC and sent automatically when the internet returns. Admins can see them arrive on **Desktop Tills**.

Pockets POS · Pocket Solutions · October 2026. Screens shown are from a working system; customer and staff details are blurred.