Standard installation procedure

preinst install
— FAILED → postrm abort-install
— FAILED

preinst install — OK → *Files are unpacked* → postinst configure
postrm abort-install — OK →
postinst configure — FAILED →
postinst configure — OK → **"Installed"** → Successful exit

"Failed-Config" **"Not Installed"** **"Half Installed"** ***"Reinst required"***

Exit with error message

Upgrade from version 1.2-3 to 1.2-4

1.2-3->prerm upgrade 1.2-4 — FAILED → 1.2-4->prerm failed-upgrade 1.2-3 — FAILED → 1.2-3->postinst abort-upgrade 1.2-4 — FAILED

1.2-3->prerm upgrade 1.2-4 — OK → 1.2-4->preinst upgrade 1.2-3
1.2-4->prerm failed-upgrade 1.2-3 — OK →
1.2-4->preinst upgrade 1.2-3 — FAILED → 1.2-4->postrm abort-upgrade 1.2-3 — FAILED
1.2-4->preinst upgrade 1.2-3 — OK → *Files are unpacked*

1.2-3->postinst abort-upgrade 1.2-4 — OK →
1.2-4->postrm abort-upgrade 1.2-3 — OK → 1.2-3->postinst abort-upgrade 1.2-4 — FAILED

"Half Installed"
(1.2-3)
"Reinst required"

"Unpacked"
(1.2-3)

"Installed"
(1.2-3)

"Installed"
(1.2-3)

"Failed-Config"
(1.2-3)
"Reinst required"

Exit with error message

1.2-3->postrm upgrade 1.2-4 — FAILED → 1.2-4->postrm failed-upgrade 1.2-4 — FAILED → 1.2-3->preinst abort-upgrade 1.2-4 — FAILED

1.2-3->postrm upgrade 1.2-4 — OK → *Old files are deleted* → 1.2-4->postinst configure 1.2-3
1.2-4->postrm failed-upgrade 1.2-4 — OK →
1.2-3->preinst abort-upgrade 1.2-4 — OK → 1.2-4->postrm abort-upgrade 1.2-3 — FAILED
1.2-4->postrm abort-upgrade 1.2-3 — OK → 1.2-3->postinst abort-upgrade 1.2-4 — FAILED

1.2-4->postinst configure 1.2-3 — OK → **"Installed"** **(1.2-4)** → Successful exit
1.2-4->postinst configure 1.2-3 — FAILED →

1.2-3->postinst abort-upgrade 1.2-4 — OK →

"Failed-Config"
(1.2-4)

"Installed"
(1.2-3)

"Unpacked"
(1.2-3)

"Half Installed"
(1.2-3)
"Reinst required"

Exit with error message