

This manual is licensed under the Creative Commons
Attribution-NonCommercial-ShareAlike 3.0 Unported License. To view a copy of this license, visit

http://creativecommons.org/licenses/by-nc-sa/3.0/
or send a letter to:
Creative Commons
171 Second Street, Suite 300
San Francisco
California, 94105, USA.

⊙2011 Peter W. Brewer Malcolm and Carolyn Wiener Laboratory for Aegean and Near Eastern Dendrochronology B48 Goldwin Smith Hall Cornell University, Ithaca, New York 14853. USA.

☎ +1 607 255 8650 ⋈ p.brewer@cornell.edu

CORINA MANUAL

For users and developers

By Peter W. Brewer, Ken Harris, and Robert Pohl

Contents

		I User Guide
L	Instal	lation
	1.1	Desktop application
	1.2	Server installation
2	The 0	Corina server
	2.1	Extending the Virtual Appliance
	2.2	Security
	2.3	Directly accessing the database
3	Meas	uring samples
	3.1	Configuring measuring platforms
	3.2	Differences in measuring hardware
	3.3	Measuring a sample
ļ	Meta	data
5	Марр	ing
	5.1	Navigation
	5.2	Interacting with data
	5.3	Background map layers
	5.4	Data map layers
	5.5	Exporting maps
•	Graph	ning
,	Impo	ting and exporting
3	Curat	ion
	8.1	Barcodes
)	Index	ing
	9.1	Types of index
	9.2	Indexing data
LO	Cross	dating and chronology building

iv CONTENTS

	II Developers guide	37
12	Systems architecture 12.1 Authentication design	39 39
	III Appendices	41
Α	Belfast AppleA.1 DescriptionA.2 Example file	43 43 44
В	Belfast Archive B.1 Description	45 45 46
С	Besançon C.1 Description	47 47 48 48
D	CATRAS D.1 Background D.2 Reading byte code D.3 Metadata D.4 Data D.5 Unknown bytes	49 49 49 51 51
E	Comma Separated Values E.1 Description	53 53 54
F	Corina Legacy F.1 Description	55 55 57
G	DendroDBG.1 DescriptionG.2 Example file	59 59 60
Н	HeidelbergH.1 DescriptionH.2 Example file - raw seriesH.3 Example file - chronology	61 64 64
I	Microsoft Excel 97/2000/XP I.1 Description I.2 Example file	65 65 66
J	Microsoft Excel 2007 J.1 Description	67
K	Nottingham K 1 Description	69

CONTENTS v

	K.2	Example file		 	 	 	 	 	 70
L		Spreadsheet							71
	L.1	Description .		 	 	 	 	 	 71
М	Oxfor	d							73
		Description .							73
		Limitations .							74
	M.3	Example file		 	 	 	 	 	 75
N	PAST								77
		Dating							79
	N.2	Example file		 	 	 	 	 	 80
0	Sheffi	eld							81
		${\sf Description}\ .$							81
		Dating							83
	0.3	Example file		 	 	 	 	 	 83
Р	Topha	am							85
	P.1	${\sf Description}\ .$		 	 	 	 	 	 85
	P.2	Example file		 	 	 	 	 	 85
Q	TRiD	aS							87
	Q.1	Description .		 	 	 	 	 	 87
	Q.2	Example file		 	 	 	 	 	 88
R	TRIM	IS							91
	R.1	Example file		 	 	 	 	 	 91
S	Tucso	an .							93
3	S.1	_							93
	S.2	RWL files							93
	S.3	CRN files							94
	S.4	Workarounds	and quirks .	 	 	 	 	 	 94
	S.5	Example file -	raw series .	 	 	 	 	 	 95
	S.6	Example file -	- chronology	 	 	 	 	 	 95
Т	Tucso	n Compact							97
	T.1	Description .		 	 	 	 	 	 97
	T.2	Example file		 	 	 	 	 	 98
U	VForr	nat							99
		Description .		 	 	 	 	 	 99
	U.2	Example file		 	 	 	 	 	 100
V	WinD	ENDRO							103
•		Description .		 	 	 	 		 103
 .		•		 	 	 	 	 • •	
W	Licen:		ماندانداند						107
	vv.1	Terms and Co	onaitions	 	 	 	 	 	 107
Re	ferenc	es							113
Inc	lex								115

Preface

Corina is the tree ring measuring and analysis program developed at the Cornell Tree-Ring Laboratory. It is focused primarily on the measurement of tree ring widths and the organization and curation of the data, metadata and physical samples. It is cross-platform (running on all Java 6 enabled operating systems including Windows, MacOSX and Linux) and open-source. It includes support for Velmex, Lintab and Hensen measuring platforms.

Corina has been developed since 2000 as a desktop Java application. Earlier iterations (version 0.x and 1.x) were built around a standard file-based data management system. In 2007, work began on a major rewrite of the software whereby this file-based data management was replaced with a true relational database and server/client webservice infrastructure. This series of releases (versions 2.x) are what are described in this manual

This manual is divided into two main sections, the first for users, the second for developers. Corina is open source software (see the details of the license on page 107) so you are welcome to inspect and edit the code. The second part of this manual should help you do that.

Over the years Corina has been developed by a number of people: Peter Brewer, Chris Dunham, Aaron Hamid, Ken Harris, Drew Kalina, Lucas Madar, Daniel Murphy, Robert 'Mecki' Pohl and Kit Sturgeon. We hope that you find Corina useful and look forward to hearing your feedback.

Part I User Guide

Installation

Corina is made up of two packages; the Corina desktop application and the Corina database server. Corina was designed primarily for laboratories with multiple users, each running the Corina desktop application on their own computer connecting to a single central server containing the lab's data. In this situation the Corina server would be run on a separate computer to those running the desktop client, but this need not necessarily be the case. It is perfectly possible to run both the server and the client on the same computer. This is likely to be the situation if you simply want to try out Corina, if you don't have a separate server, or if you do not work in a multi-user laboratory.

1.1 Desktop application

Installation packages for the Corina desktop application are available for Windows, MacOSX and Ubuntu Linux. Corina can also be run on other operating systems as long as they support Java 6.

To install Corina, download the installation file for your operating system from http://dendro.cornell.edu/corina/download.php. The website should provide you with a link to the installer for your current operating system:

- Windows Run the setup.exe and follow the instructions. If you do not have Java installed the installer will direct you to the Java website where you can get the latest version. Once installed, Corina can be launched via the Start menu.
- Mac OS X As mentioned above, Corina requires Java 6. Although MacOSX ships with Java installed, unfortunately Apple have been very slow to provide Java 6. Although it was released in 2006, it was not until August 2009 that Apple made Java 6 available as part of v10.6 (Snow Leopard). Corina can therefore only be run on Snow Leopard or later. To do so, download the dmg disk image file and mount it by double clicking on it. Drag the Corina.app into your applications folder and copy the manual and license files to somewhere convenient in your documents folder. For the more adventurous there is the possibility that you could run Corina using SoyLatte instead of the standard Java installation that comes with the operating system. This could be a possible method for running Corina even on earlier versions of MacOSX but is unsupported and largely untested.
- **Ubuntu Linux** A deb file is available which was designed for use on Ubuntu distributions but should work on any Debian based system. Install using your favorite package management system e.g.

```
∠sudo dpkg --install corina_2.xx-1_all.deb
```

On Ubuntu and similar distributions, the package should add a Corina shortcut to your applications menu. Alternatively you can start Corina from the command line by typing corina.

Other operating systems – Make sure you have Java 6 installed, then download the Corina jar file to your hard disk. You can run Corina from the command line by typing:

∠java -jar corina.jar

1.1.1 Mapping support

Corina includes 3D mapping for visualization of sampling locations. Although this is not necessary for most tasks, to make use of the mapping functions you will require a OpenGL 3D capable graphics card. To check whether your computer already supports 3D mapping, open Corina, go to Admin, then Site map. Corina will warn you if your graphics card is not supported.

All MacOSX computers should automatically support OpenGL. Most Windows and Linux computers made since 2006 should also support OpenGL, however, this does require proper drivers to be installed. In some cases Windows computers may include a compatible graphics card, but may only have the default Windows video drivers installed. If you are having trouble with the mapping in Corina make sure you have installed the most recent drivers for your graphics card. Linux users may be required to install proprietary graphics drivers.

The mapping component of Corina makes use of NASA's open source World Wind Java. NASA's website http://worldwind.arc.nasa.gov/ contains further information and instructions that you may find helpful if you are having problems getting the mapping to work.

1.2 Server installation

For the Corina desktop application to be useful you will also require access to a Corina server. If you are running Corina in a lab where the Corina server has already been set up by your systems administrator, you can skip this section.

The Corina server is made up of a number of components, which unlike the desktop client, can not be easily combined together into cross-platform packages. Although all the constituent components are open-source and available for all major platforms, building and maintaining separate packages for each platform is too large a task for a small development team. To conserve resources, we therefore made the decision to utilize Virtual Machine technology to ensure that the Corina server could still be run on all major operating systems. This means that we can package the Corina server for a single operating system (Ubuntu Linux) and then distribute it as a Virtual Appliance that can be run as a program on your normal operating system.

The Corina server is therefore available via two main methods. The first is as a VirtualBox Virtual Appliance which can be run on any major operating system, the second is as an Ubuntu package for running natively on a Linux server. The source code for the server is also available so it is perfectly possible for more experienced users to set up the Corina server to run natively on other platforms. But to do this you will require a good knowledge of Apache 2, PHP and PostgreSQL.

1.2.1 Virtual Appliance - all operating systems

To run the Corina server Virtual Appliance, you will first need to download and install VirtualBox from http://www.virtualbox.org. Installation packages are available for Windows, MacOSX, OpenSolaris and many Linux distributions.

Once you have VirtualBox installed, you will then need to download the Corina server from the Cornell website http://dendro.cornell.edu/corina. This package contains a bare-bones Ubuntu Linux server with everything required to run the Corina server installed and ready to use. As VirtualBox, the entire Ubuntu operating system and Corina server components are all open source there are no license fees to pay.

Open VirtualBox and go to File, Import Appliance, then follow the wizard selecting the Corina server appliance file when prompted. Once installed you can run your server by highlighting it in the list and pressing start. The server will boot up in a window alongside your normal operating system and eventually reach a login prompt. To save on download size and disk space only the essential packages to make the server run have been installed. This means there is no graphical interface just a command line. Hopefully this should not be a problem as once set up, the only interaction needed with the Virtual Appliance will be through the normal

Corina desktop application. If you would prefer to use a graphical interface to the server this can be easily installed. See chapter 2 for further details.latex define environment

Before you can use your server you will need to know the IP address that the server has been assigned by your network. To do this login at the prompt with the default admin credentials: user – corina; password – w3l0v3tr33s. Once logged in, type corina —test and a basic configuration test will be performed. If all is well, all tests will be passed and it will tell you the URL of your new server. You will need to set your Corina client to point at this webservice to use your server.

1.2.2 Ubuntu native installation

If you are fortunate enough to be running Ubuntu then the native Ubuntu deb package is the best and easiest method for installing the Corina server, otherwise see section 1.2.1 to install the server as a Virtual Appliance.

To install the Corina server in Ubuntu simply download the deb package from the Cornell server http://dendro.cornell.edu/corina and install with your favourite package manager. For instance, to install from the command line simply type:

```
∠sudo dpkg --install corina-server.deb
```

The package will automatically run a configuration script to assist with creating a database user, building the Corina PostgreSQL database, setting database permissions and setting up the Apache webservice. The configuration ends with a test routine to check all services are set up correctly and if so, will provide you with the URL of the newly configured Corina webservice.

1.2.3 Advanced install on other operating systems

As mentioned previously, the limited resources available for Corina development means that we have been unable to produce native installers for platforms other that Ubuntu. If you are an experience systems administrator though, it should not be too difficult to set up the Corina server manually.

The Corina server is essentially a PostgreSQL database accessed via a PHP webservice running on Apache 2. The following dependencies are therefore required: postgresql-8.4; postgis; postgresql-contrib-8.4; postgresql-8.4-pljava; sun-java6-jre; apache2; php5; php5-pgsql; php5-curl; php5-mhash.

The basic procedure for installation is as follows:

- Install all dependencies
- Create PostgreSQL database from Corina template SQL file
- Set up a database user and provide access to the server in the pg_hba.conf file
- Give this user read and write permissions to the database
- Copy the webservice code into a web accessible folder
- Set up Apache to see this folder by creating an entry in the sites-enabled folder
- Restart PostgreSQL and Apache and check you can access the webservice from a web browser

The Corina server

For basic day-to-day running of the Corina server, you simply need to make sure that the server is running. All other interaction and managment (creating users, granting permissions, accessing data) is done through the Corina desktop application. This section, however, outlines a number of aspects of the server that advanced users may find useful.

2.1 Extending the Virtual Appliance

For those of you that are unfamiliar with Linux, the basic command line prompt is not likely to be very comfortable. If you are interesting in looking at the server in more detail you may therefore prefer to install a full graphical interface. Unlike Windows, there are a number of different graphical interfaces (or desktops) to choose from in Linux, the most popular being Gnome and KDE. To install one of these you need to type one commands listed below. The first line installs Gnome and the second KDE. Windows users that are new to Linux may find KDE more familiar than Gnome.

2.2 Security

The basic installation of the Corina server includes the standard configuration for Apache, PHP and PostgreSQL. Although these products are considered secure by default, there are a number of measures that can be taken to make them more so. If your server is only accessible within your local intranet (e.g. behind a robust firewall) then you may not feel it necessary to modify the standard setup. Precautions may be deemed more important if you server is accessible from the internet. In this case it would be wise to contact your local network administrator for further information.

2.2.1 Usernames and passwords

There are a number of default usernames and passwords setup on your server. If your server is accessible for the internet we strongly advise you to change these defaults and anyone with knowledge of the Corina server could access and compromise your machine.

System user - these are the credentials you use to log in to the command prompt in your Corina Virtual Appliance. By default the user is 'corina' and the password is 'w3l0v3tr33s'. To change this log in to the command prompt and type passwd and follow the instructions.

Database user - these are the credentials used by the webservice to read and write to the database.

Corina admin user - these are the admin credentials that you use to log in with in your Corina desktop application. Be default the user is '???' and the password is '???'. To change these open the Corina desktop application, then go to Admin then Change password.

2.2.2 Authentication and encryption

Corina uses a relatively sophisticated method to ensure that unauthorised users cannot access the Corina database through the webservice. It is loosely based around http digest authentication and uses a challenge and response scheme. This makes use of cryptographic hashes (a relatively short digital fingerprint of some data but which cannot be decompiled to retrieve the original data) and nonces (a pseudo-random string used just once). All hashes used in the Corina webservice use the MD5 algorithm. This decision will be periodically reviewed to ensure that MD5 is the most appropriate and secure algorithm to use. Whilst an MD5 hash of a short phrase can be compromised, the length and randomness of the original data means with current cracking techniques this is essentially impossible. For a complete description of Corina's authentication procedure see section 12.1.

The default Corina server setup, however, uses standard HTTP protocol to communicate between the server and the desktop application. This is the same protocol used for the majority of web pages on the internet and a determined hacker could eavesdrop on this communication. Depending on how important and private you perceive your data you may choose to use Secure Socket Layer (SSL) to encrypt this communication. This is the same technology used by websites such as online banking. To make full use of this upgrade in security you will however also require a SSL certificate from an official licensing authority. These certificates typically cost several hundred dollars per year.

2.3 Directly accessing the database

Although the Corina database is designed to only be accessed by the Corina desktop application via the Corina server's webservice, you may decide that you'd like to directly access the database yourself. For instance, you may like to write complicated SQL queries to probe your database in ways not currently supported by the Corina desktop client.

Any changes made to the database may have drastic consequences. We strongly recommend that you never write changes directly to the database as this can cause loss of data and corrupt future upgrades to Corina.

2.3.1 PGAdmin3

One of the easiest ways to access the PostgreSQL database is through the application PGAdmin3. This is a cross-platform open source application for communicating with PostgreSQL databases. You can install PGAdmin3 on your desktop computer and access the remotely running database using your database user credentials. By default, PostgreSQL runs on port 5432.

2.3.2 ODBC

It is also possible to connect to your Corina database via an ODBC connection. This allows limited access to the database from a variety of database applications including programs like Microsoft Access for which further details are given here. To use ODBC you will need to install the PostgreSQL ODBC driver (http://www.postgresql.org/ftp/odbc/) on your desktop computer.

Once you've installed the driver you can then open a blank database in Access and go to Files, Get external data then Link tables. In the file dialog box change the file type to ODBC Databases(). Next, select the PostgreSQL Unicode driver, then fill out the server details. You should then be able to open the tables and views from the Corina server database directly from within Access as if they were local tables. Be warned

though that Access and ODBC have many limitations compared to PostgreSQL, especially with regards data types. For this reason we *strongly* recommend using this for read only purposes. Using the ODBC connection to write changes to your PostgreSQL database is quite likely to cause serious issues.

2.3.3 **PSQL**

The final, and most advanced method is to use the psql client on your server. This is a command line client which can be used to interrogate the database. If you're not already familiar with psql it is unlikely that this is a good method for you to use!

Measuring samples

Although it is possible to manually enter the ring widths of your samples into Corina, it is normal to automate this process using a measuring platform. Corina supports the most common measuring platforms including Velmex and Lintab.

3.1 Configuring measuring platforms

Measuring platforms typically use serial ports to communicate to computers. In recent years computer manufacturers have been phasing out serial ports so you may need to purchase a serial-USB converter. Modern MacOSX, Linux as well as Windows 7 should support most serial-USB adapters out of the box, otherwise you must install the relevant drivers before continuing. Recent Lintab USB platforms use internal seriesl-USB converters so are treated in exactly the same way by Corina.

To begin, shut down your computer, attach your platform, then reboot and launch Corina. Next, go to the preferences window and open the hardware tab and you should see an interface that looks like figure 3.1.

In the type pull down menu, select the type of measuring equipment you are using. Note that this refers to the equipment that the computer is attached to, and not necessarily the measuring platform itself. For instance, Velmex platforms are typically connected through a Metronics digital readout device. Included in this list is the EvelO device which is an open-source device designed for the Cornell Tree-Ring Laboratory. Circuit drawings for this device can be obtained from the Cornell lab to enable Hensen measuring platforms to be used with Corina (and other software).

Standard Lintab platforms use a proprietary communications protocol. Rinntech—the manufacturers of Lintab platforms—claim intellectual property rights over this protocol. During discussions between the Corina development team and Rinntech an agreement was reached whereby the Corina developers agreed not to release details of the protocol. In turn Rinntech has agreed to produce an adapter that can be attached to Lintab platforms so that they communicate with an open ASCII protocol. Users wishing to use Lintab platforms with Corina (or any software not developed by Rinntech) must therefore contact Rinntech and purchase an adapter.

Next you must choose the port that your platform is connected to from the pull down menu. In Windows this will be a COM port, in Linux and Mac this will be a /dev/xxx port. Depending on the type of platform you choose, you may also need to set various communication parameters. If these boxes are enabled, please check the documentation that came with your measuring platform to ensure these values are set correctly.

To check whether your platform is working, click the 'Start measuring test' button and attempt to measure a few rings. Once you are satisfied, click OK on the preferences window and you will be returned to the Corina home screen.




Figure 3.1: The hardware preferences dialog.

3.2 Differences in measuring hardware

Different measuring platforms have different capabilities. For instance, some include a physical switch for firing measurement events, others also include switches for resetting measurements to zero. Some platforms (e.g. Lintab) also continuously report the measurement values to the computer. So depending on the hardware you use, Corina will present the you with slightly different options.

Please note that the architecture of Corina is such that providing support for additional measuring platforms is a relatively simple task. If you have equipment that is not currently supported, please contact the developers to see if it can be included.

3.3 Measuring a sample

Once your measuring platform has been configured, measuring your first sample is simple. To start a new measurement go to File \rightarrow New or click the 'new' icon on the home screen. A dialog will appear where you can scan your sample's barcode, or press the button to enter metadata for your sample later. Barcodes minimize data entry errors and also speed up the process of measuring your samples. See section $\ref{eq:section}$ for more information. Once you have scanned your barcode or pressed the button, you will then be presented with an empty Corina data screen (figure 3.2).

The next step is to fill out the metadata tab. If you have used a barcode, nearly all of this metadata will be filled in for you, otherwise you will need to fill this out yourself. Details about metadata can be found in chapter 4, page 17.

To begin measuring your sample you can now go to Edit →Start measuring or you can press F5. While measuring you should be provided with audible feedback for each ring measured with a more pronounced sound made every 10th ring. If there is a problem communicating with your measuring hardware, check your settings in the




Figure 3.2: An empty data window ready to receive measurements. Note the status bar at the bottom includes buttons for changing the display units and cumulative statistics.

preferences dialog. If you still have problems contact the Corina developers by going to Help →Report bug on last transaction, making sure you include your email address and any further information.

While you measure your sample you can flag features in a ring by right clicking on any cell in the table and selecting one or more of the standard notes (see figure 3.3).

Corina supports all standard TRiDaS remarks including: fire damage; frost damage; crack; false ring(s); compression wood; tension wood; traumatic ducts; single pinned; double pinned; triple pinned and many others. Rings that include remarks are indicated by the relevant icon in the data screen. Depending on your method of work, this can be useful for keeping track of sample pin holes. For instance, if a missing or false ring is discovered after a sample has been pinholed, the offset in pinholes can be easily seen without resurfacing the sample. In the future Corina will also include support for user defined ring remarks.

The data screen also contains a status bar at the bottom. By click on the units section, you can switch between micron and 1/100th mm units. Corina understands the units being supplied by the measuring platform, therefore changes here are purely for dis-




Figure 3.3: Right click context menu showing some of the options for adding remarks to rings.

play purposes only. If you have a platform that measures in microns, but prefer to see the values in 1/100th mm then you can use this feature. At the bottom ring of the status bar you can choose one of a variety of summary information about your series.

Once you have finished measuring your sample, you should then go to File \rightarrow Save to save your series to the database.

Metadata

Mapping

Corina includes an integrated open source 3D mapping system (based on NASA's award winning World Wind Java SDK) similar to the program Google Earth which you're no doubt familiar with. As mentioned in the installation chapter, this mapping system requires an OpenGL 3D capable graphics card.

Before you can use the mapping in Corina, it must have something to map! See the chapter on Metadata (page 17) for information about adding coordinates to your system.

There are two ways to map data from your database. First of all, you can see a map of all the sites (i.e. TRiDaS objects) by going to Administration, then Site map. This will give you a screen like this:




Figure 5.1: Screenshot showing an example of a site map.

You can also see a map of your current series if you have latitude/longitude metadata by clicking on the map tab on the main data screen.

20 MAPPING

5.1 Navigation

You can navigate around your maps using both your mouse and keyboard.

5.1.1 Mouse with scroll wheel

Pan Left mouse button click and drag - all directions

Zoom Use the scroll wheel on the mouse or Left and Right mouse (both buttons) click and drag up and down

Tilt Right mouse button click and drag - up and down or use 'Page Up' and 'Page Down' on the keyboard.

Rotate Right mouse button click and drag – left and right Note: Crossing the top and bottom half of the screen while rotating will change direction.

Stop Spacebar

Reset Heading N

Reset all R

5.1.2 Single button mouse

Pan Left mouse button click and drag - all directions. L left mouse button click once to center view.

Zoom Hold 'Ctrl' on the keyboard and Left mouse button click and drag - up and down

Tilt Hold 'Shift' on the keyboard and Left mouse button click and drag - up and down or use "Page Up" and "Page Down" on the keyboard.

Rotate Hold 'Shift' on the keyboard and Left mouse button click and drag - left and right

Stop Spacebar

Reset Heading N

Reset all R

These controls enable you to explore your location information in 3D such as the example of Mount Vesuvius in figure 5.2.

Another method of navigating around the map is by using the built in gazetteer. You can enter and place name or coordinate information into the box at the bottom of the screen and you will fly to the requested location.

5.2 Interacting with data

Each marker on the map represents either a TRiDaS object or element in your Corina database. By clicking on these pins you can get more information from the database (see figure 5.3).

The example above shows the ring marker is of a site in Napoli called Poggiomarino (code name POG). You can see the option for searching for all series in the database associated with this site, and also the option for viewing all the metadata.

5.3 Background map layers

Corina comes ready configured with basic map layers, including high resolution satellite imagery and basic political features. You can turn background layers on and off by going to View ¿ Layers.

MAPPING 21



Figure 5.2: Example of 3D mapping in Corina.





Figure 5.3: Screenshot of a map with information pin expanded

22 MAPPING

Map layers are downloaded on-the-fly so there is likely to be a delay when you initially visit to a new region. However, up to 2Gb of map data can be cache locally to your hard disk, so on future visits, maps should load quickly.

The mapping system in Corina includes support for remote map servers that use the OGC Web Mapping Service (WMS) standard. If you go to View ¿ Layers ¿ Add remote layers you will get a dialog with a tab for each WMS server configured for your system. By default this includes the NASA Earth Observation and Jet Propulsion Lab servers, but your Corina administrator can add others. By ticking layers in this list you can add data layers to your map. Your system administrator may host a map server specifically for your lab, for instance, containing high resolution plans of an archaeological site that you are working on. Figure 5.4 shows an example overlay of sea surfaces temperatures loaded dynamically from the NASA EO server.

Figure 5.4: Map screenshot with a NASA sea surface temperature overlay dynamically loaded from the NASA WMS server.



5.4 Data map layers

Data map layers are controlled with the layer list in the bottom left of the screen. When viewing series, you will have the option of adding layers containing points for all the other series at the current site, and showing all the sites in the database.

5.5 Exporting maps

You can export maps by going to File ¿ Export map as image. For best results, maximize your map window first. You may also like to turn off various map widgets by going to the View menu. The exported image will include everything you can see on your map screen.

Graphing

Importing and exporting

Curation

8.1 Barcodes

Indexing

Trees tend to put on big rings when they're young, and smaller rings when they get older. Some trees put on very large rings, while others put on very small rings. These variations in growth can make it difficult to crossdate samples. Some dendrochronologists therefore prefer to index or normalize their ring width data before combining into chronologies.

Indexing is a manipulation you can perform on your data to make it easier to crossdate.

The procedure for indexing is as follows:

- 1. You open a series (raw data)
- 2. You ask Corina to index it
- 3. Corina shows you some possible curves
- 4. You pick a curve (based on its graph, statistical scores, and your expectation of how the tree is growing)
- 5. Corina converts each year's ring width to a ratio of actual growth to expected growth for that year
- 6. You save the series (indexed data)

Indexing changes the units of a dataset. A raw sample has units of hundredths of a millimeter (0.01 mm) or microns. An indexed sample has units of parts per thousand (0.1%, or %).

This doesn't cause a problem with crossdating. The t-score normalizes all samples as part of its test, and the trend only cares if the values are increasing or decreasing. For more information on crossdating and chronology building, see chapter 10. It does, however, cause a problem with 'summing' since summing needs to take the average (what's the average of 1mm and 75%?). Therefore, the samples in a sum must be either all raw, or all indexed.

9.1 Types of index

There are a total of six different indexing methods available in Corina:

9.1.1 Exponential Index

This is the most commonly used index as it matches the way trees typically grow. Quickly when young and then gradually slower. An exponential index is therefore by far the most common index you'll use as 9 times out of 10 this will be the best choice.

This index tries to fit an equation of the following form to your data, searching for the best values of a, b and p.

$$\bullet y = a + be - px$$

30 INDEXING

This is sometimes called a negative exponential index, because the exponent is negative. Corina doesn't require that the exponent is negative, but if it's not, using this index probably isn't such a good idea; it means the tree is generally getting bigger, not smaller.

The least-squares algorithm used comes from Cormen et al. (2001); the matrix solving function comes from Van Loan (1999).

Sometimes the exponential index does a lousy job. If a tree is living in a crowded area and the trees around it get cut down, suddenly it has much better growing conditions, so it might grow faster as it gets older, instead of slower. If you tried to use an exponential curve on a tree like this, it would exaggerate this growth, and useful data would get flattened out.

The result is you're looking at the growing conditions of this one tree, so it's not going to crossdate as well.

Alternatively, imagine you are working on a tree with a fire scar that has a few very large rings. An exponential index wouldn't take much notice of this, because most of the sample is still shaped like an exponential curve, but when you applied it they would be grossly out of proportion. For these types of samples, there are other indexing algorithms available.

9.1.2 Polynomial Index

When you ask Corina to perform a Polynomical Index it tries to fit a polynomial curve to your data using the following equation:

•
$$y = a_n x^n + a_{n-1} x^{n-1} + \ldots + a_2 x^2 + a_{1x} + a_0$$

You decide what degree polynomial, n, to use and Corina automatically finds the best values of $a_0, a_1 \dots a_n$, to fit your data.

9.1.3 Horizontal Line Index

This only changes the magnitude not shape of the curve and is used when you would link to combine raw and indexed data together. It is a special case of polynomial where the horizontal line is equal to the average value.

•
$$y = x_{avg}$$

This index is not used for crossdataing because dividing each value by the same value doesn't change the shape of the curve, only its magnitude. A horizontal line index is, however, useful because every element in a sum must use the same units, either raw or indexed. Therefore if you want to include a raw sample with an indexed sample then a horizontal line index can be used to convert the raw sample without otherwise altering the shape of the curve.

9.1.4 Floating Index

This is a running average of the 11 surrounding years. The adaptive index is generally used as a "last resort" when both exponential and a high-degree polynomial have failed. It is simply the average of the eleven surrounding years:

•
$$ind_i = 1/11(data - i - 5 + data_{i-4} + \dots + data_{i+4} + data_{i+5})$$

This index was originally called floating average, probably in reference to the fact that the index curve "floats" around, not following any explicit y=f(x)-type formula. But people tended to call it floating, and then floating-point, which means something very different. You might still hear people calling this index by these other names.

INDEXING 31

9.1.5 High-Pass Filter Index

The high-pass index is a more general case of the adaptive index. Instead of simply taking the average of 11 values, it takes a weighted average. It's an example of a "high-pass" filter because high-frequency signals can pass through, but low-frequency signals are filtered out.

The default is "1-2-4-2-1", meaning:

• $ind_i = 1/10(data_{i-2} + 2 \cdot data_{i-1} + 4 \cdot data_i + 2 \cdot data_{i+1} + data_{i+2})$

This comes from Cook and Peters (1981) who used it as a discrete filter before moving to a cubic spline. Note that almost half (4/10) of the computed value is simply its old value. The high-pass index is nearly the same as the input, so the χ^2 values are usually the lowest, therefore do not choose this index solely on a low χ^2 value.

9.1.6 Cubic Spline Index

Cubic splines are a very specific type of high-pass filter. A cubic spline curve is created by combining a collection of cubic (3rd degree polynomial) functions.

There are many methods for constructing cubic splines through a dataset. The algorithm used by Corina has a parameter, s, which controls how tightly the spline fits the data. A lower value fits the data more tightly, a higher value fits the data more loosely. Therefore, s=0 fits the data exactly while s=1 is a simple line. A good starting point for dendro data seems to be around s=1x1016.

Cubic splines were first used for dendro by Cook and Peters (1981) using an algorithm from Reinsch (1967).

You can change the s-value used for the subic spline in the preferences. You might use a cubic spline in the same cases you would use a high-pass filter e.g. when the sample doesn't generally follow an exponential or polynomial curve very well, perhaps due to a fire scar.

9.2 Indexing data

To index your data, first you need to open the series you would like to index. Next choose Tools →Index to display the indexing dialog (figure 9.1).




Figure 9.1: Indexing dialog showing the original data in blue, the exponential index of this data in green, and the normalized data in red.

From the indexing dialog you can then choose which type of index to apply to your data. The table on the right show the available options along with the χ^2 and p values to help you choose the correct index to use. The graph shows your original data, the index line and the result of applying the index to the data and changes dynamically as you pick between different indexing methods. Once you have decided which index you want to use, select it, and click OK ensuring that you have given your data series a new version number.

Chapter 10

Crossdating and chronology building

All algorithms work in pretty much the same way. There's a "fixed" sample, and there's a "moving" sample. Imagine you have printouts of their graphs on translucent paper. The fixed graph is taped to a table, and you can slide the moving sample left and right. This is actually how it was originally done, on graph paper, with one inch per decade. Start with the moving sample to the left of the fixed sample, overlapping it by 10 years. Look at how well the graphs match: this is the first score that's computed. Slide the moving sample to the right one year and so on until you reach the end.

You could do it all simply by moving graphs and eyeballing the crossdates like this but there are hundreds of sites and millennia of chronologies you'll want to crossdate your samples against, so that would take a while. Corina has a few algorithms to find likely crossdates almost instantaneously. They aren't perfect, though, and all crossdates should be inspected visually to ensure they are a good fit.

10.1 Algorithms

Corina includes a total of five different algorithms for crossdating:

10.1.1 T-Score

The t-score is the classic crossdate. Everybody quotes t-scores: if you want to brag about how good a cross is, you tell them your t-score. Unfortunately, every dendro program seems to have a slightly different implementation of tscore, so the numbers you get from Corina might not be exactly comparable to the numbers from other programs.

The version Corina uses is based on the algorithms given in ?, though with some apparent bugs corrected. In the following equations, x_0, x_1, x_2, \ldots are the data of the fixed sample in the overlap, y_0, y_1, y_2, \ldots are the data of the moving sample in the overlap, and N is the length of the overlap.

10.1.2 Trend

Trend is another popular crossdate statistic. It computes the percentage of years with the same trend (going-up- or going-down-ness). Scores greater than 60%-70% are good. Trend is also referred to as ufigkeitsko-Gleichläeffizient, Gleichläufigkeit and Eckstein's W.

The trend is the simplest crossdate. For each sample, it computes the trend of each 2-year interval (1001-1002, 1002-1003, and so on). The trend of a 2-year interval is simply whether the next ring is larger, smaller, or the same. The trend score is the percentage of intervals in the overlap which are the same. For example, a 75% trend (a very good score, by the way) means that for 75% of the intervals in the overlap, both samples went up in the same years and down in the same years.

If one sample stays the same, and the other increases or decreases, Corina considers that to be halfway between a same-trend and different-trend, and gives it half a point. Trend is a "non-parametric" algorithm, because it only takes into account if a given ring is bigger or smaller than the previous one, not by how much. To the trend, a drop of "100 1" looks exactly the same as a drop of "100 99". Two completely random samples will have a trend of 50%, on average. So you'd expect a trend must be greater than 50% to be significant.

According to ?, a trend is significant if:

- 1. $tr>50\%+\frac{50}{\sqrt{N}}$ For example a pair of samples with a 50-year overlap needs a $50+50\sqrt{50}=57.1\%$ trend to be significant, but at a 400-year overlap need only a $50+50\sqrt{400}=52.5\%$ trend. In practice, however, this doesn't tend to work terribly well. Using this scheme, there are typically about three times as many "significant" trend scores as t-scores, and users want this narrowed down a bit more. So take $\sigma=3$ and use:
- 2. $tr > 50\% + \frac{50\sigma}{\sqrt{N}}$ This gives about the same number of significant trend scores as t-scores.

Trends are also used in reconciliation. After they've been reconciled, both readings of a sample should have 100% trend.

10.1.3 Weiserjahre

An algorithm for crossdating summed samples (masters) against single samples; kind of like a trend-for-Weiserjahre-data.

10.1.4 R-Value

A score which statisticians might ask you for. You'll probably never use it on your own (though it's used by Corina when computing the t-score, so you already are, in a sense).

10.1.5 D-Score

Chapter 11

Help

Part II Developers guide

Chapter 12

Systems architecture

12.1 Authentication design

Part III Appendices

Appendix A

Belfast Apple

Format name Belfast Apple Other name(s) None known Type Text file

Extension(s) Various (typically txt and dat)

Read/write support Read and write

Reference implementation No original software is known to exist so TRiCYCLE is pro-

posed as the reference implementation

Data / metadata Data only with comment

Calendar type n/a
Absolute dating support No
Undated series support Yes
Relative dating support No
Multi series support No

Original designer John Pilcher

A.1 Description

Belfast Apple is a simple text file format (see also Belfast Archive) originating from the Queens University Belfast lab and originally designed for use on an Apple II computer. This format is not known to be actively used but a large amount of data (especially at Belfast) is archived in this format.

- Line 1 name of the site or object the data refers to.
- Line 2 identifier for the sample the data refers to.
- Line 3 number of data values in the file
- Lines 4+ line feed delimited data values as integers in 1/100th mm
- Final line contains a comment typically starting with 'COMMENT -'

A.2 Example file

```
EXAMPLE SITE
    A1805
    106
   188
    165
    184
    112
    103
    111
10
    239
    226
11
    132
12
    143
    146
14
15
    140
    100
17
    176
    139
    124
19
    115
20
   78
21
   156
    75
24
    110
    80
    130
   83
    157
29
    99
   115
31
    102
   110
    108
34
   87
35
   135
    107
37
    96
38
    70
39
   128
40
   119
41
   86
    101
43
    106
44
   129
45
46
    88
    101
    151
48
49
    106
    97
50
    110
51
    97
    91
53
    93
    100
55
    124
    99
    134
58
    125
   105
60
    96
    107
62
63
    142
   100
                  PB 15-NOV-99
   COMMENT -
```

Appendix B

Belfast Archive

Format name Belfast Archive
Other name(s) None known
Type Text file

Extension(s) Various (typically arx, txt and dat)

Read/write support Read only

Reference implementation No original software is known to exist so TRiCYCLE is pro-

posed as the reference implementation

Calendar type Gregorian
Absolute dating support Yes
Undated series support No
Relative dating support No
Multi series support Yes

Original designer Martin Munro

B.1 Description

Belfast Archive is a simple text file format based on the original Belfast Apple format at the Queens University Belfast lab. It shares the same features as Belfast Apple but with the addition of a number of metadata fields at the end of the file.

- Line 1 name of the site or object the data refers to.
- Line 2 identifier for the sample the data refers to.
- Line 3 number of data values in the file
- \bullet Lines 4+ line feed delimited data values as integers in $1/100 th\ mm$
- The lines "[[ARCHIVE]]" and "[[END OF TEXT]]" denote the start and finish of the metadata section

The metadata section contains the following lines:

- Line 1 start year as an integer.
- Line 2 unknown
- ullet Line 3 Double representing the resolution of data values e.g. .1=1/10ths mm, .01=1/100th mm, .001= microns etc
- Line 4 unknown
- Line 5 unknown
- Line 6 unknown
- Line 7 title of the data series
- Line 8 unknown

• Line 9 - unknown

B.2 Example file

```
EXAMPLE SITE
   1
2
   176
   342
   338
   334
   409
   362
   308
   264
   325
12
   318
13
   51
14
   48
15
   47
17
   60
   49
18
   48
19
   "[[ARCHIVE]]"
20
   1277
21
   9177
22
   .01
23
   1.035795
24
   0.212144
   BOB 25/03/95
EXAMPLE SITE #01
26
27
   Pith F Sap 32
28
   "[[ END OF TEXT ]]"
```

Appendix C

Besançon

Format name Besançon
Other name(s) SYLPHE
Type Text file
Extension(s) txt

Read/write support Read and write

Reference implementation

Calendar type Gregorian
Absolute dating support Yes
Undated series support Yes
Relative dating support No
Multi series support Yes

Original designer Georges Lambert

C.1 Description

The Besançon format is most commonly used in a number of French laboratories. The format allows for multiple series in the same file. Each series (or element block in Lambert's notation) is made up of a header line, optional metadata and a data block each of which are delimited by a line feed.

The header line begins with a dot character, then one or more spaces, then an element name (without spaces) followed by a space and any number of ignored characters.

The metadata fields are space or line feed delimited. Each field is recorded using a key of three letters. The format allows for the full spelling out of the field if preferred, but it is the first three letters that are read by software so LON is the same as LONGEUR. Some fields are 'unimodal' in that their presence is all that is required e.g. CAM means that cambium was observed. Other fields are 'bimodal' which means they require a value to be associated with them. In this case the field key is followed by a space and then an integer or string value e.g. POS 1950. The accepted metadata fields are as follows:

LON Number of data values

POS The temporary first ring date given relatively to a group

ORI The year for the first ring

TER The year for the last ring. Should be the same as ORI + LON

MOE Pith present

CAM Cambium present

48 BESANÇON

AUB Number of the first sapwood ring

All other information in the metadata block should be ignored. This feature is often used to allow the inclusion of multi-line comments.

The data block begins with the marker line VAL (like metadata keys, subsequent characters are ignored so sometimes the rest of this line is used for comments). Subsequent lines contain integer values delimited by a space or line feed. Missing rings are marked with a comma character and the end of the data is marked with a semicolon.

C.2 Additional information

- There is nothing in the specification to say what precision the data values should be in. Following conversations with users it appears that Besançon files are mostly 1/100th mm but this is not always the case. Some files include a Précision field, but this is not documented or standardised.
- There are a number of additional fields that are commonly used but which do not appear in the format specification. These are also supported by the DendroFileIOLib

ESP Species

ECO Bark present

C.3 Example file

```
. abc22/43
2
     Lon 129
     Esp quercus sp
                         Nat lambris
3
     Precision 1/100
     Moelle non presente
     Aub 0
    valeurs
            119
                  156
                         146
                               170
                                     187
                                            197
                                                  146
                                                        191
                                                              177
      149
8
9
      137
            108
                  160
                         108
                               120
                                     177
                                            136
                                                  174
                                                        190
                                                              109
      189
            176
                  170
                         162
                               114
                                     126
                                            133
                                                  152
                                                        146
                                                              127
10
      119
            131
                   146
                         133
                               147
                                      82
                                             57
                                                   77
                                                         77
                                                                82
       96
             49
                    97
                          76
                                88
                                      82
                                             72
                                                   83
                                                         81
                                                                90
12
       85
             87
                    78
                         104
                               111
                                     132
                                            141
                                                  105
                                                        104
                                                              120
13
                          89
      111
            121
                  115
                                             90
                                                              106
14
                                94
                                      88
                                                  115
                                                        111
      107
            120
                    80
                          92
                                98
                                      84
                                             97
                                                   82
                                                        100
                                                                86
15
                                      82
16
       99
             65
                    85
                         113
                                90
                                             57
                                                   57
                                                         99
                                                                94
       95
            105
                   120
                         110
                                93
                                      96
                                            131
                                                  133
                                                        123
                                                              122
17
      113
            119
                    95
                         127
                                88
                                     104
18
19
```

Appendix D

CATRAS

Format name **CATRAS** Other name(s) None known Type Binary Extension(s) cat Read/write support Read only Reference implementation **CATRAS** Data and some structured metadata Data / metadata Calendar type Gregorian

Absolute dating support
Undated series support
Relative dating support
No
Multi series support
No

Original designer Roland Aniol

D.1 Background

The CATRAS format (Aniol, 1983) is the only known binary dendro data format. As such it can't be read by a simple text editor, and can't be imported by spreadsheet or database programs. The format was designed by Roland Aniol for use in his program of the same name. The binary nature of the format means the files are typically much smaller than text files containing similar data. The closed nature of the format originally meant that users were tied to the application. The fact that users can't manually edit the file means that the validity of files is not a problem like it is with most other dendro formats.

CATRAS is a closed format with no documentation. The format was originally decoded in the early 1990's and permission was granted by Aniol for a converter to be included in Henri Grissino-Mayer's CONVERT5 application on the condition that the format remained closed source. Subsequently others have independently released application and code that can read ring-width data from CATRAS files to a greater or lesser extent.

D.2 Reading byte code

Reading byte code is more complicated than reading text files. Each byte is 8-bits and therefore can represent up to 256 values. Depending on the type of information each byte contains, the bytes are interpreted in one of four ways:

50 CATRAS

D.2.1 Strings

Some of the bytes in CATRAS files contain character information. In this case each byte represents a letter. In java an array of bytes can be directly decoded into a string.

D.2.2 Integers

As a byte can only represent 256 values, whenever an integer is required, CATRAS stores them as byte pairs. Each byte pair consists of a least significant byte (LSB) and a most significant byte (MSB). The order that they appear in files typically varies between platforms and is known as 'endianness'. As CATRAS solely runs of Microsoft (x86) processors we can safely assume that all CATRAS files will be using little-endian (i.e. LSB MSB). The counting in a byte pair therefore works as follows:

Value	LSB	MSB
0	0	0
1	1	0
255	255	0
256	0	1
257	1	1
258	2	1

A byte pair can therefore store $256 \times 256 = 65536$ values (more than enough for most number fields). Matters are complicated though by the need to store negative numbers. In CATRAS pairs with an MSB;=128 are positive, while pairs with an MSB ranging from 255 to 128 (counting backwards) represent negative values:

Value	LSB	MSB
-1	255	255
-2	254	255
-3	253	255
-4	252	255

D.2.3 Categories

Categories are typically recorded as single bytes as most categories have just a few possible values. They can therefore be conceptualised as being integers where 0=first option, 1=second option etc. The exception to this is for species because there are more than 256 species. In this case, a byte pair is used in exactly the same way as described for integers above. The only problem for species is that the codes are unique to each laboratory and refer to values enumerated in a separate '.wnm' file. Without this dictionary the species code is of little use.

D.2.4 Dates

Dates are stored as three single bytes, one for day, one for month, one for year. With only 256 values available for 'year', all dates are stored with 2 digit years e.g. 25/12/84. When reading CATRAS files all years $\frac{1}{2}$ 70 are therefore treated as 20th century, whereas years $\frac{1}{1}$ 70 are treated as 21st century. This is an arbitrary decision for use in this library as CATRAS does not care either way.

CATRAS 51

D.3 Metadata

The first 128 bytes contain the file header information and the remainder of the file contains the ring-width data and sample depth data. Our current understanding of the header bytes is as follows but I'm not convinced that these are all correct. Deciphering these requires painstaking work because we must try to ascertain how each byte is being used (e.g. as a byte pair, single byte or as a string):

- 1-32 Series name
- 33-40 Series code
- 41-44 File extension
- 45-46 Series length
- 47-48 Sapwood length
- 49-50 Start year
- 51-52 End year
- 53 1=pith 2=waldkante 3=pith to waldkante
- 54 1 = ew only last ring
- 55-56 Start year
- 59-60 species also needs a catras.wnm file
- 61-63 Creation date
- 64-66 Amended date
- 67 Sapwood
- 68 1=valid stats
- 69-75 dated?
- 84 0=raw 1=treecurve 2=chronology
- 85-86 User id
- 89-92 Average width
- 93-95 Standard deviation
- 96-100 Autocorrelation
- 101-104 Sensitivity

D.4 Data

The remaining bytes in the file contain the actual data values stored as integer byte pairs. It appears that older version of CATRAS included one or more padding values of -1. These values should be ignored. The end of the data values are indicated by a stop value of 999.

Following the ring-width data values there are 42 bytes of unknown meaning. These are then followed by byte pairs representing the counts/sample depth for each ring if the series is a chronology.

D.5 Unknown bytes

There are a number of bytes in both the header and data sections that are are unaccounted for and are therefore likely to contain data that we are ignoring. For this reason although we could attempt to create CATRAS files from what we know we can't be sure they would be valid:

- Header
 - 57-58
 - 69-82
 - 105-128
- Data
 - 0-42 following end of data marker

Appendix E

Format name

Comma Separated Values

Other name(s)

Type
Text file

Extension(s)

Read/write support

Reference implementation
Data / metadata
Calendar type

CSV

Text file

Various (typically txt or csv)

Read and write

n/a
Data only

Gregorian

Comma Separated Values

Absolute dating support
Undated series support
Relative dating support
Multi series support
Original designer

Greg
No
No
No
No

E.1 Description

Comma separated values format is a simple text format for representing tabular data. It is not specific to dendrochronology data and is supported by most spreadsheet and database applications. Data is delimited into columns using a comma character to indicate cell boundaries.

Support for CSV files in TRiCYCLE is limited to a particular layout of data. The expected layout is the same as for Excel and ODF spreadsheet files:

- Row 1 Header names for each column
- Column A Year values
- Column B+ One column for each series containing values in millimetres. Cells are left empty if no data is available for a series because it does not extend to a particular year. Data must be continuous for each series, so missing/unmeasured rings should be included as zero.

E.2 Example file

```
Year , MySample1 , MySample2
   500,0.33,
   501,0.26,0.26
   502,0.2,0.2
  503,0.14,0.14
  505,0.02,0.02
8 506,0.2,0.2
9 507,0.14,0.14
10
   508,0.08,0.08
  509,0.2,
  510,0.33,
12
  511,0.08,
  512,0.33,
14
  513,0.22,
```

Appendix F

Corina Legacy

Format name Corina Legacy

Other name(s) Corina
Type Text file

Extension(s) Various including raw, rec, ind, cln, sum)

Read/write support Read and write

Reference implementation Corina

Data / metadata Data and some structured metadata

Calendar type Gregorian
Absolute dating support Yes
Undated series support No
Relative dating support Yes
Multi series support No

Original designer Robert 'Mecki' Pohl

F.1 Description

The Corina Legacy format is the file format used by the Corina software prior to version 2, when it transferred to using TRiDaS. The format was originally designed for use with the MS-DOS version of Corina but was also used as the native file format in the later Java versions (up to and including v1.1).

A Corina file contains yearly data (ring-width and number of samples for that year), some fixed metadata, and optionally weiserjahre data and a listing of element samples (for summed samples).

The title comes first, on a line by itself, followed by a blank line. The title is repeated later, so this is only to make it easier for people or external programs to read the title.

The metadata section comes next. The syntax is ;TAG value. Tags are all uppercase. Their order is fixed. Some values are terminated by a newline, others by the next semicolon. Valid tags, and their internal names are:

- ID 8 character ID used when exporting to Tucson format
- NAME Name of the series
- DATING Either R (relative) or A (absolute)
- UNMEAS_PRE Number of unmeasured rings towards the pith
- UNMEAS_POST Number of unmeasured rings towards the bark
- FILENAME
- COMMENTS, COMMENTS2 etc Free text comments
- TYPE either C (core), H (charcoal) or S (section)
- SPECIES

- SAPWOOD Count of sapwood rings
- PITH either P (present), * (present but undateable), or N (absent)
- TERMINAL either B (bark), W (waney edge), v (near edge), vv (unknown)
- CONTINUOUS referring to the outer ring, either C (continuous), R (partially continuous) or N (not continuous)
- QUALITY either + (one unmeasured ring), ++ (more than one unmeasured ring)
- FORMAT either R (raw) or I (indexed)
- INDEX_TYPE type of index used
- RECONCILED Y or N indicating whether the series has been reconciled against another series

The *data section* comes next and this always starts with the line ;DATA and for reasons lost in time there are nine spaces afterwards.

Data lines come in pairs, the first line containing the year and data values, the second containing the sample depth/count for each value. For reasons unknown, the first and last data line pair have a slightly different syntax to the others.

- First data line begins with a space and an integer for the first year in the line. There then follows 9 spaces followed by the integer data value for the first ring. The remaining data values (often less than a full decades worth) on that line follow as integers left padded by spaces to take up 6 characters.
- The sample depth line that pairs with this follows next starting with 16 spaces, followed by the sample depth value enclosed in square brackets. The remaining sample depth values follow in square brackets left padding with spaces to take up 6 characters.
- Next comes the first normal data line. This begins with a space, followed by an integer year value. The data values follow as integers left padded by spaces to take up 6 characters. A data line has a decades worth of data values.
- Next comes the normal sample depth line. It begins with 7 spaces followed by each of the sample depth values enclosed in square brackets and left padded with spaces up to 6 characters.
- Data lines continue in pairs until the last line is reached. This is the same as a normal data line except
 it includes an extra data value 9990 as a stop marker. This data line may have less than a full decade of
 values.
- The final sample depth line is the same as normal except it is shifted left by 4 characters. A sample depth value is also included for the dummy 9990 stop marker year.

Following the data block there is a blank line and two option blocks of data that are only included if the file is a chronology file.

The next block of information in a chronology file is denoted by a line; ELEMENTS. The following lines contain the file names of the data files that have contributed to the creation of the chronology.

Following this is an optional block denoted by the line ;weiserjahre followed by the weiserjahre data. Each weiserjahre data line begins with a space followed by a integer year value for the first year in the line. The weiserjahre value is left padded with spaces to fill 6 characters and the value itself is written as X/Y where X is the number of samples that show an upward trend in width; and Y is the number of samples that show a downward trend in width. The weiserjahre value is forward facing so the value for ring 1001 shows the trend between ring 1001 and 1002. There is therefore one less weiserjahre value in the final row than there are ring-widths.

The final line of Corina data files contains the author's name preceded by a tilde.

F.2 Example file

```
Trebenna, Byzantine Fortress, NW tower 1AB
2
   ;ID 907010;NAME Trebenna, Byzantine Fortress, NW tower 1AB;DATING R;UNMEAS_PRE 1;
3
        UNMEAS_POST 1
   ; FILENAME G:\DATA\TRB\TRB1AB.SUM
    ; TYPE S; SPECIES Juniperus sp.; FORMAT R; PITH +
    ; TERMINAL vv; CONTINUOUS N; QUALITY +
9
    ; RECONCILED Y
    ; DATA
10
    1001
                    125
                          219
                                 207
                                        139
                                                62
                                                      107
                                                              29
                                                                     91
                                                                            65
11
                      [1]
                            [1]
                                    [1]
                                          [1]
                                                 [1]
                                                        [1]
                                                               [1]
                                                                      [1]
                                                                             [1]
12
     1010
              71
                   132
                            74
                                 150
                                               156
                                                      122
                                                              81
                                                                     46
                                                                            57
                                         75
13
               [1]
                                                       [1]
67
                                                                      [1]
14
                      [1]
                             [1]
                                    [1]
                                           [1]
                                                  [1]
                                                               [1]
                                                                             [1]
                                                                           129
     1020
             147
                     78
                            89
                                 126
                                               121
                                                              71
                                         73
                                                                     64
15
               [1]
                      [1]
                                                 [1]
                                                        [1]
                             [1]
                                          [1]
                                                               [1]
                                                                      [1]
                                                                             [1]
16
                                   [1]
     1030
                                                       90
             149
                   155
                          122
                                 126
                                         53
                                               136
                                                              65
                                                                    100
                                                                            67
17
               [1]
                            [1]
                                                 [1]
                                                        [1]
                                                                      [1]
                                                                             [2]
18
                      [1]
                                    [1]
                                          [1]
                                                               [1]
     1040
              67
                   101
                          132
                                 102
                                          40
                                                67
                                                       42
                                                              36
                                                                     62
                                                                            29
19
20
               [2]
                      [2]
                             [2]
                                   [2]
                                          [2]
                                                 [2]
                                                        [2]
                                                               [2]
                                                                      [2]
                                                                             [2]
     1050
              30
                     44
                            46
                                   40
                                                61
                                                       55
                                                              29
                                                                     44
                                                                            63
21
                                                                      [2]
22
               [2]
                     [2]
                            [2]
                                   [2]
                                          [2]
                                                 [2]
                                                        [2]
                                                               [2]
                                                                             [2]
     1060
              62
                     38
                            22
                                   26
                                         26
                                                28
                                                       37
                                                              21
                                                                     21
                                                                            27
23
               [2]
                      [2]
                             [2]
                                   [2]
                                           [2]
                                                 [2]
                                                        [2]
                                                               [2]
                                                                      [2]
                                                                             [2]
              17
                                                       17
                                                                     27
     1070
                            50
                                   21
                                         33
                                                12
                                                                            20
                     18
                                                              16
25
                     [2]
                            [2]
26
               [2]
                                   [2]
                                          [2]
                                                 [2]
                                                        [2]
                                                               [2]
                                                                      [1]
                                                                             [1]
                                   8 9990
    1080
27
              18
                    11
                            9
          [1]
               [1]
                      [1]
                             [1]
                                    [1]
28
29
   : ELEMENTS
30
   G: \DATA\TRB\TRB1A.REC
31
   G:\DATA\TRB\TRB1B.REC
32
    ; weiserjahre
33
                                                                                     0/1
            1/0
                       0/1
                                 0/1
                                            0/1
                                                      1/0
                                                                0/1
                                                                           1/0
                                                                                                1/0
34
     1001
                                                      1/0
     1010
            1/0
                       0/1
                                 1/0
                                            0/1
                                                                0/1
                                                                           0/1
                                                                                     0/1
                                                                                                1/0
35
         1/0
     1020
            0/1
                       1/0
                                 1/0
                                            0/1
                                                      1/0
                                                                0/1
                                                                           1/0
                                                                                     0/1
                                                                                                1/0
36
         1/0
     1030
            1/0
                       0/1
                                 1/0
                                            0/1
                                                      1/0
                                                                0/1
                                                                           0/1
                                                                                     1/0
                                                                                                0/1
37
         1/1
     1040
            2/0
                       2/0
                                 0/2
                                            0/2
                                                      2/0
                                                                 0/2
                                                                           0/2
                                                                                     2/0
                                                                                                0/2
         2/0
                       1/1
                                 0/2
                                                      2/0
                                                                           0/2
                                                                                     2/0
                                                                                                2/0
39
     1050
            2/0
                                            0/2
                                                                 0/2
         1/1
     1060
            0/2
                       0/2
                                 2/0
                                            1/1
                                                      2/0
                                                                 2/0
                                                                           0/2
                                                                                     1/1
                                                                                                2/0
40
         0/2
     1070
                                 0/2
                                                      0/2
                                                                 2/0
                                                                                     1/0
            1/1
                       2/0
                                            2/0
                                                                           1/1
                                                                                                0/1
41
         0/1
    1080
           0/1
                       0/1
                                 0/1
42
    ~ Unknown User
```

Appendix G

DendroDB

Format name DendroDB

Other name(s)

Type Text file Extension(s) dat Read/write support Read only

Reference implementation DendroDB website

Calendar type Astronomical

Absolute dating support Yes
Undated series support No
Relative dating support No
Multi series support Yes

Original designer Simon Brewer

G.1 Description

The DendroDB format is an export file format produced by the DendroDB website/database. There is no known software that can natively read DendroDB files so a 'writer' for this format has not been developed.

The format is self-explanatory, beginning with a copyright line, followed by 7 metadata lines, then the data itself. There are eight possible data variables: Total width; Earlywood width; Latewood width; Min. Density; Max. Density; Earlywood density; Latewood density; Average density. Ring width data is provided in microns but the units for density measurements are not document.

As of Feb 2011, the DendroDB database does not contain data prior to 441AD so handling of BC/AD transition has not been tested. The DendroDB web interface suggests that BC dates should be entered as negative integers, but it also allows request for data from year 0. This suggests the database uses an Astronomical calendar and this is how the DendrolOLib treats it.

60 DENDRODB

G.2 Example file

```
Data downloaded from DendroDB. Please acknowledge authors
    {\sf Site: Example \ site}
3 Contact: A N Other
   Species: Larix sibirica
   Parameter: Latewood width Latitude: 53.25
   Longitude: 57.35
Elevation: 1670
Tree Core Year Latewood width
10
   1 1 1648 16
   1 1 1649 21
  1 1 1650 8
  1 1 1651 10
   1 1 1652 6
15
   1 1 1653 8
   1 1 1654 11
  1 1 1655 13
  1 1 1656 9
  1 1 1657 10
19
   1 1 1658 10
21 1 1 1659 4
22 1 1 1660 5
23 1 1 1661 7

    24
    1
    1
    1662
    4

    25
    1
    1663
    8
```

Appendix H

Heidelberg

Format name Heidelberg
Other name(s) TSAP, FH
Type Text file
Extension(s) .fh

Read/write support Read and write Reference implementation TSAP-Win

Calendar type Gregorian
Absolute dating support Yes
Undated series support Yes
Relative dating support Yes
Multi series support Yes

Original designer Frank Rinn

H.1 Description

The Heidelberg format (Rinn, 2008) is the native file format for Rinntech's TSAP-Win software. It supports metadata in the form of keyword-value pairs. There are more than 140 standard keywords specified in the documentation, but users can extend these with their own. This makes the format extremely flexible, but the absence of any checking of data types (strings, numbers categories etc) and no method of validation means that there can be problems interpreting metadata entries.

Heidelberg files can store one or more series in a single file. Each series is represented by a header and a data block.

The header block begins with a line HEADER: This is followed by lines of metadata, with one field on each line, in the format keywords=value much like a standard Windows INI file. As mentioned previously there are a number of predefined keywords, all of which are outlined here:

- AcceptDate
- Age
- AutoCorrelation
- Bark
- BHD
- Bibliography
- Bibliography[n]
- BibliographyCount
- Bundle

- CardinalPoint
- ChronologyType
- ChronoMemberCount
- ChronoMemberKeycodes
- Circumference
- Client
- ClientNo
- Collector
- Comment

62 HEIDELBERG

- Comment[n]
- CommentCount
- Continent
- CoreNo
- Country
- CreationDate
- DataFormat
- DataType
- DateBegin
- Dated
- DateEnd
- DateEndRel
- DateOfSampling
- DateRelBegin[n]
- DateRelEnd[n]
- DateRelReferenceKey[n]
- DateRelCount
- DeltaMissingRingsAfter
- DeltaMissingRingsBefore
- DeltaRingsFromSeedToPith
- Disk
- District
- EdgeInformation
- EffectiveAutoCorrelation
- EffectiveMean
- EffectiveMeanSensitivity
- EffectiveNORFAC
- Key
- EffectiveNORFM
- EffectiveStandardDeviation
- Eigenvalue
- Elevation
- EstimatedTimePeriod
- Exposition
- FieldNo
- FilmNo
- FirstMeasurementDate
- FirstMeasurementPersID
- FromSeedToDateBegin
- GlobalMathComment[n]
- GlobalMathCommentCount
- GraphParam
- Group
- HouseName
- HouseNo
- ImageCellRow
- ImageComment[n]
- ImageFile[n]
- ImageCount
- ImageFile
- Interpretation
- InvalidRingsAfter
- InvalidRingsBefore
- JuvenileWood
- KeyCode
- KeyNo

- LabotaryCode
- LastRevisionDate
- LastRevisionPersID
- Latitude
- LeaveLoss
- Length
- Location
- LocationCharacteristics
- Longitude
- MajorDimension
- MathComment
- MathComment[n]
- MathCommentCount
- MeanSensitivity
- MinorDimension
- MissingRingsAfter
- MissingRingsBefore
- NumberOfSamplesInChrono
- NumberOfTreesInChrono
- Persld
- Pith
- Project
- ProtectionCode
- Province
- QualityCode
- Radius
- RadiusNo
- RelGroundWaterLevel
- RingsFromSeedToPith
- SampleType
- SamplingHeight
- SamplingPoint
- SapWoodRings
- Sequence
- SeriesEnd
- SeriesStart
- SeriesType
- ShapeOfSample
- Site
- SiteCode
- SocialStand
- SoilType
- Species
- SpeciesName
- StandardDeviation
- State
- StemDiskNo
- Street
- Timber
- TimberHeight
- TimberType
- TimberWidth
- TotalAutoCorrelation
- TotalMean
- TotalMeanSensitivity
- TotalNORFAC

- TotalNORFM
- TotalStandardDeviation
- Town
- TownZipCode
- Tree
- TreeHeight
- TreeNo

- Unit
- UnmeasuredInnerRings
- UnmeasuredOuterRings
- WaldKante
- WoodMaterialType
- WorkTraces

The meaning of many of these keywords is fairly self-explanatory but others are a little more obscure. As there is no data typing or validation the format of the contents of these fields cannot be predicted. This is particularly a problem when trying to compare fields such as Latitude, Longitude and FirstMeasurementDate, but is especially a problem when comparing files produced in different labs.

The header section is followed by a data section denoted by a line containing the keyword DATA: followed by the type of data present which can be one of Tree; HalfChrono; Chrono; Single; Double; Quad. Tree, HalfChrono and Chrono are the original keywords supported by early versions of TSAP but these are now deprecated in preferences of the more generic Single, Double and Quad terms. The terms Single, Double and Quad are largely interchangeable with Tree, HalfChrono and Chrono respectively, but not completely. Double can refer to both Tree and HalfChrono format data. When the newer terms are used, the header keyword DataFormat is used to record whether the data is equivalent to Tree, HalfChrono or Chrono.

Single format - data is typically used for storing raw measurement series. Each data line contains 10 data values each being a left space padded integer taking up 6 characters. Any spare data values in the final data line are filled with zeros. Alternatively it appears that TSAP-Win also accepts this data section as single integer values one per line.

Double format - data is for storing data with sample depth information - typically chronologies. Like the single format section, data is stored as 10 integer values, each taking up 6 characters and left padded with spaces. The values are in pairs of ring-widths and sample depths, therefore five rings are stored per line.

Quad format - data is for storing chronologies with sample depth as well as data on how many of the constituent series increase and decrease. This format therefore requires four numbers for each data point: ring-width; sample depth; increasing series; decreasing series. Numbers are stored as integers, left space padded as before, but this time only using 5 characters not 6. Four data points are included on each line, therefore this means there are 16 numbers per row and each row is 80 characters long.

64 HEIDELBERG

H.2 Example file - raw series

```
HEADER:
   DateEnd=-66
   KeyNo=27
   Project=Growth studies
   Length=103
   Location=Example site
   Species=PISY
   SapWoodRings=14
   WaldKante=WKF
   State=Colorado
10
   PersId=FR
   KeyCode=271017
12
   {\tt Country}\!\!=\!\!\!USA
   DateOfSampling=19950506
   TreeNo=5
15
   CoreNo=1
   Exposition=North-West
17
   Creation Date = 19970526
   SoilType=Sand
19
   DATA: Tree
20
                                           145
       125
              130
                      99
                            120
                                    115
                                                  151
                                                         130
                                                                135
21
                                                                        151
       200
              190
                     151
                            170
                                    170
                                           174
                                                  170
                                                         200
                                                                210
                                                                        130
22
                                                  180
23
       180
              197
                     210
                            160
                                    180
                                           155
                                                         199
                                                                140
                                                                        150
       146
              140
                     145
                            150
                                    155
                                           110
                                                  115
                                                         113
                                                                120
                                                                        130
24
25
       110
              120
                     150
                            120
                                    120
                                           110
                                                  115
                                                         160
                                                                160
                                                                        145
                                           149
                                                  120
       135
              145
                     125
                            115
                                    145
                                                                        99
                                                         150
                                                                160
26
27
       110
               75
                      70
                             82
                                     96
                                            90
                                                  120
                                                         151
                                                                155
                                                                        130
                     149
                            110
                                    130
                                           120
                                                  128
                                                         118
                                                                125
28
       132
              133
                                                                        115
        95
               90
                     110
                              98
                                     80
                                            85
                                                   97
                                                          88
                                                                 70
                                                                        100
29
        90
               70
                                                   95
                                                                 70
30
                      80
                              90
                                     85
                                            78
                                                          84
                                                                         90
        80
               75
                      70
                                      0
                                                    0
                                                           0
                                                                  0
                                                                          0
```

H.3 Example file - chronology

```
HEADER:
   KeyCode=ABCK0530
    DataFormat=HalfChrono
    SeriesType=Mean curve
   Length=60
   DateBegin=987
   DateEnd=1046
    Dated = Dated
   {\tt Location}{=}{\sf Example \ site}
    Species=QUSP
10
    {\sf GlobalMathCommentCount}{=}0
11
   ImageCount=0
12
    CommentCount=0
13
    {\tt BibliographyCount=0}
14
   DATA: Double
15
       125
                      125
                                     264
                                                    206
                                                                    115
16
                      188
                                     308
                                                    197
                                                                    419
       111
                                2
                                                               2
17
                                     279
       238
                 2
                      227
                                2
                                               2
                                                    293
                                                               2
                                                                    271
                                                                              2
                 2
       309
                      170
                                2
                                     204
                                               2
                                                    163
                                                               2
                                                                              2
                                                                    175
19
       164
                 2
                      211
                                2
                                     134
                                               2
                                                     141
                                                               2
                                                                    107
20
                 2
                                               2
        72
                                2
                                       91
                                                               2
                                                                     47
                                                                              2
                       74
                                                    110
21
        87
                 2
                       87
                                2
                                       35
                                                      47
                                                                     80
22
                 2
                                2
                                               2
                                                                              2
         66
                       38
                                       82
                                                      78
                                                               2
                                                                     65
         63
                 2
                       76
                                2
                                       67
                                               2
                                                      91
                                                               2
                                                                     73
                                                                              3
24
         39
                 3
                        41
                                3
                                       78
                                               3
                                                      57
                                                               3
                                                                     54
                                                                              3
25
                                                                     43
         41
                 3
                       39
                                3
                                       52
                                               3
                                                      53
                                                               3
                                                                              3
26
         48
                                       32
                                                      48
```

Appendix I

Microsoft Excel 97/2000/XP

Format name Microsoft Excel 97/2000/XP

Other name(s)

Binary Interchange File Format, BIFF

Type Binary file

Extension(s) xls

Read/write support
Reference implementation
Data / metadata
Calendar type
Absolute dating support
Undated series support
Read and write
Microsoft Excel
Data only
Gregorian
Yes
Undated series support
No
Relative dating support
No

Multi series support Yes
Original designer Microsoft

I.1 Description

The Excel file format is a widely used format for storing spreadsheet data. It is a proprietary binary format created by Microsoft but supported by many spreadsheet and statistical applications. It is not to be confused with the Office Open XML format which was introduced by Microsoft with MS Office 2007 and typically has the file extension xlsx.

Although Excel files can contain multiple sheets in a workbook, only the first sheet is considered. Like the CSV and ODF Spreadsheet formats, support for Excel files is limited to a particular layout or style of spreadsheet. The layout of the data sheet should be as follows:

- Row 1 Header names for each column
- Column A Year values
- Column B+ One column for each series containing values in millimetres. Cells are left empty if no data is available for a series because it does not extend to a particular year. Data must be continuous for each series, so missing/unmeasured rings should be included as zero.

I.2 Example file

	A	В	С	
1	Year	MySample1	MySample2	
2	1954	0.33		
3	1955	0.26	0.26	
4	1956	0.2	0.2	
5	1957	0.14	0.14	
6	1958	0.08	0.08	
7	1959	0.02	0.02	
8	1960	0.2	0.2	
9	1961	0.14	0.14	
10	1962	0.08	0.08	
11	1963	0.2		
12	1964	0.33		
13	1965	0.08		
14	1966	0.33		
15	1967	0.22		
16				

Appendix J

Microsoft Excel 2007

Format name Microsoft Excel 2007

Other name(s) Office Open XML Spreadsheet, OOXML, OpenXML

Type XML file Extension(s) xlsx

Read/write support
Reference implementation
Data / metadata
Calendar type
Absolute dating support
Undated series support
Polative dating support
Read and write
ISO 29500
Data only
Gregorian
Yes
Undated series support
No

Undated series support
Relative dating support
Multi series support
Original designer

No
Yes
Microsoft

J.1 Description

This is the new XML file format introduced by Microsoft with Excel 2007. Unlike the binary format used by the previous version of Excel, this format is an open standard. However, it should not be confused with the OpenDocument Format standard that was developed by the OASIS consortium.

The layout of the data sheet should be just as for the Excel 97/2000/XP format:

- Row 1 Header names for each column
- Column A Year values
- Column B+ One column for each series containing values in millimetres. Cells are left empty if no data is available for a series because it does not extend to a particular year. Data must be continuous for each series, so missing/unmeasured rings should be included as zero.

See the screenshot in the Microsoft Excel 97/2000/XP format to see how an example of how the spreadsheet should look.

Appendix K

Nottingham

Format name Nottingham

Other name(s) Nottingham Laboratory format

Type Text file

Extension(s) txt

Read/write support
Reference implementation
Data / metadata
Calendar type
Absolute dating support
Undated series support
Read and write
Unknown
Data only
n/a
No
Vo
Undated series support
Relative dating support
Mo
Multi series support
Yes

Multi series support Yes
Original designer Cliff Litton

K.1 Description

The Nottingham format was designed by Cliff Litton. It is a simple text format with no support for metadata.

Line 1 contains a series name and an integer indicating how many data values there are in the file. Subsequent lines contain the data represented as 1/100th mm integers in twenty columns seemingly in either 4 characters or 3 characters + 1 space.

There is no known reference implementation for this format and few known examples of data so little is known about how it should handle unusual situations such as negative values, values ¿999 etc.

NOTTINGHAM

K.2 Example file

```
ABCD01
             176
   342 338 334 409 362 308 360 264 325 318 134 151 219 268 290 222 278 258 173 198
2
   294 202 170 176 172 121 87 130 114 108 170 135 131 126
                                                            87 100
                                                                     86 104 103 127
                                    79
   112 94
            96 120 168 149 119 124
                                        67
                                            88
                                                90
                                                    93
                                                             49
                                                                 42
                                                                     53
                                                                        38
                                                                            57
                                                                                 43
                                                        77
    50
        41
            56
                66
                    62
                        55
                            55
                                45
                                    47
                                        63
                                            58
                                                60
                                                     44
                                                         45
                                                             49
                                                                 50
                                                                     62
                                                                         61
                                                                             43
                                                                                 54
    91
            56
                43
                    52
                        51
                            65
                                    55
                                                        78
                                                                        75
                                                                             55
                                                                                 47
        60
                                68
                                        44
                                            41
                                                75
                                                     94
                                                            63
                                                                 69
                                                                     58
    58
        46
            62
                45
                    52
                        50
                            77
                                50
                                    63
                                        75
                                            77
                                                64
                                                    66
                                                        57
                                                            80
                                                                57
                                                                     78
                                                                         65
                                                                             68
                                                                                 75
    65
       98
            85
                82 119
                        89
                            85
                                87
                                    83 108 129 123 160 117 129 121
                                                                     88
                                                                         69
                                                                             97
                                                                                 77
                        65 133
    96 106
            71
                89
                    50
                                89
                                    88
                                        50
                                           60
                                                95
                                                    95
                                                        91 102 158
                                                                     83
                                                                         55
                                                                            98
                                                                                70
    45
        46
            40
                36 64
                        58
                            52
                                58
                                    56
                                        94
                                            51
                                                48
                                                    47
                                                        60 49
```

Appendix L

ODF Spreadsheet

Format name ODF Spreadsheet

Other name(s) ODF, ODS, OpenDocument Spreadsheet, OpenOffice.org

Spreadsheet,

Type XML file

Extension(s) ods

Read/write support Read and write Reference implementation ISO/IEC 26300:2006

Data / metadata Data only
Calendar type Gregorian
Absolute dating support Yes
Undated series support No
Relative dating support No
Multi series support Yes

Original designer OASIS consortium

L.1 Description

The OpenDocument Format (ODF) spreadsheet format is an XML-based specification developed by the Organization for the Advancement of Structured Information Standards (OASIS) consortium. It should not be confused with the similarly named Office Open XML format developed by Microsoft. The ODF spreadsheet format is an open standard which can be read by most modern spreadsheet applications including MS Excel, OpenOffice.org and Google Docs.

Support for ODF spreadsheets in TRICYCLE is necessarily limited to a particular layout of spreadsheet:

- Row 1 Header names for each column
- Column A Year values
- Column B+ One column for each series containing values in millimetres. Cells are left empty if no data
 is available for a series because it does not extend to a particular year. Data must be continuous for each
 series, so missing/unmeasured rings should be included as zero.

Please see the Excel section for a screenshot of how an ODF spreadsheet should look.

Appendix M

Oxford

Format name Oxford

Other name(s) Dan Miles Format, English Heritage Format

Type Text file

Extension(s) Various including dan, ddf but often none

Read/write support Read and write

Reference implementation Various English Heritage applications

Data / metadata Data only
Calendar type Gregorian
Absolute dating support Yes
Undated series support Yes
Relative dating support Yes
Multi series support No

Original designer Ancient Monuments Laboratory of English Heritage

M.1 Description

The Oxford format seems to be only currently used in the Oxford Dendrochronology Laboratory. It was designed in the 1980s for use with a number of DOS based applications for the English Heritage Ancient Monuments Laboratory. It is still actively used by the Oxford Lab with these programs and a number of newer Windows applications.

The file is a text file format containing two header lines following by a block of data values and an optional block of count/sample depth values. Some files also contain a number of comment lines at the end of the file.

Line 1 contains the following fields:

- Char 1 Apostrophe
- Chars 2-8 Series name
- Char 9-10 spaces
- Char 11 j
- Chars 12-15 First year in sequence (when series is securely dated). Year should be left padded with spaces if less than 4 characters.
- Char 16 hyphen
- Chars 17-20 Last year in sequence (when series is securely dated). Year should be left padded with spaces if less than 4 characters.
- Char 21 space
- Char 22+ Description typically name of site/building etc
- Final char optional apostrophe

74 OXFORD

Line 2 contains:

- Integer number of years
- Comma
- Integer start year

The start year on line 2 and the first year on line 1 will be the same for securely dated series. When the series is tentatively or relatively dated the first year (and/or) the last year on line 1 will be left blank. For undated series the start year is set to 1001.

The data lines follow the two header lines. These typically contain 10 data values per line, but there can be more (if rings have been added) or less e.g. last line. The values are in 1/100th mm integers and can only contain three digits (e.g. max 999 1/100th mm). Data values are space delimited. Some example files contain values that are left padded with zeros if the value is on 1 or 2 characters wide (e.g. '025' rather than '25').

Following the data values there should be an empty line followed by an optional sample count/depth block. The count block is formatted in largely the same way as the data values block. The values are stored in columns 2 characters (rather than 3 characters) wide. Like the data values, the count values are space delimited integers, typically (but not always) 10 per line.

The file is terminated with 0, 1 or 2 free-text comment lines. A number of Oxford data files have been seen that terminate with the ASCII control character referred to variably as 'SUB', 'SUBSTITUTE' or 'CTRL+Z' (represented in Unicode as character dec 26 - hex 1A). It is not clear whether this is necessary for any particular programs to function.

M.2 Limitations

- Only holds whole ring-width data
- Does not cope with data values ¿999 1/100th mm
- Does not cope with chronologies of ¿99 samples
- Does not allow dates before 1AD

OXFORD 75

M.3 Example file

```
'ABCD
             <1850-1925> A Fictious site - abcd1 abcd2 '
   75,1850
   422 582 355 266 225 271 361 235 387 395
   794 611 446 248 277 359 111 226 189 711
   464 172 190 239 128 153 234 828 207 157
   768 180 178 168 204 163 160 255 166 136
   182 201 142 188 223 186 150 135 134 666
   191 122 223 555 123 126 108 133 137 134
   161 222 93 100 132 104 86 277 101 141
10
   185 151 261 110 145
             2 2
                  2 2
                               2
12
       2 2 2 2 2 2
    2
                         2
13
       2
                2 2 2
                            2
          2
             2
                         2
                               2
14
        2
             2
                2
15
     2
       2
          2
             2
                2
                   2
                      2
                         2
       2
17
          2
                   2
                   2 2 2
     2 2 2
             2
                2
                1
```

Appendix N

PAST4

Format name PAST4

Other name(s) P4P PAST4 Project File

Type Text file Extension(s) p4p

Read/write support Read and write

Reference implementation PAST4

Data / metadata Data and some structured metadata

Calendar type Gregorian Absolute dating support Yes

Undated series support Relative dating support

Multi series support Yes

Original designer Bernhard Knibbe

The PAST4 format (Knibbe, 2008) is the native file format for SCIEM's PAST4 software. It is a hybrid XML file, containing most metadata in structured XML but some metadata and all data as plain text. It is unique amongst dendro data formats in that it contains not only data and metadata but also settings information for the PAST4 software such as details on what colours to use in graphs, which series should be displayed on screen etc. The general structure of a P4P file is as follows:

- Project header (required)
- Settings (optional)
- Groups (required, repeatable)
- Records (required, repeatable)

The root XML tag for the file is <PAST_4_PROJECT_FILE>. Inside this is the <PROJECT> tag which contains the following attributes:

- ActiveGroup Zero based index specifying which group is active
- EditDate Date the file was last edited
- Groups Number of groups within this project
- Locked Either TRUE or FALSE indicating whether a password is required to open the file
- Name Name of the project
- Password Password used to lock the project
- PersID Abbreviation of the authors name
- Records Number of records in the project
- Reference Zero based index indicated which is the reference series (-1 if none selected)
- Sample Zero based index indicating which is the selected sample (-1 if none selected)
- Version Version number for this PAST4 format. At the time of writing only one version exists (400).

78 PAST4

Of these fields only Name, Groups and Records are mandatory. The project tag can also contain a <! [CDATA [tag which allows the storing of a project description in plain text.

Next comes the <SETTINGS> tag. This is one very large XML tag with many attributes controlling the what PAST4 should display the data. The contents of this tag are optional and are therefore irrelevant for the transfer of dendro data.

Next comes one or more <GROUPS> tags. A group is an arbitrary collection of series, perhaps representing a number of measurements of a single object, or perhaps an administrative collection of series. Groups can be nested in a hierarchy, but rather than use the hierarchical nature of XML files, the format instead lists all groups side-by-side and maintains the relationships through the use of an 'owner' attribute containing the index of the parent group. This arrangement means than any changes to the hierarchy, or the deletion of a group requires all indices to be carefully updated to avoid corrupting the file. The group tag has the following attributes:

- Name Name of the group
- Visible Either TRUE or FALSE indicating whether the group should be shown in graphs
- Fixed Either TRUE or FALSE indicating whether the group can be moved
- Locked Either TRUE or FALSE. If locked the group can be used in the calculation of further mean values.
- Changed Internal TRUE or FALSE value for keeping track of changes
- Expanded TRUE or FALSE value indicating whether the group should be expanding in the project navigator window
- UseColor TRUE or FALSE value for is content should be displayed in color
- HasMeanValue TRUE or FALSE indicating if the group has a dynamic mean value
- IsChrono TRUE or FALSE indicating if the group mean is calculated with sample depth information
- Checked TRUE or FALSE indicating if the group is locked and checked
- Selected TRUE or FALSE indicated in the group is selected in the project navigation window
- Color 24bit integer indicating the RGB volor value for the group using Borland format
- Quality Integer value describing the quality of the group mean
- MVKeycode String code for the group. If empty the Name field is used
- Owner Integer pointing containing the index of the parent group if this group is in a hierarchy. If its a top level group it should be -1.

As with the project tag, the group tag can also contain a <! [CDATA [section for storing a plain text description of the group.

The final tag type in the file is the <RECORDS> tag. These contain the actual data series and most of the metadata. Like group tags, records tags are placed side-by-side in the file and are placed into the group hierarchy by the use of the 'owner' attribute. In addition, the tag also has the following attributes:

- Keycode Name of the series
- Length Integer for the number of rings
- Owner Integer index to the group to which this record belongs
- Chrono TRUE or FALSE indicating whether this record has density information
- Locked TRUE or FALSE indicating in the record can be moved
- Filter TRUE or FALSE indicating if an indexing function is appled to the data
- FilterIndex Integer index for the filter used
- FilterS1 Parameter 1 for the filter
- FilterS2 Parameter 2 for the filter
- FilterB1 Additional filter parameter
- FilterWeight Additional filter parameter
- Offset Position of the first ring
- Color 24bit RGB color for record in Borland format
- Checked TRUE or FALSE indicating is the record is selected for use in the dynamic group mean
- !VShift Temporary integer value added to data value to shift vertically in graphs
- IsMeanValue TRUE or FALSE indicating if this is a dynamic mean value
- Pith TRUE or FALSE
- SapWood Integer storing the number of sapwood rings
- Location String location information

PAST4 79

- Waldkante String description of presence of waney edge
- FirstValidRing Integer indicating which ring is the first valid ring. If j0 then some rings are discarded
- LastValidRing Integer indicating which ring is the last valid ring. If ¿0 then some rings are discarded
- UseValidRingsOnly TRUE or FALSE internal use only
- Quality Integer indicating the quality of the record

The record tag then contains a <HEADER> tag with a <! [CDATA [section which includes additional free-text header information. There are no requirements as to how information should be laid out in this field however many users seem to adopt the Heidelberg style of keyword=value.

Next comes the <DATA> tag which is empty except another <! [CDATA [section. This is where the actual ring-width data is stored. Each data value is recorded on a separate line (using CR LR line breaks). Each line contains the following six tab delimited fields:

- Ring width as a floating point number
- Sample depth
- Number of sample increasing
- Latewood percentage as a floating point value 0-1 (0 if not known)
- Duplicate/backup ring-width value to store the original ring-width value. If an index is applied the ring-width value in column 1 is altered.
- Comment string about this particular ring

N.1 Dating

PAST4 contains an option for enabling/disabling the year 0 but it does not record within the data file whether the option was set when the file was created. By default the year 0 is disabled therefore the library treats PAST4 files as if they use the Gregorian calendar but it is possible that files were in fact created with the Astronomical calendar in mind.

80 PAST4

N.2 Example file

```
<?xml version="1.0"?>
       <PAST_4_PROJECT_FILE>
2
               <PROJECT Name="title0" Version="400" Locked="FALSE" Password=""</pre>
3
                        {\sf CreationDate} = "04/05/2006 \ 2:13:51 \ {\sf PM"} \ {\sf EditDate} = "09/01/2010 \ 13:02" \ {\sf ActiveGroup} = "0" \ {\sf Active
                        Reference="-1" Sample="-1" PersID="investigator0" Groups="2" Records="3">
5
       <![CDATA[description0
       ]]></PROJECT>
7
               <SETTINGS/>
              <GROUP Name="title1" Visible="TRUE" Fixed="FALSE" Locked="FALSE" Changed="FALSE"
    Expanded="TRUE" UseColor="TRUE" HasMeanValue="FALSE" IsChrono="FALSE"
    Checked="FALSE" Selected="FALSE" Color="0" MVKeycode="" Owner="-1">
q
10
11
                        <![CDATA[]]></GROUP>
12
               <GROUP Name="Unnamed Group" Visible="TRUE" Fixed="FALSE" Locked="FALSE" Changed="
13
                        FALSE"
                        Expanded="TRUE" UseColor="TRUE" HasMeanValue="FALSE" IsChrono="FALSE" Checked="
14
                                FALSE'
                        Selected="FALSE" Color="0" MVKeycode="" Owner="-1"><![CDATA[]]></GROUP>
15
               <RECORD Keycode="title6" Length="4" Owner="0" Chrono="FALSE" Locked="FALSE" Filter="</pre>
                        FilterIndex="-1" FilterS1="100" FilterS2="100" FilterB1="FALSE" FilterWeight=""
17
                                 Offset = "0"
                        Color="0" Checked="FALSE" VShift="0" IsMeanValue="0" Pith="FALSE" SapWood="0"
18
                        Location="locationComment1" Species="Quercus" Waldkante="" FirstValidRing="0"
19
                        LastValidRing="0" UseValidRingsOnly="FALSE">
20
                        <HEADER> <![CDATA[Unit=1/100th millimetres</pre>
21
      ]]></HEADER>
22
                        <DATA> <![CDATA[123]</pre>
                                                                            1
                                                                                                               0
                                                                                                                                123
23
       123
                        1
                                         1
                                                          0
                                                                            123
24
       123
                        1
                                         1
                                                          0
                                                                            123
25
       125
                        1
                                         1
                                                          0
                                                                            125
26
      ]]></DATA>
27
               </RECORD>
28
               <RECORD Keycode="title6" Length="4" Owner="0" Chrono="FALSE" Locked="FALSE" Filter="</pre>
29
                        FilterIndex="-1" FilterS1="100" FilterS2="100" FilterB1="FALSE" FilterWeight=""
30
                                 Offset = "0"
                        Color="0" Checked="FALSE" VShift="0" IsMeanValue="0" Pith="FALSE" SapWood="0"
31
                        Location="locationComment1" Species="QUSP" Waldkante="" FirstValidRing="0"
32
                        LastValidRing="0" UseValidRingsOnly="FALSE">
33
                       <HEADER> <![CDATA[Unit=1/100th millimetres</pre>
34
      ]]></HEADER>
35
                        <DATA> <![CDATA[123]</pre>
                                                                            1
                                                                                                                                123
                                                          0
       123
                        1
                                                                            123
37
                                         1
38
       123
                        1
                                         1
                                                           0
                                                                            123
                                                          0
       125
                                                                            125
                        1
                                         1
39
      ]]></DATA>
40
               </RECORD>
41
               <RECORD Keycode="Unnamed series" Length="2" Owner="1" Chrono="FALSE" Locked="FALSE"
Filter="FALSE" FilterIndex="-1" FilterS1="100" FilterS2="100" FilterB1="FALSE"</pre>
42
43
                        FilterWeight="" Offset="0" Color="0" Checked="FALSE" VShift="0" IsMeanValue="0"
44
                        Pith="FALSE" SapWood="0" Location="" Species="" Waldkante="" FirstValidRing="0"
45
                        LastValidRing="0" UseValidRingsOnly="FALSE">
46
                        <HEADER> <![CDATA[Unit=Wierd units</pre>
47
      ]]></HEADER>
48
                       <DATA><![CDATA[96]
                                                                                                              0
                                                                                                                                96
                                                                                                                                                  fire_damage; fire_damage;
49
       34
                                                                            34
                        1
                                         1
                                                                                              fire_damage; fire_damage;
50
      ]]></DATA>
51
               </RECORD>
52
       </PAST_4_PROJECT_FILE>
```

Appendix O

Sheffield

Sheffield Format name Other name(s) D Format Type Text file Extension(s) Read and write Read/write support Dendro for Windows Reference implementation Data / metadata Data and some structured metadata Calendar type Gregorian Yes Absolute dating support

Undated series support No
Relative dating support Yes
Multi series support No
Original designer Ian Tyers

0.1 Description

Sheffield format (Tyers, 1999) is a dendro specific text file designed by Ian Tyers for his Dendro for Windows application. It is probably most widely used in the UK but is also used in continental Europe as well as New Zealand.

The format contains both data and some structured metadata with each field/value stored one per line. The order of fields is fixed so missing data must be indicated by the use of a question mark. The data present on each line is as follows:

- 1. Site name/sample number Free form text not including ,"() up to 64 characters
- 2. Number of rings Whole positive number
- 3. Date type Single character; A = absolute date, R = relative date
- 4. Start date Whole number (can be negative). If absolute year then add 10000 to value so 1AD = 10001
- 5. Raw data type or Mean data type
 - Single character; R = annual raw ring-width data (NB earlier versions used some other codes here for species e.g. ABEFPSU these are all interpreted as equivalent to R)
 - Single character; W=timber mean with signatures, X=chron mean with signatures, T = timber mean, C = chron mean, M = un-weighted master sequence
- 6. Raw sapwood number or mean number of timbers/chronologies
 - Whole positive number or 0
 - Whole positive number
- 7. Raw edges inf. or Mean chronology type

82 SHEFFIELD

- Single character; Y = has bark, ! = has ?bark, W = terminal ring probably complete (i.e. possibly Winter Felled), S = terminal ring probably incomplete (i.e. possibly Summer Felled), B = has h/s boundary, ? = has ?h/s boundary, N = has no specific edge, (NB but may have sap), U = sap/bark unknown, C = charred outer edge, P = possibly charred outer edge
- Single character; R = raw unfiltered data, 5 = 5 year running mean, I = indexed data, U = unknown mean type
- 8. Author and comment Free form text not including ,"() up to 64 characters
- 9. UK National grid reference 2 characters +even no of digits up to 14 characters in all, ? = not known e.g. TQ67848675
- 10. Latitude and longitude Either decimal format e.g. 53.382457;-1.513623 or previously N51^30 W1^20
- 11. Pith single character; C = centre of tree, V = within 5 years of centre, F = 5-10 years of centre, G = greater than 10, ? = unknown
- 12. Cross-section code Two character code; first character, A = whole roundwood, B = half round, C quartered, D radial/split plank, E tangential/sawn plank. second character, 1 untrimmed, 2 trimmed, X irregularly trimmed. or, X = core /unclassifiable, ? unknown/unrecorded
- 13. Major dimension whole number in mm, 0 if unrecorded or mean
- 14. Minor dimension whole number in mm, 0 if unrecorded or mean
- 15. Unmeasured inner rings single character+whole number; use pith codes + number of rings or, H =heartwood, N =none
- 16. Unmeasured outer rings single character+whole number; use edges code + number of rings except that S =sapwood with no edge and V is the spring felling equivalent other codes are, H =heartwood with no edge, N =none
- 17. Group/Phase free form text not including, " () up to 14 characters
- 18. Short title free form text not including , " () up to 8 characters
- 19. Period single character; C = modern, P = post medieval, M = medieval, S = Saxon, R = Roman, A = pre Roman, 2 = duplicate e.g. repeat measure, B = multiperiod e.g. long master, ? = unknown
- 20. ITRDB species code 4 character code refer to ITRDB species codes
- 21. Interpretation and anatomical notes ? =no interpretation/notes. The interpretation and the anatomical notes can be in any order but each must consist of three parts, a single character A or I for anatomy or interpretation, a separator , for interpretations the date of the start, for anatomy the ringno, a separator , for anatomy the anatomical code for interpretations P for plus, 0 for felled and a number for the length of the range, where more than one record is present these are separated by , there must not be a terminal separator and each record must consist of the tree parts. The anatomical codings can be anything of a single character but supported usage is based on Hans-Hubert Leuschners anatomical codes; D = Density Band, R = Reaction Wood, L = Light Latewood, H = Dense Latewood, F = Frost Ring, K = Small Earlywood Vessels oak, G = Great Latewood Vessels oak, T = Wound Tissue, N = Narrow Latewood, A = Light Latewood End, P = Narrow and Light Latewood, Q = Narrow and Dense Latewood
- 22. Data type single character; D = ring widths, E = early-wood widths only, L = late-wood widths only, R = late+early wood widths (i.e. reverse of normal rings), I = minimum density, A = maximum density, S = early, late; (i.e. sequentially and separately), M = mixed (?means of others)

The remaining lines contain the data:

- For each width (equivalent to the value of length) the individual increments etc. if a C X T or W type mean. No negatives or zeros
- Check field Single character H
- For each width the individual weightings of the mean sequences. If an X or W type mean. No negatives or zeros
- Check field Single character R
- For each width the number of individual series with rising values. No negatives or zeros.
- Check field Single character F
- For each width the number of individual series with falling values. No negatives.

SHEFFIELD 83

0.2 Dating

The format copes with the problem of the non-existent year 0AD/BC by adding 10000 to all year values. Therefore:

Year	Value in file
1AD	10001
1BC	10000
9999BC	2
10000BC	1

0.3 Example file

```
Ship wreck 4 timber mean
   170
   10784
   made PB 22/6/2004
11
12
   0
15
   Ν
16
17
   Example
19
   QUSP
21
   D
   391
24
   309
   314
   270
   273
   229
   319
   267
   276
   128
33
34
   163
   221
   269
   214
   201
   218
   199
   198
   209
   156
43
   177
```

Appendix P

Topham

Format name **Topham** Other name(s) Instrument format Type Text file Extension(s) txt Read and write Read/write support Reference implementation Data / metadata Data only Calendar type n/a Absolute dating support No Yes Undated series support Relative dating support No Multi series support No Original designer John Topham

P.1 Description

The Topham format is probably the most simplistic of formats consisting of just a column of decimal data values and no metadata whatsoever. Each data value is a decimal ring width in millimetres.

P.2 Example file

```
1 3.42
2 3.38
3 3.34
4 4.09
5 3.62
6 3.08
7 3.60
8 2.64
9 3.25
10 3.18
11 3.42
12 3.38
13 ...
```

Appendix Q

TRiDaS

Format name TRiDaS

Other name(s) Tree-Ring Data Standard, TRiDaS XML

Type Text file Extension(s) xml

Read/write support Read and write Reference implementation TRICYCLE

Data / metadata Data and structured metadata

Calendar type Gregorian
Absolute dating support Yes
Undated series support Yes
Relative dating support Yes
Multi series support Yes

Original designer Esther Jansma, Peter Brewer and Ivo Zandhuis

Q.1 Description

TRiDaS (Tree-Ring Data Standard see http://www.tridas.org) is a data format designed by over 80 dendrochronologists, computer scientists and users of dendrochronological data from a variety of associated fields as part of the DCCD project and the Dendro Data Standard forum. It is designed to accurately represent any dendro data and metadata and it is hoped over time the dendro community will accept TRiDaS as the de facto standard for all dendro data.

The format uses extensible markup language (XML) which means the standard can be extended and evolve as future needs change. The format is structured around the eight data entities described below:

A project is defined by a laboratory and encompasses dendrochronological research of a particular object or group of objects. Examples include: the dating of a building; the research of forest dynamics in a stand of living trees; the dating of all Rembrandt paintings in a museum. What is considered a "project" is up to the laboratory performing the research. It could be the dating of a group of objects, but the laboratory can also decide to define a separate project for each object. Therefore, a project can have one or more objects associated with it.

An object is the item to be investigated. Examples include: violin; excavation site; painting on a wooden panel; water well; church; carving; ship; forest. An object could also be more specific, for example: mast of a ship; roof of a church. Depending on the object type various descriptions are made possible. An object can have one or more elements and can also refer to another (sub) object. For instance a single file may contain three objects: an archaeological site object, within which there is a building object, within which there is a beam object. The list of possible object types is extensible and is thus flexible enough to incorporate the diversity of data required by the dendro community. Only information that is

88 TRIDAS

essential for dendrochronological research is recorded here. Other related data may be provided in the form of a link to an external database such as a museum catalogue.

- An element is a piece of wood originating from a single tree. Examples include: one plank of a water well; a single wooden panel in a painting; the left-hand back plate of a violin; one beam in a roof; a tree trunk preserved in the soil; a living tree. The element is a specific part of exactly one object or sub object. An object will often consist of more than one element, e.g., when dealing with the staves (elements) of a barrel (object). One or more samples can be taken from an element and an element may be dated using one or more derivedSeries.
- A sample is a physical specimen or non-physical representation of an element. Examples include: core from a living tree; core from a rafter in a church roof; piece of charcoal from an archaeological trench; slice from a pile used in a pile foundation; wax imprint of the outer end of a plank; photo of a back plate of a string instrument. Note that a sample always exists and that it can either be physical (e.g. a core) or representative (e.g. a picture). A sample is taken from exactly one element and can be represented by one or more radii.
- **A radius** is a line from pith to bark along which the measurements are taken. A radius is derived from exactly one sample. It can be measured more than once resulting in multiple measurementSeries.
- A measurementSeries is a series of direct, raw measurements along a radius. A single measurementSeries can be standardised or a collection of measurementSeries can be combined into a derived- Series. The measurements themselves are stored separately as values.
- A derivedSeries is a calculated series of values and is a minor modification of the "v-series" concept proposed by Brewer et al. (2010). Examples include: index; average of a collection of measurementSeries such as a chronology. A derivedSeries is derived from one or more measurementSeries and has multiple values associated with it.
- A value is the result of a single ring measurement. Examples include: total ring width; earlywood width; latewood width. The values are related to a measurementSeries or a derivedSeries. In case of a measurementSeries the variable and its measurement unit (e.g. microns, 1/100th mm etc) are recorded as well.

For a full description of the standard see Jansma et al. (2010).

Q.2 Example file

```
<?xml version="1.0" encoding="UTF-8"?>
         <tridas xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
 2
                      xsi:schemaLocation="http://www.tridas.org/1.2.1 ../dev/sourceforge/tridas/XMLSchema
 3
                                  /1.2.1/tridas -1.2.1.xsd"
                     xmlns="http://www.tridas.org/1.2.1" xmlns:xlink="http://www.w3.org/1999/xlink">
                     ct>
                                 <title>Aegean Dendrochronology Project</title>
 6
                                 <identifier domain="dendro.cornell.edu">C</identifier>
                                 <\!\!\mathsf{createdTimestamp} \quad \mathsf{certainty} = "\mathsf{exact}" > 1997 - 02 - 01\mathsf{T}14:13:51.0\mathsf{Z} <\!\!/ \mathsf{createdTimestamp} > 100\mathsf{T}14:13:10.0\mathsf{Z} <\!\!/ \mathsf{createdTimestamp} > 100\mathsf{T}14:10.0\mathsf{Z} <\mathsf{createdTimestamp} > 100\mathsf{T}14:100.0\mathsf{C} <\mathsf{createdTimestamp} > 1000\mathsf{T}14:100.0\mathsf{C} <\mathsf{created
 8
                                 <lastModifiedTimestamp certainty="exact">1997-02-01T14:13:51.0Z
                                              lastModifiedTimestamp>
                                 <type>Dating</type>
10
11
                                 <description>Our key long-range goal is to build long multi-millennial scale tree
                                             -ring
                                              chronologies in the Aegean and Near East that will extend from the present to
12
                                                            the
                                              early Holocene to cover, broadly speaking, the last 10,000 years of human and
13
                                              environmental history. Our raison d'etre is to provide a dating method for
                                                          the study
15
                                              of history and prehistory in the Aegean that is accurate to the year. This
                                                          kind of
                                              precision has, up to now, been lacking in ancient studies of this area.
16
                                                          Indeed, few
                                              archaeological problems stimulate as much rancor as chronology, especially
17
                                              the Eastern Mediterranean. The work of the Aegean and Near Eastern
18
                                                          Dendrochronology
                                              Project aims to help to bring some kind of rational and neutral order to
19
                                                          Aegean and
                                              Near Eastern chronology from the Neolithic to the present. </description>
20
```

TRIDAS 89

```
21
            < laboratory >
                <name>Malcolm and Carolyn Weiner Laboratory for Aegean and Near Eastern
22
                     Dendrochronology </name>
                <address>
23
                     <addressLine1>B48 Goldwin Smith Hall</addressLine1>
24
                    <\! \mathsf{addressLine2} \!>\! \mathsf{Cornell} \quad \mathsf{University} <\! / \mathsf{addressLine2} \!>\!
25
                    <cityOrTown>Ithaca/cityOrTown>
26
27
                    <stateProvinceRegion >NY</stateProvinceRegion >
                    <postalCode > 14853</postalCode >
28
                     <country>USA</country>
                </address>
30
            </laboratory>
31
            <category>Archaeology</category>
32
            <investigator>Peter I Kuniholm</investigator>
33
            <period >1976-present </period >
34
            <reference>reference1</reference>
35
            <object>
                <title > White Tower, Thessaloniki </title > <identifier domain="dendro.cornell.edu"
37
38
                     >28acb483-f337-412f-a063-59d911c37594</identifier>
39
                <createdTimestamp certainty="exact">1997-02-01T14:13:51.0Z</createdTimestamp>
40
                <lastModifiedTimestamp certainty="exact">1997-02-01T14:13:51.0Z
                     lastModifiedTimestamp>
                <type normalStd="Corina Dictionary" normalId="4" normal="Building">Building </
42
                    type>
                <description > The White Tower of Thessaloniki was originally constructed by
43
                    the Ottomans
                     to fortify the city's harbour.</description>
44
                    <coverageTemporal>Ottoman</coverageTemporal>
46
                    <coverageTemporalFoundation>Stylistic</coverageTemporalFoundation>
47
                </coverage>
48
                <location>
49
                     <locationGeometry xmlns:gml=" http://www.opengis.net/gml">
50
                         <gml:Point srsName="urn:ogc:def:crs:EPSG:6.6:4326">
51
                              <gml:pos>40.6263 22.9485/gml:pos>
52
                         </gml:Point>
53
                    </le>
54
                    <locationPrecision>20</locationPrecision>
                    <locationComment>Thessaloniki, Greece/locationComment>
56
                </location>
57
58
                <object>
                     <title>Fourth floor</title>
59
                    <type>Floor</type>
                     <element>
61
                         <title>C-TWT-65</title>
62
                         <identifier domain="dendro.cornell.edu"</pre>
63
                              >89dbd409-03a3-42a0-9391-62c6be7009ad</identifier>
64
                         <createdTimestamp certainty="exact">1997-02-01T14:13:51.0Z</
65
                              created Timestamp>
                         <lastModifiedTimestamp certainty="exact"</pre>
                             >1997-02-01T14:13:51.0Z</lastModifiedTimestamp>
67
                         <type normalStd="Corina Dictionary" normalId="3" normal="Rafter">
68
                              Rafter</type>
                         <description>15th Rafter from the south</description>
69
                         <taxon normalStd="Catalogue of Life Annual Checklist 2008" normal="</pre>
                              Quercus'
                              normalId="49139">Quercus sp.</taxon>
                         <dimensions>
72
                              <unit normalTridas="metres"/>
73
74
                              <height>1</height>
                              <width>1</width>
75
                              <depth>1</depth>
76
                         </dimensions>
77
                         <authenticity>Original</authenticity>
78
79
                         <sample>
                              <title>C-TWT-65-A</title>
80
                              <identifier domain="dendro.cornell.edu"</pre>
                                  >ff688357-b2d4-4394-a21a-90696cd4558c</identifier>
82
                              <createdTimestamp certainty="exact"</pre>
83
84
                                  >1997-02-01 T14:13:51.0Z</created Timestamp>
```

90 TRIDAS

```
<lastModifiedTimestamp certainty="exact"</pre>
85
                                     >1997-02-01T14:13:51.0Z</lastModifiedTimestamp>
86
                                <type normal="Corina Dictionary" normalId="1" normalStd="Section"</pre>
87
88
                                     >Section</type>
                                <samplingDate certainty="exact">1981-07-25</samplingDate>
89
qη
                                <state>Dry</state>
                                <radius>
91
92
                                     <title>C-TWT-65-A-B</title>
                                     <identifier domain="dendro.cornell.edu"</pre>
93
                                         >5b7baa8b-cd4e-4b3b-88fa-82939420e544</identifier>
                                     <createdTimestamp certainty="exact"</pre>
95
                                         >2006-05-04T18:13:51.0Z</createdTimestamp>
96
                                     <lastModifiedTimestamp certainty="exact"</pre>
97
                                         >2006-05-04T18:13:51.0Z</lastModifiedTimestamp>
98
                                     <woodCompleteness>
99
                                         <pith presence="absent"/>
100
                                         <heartwood presence="incomplete"/>
101
102
                                         <sapwood presence="complete"/>
                                         <bark presence="present"/>
103
104
                                     </woodCompleteness>
                                     <measurementSeries>
105
                                         <title>C-TWT-65-A-B-A</title>
106
                                         <identifier domain="dendro.cornell.edu"</pre>
107
                                              >8c50234e-8eda-41bb-b578-01cc881d1ea1</identifier>
108
                                         <created\mathsf{Timestamp} certainty="exact"
109
                                              >1997-02-01T14:13:51.0Z</createdTimestamp>
110
111
                                         <lastModifiedTimestamp certainty="exact"</pre>
                                              > \!\! 1997 - 02 - 01\,T14 \colon\! 13 \colon\! 51 .0\,Z \!\! < \!\! /\, \mathsf{lastModifiedTimestamp} \!\! >
112
113
                                         <analyst>Laura Steele</analyst>
                                         <\! {\tt dendrochronologist} \!\!>\! {\tt Peter\ I\ Kuniholm} <\! /\, {\tt dendrochronologist} >
114
                                         <measuringMethod normalStd="Corina Dictionary" normalId="</pre>
115
                                              1"
                                              >Measuring platform</measuringMethod>
116
                                         <interpretation>
117
                                              <firstYear suffix="AD">1254</firstYear>
118
                                              <statFoundation>
119
                                                   <statValue>8.3</statValue>
120
                                                   <type>t-score</type>
121
                                                   <usedSoftware>Corina 2.10</usedSoftware>
122
123
                                              </statFoundation>
                                              <deathYear suffix="AD">1535</deathYear>
124
                                              cprovenance>Possibly from the region of Serres/
125
                                                   provenance>
                                         </interpretation>
                                         <values>
127
                                              <variable normalTridas="Ring width"/>
128
                                              <unit normalTridas="1/100th millimetres"/>
129
                                              <value value="54"/>
<value value="111"/>
130
131
                                              <value value="71"/>
132
                                              <value value="40"/>
                                              <value value="56"/>
134
                                         </values>
135
                                     </measurementSeries>
136
                                </radius>
137
                           </sample>
138
                      </element>
139
                  </object>
140
             </object>
141
        </project>
142
    </tridas>
143
```

Appendix R

TRIMS

Format name	TRIMS
Other name(s)	None known
Type	Text file
Extension(s)	.rw
Read/write support	Read and write
Reference implementation	
Data / metadata	Data only
Calendar type	Gregorian
Absolute dating support	Yes
Undated series support	Yes
Relative dating support	No
Multi series support	No
Original designer	Unknown

This is a simple data only text file format. These files were originally produced using the Henson rotary micrometer measuring stages but have largely been phased out.

- Line 1 Initials of user that created the series
- Line 2 Date the file was created in dd/MM/YY format
- Line 3 Year of first data value (0 treated as undated series)
- ullet Line 4+ Space character followed by an integer data value in $1/100 {
 m th}$ mm
- ullet Final line Space character + 999 denoting end of series.

R.1 Example file

Appendix S

Tucson

Format name Tucson

Other name(s) Decadal, RWL, CRN, ITRDB, Time series format, TSF

Type Text file

Extension(s) Various including tuc, rwl, dec, crn

Read/write support Read and write Reference implementation COFECHA

Data / metadata Data with some structured metadata, however, standardisa-

tion of metadata is very poor resulting in metadata often being

little more than free text comments

Calendar type Astronomical

Absolute dating support Yes
Undated series support No
Relative dating support No
Multi series support Yes

Original designer Richard Holmes

S.1 Description

The Tucson format is perhaps the most widely used dendro data format. Unfortunately it seems there was never definitive documentation. Support for the format has been incorporated into a number of dendro applications but without format documentation there are variations in these implementations resulting in quite a lot of subtle differences in files. The often tight association between the Dendro Program Library (DPL) and the ITRDB means that perhaps the most definitive documentation for the format is the ITRDB website.

The Tucson format is best considered as covering two different sub-formats which are often referred to by their file extensions (RWL and CRN). RWL files are used for storing ring-width data, whereas CRN files are used for storing chronologies.

The ITRDB website includes detailed information on how to include structured metadata in Tucson format files. Unfortunately there are no tools for creating and/or validating Tucson files so the vast majority of files circulating in the community today (including those in the ITRDB) do not adhere to these standards.

S.2 RWL files

Tucson RWL files begin with three lines of metadata. Strictly these lines should contain structured metadata, but with no software to assist in this, users either only partially stick to these rules, or reject them entirely instead using the three lines as free-text comment lines. The metadata should be set out as follows:

94 TUCSON

- Line 1 Chars 1-6 Site ID
- Line 1 Chars 10-61 Site Name
- Line 1 Chars 62-65 Species Code followed by optional ID number
- Line 2 Chars 1-6 Site ID
- Line 2 Chars 10-22 State/Country
- Line 2 Chars 23-30 Species
- Line 2 Chars 41-45 Elevation
- Line 2 Chars 48-57 Lat-Long in degrees and minutes, ddmm or dddmm
- Line 2 Chars 68-76 1st and last Year
- Line 3 Chars 1-6 Site ID
- Line 3 Chars 10-72 Lead Investigator
- Line 3 Chars 73-80 comp. date

Then follows the data lines which are set out as follows:

- Chars 1-8 Series ID the series ID should be unique in the file so that it is clear where one series ends and another begins when multiple series are present in the same file.
- Next 4 chars Year of first value in this row.
- Ten data values consisting of a space character and 5 integers. The file and last data line for a series may have less than 10 data values so that the majority of lines begin at the start of a decade.

The final data value should be followed by a a stop marker which is either 999 or -9999. When a stop marker of 999 is used this indicates that the integer values in the file are measured in 0.01mm (1/100th mm) units, whereas if a -9999 stop marker is used the units are 0.001mm (microns). The stop marker is therefore used to indicate the end of the data series and the units the data are stored in.

There appears to be no official specification as to how missing rings should be encoded, but the standard notation seems to be to use -999 or 0.

S.3 CRN files

Tucson CRN files are used to store chronology data. In addition to each data values they also have space for a sample depth or count value to record how many values were combined to give each data value. CRN files should strictly begin with the same 3 header lines that are described above for RWL. Like RWL files the specification is often partially adhered to and at times ignored completely.

The data lines for CRN files are quite different to RWL:

- Chars 1-6 Series ID
- Next 4 chars Year of first value in this row.
- Ten data value blocks consisting of four integer characters for the data value, then a space, then two integer characters for sample depth.

The stop marker in a CRN file should be 9990.

S.4 Workarounds and quirks

- No information was given as to how to handle the non-existent year 0AD/BC. For data files with years all in the AD period, this is not a problem. Most dendro software seem to treat year numbers in Tucson files as using the 'Astronomical Calendar' whereby 1=1AD, 0=1BC, -1=2BC etc. This goes against what most dendrochronologists assume (and do) when using Tucson files. For instance most people that work entirely in the BC period use negative integers to represent BC years e.g. -5 as 5BC. With no clear specification and different people interpreting the format in different ways, there is no way of being certain what data negative year numbers in Tucson files mean.
- Tucson format places a restriction of just four characters to the year values. This means that strictly
 the earliest value a Tucson file can represent is -999. Some users work around this by steeling the last
 character of the series ID to give them five characters for the year. For example: ABCDEFG-9999. This

TUCSON 95

conversely limits the series ID to 7 characters. To add to the confusion, other users have been known to add an arbitrary number (e.g. 5000) to all year numbers to overcome this problem.

- The fact that 999 is used as the stop marker for series in 1/100th mm means that Tucson files cannot store a ring value of 9.99mm. In the unlikely event that a sample should have this large a ring, it should be rounded up or down to 998 or 1000.
- Some programs appears to add padding values after the stop marker to fill the rest of the 10 data values
 in the row.
- Some data files seem to use 9990 as a stop marker
- Some files appears to use a full-stop character to indicate empty data values after the stop marker.
- Data values in RWL files are space delimited, however some programs use tabs instead.
- When reading Tucson files, COFECHA and ARSTAN ignore all lines that do not match the standard data line format. As such, some users have used this to enable them to include multiple comment lines in their files.
- The ITRDB documentation says they should be recorded as DDMM or DDDMM, but this along with sign (N,S,E,W,+ or -) would require 11 characters, when the Tucson specification only allows for 10. Perhaps this was due to an assumption that all places would be in the northern hemisphere? This has resulted in a large amount of variation in the way that coordinates are recorded making it extremely difficult to parse them without error. Here are some examples (including some that use 11 chars not 10):

- 4652N01101E - 4652-01101 - +4652-01101 - 465201101 - N4652E01101 - 4652 01101

S.5 Example file - raw series

1	107	1 OBER	GURGL										
2	107	2 AUST	RIA	NORV	VAY SPF	RUCE	672	26 465	52 N0110)1E	1911	1959	
3	107	3 GIERT	ΓZ								80	76	
4	107011	1911	78	93	43	100	93	110	135	115	102		
5	107011	1920	92	125	110	135	98	80	75	125	102	110	
6	107011	1930	105	105	95	120	135	140	110	120	130	135	
7	107011	1940	120	130	130	165	135	145	155	160	88	135	
8	107011	1950	140	150	140	130	115	130	130	110	110	135	
9	107011	1960	125	120	135	160	15	102	105	135	105	140	
10	107011	1970	120	115	100	110	110	999					
11	107012	1862	450	580	550	480	620	420	390	420			
12	107012	1870	360	370	300	360	470	460	410	430	510	500	
13	107012	1880	500	510	500	410	380	430	340	380	350	400	
14	107012	1890	290	260	270	320	340	370	330	310	240	170	
15	107012	1900	280	300	300	310	350	400	300	280	280	180	
16	107012	1910	190	290	270	210	230	300	220	360	240	260	
17	107012	1920	200	270	250	230	270	210	160	210	220	200	
18	107012	1930	170	250	200	130	140	210	210	180	190	180	
19	107012	1940	170	180	190	190	190	200	190	180	110	180	
20	107012	1950	220	230	180	220	200	240	220	210	240	999	

S.6 Example file - chronology

```
CDLI
  107089 1 Antalya, Elmali Isletmesi
  107089 2 Turkey
2
                           Cedar
                                              1800M 3640 02955
                                                                            1370 1988
  107089 3 Peter I.
                      Kuniholm
                                   11105
  1070001370 567
                   11115
                           1 798
                                           11407
                                                  1 398
                                                          1 436
                                                                  1 543
                                                                         1 490
                                                                                 1 225
  1070001380 127
                               29
                                           1 178
                                                  1 445
                                                          1 227
                                                                    510
                                                                         11020
                                                                                 11120
                    1 39
                           1
                                   1 69
                                                                  1
                                                                                         1
  10700013901390
                    11310
                           1 979
                                   11585
                                           11111
                                                   1 444
                                                          1 214
                                                                  1
                                                                    520
                                                                         1 275
  1070001400 153
                                                  1 687
                                                                  1 291
                    1 371
                           1 567
                                   1 711
                                           1 835
                                                          1 322
                                                                           291
                                                                                   218
                                                                         1
                                                                                 1
                                                                                         1
   1070001410
              168
                    1
                      378
                           1
                              557
                                   1
                                     410
                                           1
                                             315
                                                   1
                                                     202
                                                          1
                                                            531
                                                                    765
                                                                            797
                                                                                         1
                    1 774
                           1 946
                                           1 397
                                                  1 380
                                                                  1 510
  1070001420 440
                                   1 838
                                                          1
                                                            206
                                                                         1 695
                                                                                 1 521
                                                                                         1
  1070001430 461
                    1 978
                           1 967
                                   1 857
                                           1 978
                                                  1 733
                                                          1 522
                                                                  1 333
                                                                         1 577
                                                                                 1 477
                                                                                         1
  1070001440 730
                   1 752
                           1 932
                                   1 955
                                          1 898
                                                  1 629
                                                          11170
                                                                  1 738
                                                                         1 920
```

96 TUCSON

	1070001450 063	1 000	1 005	1 200	1 170	1 100	1 (0	1 000	1 212	1 000	1
12	1070001450 863	1 896	1 965	1 390	1 172	1 126	1 69	1 209	1 313	1 883	1
13	10700014601255	11220	11364	11035	11364	11282	11364	11611	11369	11273	1
14	10700014701797	12035	11821	11927	11819	11807	11464	21421	21009	21089	2
15	10700014801042	21040	21404	2 955	21291	2 982	21186	21042	2 728	2 781	2
16	1070001490 800	21040	2 503	2 869	21387	21365	21574	21591	22178	21594	3
17	10700015001629	31282	31126	31409	31433	31406	31239	31479	3 990	31063	3
18	10700015101026	31035	31175	31217	31500	31358	31171	31140	31005	31340	3
19	10700015201225	31164	31283	31496	31439	31603	31335	3 982	3 973	31147	3
20	10700015301086	31146	41403	41454	41209	41451	41292	4 964	41003	41289	4
21	1070001540 895	4 951	4 745	4 835	4 800	41182	4 952	41097	4 973	4 973	4
22	10700015501158	41370	41245	41392	41215	41047	51133	5 847	5 961	51295	5
23	10700015601287	51082	5 899	51012	51195	51409	51107	5 962	5 970	51031	5
24	1070001570 990	51028	51206	51092	51414	51209	51090	51265	51261	51019	5
	1070001570 990	5 995	5 956	5 933	61144	61022	61001	61007	61097	61290	6
25	1070001500 791	6 902	71002	71151	71032	8 968	8 592	8 940	8 936	81131	8
26	10700013901203	81128	81334	81255	91136		101273				
27											
28	1070001610 915										10
29	10700016201173										
30	10700016301123										10
31	10700016401093										
32	10700016501030										
33	1070001660 917										
34	1070001670 750										
35	1070001680 797	12 940	12 955	12 886	12 878	12 970	12 916	12 861	12 861	121021	13
36	1070001690 928	13 961	131043	13 936	13 939	131003	13 619	13 846	13 838	13 822	13
37	1070001700 717	13 699	14 746	14 900	141022	14 781	14 968	141028	141051	141341	14
38	1070001710 980	14 817	14 718	14 642	14 554	14 589	14 637	14 677	16 710	16 877	16
39	1070001720 930	16 931	16 718	16 721	16 616	16 576	16 519	16 790	161046	161067	16
40	10700017301047	171141	181080	181128	181144	181112	191066	191252	19 971	191076	19
41	10700017401284	191242	191001	191145	191219	191162	19 576	20 979	231148	231062	23
42	10700017501119										
43	10700017601118										
44	10700017701072										
45	10700017801098										
46	10700017001030										
47	1070001730 374										
48	10700018101068										
	1070001810188										
49	1070001820 839										
50	1070001830 920										
51	1070001840 097										
52	1070001850 819										
53											
54	1070001870 822										
55	10700018801021										
56	1070001890 798										
57	1070001900 977										
58	10700019101167										
59	10700019201387										
60	10700019301235										
61	10700019401537										
62	10700019501384										
63	10700019601547										
64	1070001970 963										19
65	10700019801034	19 870	191186	191047	19 968	191089	191272	191231	191083	189990	0

Appendix T

Tucson Compact

Format name Tucson Compact

Other name(s)

Type

Extension(s)

Compact

Text file

rwm

Read/write support Read and write

Reference implementation Various DPL programs including FMT

Data / metadata Data only
Calendar type Astronomical

Absolute dating support
Undated series support
Relative dating support
Multi series support
Yes

Original designer Richard Holmes

T.1 Description

The Tucson Compact format was design by Richard Holmes for use with a number of the applications in the Dendro Program Library (DPL). Holmes designed it as a space saving alternative to the standard Tucson format at a time when disk space was expensive. The format never really caught on, perhaps due to the complexity and variability of the format.

The key feature of Tucson Compact format is the inclusion of a code that describes the layout of the data within the series. This code means that only the required amount of space is allocated to each data value in the text file with little wastage. No space is provided for metadata.

Tucson Compact files can contain one or more series of data so the description of a data series below can be repeated multiple times in a single file. All lines should be 80 characters long and the first line of a series is denoted by a tilde () in the final column. This meta line contains four fields:

- Chars 0-9 = number of data values terminated with =N
- Chars 11-19 = start year terminated with =I
- Chars 21-68 = series title
- Chars 69-79 = fortran format descriptor
- Char 80 = Tilde marker

The Fortran format descriptor in the example below is -2(26F3.0). The constituent parts are as follows:

• -2 = this is the scaling factor for the data values. In this case -2 = 10-2 = 0.01. Please note that in the Convert5 program this scaling factor is only read once in the first header line so files with multiple series each with different scaling factors will read incorrectly.

- 26F = means there are 26 values in each line
- 3.0 = means that each data value should be read as 3 integer values

The example below therefore means there are 26 data values per line each consisting of 3 digits which should be interpreted by multiplying by 0.01 (i.e. values are in 1/10ths mm).

T.2 Example file

Appendix U

VFormat

Format name VFormat
Other name(s) OJ Format
Type Text file

Extension(s) Various depending on data type but commonly .!oj

Read/write support Read and write

Reference implementation VFormat

Data / metadata Data with some structure metadata

Calendar type Gregorian
Absolute dating support Yes
Undated series support No
Relative dating support No
Multi series support Yes

Original designer Thomas Reimer and Hans-Hubert Leuschner

U.1 Description

A relatively extensive format which includes highly encoded header lines for metadata. VFormat files have an array of file extensions depending on the type of data the files contain.

VFormat files can contain mutliple data series. Each series contains 2-4 header lines followed by a number of data lines. The metadata fields are encoded into the header lines in specific character positions. In line 1 the character positions are as follows:

- 1-12 = Series identifier. The series identifier also determines the filename. If there is just one series in the file then the series identifier will be the same as the filename. For files with multiple series, the filename will use characters 1-7 of the series identifiers that are the same throughout the file with the remaining (different) characters replaced by an underscore. The 8th character of the filename would contain a running number for files that would otherwise be named the same. The series identifier is made up of the following characters:
 - -1 = Code representing the project or country
 - 2 = Code representing the region of ecological area
 - 3-4 = Code number for sample site (optionally encoded using hexadecimal or hexatresimal to enable values greater than 99).
 - -5-6 = Series/tree number (optionally encoded using hexadecimal or hexatresimal to enable values greater than 99).
 - 7 = Height code encoded as follows: 1 = 1m, 2=2m, 9=9m, A=10m, B=11m, S = Lumber height 30cm, T = breast height =130cm.
 - -8 = Running number if several series have the same values in columns 1-7.

100 VFORMAT

- -9 = Fixed as a dot character
- 10 = Either ! (single), % (partial), # (mean curves or chronologies)
- 11 = Code for statistical treatment. One of F (frequency filtered series); I (index); M (mean); O (original); P (pointer-year stat); Q (cluster-pointer-year stat); R (residual); S (moving deviation or variance); T (trend, fitted curve, model); W (wuchswert); X (series with standardized running mean and variance); Z (central moment, deviation or variance between several series).
- 12 = Code for the measured parameter. One of D (mean density); F (earlywood width); G (maximum density); J (ring width); K (minimum density); P (percentage latewood); S (width of latewood).
- 13-15 Measurement units
- 16-20 Length of series
- 21-24 Species either encoded using ITRDB taxon codes or by using the first two letters of the genus and species.
- 25-30 Year of the last ring
- 31-50 Description
- 51-58 Measurement date (ddMMyy or ddMMyyyy)
- 59-60 Initials of author
- 61-68 Last modified date (ddMMyy or ddMMyyyy)
- 69-70 VFormat version identifier (00,01 etc)
- 71-73 Estimated number of missing rings as the start of the series
- 74-75 Standard error of this estimate (. if unknown)
- 76-78 Estimated number of missing rings at the end of the series
- 79-80 Standard error of this estimate (. if unknown)

The second data line is a free text comment up to 80 characters.

VFormat files from version 10 onwards then contain a third header line. This contains 8 floating point numbers of 10 digits each. These represent:

- Longitude
- Latitude
- Altitude
- Height of the tree's measurement
- Four other user definable numbers

VFormat files from version 20 onwards contain a forth header line. This is of the same format as line 3 but each of the values is user definable.

Following the 2-4 header lines come the data lines. These lines are made up of 10 data fields each containing 8 characters. Each data field is made up as follows:

- Two character code for validity and importance:
 - space = full validity
 - -! = not yet used
 - " = not yet used
 - # = not yet used
 - \$ = no validity for long-term evaluations
 - -% = no validity for single-value evaluations
 - &= no validity except for cumulative stats
 - ' = no validity at all, unknown value

The second character is a pseudo-binary character used to define a weighting factor. For full details of the complex method for calculating this weighting factor see the VFormat documentation.

- One character user definable code for recording information about the data value
- Five digit floating point data value which is divided by 100 for interpretation

U.2 Example file

VFORMAT 101

1	C1101020	I O Imm	91 Ouen	1510FLA-02	3.2	/572		HL01.04.9	2002 810	0 10 .	
2	G1101020				32	/312		11201.04.5	9002 010	J 10 .	
3	281	221	225	169	178	197	126	103	112	130	
4	132	207	176	175	126	150	99	131	187	204	
5	218	172		115	135	130	196	135	142	129	
5	144	116		71	109	120	137	98	86	117	
-	64	79		61	62	82	75	96 81	83	69	
7	83	66		95	85	94	87	99	92	109	
8	150	108		113	119	120	122	107	111	114	
9											
10	123	145	112	145	164	158	122	177	155	182	
11	153	101	1010	1516514 05	10	/506		111.01.04.6	2000 1510	1 1 2	
12				1516FLA-05	13	/580		HL01.04.9	9002 1510	J 13 .	
13	G1101050				246	271	7.45	710	500	466	
14	448	286	341	213	346	371	745	719	580	466	
15	487	353		323	422	436	351	238	135	172	
16	179	210		145	165	261	263	190	194	183	
17	127	110		189	135	154	217	110	115	99	
18	106	101		198	191	185	185	160	112	152	
19	93	95		176	165	193	139	101	93	113	
20	85	145	174	157	132	130	74	52	114	138	
21	174	132	144	125	83	124	118	127	150	189	
22	152	133	117	91	104	96	56	90	130	126	
23	103	163	92	103	174	99	117	85	123	116	
24	147	127	145	133	155	144	114	115	121	111	
25	174	113	112	89	99	130	111	104	164	110	
26	139										

Appendix V

WinDENDRO

Format name WinDENDRO

Other name(s)

Type Text file
Extension(s) txt
Read/write support Reference implementation WinDENDRO

Data / metadata Data with some structured metadata

Calendar type Gregorian
Absolute dating support Yes
Undated series support Yes
Relative dating support No
Multi series support Yes

Original designer Regent Instruments

V.1 Description

WinDENDRO format is a dendro text file format designed by Regent Instruments for their WinDENDRO software. Regent Instruments claims the format is proprietary. Although it is unclear whether such a claim is legally binding for a plain text file, the authors of DendroFilelOLib have decided to comply by not implementing a WinDENDRO format writer. However, in the interests of the dendro community and to ensure users can gain access to their data, DendroFilelOLib does include support for reading WinDENDRO format files.

WinDENDRO files differ from most other formats in that they contain a great deal of information specific to the image used to measure the sample. The WinDENDRO software allows users to measure ring widths from scans or photographs of samples rather than by using a traditional measuring platform.

WinDENDRO files are really just tab-delimited text files with data in columns in a specific order with a few additional header lines.

Line 1 should contain 8 tab-delimited fields

- Field 1 = WINDENDRO
- Field 2 = WinDENDRO file format version number, either 3 or 4
- Field 3 = Orientation of the data: R = in rows; C = in columns. All WinDENDRO files are in rows
- Field 4 = The column number where the data values begin. For version 3 files this is 13 and version 4 files this is 36
- Field 5 = The direction the data is recording in: P = pith to bark; B = bark to pith
- Field 6 = Whether the data is recorded incrementally (I) or cumulatively (C). WinDENDRO files are always incremental.

104 WINDENDRO

- Field 7 = Whether the bark width has been measured (Y or N). If yes, then there will be one more data value than there are rings
- Field 8 = RING

Line 2 contains the field names. For version 3 files these are:

- TreeName The name of the tree being measured
- Path identification ID of the path along which the series is measured
- Site identification Name of the site from which the tree was taken
- YearLastRing Year of the last ring in the series
- Sapwood Distance (in mm) from the start of the sample to the start of the sapwood.
- Tree height Height of tree in metres
- Tree age Age of the tree. If unknown this should be 0, then it is assumed to be equal to the number of rings
- SectionHeight Height up the tree in metres at which the sample was taken
- User variable User defined variable must be numerical
- RingCount Number of rings the series contains
- DataType Keyword indicating the type of data measured. This can be: RINGWIDTH; EARLYWIDTH; LATEWIDTH; EARLYWIDTH%; LATEWIDTH%; DENSITY; EARLYDENSITY; LATEDENSITY; MAXDENSITY; MINDENSITY; RINGANGLE.
- OffsetToNext The number of lines to skip to go to the next data line of the same type. For instance a file can contain earlywood and latewood data for multiple samples. If this is the case then each sample will have two rows, one for each variable, and the OffsetToNext field will be 1.

In additional to these fields, version 4 files also include the following:

- ImageName The filename for the image used to do this analysis. If the image was taken directly from the scanner or camera then this field will be SCANNER
- Analysis Date Time Date and time the measurements were initially saved to disk in format dd/m-m/YYYY HH:mm
- Acquisition Date Time Date and time the image file was acquired in format dd/mm/YYYY HH:mm
- Modified Date Time Date and time the file was last modified in format dd/mm/YYYY HH:mm
- ImageSize H V NBits Channel The image size in pixels followed by bits per pixel per channel (8 or 16), channel used for analysis (Grey, RGB, R G or B)
- CalibMethod XCal YCal EditedDendro Method of calibration: Intr (Intrinsic); Obj (ObjKnownDiam).
 This is followed by the size of a pixel and Y or N indicating if the image has been edited in WinDENDRO
- ScannerCamera Make Model Software Details about the imaging hardware
- LensFocLength [35mm] The 35mm equivalent focal length of the imaging lens
- PathBegX BegY EndX EndY Width The coordinates for the start of the path/radius followed by the path width
- RingBoundary AutoMan Meth Precise Details about the path taken. Ring boundary Tg (tangent to ring) or Perp (perpendicular to path); Detection method A (automatic) or M (manual); Ring detection method Int (intensity differences) or T&S (teach and show); whether the 'more precise detection' method is active (Y) or not (N)
- EarlywoodDef Earlywood-latewood transition criteria
- DensActive Media Calib Density Analysis active (Y or N); Density Media setting (F negative file or photo, W wood direct xray, positive film or photo); Light calibration setting (Acq - after image acquisition, Man - manual; No - none)
- DensNSteps MatDens Interpol Number of steps and the density of the step wedge used for calibration followed by the interpolation method used between steps: Lin (Linear) Spl (Spline)
- DensStepsThick The thickness of each step of the wedge used for density calibration
- DensStepsLightInt The light intensity of each step of the wedge determined during the light intensity calibration
- DensStepsWoodDens Equivalent wood density of each step of the wedge determined during light intensity calibration
- DiskArea Area of the sample
- DiskPerim Perimeter of the sample
- DiskAvgDiam Average diameter of the sample

WINDENDRO 105

- DiskFormCoef Sample area form coefficient
- CompWoodArea Total area occupied by the compression areas
- VoidArea Total area occupied by the void areas
- PathLength Length of radius measured

Lines 3+ contain the actual data and metadata, one line for each series. Following the 13 or 36 columns of metadata (depending on file version) there are x number of columns containing ring values. The values are recorded as floating point data. The units for these data values are: mm for widths; % for percentages; g/cm^3 for densities; radians for angles.

Appendix W

License

The Corina server and desktop client are released under the GNU General Public License (GPL) version 3.

Copyright © 2011 Peter Brewer

This program is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

W.1 Terms and Conditions

0. Definitions.

"This License" refers to version 3 of the GNU General Public License.

"Copyright" also means copyright-like laws that apply to other kinds of works, such as semiconductor masks.

"The Program" refers to any copyrightable work licensed under this License. Each licensee is addressed as "you". "Licensees" and "recipients" may be individuals or organizations.

To "modify" a work means to copy from or adapt all or part of the work in a fashion requiring copyright permission, other than the making of an exact copy. The resulting work is called a "modified version" of the earlier work or a work "based on" the earlier work.

A "covered work" means either the unmodified Program or a work based on the Program.

To "propagate" a work means to do anything with it that, without permission, would make you directly or secondarily liable for infringement under applicable copyright law, except executing it on a computer or modifying a private copy. Propagation includes copying, distribution (with or without modification), making available to the public, and in some countries other activities as well.

To "convey" a work means any kind of propagation that enables other parties to make or receive copies. Mere interaction with a user through a computer network, with no transfer of a copy, is not conveying.

An interactive user interface displays "Appropriate Legal Notices" to the extent that it includes a convenient and prominently visible feature that (1) displays an appropriate copyright notice, and (2) tells the user that there is no warranty for the work (except to the extent that warranties are provided), that licensees may convey the work under this License, and how to view a copy of this License. If the interface presents a list of user commands or options, such as a menu, a prominent item in the list meets this criterion.

1. Source Code.

The "source code" for a work means the preferred form of the work for making modifications to it. "Object code" means any non-source form of a work.

A "Standard Interface" means an interface that either is an official standard defined by a recognized standards body, or, in the case of interfaces specified for a particular programming language, one that is widely used among developers working in that language.

The "System Libraries" of an executable work include anything, other than the work as a whole, that (a) is included in the normal form of packaging a Major Component, but which is not part of that Major Component, and (b) serves only to enable use of the work with that Major Component, or to implement a Standard Interface for which an implementation is available to the public in source code form. A "Major Component", in this context, means a major essential component

(kernel, window system, and so on) of the specific operating system (if any) on which the executable work runs, or a compiler used to produce the work, or an object code interpreter used to run it.

The "Corresponding Source" for a work in object code form means all the source code needed to generate, install, and (for an executable work) run the object code and to modify the work, including scripts to control those activities. However, it does not include the work's System Libraries, or general-purpose tools or generally available free programs which are used unmodified in performing those activities but which are not part of the work. For example, Corresponding Source includes interface definition files associated with source files for the work, and the source code for shared libraries and dynamically linked subprograms that the work is specifically designed to require, such as by intimate data communication or control flow between those subprograms and other parts of the work.

The Corresponding Source need not include anything that users can regenerate automatically from other parts of the Corresponding Source.

The Corresponding Source for a work in source code form is that same work.

2. Basic Permissions.

All rights granted under this License are granted for the term of copyright on the Program, and are irrevocable provided the stated conditions are met. This License explicitly affirms your unlimited permission to run the unmodified Program. The output from running a covered work is covered by this License only if the output, given its content, constitutes a covered work. This License acknowledges your rights of fair use or other equivalent, as provided by copyright law.

You may make, run and propagate covered works that you do not convey, without conditions so long as your license otherwise remains in force. You may convey covered works to others for the sole purpose of having them make modifications exclusively for you, or provide you with facilities for running those works, provided that you comply with the terms of this License in conveying all material for which you do not control copyright. Those thus making or running the covered works for you must do so exclusively on your behalf, under your direction and control, on terms that prohibit them from making any copies of your copyrighted material outside their relationship with you.

Conveying under any other circumstances is permitted solely under the conditions stated below. Sublicensing is not allowed; section 10 makes it unnecessary.

3. Protecting Users' Legal Rights From Anti-Circumvention Law.

No covered work shall be deemed part of an effective technological measure under any applicable law fulfilling obligations under article 11 of the WIPO copyright treaty adopted on 20 December 1996, or similar laws prohibiting or restricting circumvention of such measures.

When you convey a covered work, you waive any legal power to forbid circumvention of technological measures to the extent such circumvention is effected by exercising rights under this License with respect to the covered work, and you disclaim any intention to limit operation or modification of the work as a means of enforcing, against the work's users, your or third parties' legal rights to forbid circumvention of technological measures.

4. Conveying Verbatim Copies.

You may convey verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice; keep intact all notices stating that this License and any non-permissive terms added in accord with section 7 apply to the code; keep intact all notices of the absence of any warranty; and give all recipients a copy of this License along with the Program.

You may charge any price or no price for each copy that you convey, and you may offer support or warranty protection for a fee.

5. Conveying Modified Source Versions.

You may convey a work based on the Program, or the modifications to produce it from the Program, in the form of source code under the terms of section 4, provided that you also meet all of these conditions:

- (a) The work must carry prominent notices stating that you modified it, and giving a relevant date.
- (b) The work must carry prominent notices stating that it is released under this License and any conditions added under section 7. This requirement modifies the requirement in section 4 to "keep intact all notices".
- (c) You must license the entire work, as a whole, under this License to anyone who comes into possession of a copy. This License will therefore apply, along with any applicable section 7 additional terms, to the whole of the work, and all its parts, regardless of how they are packaged. This License gives no permission to license the work in any other way, but it does not invalidate such permission if you have separately received it.
- (d) If the work has interactive user interfaces, each must display Appropriate Legal Notices; however, if the Program has interactive interfaces that do not display Appropriate Legal Notices, your work need not make them do so.

A compilation of a covered work with other separate and independent works, which are not by their nature extensions of the covered work, and which are not combined with it such as to form a larger program, in or on a volume of a storage or distribution medium, is called an "aggregate" if the compilation and its resulting copyright are not used to limit the access or legal rights of the compilation's users beyond what the individual works permit. Inclusion of a covered work in an aggregate does not cause this License to apply to the other parts of the aggregate.

6. Conveying Non-Source Forms.

You may convey a covered work in object code form under the terms of sections 4 and 5, provided that you also convey the machine-readable Corresponding Source under the terms of this License, in one of these ways:

- (a) Convey the object code in, or embodied in, a physical product (including a physical distribution medium), accompanied by the Corresponding Source fixed on a durable physical medium customarily used for software interchange.
- (b) Convey the object code in, or embodied in, a physical product (including a physical distribution medium), accompanied by a written offer, valid for at least three years and valid for as long as you offer spare parts or customer support for that product model, to give anyone who possesses the object code either (1) a copy of the Corresponding Source for all the software in the product that is covered by this License, on a durable physical medium customarily used for

software interchange, for a price no more than your reasonable cost of physically performing this conveying of source, or (2) access to copy the Corresponding Source from a network server at no charge.

- (c) Convey individual copies of the object code with a copy of the written offer to provide the Corresponding Source. This alternative is allowed only occasionally and noncommercially, and only if you received the object code with such an offer, in accord with subsection 6b.
- (d) Convey the object code by offering access from a designated place (gratis or for a charge), and offer equivalent access to the Corresponding Source in the same way through the same place at no further charge. You need not require recipients to copy the Corresponding Source along with the object code. If the place to copy the object code is a network server, the Corresponding Source may be on a different server (operated by you or a third party) that supports equivalent copying facilities, provided you maintain clear directions next to the object code saying where to find the Corresponding Source. Regardless of what server hosts the Corresponding Source, you remain obligated to ensure that it is available for as long as needed to satisfy these requirements.
- (e) Convey the object code using peer-to-peer transmission, provided you inform other peers where the object code and Corresponding Source of the work are being offered to the general public at no charge under subsection 6d.

A separable portion of the object code, whose source code is excluded from the Corresponding Source as a System Library, need not be included in conveying the object code work.

A "User Product" is either (1) a "consumer product", which means any tangible personal property which is normally used for personal, family, or household purposes, or (2) anything designed or sold for incorporation into a dwelling. In determining whether a product is a consumer product, doubtful cases shall be resolved in favor of coverage. For a particular product received by a particular user, "normally used" refers to a typical or common use of that class of product, regardless of the status of the particular user or of the way in which the particular user actually uses, or expects or is expected to use, the product. A product is a consumer product regardless of whether the product has substantial commercial, industrial or non-consumer uses, unless such uses represent the only significant mode of use of the product.

"Installation Information" for a User Product means any methods, procedures, authorization keys, or other information required to install and execute modified versions of a covered work in that User Product from a modified version of its Corresponding Source. The information must suffice to ensure that the continued functioning of the modified object code is in no case prevented or interfered with solely because modification has been made.

If you convey an object code work under this section in, or with, or specifically for use in, a User Product, and the conveying occurs as part of a transaction in which the right of possession and use of the User Product is transferred to the recipient in perpetuity or for a fixed term (regardless of how the transaction is characterized), the Corresponding Source conveyed under this section must be accompanied by the Installation Information. But this requirement does not apply if neither you nor any third party retains the ability to install modified object code on the User Product (for example, the work has been installed in ROM).

The requirement to provide Installation Information does not include a requirement to continue to provide support service, warranty, or updates for a work that has been modified or installed by the recipient, or for the User Product in which it has been modified or installed. Access to a network may be denied when the modification itself materially and adversely affects the operation of the network or violates the rules and protocols for communication across the network.

Corresponding Source conveyed, and Installation Information provided, in accord with this section must be in a format that is publicly documented (and with an implementation available to the public in source code form), and must require no special password or key for unpacking, reading or copying.

7. Additional Terms.

"Additional permissions" are terms that supplement the terms of this License by making exceptions from one or more of its conditions. Additional permissions that are applicable to the entire Program shall be treated as though they were included in this License, to the extent that they are valid under applicable law. If additional permissions apply only to part of the Program, that part may be used separately under those permissions, but the entire Program remains governed by this License without regard to the additional permissions.

When you convey a copy of a covered work, you may at your option remove any additional permissions from that copy, or from any part of it. (Additional permissions may be written to require their own removal in certain cases when you modify the work.) You may place additional permissions on material, added by you to a covered work, for which you have or can give appropriate copyright permission.

Notwithstanding any other provision of this License, for material you add to a covered work, you may (if authorized by the copyright holders of that material) supplement the terms of this License with terms:

- (a) Disclaiming warranty or limiting liability differently from the terms of sections 15 and 16 of this License; or
- (b) Requiring preservation of specified reasonable legal notices or author attributions in that material or in the Appropriate Legal Notices displayed by works containing it; or
- (c) Prohibiting misrepresentation of the origin of that material, or requiring that modified versions of such material be marked in reasonable ways as different from the original version; or
- (d) Limiting the use for publicity purposes of names of licensors or authors of the material; or
- (e) Declining to grant rights under trademark law for use of some trade names, trademarks, or service marks; or
- (f) Requiring indemnification of licensors and authors of that material by anyone who conveys the material (or modified versions of it) with contractual assumptions of liability to the recipient, for any liability that these contractual assumptions directly impose on those licensors and authors.

All other non-permissive additional terms are considered "further restrictions" within the meaning of section 10. If the Program as you received it, or any part of it, contains a notice stating that it is governed by this License along with a term that is a further restriction, you may remove that term. If a license document contains a further restriction but permits relicensing or conveying under this License, you may add to a covered work material governed by the terms of that license document, provided that the further restriction does not survive such relicensing or conveying.

If you add terms to a covered work in accord with this section, you must place, in the relevant source files, a statement of the additional terms that apply to those files, or a notice indicating where to find the applicable terms.

Additional terms, permissive or non-permissive, may be stated in the form of a separately written license, or stated as exceptions; the above requirements apply either way.

8. Termination.

You may not propagate or modify a covered work except as expressly provided under this License. Any attempt otherwise to propagate or modify it is void, and will automatically terminate your rights under this License (including any patent licenses granted under the third paragraph of section 11).

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, you do not qualify to receive new licenses for the same material under section 10.

9. Acceptance Not Required for Having Copies.

You are not required to accept this License in order to receive or run a copy of the Program. Ancillary propagation of a covered work occurring solely as a consequence of using peer-to-peer transmission to receive a copy likewise does not require acceptance. However, nothing other than this License grants you permission to propagate or modify any covered work. These actions infringe copyright if you do not accept this License. Therefore, by modifying or propagating a covered work, you indicate your acceptance of this License to do so.

10. Automatic Licensing of Downstream Recipients.

Each time you convey a covered work, the recipient automatically receives a license from the original licensors, to run, modify and propagate that work, subject to this License. You are not responsible for enforcing compliance by third parties with this License.

An "entity transaction" is a transaction transferring control of an organization, or substantially all assets of one, or subdividing an organization, or merging organizations. If propagation of a covered work results from an entity transaction, each party to that transaction who receives a copy of the work also receives whatever licenses to the work the party's predecessor in interest had or could give under the previous paragraph, plus a right to possession of the Corresponding Source of the work from the predecessor in interest, if the predecessor has it or can get it with reasonable efforts.

You may not impose any further restrictions on the exercise of the rights granted or affirmed under this License. For example, you may not impose a license fee, royalty, or other charge for exercise of rights granted under this License, and you may not initiate litigation (including a cross-claim or counterclaim in a lawsuit) alleging that any patent claim is infringed by making, using, selling, offering for sale, or importing the Program or any portion of it.

11. Patents

A "contributor" is a copyright holder who authorizes use under this License of the Program or a work on which the Program is based. The work thus licensed is called the contributor's "contributor version".

A contributor's "essential patent claims" are all patent claims owned or controlled by the contributor, whether already acquired or hereafter acquired, that would be infringed by some manner, permitted by this License, of making, using, or selling its contributor version, but do not include claims that would be infringed only as a consequence of further modification of the contributor version. For purposes of this definition, "control" includes the right to grant patent sublicenses in a manner consistent with the requirements of this License.

Each contributor grants you a non-exclusive, worldwide, royalty-free patent license under the contributor's essential patent claims, to make, use, sell, offer for sale, import and otherwise run, modify and propagate the contents of its contributor version.

In the following three paragraphs, a "patent license" is any express agreement or commitment, however denominated, not to enforce a patent (such as an express permission to practice a patent or covenant not to sue for patent infringement). To "grant" such a patent license to a party means to make such an agreement or commitment not to enforce a patent against the party.

If you convey a covered work, knowingly relying on a patent license, and the Corresponding Source of the work is not available for anyone to copy, free of charge and under the terms of this License, through a publicly available network server or other readily accessible means, then you must either (1) cause the Corresponding Source to be so available, or (2) arrange to deprive yourself of the benefit of the patent license for this particular work, or (3) arrange, in a manner consistent with the requirements of this License, to extend the patent license to downstream recipients. "Knowingly relying" means you have actual knowledge that, but for the patent license, your conveying the covered work in a country, or your recipient's use of the covered work in a country, would infringe one or more identifiable patents in that country that you have reason to believe are valid.

If, pursuant to or in connection with a single transaction or arrangement, you convey, or propagate by procuring conveyance of, a covered work, and grant a patent license to some of the parties receiving the covered work authorizing them to use, propagate, modify or convey a specific copy of the covered work, then the patent license you grant is automatically extended to all recipients of the covered work and works based on it.

A patent license is "discriminatory" if it does not include within the scope of its coverage, prohibits the exercise of, or is conditioned on the non-exercise of one or more of the rights that are specifically granted under this License. You may not convey a covered work if you are a party to an arrangement with a third party that is in the business of distributing software, under which you make payment to the third party based on the extent of your activity of conveying the work, and

under which the third party grants, to any of the parties who would receive the covered work from you, a discriminatory patent license (a) in connection with copies of the covered work conveyed by you (or copies made from those copies), or (b) primarily for and in connection with specific products or compilations that contain the covered work, unless you entered into that arrangement, or that patent license was granted, prior to 28 March 2007.

Nothing in this License shall be construed as excluding or limiting any implied license or other defenses to infringement that may otherwise be available to you under applicable patent law.

12. No Surrender of Others' Freedom.

If conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot convey a covered work so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not convey it at all. For example, if you agree to terms that obligate you to collect a royalty for further conveying from those to whom you convey the Program, the only way you could satisfy both those terms and this License would be to refrain entirely from conveying the Program.

13. Use with the GNU Affero General Public License.

Notwithstanding any other provision of this License, you have permission to link or combine any covered work with a work licensed under version 3 of the GNU Affero General Public License into a single combined work, and to convey the resulting work. The terms of this License will continue to apply to the part which is the covered work, but the special requirements of the GNU Affero General Public License, section 13, concerning interaction through a network will apply to the combination as such.

14. Revised Versions of this License.

The Free Software Foundation may publish revised and/or new versions of the GNU General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies that a certain numbered version of the GNU General Public License "or any later version" applies to it, you have the option of following the terms and conditions either of that numbered version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of the GNU General Public License, you may choose any version ever published by the Free Software Foundation.

If the Program specifies that a proxy can decide which future versions of the GNU General Public License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Program.

Later license versions may give you additional or different permissions. However, no additional obligations are imposed on any author or copyright holder as a result of your choosing to follow a later version.

15. Disclaimer of Warranty.

THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. Limitation of Liability.

IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MODIFIES AND/OR CONVEYS THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

17. Interpretation of Sections 15 and 16.

If the disclaimer of warranty and limitation of liability provided above cannot be given local legal effect according to their terms, reviewing courts shall apply local law that most closely approximates an absolute waiver of all civil liability in connection with the Program, unless a warranty or assumption of liability accompanies a copy of the Program in return for a fee.

References

Aniol, R., 1983. Tree-ring analysis using CATRAS. Dendrochronologia 1, 45-53.

Brewer, P., Sturgeon, K., Madar, L., Manning, S., 2010. A new approach to dendrochronological data management. Dendrochronologia 28, 131–134.

Cook, E., Peters, K., 1981. The smoothing spline: A new approach to standardizing forest interior tree-ring width series for dendroclimatic studies. Tree-Ring Bulletin 41, 45–53.

Cormen, T., Leiserson, C., RL, R., C, S., 2001. Introduction to Algorithms. The MIT Press.

Jansma, E., Brewer, P., Zandhuis, I., 2010. TRiDaS 1.1: The tree-ring data standard. Dendrochronologia 28, 99–130.

Knibbe, B., 2008. PAST4 - Personal Analysis System for Treering Research software version 4.5. SCIEM.

Reinsch, C., 1967. Smoothing by spline functions. Numerische Mathematik 10, 177–183.

Rinn, F., 2008. TSAP-Win software. Rinntech, Heidelberg.

Tyers, I., 1999. Dendro For Windows program guide. ARCUS Report 500.

Van Loan, C., 1999. Introduction to Scientific Computing: A Matrix-Vector Approach Using MATLAB. Prentice Hall.

Index

Mapping, 6, 17