

A.4.21 SMS/CBS 7-bit Sinhala Alphabet (0x21)

A.4.21.1 SMS/CBS 7-bit Sinhala Alphabet (0x21) base table

					b7	0	0	0	0	1	1	1	1
					b6	0	0	1	1	0	0	1	1
					b5	0	1	0	1	0	1	0	1
b4	b3	b2	b1			0	1	2	3	4	5	6	7
0	0	0	0	0	ඊ	0D81	එළු	SP	0	බ	0DCF		p
0	0	0	1	1	උ	0D82		ක	1	භ	0DD2	a	q
0	0	1	0	2	ඌ	0D83	ඔ	ච	2	ම	0DD3	b	r
0	0	1	1	3	ඍ	0D85	ඔ	#	3	ය	0DD4	c	s
0	1	0	0	4	ඎ	0D86	ඔ	ඵ	4	ර	0DD6	d	t
0	1	0	1	5	ඏ	0D89	ක	ඨ	5		0DD8	e	u
0	1	1	0	6	ඐ	0D8A	බ	ද	6	ල	0DDF	f	v
0	1	1	1	7	එ	0D8B	ග	ඞ	7	ළ		g	w
1	0	0	0	8	ඒ	0D8C	ඝ	ඪ	8		0DD9	h	x
1	0	0	1	9	උ	0D8D	ඞ	ඹ	9	ච	0DDA	i	y
1	0	1	0	A	LF	000A	ච	*	:	ඪ	0DDB	j	z
1	0	1	1	B	ඔ	0D8F	SS2	+	;	ඪ		k	ඇ
1	1	0	0	C		0DA1	ඡ	,	ඹ	ග	0DDC	l	ඈ
1	1	0	1	D	CR	000D	ඡ	න	ඪ	භ	0DDD	m	ඉ
1	1	1	0	E	ඵ	0D91	ක	.	ඵ	ඟ	0DDE	n	ඊ
1	1	1	1	F	ඵ	0D92	ක	/	?	ඵ	0DCA	o	ඵ

In the event that an MS receives a code where a symbol is not represented in the above table then the MS shall display the REPLACEMENT CHARACTER (U+FFFD).

LF: LINE FEED; moves to the next line (with implied carriage return).

CR: CARRIAGE RETURN; CR is not used as CR but is used as a filler after the actual SMS/CBS message text. CR should not occur inside a message text, but if it does, it must be converted to LF. Note though that <SS2,CR> is actually CSI (see next table), and that "CR" is not a filler, nor LF.

SS2: SINGLE SHIFT TWO; This code shifts the next 7-bit code unit to refer to an extension of this table (subclause A.4.21.2).

When splitting a message text into submessages, there must be no cut right after an SS2.

U+0DCA: SINHALA SIGN AL-LAKUNA: Virama; This is a control character for forming conjuncts. If the display font does not support the requested conjunct, U+0DCA is a combining character with nominal glyph.

A.4.21.2 SMS/CBS 7-bit Sinhala Alphabet (0x21) extension (SS2) table

				b7	0	0	0	0	1	1	1	1
				b6	0	0	1	1	0	0	1	1
				b5	0	1	0	1	0	1	0	1
b4	b3	b2	b1	1B	0	1	2	3	4	5	6	7
0	0	0	0	0	@ 0040	< 003C	ඒ 0DEA	ඃaa 0D8E	 007C	P 0050	¼ 00BC	△ 26A0
0	0	0	1	1	£ 00A3	= 003D	ද 0DEB	භ 0D90	A 0041	Q 0051	½ 00BD	∞ 221E
0	0	1	0	2	\$ 0024	> 003E	ඞ 0DEC	ාaa 0DF2	B 0042	R 0052	¾ 00BE	² 00B2
0	0	1	1	3	¥ 00A5	₹ 20B9	ඡ 0DED	ා 0DF3	C 0043	S 0053	“ 201C	³ 00B3
0	1	0	0	4	§ 00A7	^ 005E	උ 0DEE		D 0044	T 0054	” 201D	
0	1	0	1	5	" 0022		ඹ 0DEF		E 0045	U 0055	¤ 00A4	
0	1	1	0	6	€ 20AC				F 0046	V 0056	Ω 03A9	
0	1	1	1	7	% 0025	(0028	ℳ 0DF4		G 0047	W 0057	μ 03BC	
1	0	0	0	8	& 0026	) 0029	{ 007B	ට 200D,0DCA	H 0048	X 0058	° 00B0	
1	0	0	1	9	' 0027	 0964	} 007D	ඟ 0DB9	I 0049	Y 0059	× 00D7	ඹ 0D9F
1	0	1	0	A	FF 000C	 0965	ඹඒ 0DE7,2044,0DEA	≈ 2248	J 004A	Z 005A	÷ 00F7	ඳ 0DA5
1	0	1	1	B	- 2212	SS3 ----	ඹඹ 0DE7,2044,0DE8	≠ 2260	K 004B		± 00B1	ඒ 0DA6
1	1	0	0	C	! 0021	‡ 0DE6	ඹඹඒ 0DE9,2044,0DEA	[005B	L 004C		‰ 2030	ඪ 0DAC
1	1	0	1	D	CSI 009B	ඹ 0DE7	≤ 2A7D	~ 007E	M 004D		« 00AB	ඳ 0DB3
1	1	1	0	E	- 002D	ඹ 0DE8	≥ 2A7E	] 005D	N 004E		» 00BB	
1	1	1	1	F		ඹ 0DE9	\ 005C	· 00B7	O 004F		' 2019	

In the event that an MS receives a code where a symbol is not represented in the above table then the MS shall display the REPLACEMENT CHARACTER (U+FFFD).

FF: FORM FEED; This code is defined as a Page Break character (with implied carriage return). Any mobile station which does not have pagination shall treat it as a LF (with implied carriage return).

CSI: CONTROL SEQUENCE INTRODUCER; enables decimal character references, enables styling. An MS which does not support CSI shall convert it to REPLACEMENT CHARACTER.

SS3: SINGLE SHIFT THREE; This code is reserved for the extension to another extension table. When splitting a message text into submessages, there must be no cut right after an SS3.

U+2044: FRACTION SLASH; the sequence may need to be isolated from adjacent digits by ZWNJ.