IP Addressing and Subnetting

© 2026 Dan Mill Training. All rights reserved.

A Beginner's Guide

By Dan Mill

Master the fundamentals of IP addressing, subnet masks, CIDR notation, and network design

© 2026 Dan Mill Training. All rights reserved.

Table of Contents

- Chapter 1: Introduction to IP Addressing
- Chapter 2: IP Address Classes
- Chapter 3: Understanding Subnet Masks
- Chapter 4: CIDR Notation
- Chapter 5: Subnetting Basics
- Chapter 6: Advanced Subnetting
- Chapter 7: Subnetting Tips and Tricks
- Chapter 8: Real-World Applications
- Conclusion
- Appendix: Quick Reference Charts

© 2026 Dan Mill Training. All rights reserved.

Chapter 1: Introduction to IP Addressing

Welcome to the world of IP addressing! If you've ever wondered how computers find each other on a network, or how the internet knows where to send your emails and web requests, you're in the right place. This book will take you from absolute beginner to confident practitioner in IP addressing and subnetting.

What is an IP Address?

An IP (Internet Protocol) address is a unique numerical identifier assigned to every device connected to a network. Think of it like a street address for your computer. Just as the postal service uses your street address to deliver mail to your home, networks use IP addresses to deliver data to the correct device.

There are two versions of IP addresses in use today:

- IPv4 (Internet Protocol version 4) - Uses 32-bit addresses
- IPv6 (Internet Protocol version 6) - Uses 128-bit addresses

This book will focus primarily on IPv4, as it's still the most commonly used version and provides an excellent foundation for understanding networking concepts.

The Structure of an IPv4 Address

An IPv4 address consists of 32 bits (binary digits), but we usually write them in a more human-readable format called dotted decimal notation. The 32 bits are divided into four groups of 8 bits each (called octets). Each octet is then converted to a decimal number between 0 and 255.

Example:

```
192.168.1.100
```

Let's break this down:

- 192 is the first octet
- 168 is the second octet
- 1 is the third octet
- 100 is the fourth octet

Binary and Decimal Conversion

To truly understand IP addressing, you need to be comfortable converting between binary and decimal. Binary is a base-2 number system that uses only two digits: 0 and 1. Each position in a binary number represents a power of 2.

© 2026 Dan Mill Training. All rights reserved.

Understanding Binary

For an 8-bit octet, the positions represent these values (from right to left):

128	64	32	16	8	4	2	1

To convert binary to decimal, simply add up the values where there's a 1 in the binary number.

Example: Convert 11000000 to binary

```
Position:  128  64  32  16   8   4   2   1

Binary:      1   1   0   0   0   0   0   0

Values:    128+ 64 = 192
```

So 11000000 in binary equals 192 in decimal.

Converting Decimal to Binary

To convert from decimal to binary, we use a simple subtraction method:

Example: Convert 192 to binary

1. Start with 192
2. Can we subtract 128? Yes! Write 1, remainder is 64
3. Can we subtract 64? Yes! Write 1, remainder is 0
4. For the remaining positions (32, 16, 8, 4, 2, 1), we can't subtract, so write 0

Result: 11000000

© 2026 Dan Mill Training. All rights reserved.

Chapter 2: IP Address Classes

When IP addressing was first designed, addresses were divided into different classes to accommodate networks of various sizes. While this classful system is largely obsolete today (replaced by CIDR), understanding it provides valuable context.

The Five Address Classes

Class	IP Range	Default Mask	Use Case
Class A	0.0.0.0 - 127.255.255.255	255.0.0.0	Very large networks
Class B	128.0.0.0 - 191.255.255.255	255.255.0.0	Medium networks
Class C	192.0.0.0 - 223.255.255.255	255.255.255.0	Small networks
Class D	224.0.0.0 - 239.255.255.255	N/A	Multicast
Class E	240.0.0.0 - 255.255.255.255	N/A	Experimental

Private IP Address Ranges

Certain IP address ranges are reserved for private networks and cannot be routed on the public internet. These are defined in RFC 1918:

- Class A: 10.0.0.0 to 10.255.255.255 (10.0.0.0/8)
- Class B: 172.16.0.0 to 172.31.255.255 (172.16.0.0/12)
- Class C: 192.168.0.0 to 192.168.255.255 (192.168.0.0/16)

Special IP Addresses

- 127.0.0.1 - Loopback address (refers to the local computer)
- 0.0.0.0 - Represents 'any address' or an unknown address
- 255.255.255.255 - Broadcast address (sends to all devices)

© 2026 Dan Mill Training. All rights reserved.

Chapter 3: Understanding Subnet Masks

A subnet mask is like a filter that separates an IP address into two parts: the network portion and the host portion.

What is a Subnet Mask?

A subnet mask is a 32-bit number that looks similar to an IP address. It determines which part of an IP address identifies the network and which part identifies the individual host (device) on that network.

How Subnet Masks Work

In binary, a subnet mask consists of consecutive 1s followed by consecutive 0s:

- The 1s indicate the network portion of the address
- The 0s indicate the host portion of the address

Example subnet mask in different formats:

```
Decimal:      255.255.255.0

Binary:       11111111.11111111.11111111.00000000
```

Common Subnet Masks

Decimal	Binary	CIDR
255.0.0.0	11111111.00000000.00000000.00000000	/8
255.255.0.0	11111111.11111111.00000000.00000000	/16
255.255.255.0	11111111.11111111.11111111.00000000	/24
255.255.255.128	11111111.11111111.11111111.10000000	/25
255.255.255.192	11111111.11111111.11111111.11000000	/26

Calculating Network and Host Portions

Given:

```
IP Address:    192.168.1.100

Subnet Mask:   255.255.255.0
```

Step 1: Convert both to binary

```
IP (binary):   11000000.10101000.00000001.01100100

Mask (binary): 11111111.11111111.11111111.00000000
```

Step 2: The network portion is where the mask has 1s

```
Network:       192.168.1.0
```

Step 3: The host portion is where the mask has 0s

© 2026 Dan Mill Training. All rights reserved.

```
Host:           100
```

© 2026 Dan Mill Training. All rights reserved.

Chapter 4: CIDR Notation

CIDR (Classless Inter-Domain Routing) notation is a more modern and flexible way of representing IP addresses and their associated subnet masks. It's pronounced 'cider' like the apple drink!

What is CIDR?

CIDR notation combines an IP address with a suffix that indicates how many bits are used for the network portion.

```
192.168.1.0/24
```

The /24 means that the first 24 bits are the network portion, leaving 8 bits for hosts.

CIDR Quick Reference Table

CIDR	Subnet Mask	Host Bits	Available Hosts
/8	255.0.0.0	24	16,777,214
/16	255.255.0.0	16	65,534
/24	255.255.255.0	8	254
/25	255.255.255.128	7	126
/26	255.255.255.192	6	62
/27	255.255.255.224	5	30
/28	255.255.255.240	4	14
/30	255.255.255.252	2	2

Why Aren't All Host Addresses Available?

Two addresses in every subnet are reserved:

- Network Address: The first address (all host bits = 0)
- Broadcast Address: The last address (all host bits = 1)

For example, in the 192.168.1.0/24 network:

- Network address: 192.168.1.0 (reserved)
- First usable host: 192.168.1.1
- Last usable host: 192.168.1.254
- Broadcast address: 192.168.1.255 (reserved)

© 2026 Dan Mill Training. All rights reserved.

Chapter 5: Subnetting Basics

Subnetting is the process of dividing a larger network into smaller sub-networks (subnets). This is one of the most important skills in networking.

Why Subnet?

5. Improved Performance: Smaller networks mean less broadcast traffic
6. Enhanced Security: Different departments can be isolated
7. Efficient IP Address Usage: Allocate only what you need
8. Easier Management: Smaller networks are easier to troubleshoot
9. Organizational Logic: Group devices by function or location

The Subnetting Process

Subnetting involves borrowing bits from the host portion to create additional network bits.

Original /24 network:

```
Network bits:  24 (NNNNNNNN.NNNNNNNN.NNNNNNNN.********)

Host bits:      8 (                              HHHHHHHH)
```

After subnetting to /26 (borrowing 2 host bits):

```
Network bits:  26 (NNNNNNNN.NNNNNNNN.NNNNNNNN.NN******)

Host bits:      6 (                                HHHHHH)
```

By borrowing 2 bits, we create 4 subnets (2^2 = 4), each with 62 usable hosts (2^6 - 2 = 62).

Example: Subnetting 192.168.1.0/24 into /26

Subnet	Network Address	Host Range	Broadcast
1	192.168.1.0	192.168.1.1 - 192.168.1.62	192.168.1.63
2	192.168.1.64	192.168.1.65 - 192.168.1.126	192.168.1.127
3	192.168.1.128	192.168.1.129 - 192.168.1.190	192.168.1.191
4	192.168.1.192	192.168.1.193 - 192.168.1.254	192.168.1.255

The Magic Number Method

The 'magic number' is a quick way to determine subnet boundaries:

Magic Number = 256 - (interesting octet value)

© 2026 Dan Mill Training. All rights reserved.

For /26 (mask = 255.255.255.192):

Magic Number = 256 - 192 = 64

The subnets increment by 64: 0, 64, 128, 192

© 2026 Dan Mill Training. All rights reserved.

Chapter 6: Advanced Subnetting

VLSM: Variable Length Subnet Masking

VLSM allows you to use different subnet mask lengths within the same major network. This is extremely useful for efficient IP address allocation.

Scenario: Subnet 192.168.1.0/24 for:

- Department A: 100 hosts
- Department B: 50 hosts
- Department C: 25 hosts
- Point-to-point link: 2 hosts

VLSM Solution

Department A (100 hosts):

Need 7 host bits (2^7 - 2 = 126 hosts)

Subnet: 192.168.1.0/25 (255.255.255.128)

Department B (50 hosts):

Need 6 host bits (2^6 - 2 = 62 hosts)

Subnet: 192.168.1.128/26 (255.255.255.192)

Department C (25 hosts):

Need 5 host bits (2^5 - 2 = 30 hosts)

Subnet: 192.168.1.192/27 (255.255.255.224)

Point-to-point link (2 hosts):

Need 2 host bits (2^2 - 2 = 2 hosts)

Subnet: 192.168.1.224/30 (255.255.255.252)

© 2026 Dan Mill Training. All rights reserved.

Chapter 7: Subnetting Tips and Tricks

The Power of 2 Table

Exponent	Value	Usable Hosts
2^1	2	0
2^2	4	2
2^3	8	6
2^4	16	14
2^5	32	30
2^6	64	62
2^7	128	126
2^8	256	254

Common Mistakes to Avoid

10. Forgetting to subtract 2 from total hosts
11. Using the broadcast address as a host address
12. Confusing 'number of subnets' with 'number of hosts'
13. Forgetting that smaller CIDR prefix = MORE hosts

© 2026 Dan Mill Training. All rights reserved.

Chapter 8: Real-World Applications

Home Network Design

A typical home network uses a single /24 subnet, usually 192.168.1.0/24 or 192.168.0.0/24. Your router acts as the gateway and typically uses .1 as its address.

Small Business Network

A small business might segment their network into VLANs:

- VLAN 10 - Management: 192.168.0.0/26 (62 hosts)
- VLAN 20 - Employees: 192.168.0.64/25 (126 hosts)
- VLAN 30 - Guest Wi-Fi: 192.168.0.192/26 (62 hosts)
- VLAN 40 - Servers: 192.168.1.0/27 (30 hosts)

Cloud and Virtual Networks

Example AWS VPC:

- VPC: 10.10.0.0/16
- Public Subnet AZ1: 10.10.1.0/24
- Private Subnet AZ1: 10.10.10.0/24
- Database Subnet AZ1: 10.10.100.0/24

© 2026 Dan Mill Training. All rights reserved.

Conclusion

Congratulations! You've completed this comprehensive guide to IP addressing and subnetting.

You now understand:

- The structure and purpose of IP addresses
- How to convert between binary and decimal
- IP address classes and their characteristics
- How subnet masks work
- CIDR notation and its advantages
- How to calculate subnets and hosts
- VLSM for efficient address allocation
- Real-world applications

Next Steps

14. Practice regularly - subnetting improves with repetition
15. Use online subnet calculators to check your work
16. Set up a home lab to apply concepts practically
17. Study for certifications like CompTIA Network+ or Cisco CCNA
18. Explore IPv6 addressing

Final Thoughts

IP addressing and subnetting are foundational skills for anyone working in IT or networking. Remember that practice makes perfect. Don't be discouraged if subnetting seems challenging at first - everyone struggles with it initially. Keep working through examples, and soon you'll be calculating subnets in your head!

Thank you for taking the time to learn with this guide. Best of luck on your networking journey!

© 2026 Dan Mill Training. All rights reserved.

Appendix: Quick Reference Charts

Complete Subnet Mask Reference

CIDR	Subnet Mask	Total Addresses	Usable Hosts
/32	255.255.255.255	1	1
/31	255.255.255.254	2	2
/30	255.255.255.252	4	2
/29	255.255.255.248	8	6
/28	255.255.255.240	16	14
/27	255.255.255.224	32	30
/26	255.255.255.192	64	62
/25	255.255.255.128	128	126
/24	255.255.255.0	256	254
/16	255.255.0.0	65,536	65,534
/8	255.0.0.0	16,777,216	16,777,214

Subnetting Formulas

Quick formulas to remember:

- Number of subnets = 2^(borrowed bits)
- Hosts per subnet = 2^(host bits) - 2
- Magic number = 256 - interesting octet value
- Broadcast = Next network - 1

This completes your comprehensive guide to IP Addressing and Subnetting. Happy networking!

© 2026 Dan Mill Training. All rights reserved.