
MATLAB®

Object-Oriented Programming



MATLAB®



How to Contact MathWorks



Latest news: www.mathworks.com

Sales and services: www.mathworks.com/sales_and_services

User community: www.mathworks.com/matlabcentral

Technical support: www.mathworks.com/support/contact_us

T

Phone: 508-647-7000



The MathWorks, Inc. 1 Apple Hill Drive Natick, MA 01760-2098

Object-Oriented Programming

© COPYRIGHT 1984-2024 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

nevision motory		
March 2008	Online only	New for MATLAB 7.6 (Release 2008a)
October 2008	Online only	Revised for MATLAB 7.7 (Release 2008b)
March 2009	Online only	Revised for MATLAB 7.8 (Release 2009a)
September 2009	Online only	Revised for MATLAB 7.9 (Release 2009b)
March 2010	Online only	Revised for MATLAB 7.10 (Release 2010a)
September 2010	Online only	Revised for MATLAB 7.11 (Release 2010b)
April 2011	Online only	Revised for MATLAB 7.12 (Release 2011a)
September 2011	Online only	Revised for MATLAB 7.13 (Release 2011b)
March 2012	Online only	Revised for MATLAB 7.14 (Release 2012a)
September 2012	Online only	Revised for MATLAB 8.0 (Release 2012b)
March 2013	Online only	Revised for MATLAB 8.1 (Release 2013a)
September 2013	Online only	Revised for MATLAB 8.2 (Release 2013b)
March 2014	Online only	Revised for MATLAB 8.3 (Release 2014a)
October 2014	Online only	Revised for MATLAB 8.4 (Release 2014b)
March 2015	Online only	Revised for MATLAB 8.5 (Release 2015a)
September 2015	Online only	Revised for MATLAB 8.6 (Release 2015b)
March 2016	Online only	Revised for MATLAB 9.0 (Release 2016a)
September 2016	Online only	Revised for MATLAB 9.1 (Release 2016b)
March 2017	Online only	Revised for MATLAB 9.2 (Release 2017a)
September 2017	Online only	Revised for MATLAB 9.3 (Release 2017b)
March 2018	Online only	Revised for MATLAB 9.4 (Release 2018a)
September 2018	Online only	Revised for MATLAB 9.5 (Release 2018b)
March 2019	Online only	Revised for MATLAB 9.6 (Release 2019a)
September 2019	Online only	Revised for MATLAB 9.7 (Release 2019b)
March 2020	Online only	Revised for MATLAB 9.8 (Release 2020a)
September 2020	Online only	Revised for MATLAB 9.9 (Release 2020b)
March 2021	Online only	Revised for MATLAB 9.10 (Release 2021a)
September 2021	Online only	Revised for MATLAB 9.11 (Release 2021b)
March 2022	Online only	Revised for MATLAB 9.12 (Release 2022a)
September 2022	Online only	Revised for MATLAB 9.13 (Release 2022b)
March 2023	Online only	Revised for MATLAB 9.14 (Release 2023a)
September 2023	Online only	Revised for Version 23.2 (R2023b)
March 2024	Online only	Revised for Version 24.1 (R2024a)
September 2024	Online only	Revised for Version 24.2 (R2024b)
-	•	

Contents

	Using Object-Oriented Design in MAT
Wh	y Use Object-Oriented Design
	Approaches to Writing MATLAB Programs
	When Should You Create Object-Oriented Programs
Haı	ndle Object Behavior
	What Is a Handle?
	Copies of Handles
	Handle Objects Modified in Functions
	Determine If an Object Is a Handle
	Deleted Handle Objects
	Basic Exam
Cre	ating a Simple Class
0_0	Design Class
	Create Object
	Access Properties
	Call Methods
	Add Constructor
	Vectorize Methods
	Overload Functions
	BasicClass Code Listing
	MATLAB Classes Over
Rol	e of Classes in MATLAB
	Classes
	Some Basic Relationships
Dev	reloping Classes That Work Together
	Formulating a Class
	Specifying Class Components
	BankAccount Class Implementation
	Formulating the AccountManager Class
	Implementing the AccountManager Class
	AccountManager Class Synopsis

Representing Structured Data with Cl	asses
	S
	structor
Mothed to Diet Strees vs. Strein	
TelislieData Class Syllopsis	
Implementing Linked Lists with Class	es
Class Definition Code	
dlnode Class Design	
Why Use a Handle Class for Linked	Lists?
4	
	Static I
Ctatia Data	
What Is Static Data Static Variable	
What Is Static Data	
What Is Static Data	ss Definition—Syntax Refere
What Is Static Data	ss Definition—Syntax Refere
What Is Static Data	ss Definition—Syntax Refere
What Is Static Data	ss Definition—Syntax Refere
What Is Static Data Static Variable Static Data Object Constant Data Class Class Building Blocks Class Definition Block Properties Block	ss Definition—Syntax Refere
What Is Static Data Static Variable Static Data Object Constant Data Class Class Building Blocks Class Definition Block Properties Block	ss Definition—Syntax Refere
What Is Static Data Static Variable Static Data Object Constant Data Class Building Blocks Class Definition Block Properties Block Methods Block	ss Definition—Syntax Refere
What Is Static Data Static Variable Static Data Object Constant Data Class Definition Block Properties Block Methods Block Events Block	ss Definition—Syntax Refere
What Is Static Data Static Variable Static Data Object Constant Data Clas Class Building Blocks Class Definition Block Properties Block Methods Block Events Block Attribute Specification	ss Definition—Syntax Refere
What Is Static Data Static Variable Static Data Object Constant Data Clas Clas Class Building Blocks Class Definition Block Properties Block Methods Block Events Block Attribute Specification Enumeration Classes	ss Definition—Syntax Refere
What Is Static Data Static Variable Static Data Object Constant Data Clas Class Building Blocks Class Definition Block Properties Block Methods Block Events Block Attribute Specification Enumeration Classes	ss Definition—Syntax Refere
What Is Static Data Static Variable Static Data Object Constant Data Components of a Class Class Building Blocks Class Definition Block Properties Block Methods Block Events Block Attribute Specification Enumeration Classes Related Information Method Syntax	ss Definition—Syntax Refere
What Is Static Data Static Variable Static Data Object Constant Data Components of a Class Class Building Blocks Class Definition Block Properties Block Methods Block Events Block Attribute Specification Enumeration Classes Related Information Method Syntax	ss Definition—Syntax Refere

Special Considerations for Validation in Methods	. 5-10
Call Superclass Methods on Subclass Objects	. 5-11
Superclass Relation to Subclass	. 5-11
How to Call Superclass Methods	
How to Call Superclass Constructor	
Using a Class to Display Graphics	. 5-13
Class Calculates Area	
Description of Class Definition	. 5-15
MATLAB Code Analyzer Warnings	. 5-18
Syntax Warnings and Property Names	
Variable/Property Name Conflict Warnings	
Exception to Variable/Property Name Rule	
	- 20
Objects in Conditional Statements	5-20
Enable Use of Objects in Conditional Statements	. 5-20
How MATLAB Evaluates Switch Statements	
How to Define the eq Method	
Enumerations in Switch Statements	. 3-23
Use of Editor and Debugger with Classes	. 5-25
Write Class Code in the Editor	. 5-25
How to Refer to Class Files	
How to Debug Class Files	. 5-25
Automatic Updates for Modified Classes	. 5-27
When MATLAB Loads Class Definitions	. 5-27
Consequences of Automatic Update	. 5-27
What Happens When Class Definitions Change	
Ensure Defining Folder Remains in Scope	
Actions That Do Not Trigger Updates	. 5-29
Multiple Updates to Class Definitions	. 5-29
Object Validity with Deleted Class File	
When Updates Are Not Possible	. 5-29
Potential Consequences of Class Updates	. 5-29
Interactions with the Debugger	5-30
Updates to Class Attributes	5-30
Updates to Property Definitions	. 5-31
Updates to Method Definitions	
Updates to Event Definitions	5-32
Comparison of MATLAB and Other OO Languages	. 5-34
Some Differences from C++ and Java Code	
Object Modification	
Static Properties	. 5-38
Common Object-Oriented Techniques	. 5-38

6

User-Defined Classes	6-2
What Is a Class Definition	6-2
Attributes for Class Members	6-2 6-2
Kinds of Classes	6-2 6-3
Constructing Objects	6-3
classdef Syntax	6- 3
Class Code	6- 3
Class Code	0-0
Class Attributes	6-5
Specifying Class Attributes	6-5
Specifying Attributes	6-7
Class-Specific Attributes	6-7
Functions Inside Class Definition Files	6-8
Embertion of Emmarians in Class Definitions	C (
Evaluation of Expressions in Class Definitions	6-9 6-9
Why Use Expressions	6-9
Where to Use Expressions in Class Definitions	6-11
How MATLAB Evaluates Expressions	6-11
Expression Evaluation in Handle and Value Classes	6-11
Expression Evaluation in Handle and value Classes	0-11
Folders Containing Class Definitions	6-14
Using Path Folders	6-14
Using Class Folders	6-14
Functions in Private Folders Within Class Folders	6-15
Class Precedence and MATLAB Path	6-15
Changing the Path to Update Class Definitions	6-16
Class Precedence	6-18
Use of Class Precedence	6-18
Why Mark Classes as Inferior	6-18
InferiorClasses Attribute	6-18
Create Namespaces	6-20
Namespace Folders	6-20
Define Code in Namespaces	6-20
Reference Namespace Members	6-2 1
Namespaces and the MATLAB Path	6-22
How MATLAB Handles Duplicate Names	6-22
The internal Namespace	6-22
Import Nameonace Members into Eventions	6-24
Import Classes Namespace Functions	6-24
Import Classes, Namespace Functions, and Static Methods	6-24
Importing Namespace Members with the Same Name	6-25
Clear an Import List	U- 23
Creating and Managing Class Aliases	6-26
Creating and Managing Class Anases	6-26
Viewing Alias Definitions	6-27
	· · · · · ·

Value or Handle Class — Which to Use

7

Comparison of Handle and Value Classes	7-2
Basic Difference	7-2
Behavior of MATLAB Built-In Classes	7-2
User-Defined Value Classes	7-3
User-Defined Handle Classes	7-4
Determining Equality of Objects	7-6
Functionality Supported by Handle Classes	7-7
Which Kind of Class to Use	7-9
Examples of Value and Handle Classes	7-9
When to Use Value Classes	7-9
When to Use Handle Classes	7-9
when to use flandle classes	7-3
The Handle Superclass	7-11
Building on the Handle Class	7-11
Handle Class Methods	7-11
Event and Listener Methods	7-11 7-11
Relational Methods	7-12
Test Handle Validity	7-12
When MATLAB Destroys Objects	7-12
II II OL D	= 40
Handle Class Destructor	7-13
Basic Knowledge	7-13
Syntax of Handle Class Destructor Method	7-13
Handle Object During delete Method Execution	7-14
Support Destruction of Partially Constructed Objects	7-15
When to Define a Destructor Method	7-15
Destructors in Class Hierarchies	7-16
Object Lifecycle	7-16
Restrict Access to Object Delete Method	7-17
Nondestructor Delete Methods	7-18
External References to MATLAB Objects	7-18
Find Handle Objects and Properties	7-21
Find Handle Objects	7-21
Find Handle Object Properties	7-21
Implement Set/Get Interface for Properties	7-22
The Standard Set/Get Interface	7-22
Subclass Syntax	7-22
Get Method Syntax	7-22
Set Method Syntax	7-23
Class Derived from matlab.mixin.SetGet	7-24
Set Priority for Matching Partial Property Names	7-27
Implement Copy for Handle Classes	7-30
Copy Method for Handle Classes	7-30 7-30
CODY MEDIUM IN HAMME CIASSES	7-30

	Customize Copy Operation
Wea	k Reference Handles
wea	Create Weak References
	Create Back Pointers Using Properties Defined with WeakHandle Attribute
	Create a Cache Using the matlab.lang.WeakReference Class
	Immediate Destruction of Weak References
	Properties — Storing Class 1
	110perties storing class
Way	s to Use Properties
	What Are Properties
	Types of Properties
Pror	perty Syntax
1101	Property Definition Block
	Property Validation Syntax
	Property Access Syntax
Pror	perty Attributes
1101	Purpose of Property Attributes
	Specify Property Attributes
	Table of Property Attributes
	Property Access Lists
Initi	alize Property Values
	Define Properties with Default Values
	Set Property Values in the Constructor
Mut	able and Immutable Properties
	Set Access to Property Values
	Define Immutable Property
Valid	late Property Values
	Property Validation in Class Definitions
	Sample Class Using Property Validation
	Order of Validation
	Abstract Property Validation
	Objects Not Updated When Changing Validation Validation During Load Operation
Dro-	porty Class and Size Validation
LIUI	Property Class and Size Validation
	Property Size Validation
	Property Class Validation
	Default Values Per Size and Class

MATLAB Validation Functions	8-3
Metadata Interface to Property Validation	8-3
Property Get and Set Methods	
Property Get Methods	
Get and Set Methods for Dependent Properties	8-4
Define a Get Method for a Dependent Property	
Properties Containing Objects	8-4
Assigning Objects as Default Property Values	8-4
Assigning to Read-Only Properties Containing Objects	
Assignment Behavior	8-4
Dynamic Properties — Adding Properties to an Instance	8-4
What Are Dynamic Properties	8-4
Define Dynamic Properties	
List Object Dynamic Properties	8- 5
Set and Get Methods for Dynamic Properties	
Create Access Methods for Dynamic Properties	8- 5
Dynamic Property Events	8-5
Dynamic Properties and Ordinary Property Events	
Dynamic-Property Events	
Listen for a Specific Property Name	8-5
PropertyAdded Event Callback Execution	8- 5
How to Find matlab.metadata.DynamicProperty Objects	
110.1. to 1 1114 1114 1114 1114 1114 1114 1114	
Dynamic Properties and ConstructOnLoad	0-1
Dynamic Properties and ConstructOnLoad	eration
Methods — Defining Class Ope	
Methods — Defining Class Ope Methods in Class Design Class Methods	9 9
Methods — Defining Class Ope Methods in Class Design Class Methods Examples and Syntax	9 9
Methods — Defining Class Ope Methods in Class Design Class Methods Examples and Syntax Kinds of Methods	9 9 9
Methods — Defining Class Ope Methods in Class Design Class Methods Examples and Syntax	9 9 9
Methods — Defining Class Ope Methods in Class Design Class Methods Examples and Syntax Kinds of Methods	9 9 9 9
Methods — Defining Class Ope Methods in Class Design Class Methods Examples and Syntax Kinds of Methods Method Naming	9 9 9 9
Methods — Defining Class Ope Methods in Class Design Class Methods Examples and Syntax Kinds of Methods Method Naming Method Attributes	9 9 9 9 9 9.

Ordinary Methods	9-6
Ordinary Methods Operate on Objects	9-6
Methods Inside classdef Block	9-6
Method Files	9-7
Methods in Separate Files	9-8
Class Folders	9-8
Define Method in Function File	9-8
Specify Method Attributes in classdef File	9-9
Methods You Must Define in the classdef File	9-10
Method Invocation	9-11
Dot and Function Syntaxes	9-11
	9-11
Determining Which Method Is Invoked	9-12
Class Constructor Methods	9-15
Purpose of Class Constructor Methods	9-15
Basic Structure of Constructor Methods	9-15
Guidelines for Constructors	9-16
Default Constructor	9-17
When to Define Constructors	9-17
Related Information	9-17
Initializing Objects in Constructor	9-17
No Input Argument Constructor Requirement	9-19
Subclass Constructors	9-19
Implicit Call to Inherited Constructor	9-21
Errors During Class Construction	9-22
Output Object Suppressed	9-22
Static Methods	9-24
What Are Static Methods	9-24
Why Define Static Methods	9-24
Defining Static Methods	9-24
Calling Static Methods	9-24
Inheriting Static Methods	9-24
inheriting Static Methods	9-23
Overload Functions in Class Definitions	9-26
Why Overload Functions	9-26
Implementing Overloaded MATLAB Functions	9-26
Rules for Naming to Avoid Conflicts	9-28
Class Support for Amor Creation For these	0.20
Class Support for Array-Creation Functions	9-29
Extend Array-Creation Functions for Your Class	9-29
Which Syntax to Use	9-30 9-31
Implement Support for Array-Creation Functions	9-31
Class Methods for Graphics Callbacks	9-37
Referencing the Method	9-37
Syntax for Method Callbacks	9-37
Use a Class Method for a Slider Callback	9-38

7	1	A)
J	•	J

Create an Object Array Using a Loop Create an Object Array Using createArray Create an Object Array by Constructing the Last Element Create an Object Array in the Constructor CCCESSING Properties and Methods in Object Arrays Reference Properties in an Object Array Assigning Values to Properties in an Object Array Invoking Methods on an Object Array Concatenation Subscripted Assignment	10 10 11 11 10
Create an Object Array by Constructing the Last Element Create an Object Array in the Constructor CCCESSING Properties and Methods in Object Arrays Reference Properties in an Object Array Assigning Values to Properties in an Object Array Invoking Methods on an Object Array CONCATENTIAL CONCESSION CONCATENTIAL CONCESSION CONCATENTIAL CONSTRUCTION CONSTRUCTION CONCATENTIAL CONSTRUCTION CONSTRUCTION CONCATENTIAL CONSTRUCTION CONSTR	1 1 1 1 1
Create an Object Array in the Constructor CCCESSING Properties and Methods in Object Arrays Reference Properties in an Object Array Assigning Values to Properties in an Object Array Invoking Methods on an Object Array Concatenation	10
Reference Properties in an Object Array Assigning Values to Properties in an Object Array Invoking Methods on an Object Array mplicit Class Conversion Concatenation	1 1 1
Reference Properties in an Object Array Assigning Values to Properties in an Object Array Invoking Methods on an Object Array mplicit Class Conversion Concatenation	10
Assigning Values to Properties in an Object Array	10
Invoking Methods on an Object Array	10
mplicit Class Conversion	10
Concatenation	
	10
Subscripted Assignment	10
bubberipted rissignment	10
Property Validation	10
Function and Method Argument Validation	10
oncatenating Objects of Different Classes	10
	10
MATLAB Concatenation Rules	10
	10
	10
Converter Methods	1
esigning Heterogeneous Class Hierarchies	10
	10
	10
	10
	10
	10
	1
	10
	1
	10
	10
Empty Arrays of fleterogeneous Abstract Classes	1,
	10
	10
	10
Initialize Array in Superclass Constructor	10
Commis Implementation	
Sample Implementation	10
	Basic Knowledge MATLAB Concatenation Rules Concatenating Objects Calling the Dominant-Class Constructor Converter Methods Designing Heterogeneous Class Hierarchies Creating Classes That Support Heterogeneous Arrays MATLAB Arrays Heterogeneous Hierarchies Heterogeneous Arrays Heterogeneous Array Concepts Nature of Heterogeneous Arrays Unsupported Hierarchies Default Object Conversion During Assignment and Concatenation Empty Arrays of Heterogeneous Abstract Classes Heterogeneous Array Constructors Building Arrays in Superclass Constructors When Errors Can Occur

Events and Listeners Basics	11-2
Event Syntax	11-2
Create Listener	11-3
Define Custom Event Data	11-5
	11-5
Class Event Data Requirements	_
Define and Trigger Event	11-5
Define Event Data	11-6
Create Listener for Overflow Event	11-6
Observe Changes to Property Values	11-8
Implement Property Set Listener	11-10
PushButton Class Design	11-10
Tushbutton Gluss Dosign	11 10
Event and Listener Concepts	11-12
The Event Model	11-12
Limitations	11-13
Default Event Data	11-13
Events Only in Handle Classes	11-14
Property-Set and Query Events	11-14
	11-14
Listeners	11-13
Event Attributes	11-16
Specify Event Attributes	11-16
Events and Listanova Comtan	11 10
Events and Listeners Syntax	11-18
Components to Implement	11-18
Name Events	11-18
Trigger Events	11-18
Listen to Events	11-19
Define Event-Specific Data	11-21
	44.00
Listener Lifecycle	11-23
Control Listener Lifecycle	11-23
Temporarily Deactivate Listeners	11-23
Permanently Delete Listeners	11-23
The same Or Wheels Control	11 04
Listener Callback Syntax	11-24
Specifying Listener Callbacks	11-24
Input Arguments for Callback Function	11-24
Additional Arguments for Callback Function	11-25
Callback Execution	11-27
When Callbacks Execute	11-27
Listener Order of Execution	11-27
Callbacks That Call notify	11-27
Manage Callback Errors	11-27
Invoke Functions from Function Handles	11-27
Determine If Event Hee Listeners	11 20
Determine If Event Has Listeners	11-29
Do Listeners Exist for This Event?	11-29
Why Test for Listeners	11-29
Coding Patterns	11-29
Listeners in Heterogeneous Arrays	11-29

Assignment When Property Value Is Unchanged 11-35 AbortSet When Value Does Not Change 11-35 How MATLAB Compares Values 11-35 When to Use AbortSet 11-35 Implement AbortSet 11-36 Using Demonstrated in Property Validation 11-37 Techniques for Using Events and Listeners 11-40 Example Overview 11-40 Techniques Demonstrated in This Example 11-41 Summary of feneval Class 11-41 Summary of fenview Class 11-42 Methods Inherited from Handle Class 11-43 Using the feneval and fenview Classes 11-43 Implement UpdateGraph Event and Listener 11-45 The PostSet Event Listener 11-48 Enable and Disable Listeners 11-49 @feneval/feneval.m Class Code 11-51 @fcnview/fcnview.m Class Code 11-51 @fcnview/fcnview.m Class Code 11-52 How to Build on Other Classes How to Build on Other Classes Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-3 Subclass Syntax 12-5	Create Property Listeners	11-32 11-32 11-33
AbortSet When Value Does Not Change	Property Event and Listener Classes	11-33
AbortSet When Value Does Not Change	Assignment When Property Value Is Unchanged	11-35
How MATLAB Compares Values		
When to Use AbortSet	•	
Implement AbortSet 11-36 Using AbortSet with Property Validation 11-37 Techniques for Using Events and Listeners 11-40 Example Overview 11-40 Techniques Demonstrated in This Example 11-41 Summary of fcneval Class 11-41 Summary of fcneval Class 11-42 Methods Inherited from Handle Class 11-43 Using the fcneval and fcnview Classes 11-43 Using the fcneval and fcnview Classes 11-43 Using the fcneval and fcnview Classes 11-43 Implement UpdateGraph Event and Listener 11-45 The PostSet Event Listener 11-45 The PostSet Event Listener 11-45 Gfcneval/fcneval.m Class Code 11-51 Gfcnview/fcnview.m Class Code 11-51 Gfcnview/fcnview.m Class Code 11-52 Hierarchies of Classes - Concepts 12-2 Classification 12-3 Develop the Abstraction 12-3 Develop the Abstraction 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-4 Subclass Syntax 12-5 Subclass Syntax 12-5 Subclass Constructor Explicitly 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor From Subclass 12-7 Call Only Direct Superclass from Constructor 12-9 Control Sequence of Constructor Calls 12-13 Extend Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Methods 12-13 Reimplement Superclass Methods 12-13 Redefine Superclass Methods 12-13 Redefine Superclass Methods 12-14 Redefine Superclass Methods 12-15 Call Superclass Methods 12-14 Redefine Superclass Methods 12-15 Redefine Superclass Methods 12-15 Redefine Superclass Methods 12-15 Redefine Superclass Methods 12-15 Call Superclass Me		
Using AbortSet with Property Validation 11-37		
Example Overview		
Example Overview	Techniques for Using Events and Listeners	11-40
Techniques Demonstrated in This Example		11-40
Summary of feneval Class 11-41		11-41
Summary of fenview Class 11-42		11-41
Methods Inherited from Handle Class 11-43 Using the feneval and fenview Classes 11-43 Implement UpdateGraph Event and Listener 11-45 The PostSet Event Listener 11-48 Enable and Disable Listeners 11-50 @fcneval/fcneval.m Class Code 11-51 @fcnview/fcnview.m Class Code 11-52 How to Build on Other Classes Hierarchies of Classes — Concepts 11-52 Classification 12-2 Develop the Abstraction 12-3 Design of Class Hierarchies 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-4 Subclass Syntax 12-5 Subclass Syntax 12-5 Subclass Definition Syntax 12-5 Subclass Gonstructor Explicitly 12-5 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor From Subclass 12-7 Subclass Constructor Implementation 12-8 Call Only Direct Superclass from Constructor 12-9 Control Sequence of Constructor Calls 12-13 When to Modify Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Methods 12-13 Reimplement Superclass Methods 12-14 Redefine Superclass Methods 12-14 Redefine Superclass Methods 12-15		11-42
Using the fcneval and fcnview Classes 11-43 Implement UpdateGraph Event and Listener 11-45 The PostSet Event Listener 11-48 Enable and Disable Listeners 11-50 @fcneval/fcneval.m Class Code 11-51 @fcnview/fcnview.m Class Code 11-52 How to Build on Other Classes Hierarchies of Classes — Concepts 12-2 Classification 12-3 Develop the Abstraction 12-3 Design of Class Hierarchies 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-4 Subclass Syntax 12-5 Subclass Definition Syntax 12-5 Subclass Definition Syntax 12-5 Subclass double 12-5 Design Subclass Constructor Explicitly 12-7 Call Superclass Constructor Constructor 12-9 Control Sequence of Constructor Calls 12-13 Extend Superclass Methods 12-13 Extend Superclass Methods 12-13 Extend Superclass Methods 12-14 Redefine Superclass Methods 12-15		
Implement UpdateGraph Event and Listener 11-45 The PostSet Event Listener 11-48 Enable and Disable Listeners 11-50 @fcneval/fcneval.m Class Code 11-51 @fcnview/fcnview.m Class Code 11-52 Hierarchies of Classes — Concepts 11-52 Classification 12-2 Develop the Abstraction 12-3 Design of Class Hierarchies 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-4 Subclass Syntax 12-5 Subclass Opinition Syntax 12-5 Subclass Definition Syntax 12-5 Subclass Constructor Explicitly 12-5 Subclass Constructor From Subclass 12-7 Call Superclass Constructor From Subclass 12-7 Call Superclass Constructor From Subclass 12-7 Subclass Constructor Implementation 12-8 Call Only Direct Superclass from Constructor 12-9 Control Sequence of Constructor Calls 12-13 When to Modify Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Methods 12-13 Reimplement Superclass Process in Subclass 12-14 Redefine Superclass Methods 12-15		
The PostSet Event Listener	•	
Enable and Disable Listeners		
@fcneval/fcneval.m Class Code 11-51 @fcnview/fcnview.m Class Code 11-52 How to Build on Other Classes Hierarchies of Classes — Concepts 12-2 Classification 12-2 Develop the Abstraction 12-3 Design of Class Hierarchies 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-3 Subclass Syntax 12-5 Subclass Definition Syntax 12-5 Subclass double 12-5 Design Subclass Constructors 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor From Subclass 12-7 Subclass Constructor Implementation 12-8 Call Only Direct Superclass from Constructor 12-8 Call Only Direct Superclass Methods 12-11 Modify Inherited Methods 12-13 Extend Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Methods 12-14 Redefine Superclass Methods 12-15		_
Hierarchies of Classes — Concepts 12-2 Classification 12-2 Develop the Abstraction 12-3 Design of Class Hierarchies 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-4 Subclass Syntax 12-5 Subclass Definition Syntax 12-5 Subclass Definition Syntax 12-5 Subclass Gonstructors 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor Explicitly 12-7 Subclass Constructor Implementation 12-8 Call Only Direct Superclass from Constructor 12-9 Control Sequence of Constructor Calls 12-13 When to Modify Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Process in Subclass 12-14 Redefine Superclass Methods 12-15		
Hierarchies of Classes — Concepts 12-2 Classification 12-2 Develop the Abstraction 12-3 Design of Class Hierarchies 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-4 Subclass Syntax 12-5 Subclass Definition Syntax 12-5 Subclass Definition Syntax 12-5 Subclass double 12-5 Design Subclass Constructors 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor Fom Subclass 12-7 Subclass Constructor Implementation 12-8 Call Only Direct Superclass from Constructor 12-9 Control Sequence of Constructor Calls 12-13 When to Modify Superclass Methods 12-13 Extend Superclass Methods 12-13 Extend Superclass Methods 12-14 Redefine Superclass Methods 12-15		
Classification 12-2 Develop the Abstraction 12-3 Design of Class Hierarchies 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-4 Subclass Syntax 12-5 Subclass Definition Syntax 12-5 Subclass double 12-5 Design Subclass Constructors 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor from Subclass 12-7 Subclass Constructor Implementation 12-8 Call Only Direct Superclass from Constructor 12-9 Control Sequence of Constructor Calls 12-11 Modify Inherited Methods 12-13 When to Modify Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Process in Subclass 12-14 Redefine Superclass Methods 12-15	How to Build on Other Cla	asses
Classification 12-2 Develop the Abstraction 12-3 Design of Class Hierarchies 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-4 Subclass Syntax 12-5 Subclass Definition Syntax 12-5 Subclass double 12-5 Design Subclass Constructors 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor from Subclass 12-7 Subclass Constructor Implementation 12-8 Call Only Direct Superclass from Constructor 12-9 Control Sequence of Constructor Calls 12-11 Modify Inherited Methods 12-13 When to Modify Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Process in Subclass 12-14 Redefine Superclass Methods 12-15		
Design of Class Hierarchies 12-3 Super and Subclass Behavior 12-3 Implementation and Interface Inheritance 12-4 Subclass Syntax 12-5 Subclass Definition Syntax 12-5 Subclass double 12-5 Design Subclass Constructors 12-7 Call Superclass Constructor Explicitly 12-7 Call Superclass Constructor from Subclass 12-7 Subclass Constructor Implementation 12-8 Call Only Direct Superclass from Constructor 12-9 Control Sequence of Constructor Calls 12-11 Modify Inherited Methods 12-13 When to Modify Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Process in Subclass 12-14 Redefine Superclass Methods 12-15	Hierarchies of Classes — Concepts	12-2
Super and Subclass Behavior12-3Implementation and Interface Inheritance12-4Subclass Syntax12-5Subclass Definition Syntax12-5Subclass double12-5Design Subclass Constructors12-7Call Superclass Constructor Explicitly12-7Call Superclass Constructor from Subclass12-7Subclass Constructor Implementation12-8Call Only Direct Superclass from Constructor12-9Control Sequence of Constructor Calls12-11Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15		
Implementation and Interface Inheritance12-4Subclass Syntax12-5Subclass Definition Syntax12-5Subclass double12-5Design Subclass Constructors12-7Call Superclass Constructor Explicitly12-7Call Superclass Constructor from Subclass12-7Subclass Constructor Implementation12-8Call Only Direct Superclass from Constructor12-9Control Sequence of Constructor Calls12-11Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification	12-2
Implementation and Interface Inheritance12-4Subclass Syntax12-5Subclass Definition Syntax12-5Subclass double12-5Design Subclass Constructors12-7Call Superclass Constructor Explicitly12-7Call Superclass Constructor from Subclass12-7Subclass Constructor Implementation12-8Call Only Direct Superclass from Constructor12-9Control Sequence of Constructor Calls12-11Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification	12-2 12-3
Subclass Definition Syntax12-5Subclass double12-5Design Subclass Constructors12-7Call Superclass Constructor Explicitly12-7Call Superclass Constructor from Subclass12-7Subclass Constructor Implementation12-8Call Only Direct Superclass from Constructor12-9Control Sequence of Constructor Calls12-11Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification	12-2 12-3 12-3
Subclass double12-5Design Subclass Constructors12-7Call Superclass Constructor Explicitly12-7Call Superclass Constructor from Subclass12-7Subclass Constructor Implementation12-8Call Only Direct Superclass from Constructor12-9Control Sequence of Constructor Calls12-11Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification	12-2 12-3 12-3 12-3
Design Subclass Constructors12-7Call Superclass Constructor Explicitly12-7Call Superclass Constructor from Subclass12-7Subclass Constructor Implementation12-8Call Only Direct Superclass from Constructor12-9Control Sequence of Constructor Calls12-11Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance	12-2 12-3 12-3 12-3 12-4
Call Superclass Constructor Explicitly12-7Call Superclass Constructor from Subclass12-7Subclass Constructor Implementation12-8Call Only Direct Superclass from Constructor12-9Control Sequence of Constructor Calls12-11Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax	12-2 12-3 12-3 12-3 12-4 12-5
Call Superclass Constructor from Subclass12-7Subclass Constructor Implementation12-8Call Only Direct Superclass from Constructor12-9Control Sequence of Constructor Calls12-11Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax	12-2 12-3 12-3 12-3 12-4 12-5 12-5
Subclass Constructor Implementation 12-8 Call Only Direct Superclass from Constructor 12-9 Control Sequence of Constructor Calls 12-11 Modify Inherited Methods 12-13 When to Modify Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Process in Subclass 12-14 Redefine Superclass Methods 12-15	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors	12-2 12-3 12-3 12-3 12-4 12-5 12-5
Call Only Direct Superclass from Constructor12-9Control Sequence of Constructor Calls12-11Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-5
Control Sequence of Constructor Calls 12-11 Modify Inherited Methods 12-13 When to Modify Superclass Methods 12-13 Extend Superclass Methods 12-13 Reimplement Superclass Process in Subclass 12-14 Redefine Superclass Methods 12-15	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors Call Superclass Constructor Explicitly	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-5 12-7 12-7
Modify Inherited Methods12-13When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors Call Superclass Constructor Explicitly Call Superclass Constructor from Subclass	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-7 12-7 12-7
When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors Call Superclass Constructor Explicitly Call Superclass Constructor from Subclass Subclass Constructor Implementation	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-7 12-7 12-7 12-8
When to Modify Superclass Methods12-13Extend Superclass Methods12-13Reimplement Superclass Process in Subclass12-14Redefine Superclass Methods12-15	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors Call Superclass Constructor Explicitly Call Superclass Constructor from Subclass Subclass Constructor Implementation Call Only Direct Superclass from Constructor	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-7 12-7 12-7 12-7 12-8 12-9
Extend Superclass Methods	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors Call Superclass Constructor Explicitly Call Superclass Constructor from Subclass Subclass Constructor Implementation Call Only Direct Superclass from Constructor Control Sequence of Constructor Calls	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-7 12-7 12-7 12-8 12-9
Reimplement Superclass Process in Subclass	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors Call Superclass Constructor Explicitly Call Superclass Constructor from Subclass Subclass Constructor Implementation Call Only Direct Superclass from Constructor Control Sequence of Constructor Calls Modify Inherited Methods	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-7 12-7 12-7 12-8 12-9 12-11
Redefine Superclass Methods	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors Call Superclass Constructor Explicitly Call Superclass Constructor from Subclass Subclass Constructor Implementation Call Only Direct Superclass from Constructor Control Sequence of Constructor Calls Modify Inherited Methods When to Modify Superclass Methods	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-7 12-7 12-7 12-7 12-8 12-9 12-11
<u> </u>	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors Call Superclass Constructor Explicitly Call Superclass Constructor from Subclass Subclass Constructor Implementation Call Only Direct Superclass from Constructor Control Sequence of Constructor Calls Modify Inherited Methods When to Modify Superclass Methods Extend Superclass Methods	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-7 12-7 12-7 12-7 12-9 12-11 12-13 12-13 12-13
	Classification Develop the Abstraction Design of Class Hierarchies Super and Subclass Behavior Implementation and Interface Inheritance Subclass Syntax Subclass Definition Syntax Subclass double Design Subclass Constructors Call Superclass Constructor Explicitly Call Superclass Constructor from Subclass Subclass Constructor Implementation Call Only Direct Superclass from Constructor Control Sequence of Constructor Calls Modify Inherited Methods When to Modify Superclass Methods Extend Superclass Methods Reimplement Superclass Process in Subclass	12-2 12-3 12-3 12-3 12-4 12-5 12-5 12-7 12-7 12-7 12-7 12-13 12-13 12-13 12-14

Modify Inherited Properties	12-17 12-17
Private Local Property Takes Precedence in Method	12-1 7
Subclassing Multiple Classes	12-19
Specify Multiple Superclasses	12-19
Class Member Compatibility	12-19
Multiple Inheritance	12-20
Specify Allowed Subclasses	12-21
Why Control Allowed Subclasses	12-21
Specify Allowed Subclasses	12-21
Define Sealed Hierarchy of Classes	12-22
Class Members Access	12-2 3
Basic Knowledge	12-2 3
Applications for Access Control Lists	12-2 4
Specify Access to Class Members	12-2 4
Properties with Access Lists	12-2 5
Methods with Access Lists	12-2 5
Abstract Methods with Access Lists	12-28
Method Access List	12-29
Event Access List	12-30
Handle Compatible Classes	12-31
Basic Knowledge	12-31
When to Use Handle-Compatible Classes	12-3 1
Handle Compatibility Rules	12-31
Identify Handle Objects	12-3 2
How to Define Handle-Compatible Classes	12-3 3
What Is Handle Compatibility?	12-3 3
Subclassing Handle-Compatible Classes	12-3 5
Methods for Handle-Compatible Classes	12-37
Methods for Handle and Value Objects	12-3 7
Modify Value Objects in Methods	12-37
Handle-Compatible Classes and Heterogeneous Arrays	12-38
Heterogeneous Arrays	12-38
Methods Must Be Sealed	12-38
Template Technique	12-38
Subclasses of MATLAB Built-In Types	12-40
MATLAB Built-In Types	12-40
Built-In Types You Can Subclass	12-40
Why Subclass Built-In Types	12-40
Which Functions Work with Subclasses of Built-In Types	12-41
Behavior of Built-In Functions with Subclass Objects	12-41
Built-In Subclasses That Define Properties	12-4 2
Behavior of Inherited Built-In Methods	12-43
Subclass double	12-43

	Built-In Data Organization Methods
	Built-In Indexing Methods
S	ubclasses of Built-In Types Without Properties
	Specialized Numeric Types
	A Class to Manage uint8 Data
	Using the DocUint8 Class
S	ubclasses of Built-In Types with Properties
	Specialized Numeric Types with Additional Data Storage
	Subclasses with Properties
	Property Added
	Methods Implemented
	Using ExtendDouble
	Concatenation of ExtendDouble Objects
U	se of size and numel with Classes
	size and numel
	Built-In Class Behavior
	Subclasses Inherit Behavior
	Classes Not Derived from Built-In Classes
	Change the Behavior of size or numel
	Overload numArgumentsFromSubscript Instead of numel
D	etermine Array Class
	Query the Class Name
	Test for Array Class
	Test for Specific Types
	Test for Subclasses of Built-in Types
A	bstract Classes and Class Members
	Abstract Classes
	Declare Classes as Abstract
	Determine If a Class Is Abstract
	Find Inherited Abstract Properties and Methods
D	efine an Interface Superclass
	Interfaces
	Interface Class Implementing Graphs

Control Property Loading	13-4
	13-4
Property Value Computed from Other Properties	13-6
When to Customize the Serialization Process	13-7
How to Modify the Serialization Process	13-7
Maintain Backward and Forward Compatibility Between Class Definition	
Backward Compatibility	13-9 13-9
Forward Compatibility	13-11
Serialization with Class Hierarchies	13-13
Call Superclass Methods of matlab.mixin.CustomElementSerialization	13-13
Customize Serialization in Both Superclasses and Subclasses	13-15
Transitioning Serialization and Deserialization Processes to	
matlab.mixin.CustomElementSerialization	13-17
Implementations and matlab.mixin.CustomElementSerialization	13-17
Private Properties with the Same Name in Class Hierarchies	13-20
Maintaining Existing loadobj and saveobj Implementations	13-22
Code Patterns for saveobj and loadobj	13-24
Using saveobj and loadobj	13-24
saveobj and loadobj with Subclass Objects	13-26 13-28
Enumera	tions
Named Values	14-2
Named Values	14-2 14-2 14-2
Kinds of Predefined Names	14-2 14-2
Kinds of Predefined Names	14-2
Kinds of Predefined Names Techniques for Defining Enumerations Define Enumeration Classes Enumeration Class Construct an Enumeration Member	14-2 14-2 14-4 14-4 14-4
Kinds of Predefined Names Techniques for Defining Enumerations Define Enumeration Classes Enumeration Class Construct an Enumeration Member Convert to Superclass Value	14-2 14-2 14-4 14-4 14-4 14-4
Kinds of Predefined Names Techniques for Defining Enumerations Define Enumeration Classes Enumeration Class Construct an Enumeration Member Convert to Superclass Value Define Methods in Enumeration Classes	14-2 14-2 14-4 14-4 14-4 14-4 14-5
Kinds of Predefined Names Techniques for Defining Enumerations Define Enumeration Classes Enumeration Class Construct an Enumeration Member Convert to Superclass Value	14-2 14-2 14-4 14-4 14-4 14-4
Kinds of Predefined Names Techniques for Defining Enumerations Define Enumeration Classes Enumeration Class Construct an Enumeration Member Convert to Superclass Value Define Methods in Enumeration Classes Define Properties in Enumeration Classes Enumeration Class Constructor Calling Sequence	14-2 14-2 14-4 14-4 14-4 14-5 14-6
Kinds of Predefined Names Techniques for Defining Enumerations Define Enumeration Classes Enumeration Class Construct an Enumeration Member Convert to Superclass Value Define Methods in Enumeration Classes Define Properties in Enumeration Classes Enumeration Class Constructor Calling Sequence Refer to Enumerations Instances of Enumeration Classes	14-2 14-2 14-4 14-4 14-4 14-5 14-6 14-7
Kinds of Predefined Names Techniques for Defining Enumerations Define Enumeration Classes Enumeration Class Construct an Enumeration Member Convert to Superclass Value Define Methods in Enumeration Classes Define Properties in Enumeration Classes Enumeration Class Constructor Calling Sequence Refer to Enumerations Instances of Enumeration Classes Conversion of Characters to Enumerations	14-2 14-2 14-4 14-4 14-4 14-5 14-6 14-7 14-9 14-9
Kinds of Predefined Names Techniques for Defining Enumerations Define Enumeration Classes Enumeration Class Construct an Enumeration Member Convert to Superclass Value Define Methods in Enumeration Classes Define Properties in Enumeration Classes Enumeration Class Constructor Calling Sequence Refer to Enumerations Instances of Enumeration Classes	14-2 14-2 14-4 14-4 14-4 14-5 14-6 14-7
Kinds of Predefined Names Techniques for Defining Enumerations Define Enumeration Classes Enumeration Class Construct an Enumeration Member Convert to Superclass Value Define Methods in Enumeration Classes Define Properties in Enumeration Classes Enumeration Class Constructor Calling Sequence Refer to Enumerations Instances of Enumeration Classes Conversion of Characters to Enumerations	14-2 14-2 14-4 14-4 14-4 14-5 14-6 14-7 14-9 14-9

	Example of Restricted Property
C	Operations on Enumerations
Ī	Operations Supported by Enumerations
	Example Enumeration Class
	Default Methods
	Convert Enumeration Members to Strings or char Vectors
	Convert Enumeration Arrays to String Arrays or Cell Arrays of char Vector
	Relational Operations with Enumerations, Strings, and char Vectors
	Enumerations in switch Statements
	Enumeration Set Membership
	Enumeration Text Comparison Methods
	Get Information About Enumerations
	Testing for an Enumeration
F	Iide Enumeration Members
	Hide Pure Enumerations
	Find Hidden Enumeration Members
Ŀ	numeration Class Restrictions
E	numerations Derived from Built-In Classes
	Subclassing Built-In Classes
	Derive Enumeration Class from Numeric Class
	How to Alias Enumeration Names
	Superclass Constructor Returns Underlying Value
	Default Converter
N	Mutable Handle vs. Immutable Value Enumeration Members
	Select Handle- or Value-Based Enumerations
	Value-Based Enumeration Classes
	Handle-Based Enumeration Classes
	Represent State with Enumerations
E	Enumerations That Encapsulate Data
	Enumeration Classes with Properties
	Store Data in Properties
c	ave and Load Enumerations
J	Basic Knowledge
	Built-In and Value-Based Enumeration Classes
	Simple and Handle-Based Enumeration Classes
	Causes: Load as struct Instead of Object
	Sausses. Zoud at our dot intitional of Object
	Constant Prov
_	Constant Prop
	Constant Prop
	Define Class Properties with Constant Values
	Define Class Properties with Constant Values
_	Define Class Properties with Constant Values

Constant P	Properties	Do Not	Support	Events

1	5	_	5
		-	

17-7

17-8

Class Metadata	
What Is Class Metadata?	
The matlab.metadata Namespace	
Metaclass Objects	
Metaclass Object Lifecycle	
Class Introspection with Metadata	
Using Class Metadata	
Inspect the EmployeeData Class	
Metaclass EnumeratedValues Property	
Find Objects with Specific Values	
Find Handle Objects	
Find by Attribute Settings	
Get Information About Properties	
The matlab.metadata.Property Object	
How to Find Properties with Specific Attributes	
Find Default Values in Property Metadata	
Default Values	
matlab.metadata.Property Data	
Specialize (Object Bo
Specialize (Object Be
Methods That Modify Default Behavior	
Methods That Modify Default Behavior	
Methods That Modify Default Behavior	
Methods That Modify Default Behavior	
Methods That Modify Default Behavior How to Customize Class Behavior Which Methods Control Which Behaviors Overload Functions and Override Methods Concatenation Methods	
Methods That Modify Default Behavior How to Customize Class Behavior Which Methods Control Which Behaviors Overload Functions and Override Methods Concatenation Methods Default Concatenation	
Methods That Modify Default Behavior How to Customize Class Behavior Which Methods Control Which Behaviors Overload Functions and Override Methods Concatenation Methods Default Concatenation Methods to Overload	
Methods That Modify Default Behavior How to Customize Class Behavior Which Methods Control Which Behaviors Overload Functions and Override Methods Concatenation Methods Default Concatenation Methods to Overload Object Converters	

	Code Patterns for subsref and subsasgn Methods Customize Indexed Reference and Assignment Syntax for subsref and subsasgn Methods Indexing Structure Describes Indexing Expressions Values of the Indexing Structure Typical Patterns for Indexing Methods	17-9 17-9 17-9 17-9 17-10 17-11
	Overload end for Classes Syntax and Default Behavior How RedefinesParen Overloads end	17-15 17-15 17-15
	Objects in Index Expressions Objects as Indexes Ways to Implement Objects as Indices subsindex Implementation	17-17 17-17 17-17 17-17
	Operator Overloading Why Overload Operators How to Define Operators Sample Implementation — Addable Objects MATLAB Operators and Associated Functions	17-19 17-19 17-19 17-20 17-21
	Customize Parentheses Indexing for Mapping Class	17-23
	Forward Indexing Operations	17-30
L8	Customizing Object Di	splay
L8	Custom Display Interface Command Window Display Default Object Display CustomDisplay Class Methods for Customizing Object Display	18-2 18-2 18-2 18-3 18-3
18	Custom Display Interface	18-2 18-2 18-2 18-3
L8	Custom Display Interface Command Window Display Default Object Display CustomDisplay Class Methods for Customizing Object Display How CustomDisplay Works Steps to Display an Object	18-2 18-2 18-2 18-3 18-3 18-7 18-7
18	Custom Display Interface Command Window Display Default Object Display CustomDisplay Class Methods for Customizing Object Display How CustomDisplay Works Steps to Display an Object Methods Called for a Given Object State Role of size Function in Custom Displays How size Is Used	18-2 18-2 18-3 18-3 18-7 18-7 18-7 18-9 18-9

Ways to Implement a Custom Display	
Sumple ripproudings Comy the Interface	• • • • •
Customize Property Display	· · · · ·
Objective	
Change the Property Order	
Change the Values Displayed for Properties	
Customize Header, Property List, and Footer	
Objective	
Design of Custom Display	
getHeader Method Override	
getPropertyGroups Override	
getFooter Override	
Customize Display of Scalar Objects	
Objective	
Design of Custom Display	
displayScalarObject Method Override	
getPropertyGroups Override	
Customize Display of Object Arrays	
Objective	
Design of Custom Display	
The displayNonScalarObject Override	
The displayEmptyObject Override	
Overloading the disp Function	
Display Methods	
Overloaded disp	
Relationship Between disp and display	
Custom Compact Display Interface	
Custom Compact Display Interface	
Custom Compact Display Interface	
Custom Compact Display Interface	
Custom Compact Display Interface Customization Options Available for Compact Display Designing a Class with a Customized Compact Display Defining Custom Representing Polynomials with Classes	Data T
Custom Compact Display Interface Customization Options Available for Compact Display Designing a Class with a Customized Compact Display Defining Custom Representing Polynomials with Classes Class Requirements	Data T
Custom Compact Display Interface Customization Options Available for Compact Display Designing a Class with a Customized Compact Display Defining Custom Representing Polynomials with Classes Class Requirements DocPolynom Class Members	Data T
Custom Compact Display Interface Customization Options Available for Compact Display Designing a Class with a Customized Compact Display Defining Custom Representing Polynomials with Classes Class Requirements DocPolynom Class Members DocPolynom Class Synopsis	Data T
Custom Compact Display Interface Customization Options Available for Compact Display Designing a Class with a Customized Compact Display Defining Custom Representing Polynomials with Classes Class Requirements DocPolynom Class Members DocPolynom Class Synopsis The DocPolynom Constructor	Data T
Custom Compact Display Interface Customization Options Available for Compact Display Designing a Class with a Customized Compact Display Defining Custom Representing Polynomials with Classes Class Requirements DocPolynom Class Members DocPolynom Class Synopsis The DocPolynom Constructor Convert DocPolynom Objects to Other Classes	Data T
Custom Compact Display Interface Customization Options Available for Compact Display Designing a Class with a Customized Compact Display Defining Custom Representing Polynomials with Classes Class Requirements DocPolynom Class Members DocPolynom Class Synopsis The DocPolynom Constructor Convert DocPolynom Objects to Other Classes Overload disp for DocPolynom	Data T
Custom Compact Display Interface Customization Options Available for Compact Display Designing a Class with a Customized Compact Display Defining Custom Representing Polynomials with Classes Class Requirements DocPolynom Class Members DocPolynom Class Synopsis The DocPolynom Constructor Convert DocPolynom Objects to Other Classes	Data T

Designing Related Classes

20

A	Class Hierarchy for Heterogeneous Arrays
	Interfaces Based on Heterogeneous Arrays
	Define Heterogeneous Hierarchy
	Assets Class
	Stocks Class
	Bonds Class
	Cash Class
	Default Object
	Operating on an Assets Array

Using Object-Oriented Design in MATLAB

- "Why Use Object-Oriented Design" on page 1-2
- "Handle Object Behavior" on page 1-7

Why Use Object-Oriented Design

In this section...

"Approaches to Writing MATLAB Programs" on page 1-2

"When Should You Create Object-Oriented Programs" on page 1-2

Approaches to Writing MATLAB Programs

Creating software applications typically involves designing the application data and implementing operations performed on that data. Procedural programs pass data to functions, which perform the necessary operations on the data. Object-oriented software encapsulates data and operations in objects that interact with each other via the object's interface.

The MATLAB language enables you to create programs using both procedural and object-oriented techniques and to use objects and ordinary functions together in your programs.

Procedural Program Design

In procedural programming, your design focuses on the steps that must execute to achieve a desired state. Typically, you represent data as individual variables or fields of a structure. You implement operations as functions that take the variables as arguments. Programs usually call a sequence of functions, each one of which is passed data, and then returns modified data. Each function performs an operation or many operations on the data.

Object-Oriented Program Design

The object-oriented program design involves:

- · Identifying the components of the system or application that you want to build
- Analyzing and identifying patterns to determine what components are used repeatedly or share characteristics
- Classifying components based on similarities and differences

After performing this analysis, you define classes that describe the objects your application uses.

Classes and Objects

A class describes a set of objects with common characteristics. Objects are specific instances of a class. The values contained in an object's properties are what make an object different from other objects of the same class. The functions defined by the class (called methods) are what implement object behaviors that are common to all objects of a class.

When Should You Create Object-Oriented Programs

You can implement simple programming tasks as simple functions. However, as the magnitude and complexity of your tasks increase, functions become more complex and difficult to manage.

As functions become too large, you can break them into smaller functions and pass data from one to function to another. However, as the number of functions becomes large, designing, and managing the data passed to functions becomes difficult and error prone. At this point, consider moving your MATLAB programming tasks to object-oriented designs.

Understand a Problem in Terms of Its Objects

Thinking in terms of objects is simpler and more natural for some problems. Think of the nouns in your problem statement as the objects to define and the verbs as the operations to perform.

Consider the design of classes to represent money lending institutions (banks, mortgage companies, individual money lenders, and so on). It is difficult to represent the various types of lenders as procedures. However, you can represent each one as an object that performs certain actions and contains certain data. The process of designing the objects involves identifying the characteristics of a lender that are important to your application.

Identify Commonalities

What do all money lenders have in common? All MoneyLender objects can have a loan method and an InterestRate property, for example.

Identify Differences

How does each money lender differ? One can provide loans to businesses while another provides loans only to individuals. Therefore, the loan operation might need to be different for different types of lending institutions. Subclasses of a base MoneyLender class can specialize the subclass versions of the loan method. Each lender can have a different value for its InterestRate property.

Factor out commonalities into a superclass and implement what is specific to each type of lender in the subclass.

Add Only What Is Necessary

These institutions might engage in activities that are not of interest to your application. During the design phase, determine what operations and data an object must contain based on your problem definition.

Objects Manage Internal State

Objects provide several useful features not available from structures and cell arrays. For example, objects can:

- Constrain the data values assigned to any given property
- Calculate the value of a property only when it is gueried
- Broadcast notices when any property value is gueried or changed
- Restrict access to properties and methods

Reducing Redundancy

As the complexity of your program increases, the benefits of an object-oriented design become more apparent. For example, suppose that you implement the following procedure as part of your application:

- 1 Check inputs
- **2** Perform computation on the first input argument
- **3** Transform the result of step 2 based on the second input argument
- 4 Check validity of outputs and return values

You can implement this procedure as an ordinary function. But suppose that you use this procedure again somewhere in your application, except that step 2 must perform a different computation. You

could copy and paste the first implementation, and then rewrite step 2. Or you could create a function that accepted an option indicating which computation to make, and so on. However, these options lead to more complicated code.

An object-oriented design can factor out the common code into what is called a base class. The base class would define the algorithm used and implement whatever is common to all cases that use this code. Step 2 could be defined syntactically, but not implemented, leaving the specialized implementation to the classes that you then derive from this base class.

```
Step 1
function checkInputs()
   % actual implementation
end
Step 2
function results = computeOnFirstArg()
   % specify syntax only
end
Step 3
function transformResults()
   % actual implementation
end
Step 4
function out = checkOutputs()
   % actual implementation
end
```

The code in the base class is not copied or modified. Classes you derive from the base class inherit this code. Inheritance reduces the amount of code to be tested, and isolates your program from changes to the basic procedure.

Defining Consistent Interfaces

The use of a class as the basis for similar, but more specialized classes is a useful technique in object-oriented programming. This class defines a common interface. Incorporating this kind of class into your program design enables you to:

- Identify the requirements of a particular objective
- Encode requirements into your program as an interface class


Reducing Complexity

Objects reduce complexity by reducing what you must know to use a component or system:

- Objects provide an interface that hides implementation details.
- Objects enforce rules that control how objects interact.

To illustrate these advantages, consider the implementation of a data structure called a doubly linked list. See "Implementing Linked Lists with Classes" on page 3-23 for the actual implementation.

Here is a diagram of a three-element list:




To add a node to the list, disconnect the existing nodes in the list, insert the new node, and reconnect the nodes appropriately. Here are the basic steps:

First disconnect the nodes:

- 1 Unlink n2. Prev from n1
- 2 Unlink n1.Next from n2

Now create the new node, connect it, and renumber the original nodes:

- 1 Link new. Prev to n1
- 2 Link new. Next to n3 (was n2)
- 3 Link n1.Next to new (will be n2)
- 4 Link n3. Prev to new (will be n2)



The details of how methods perform these steps are encapsulated in the class design. Each node object contains the functionality to insert itself into or remove itself from the list.

For example, in this class, every node object has an insertAfter method. To add a node to a list, create the node object and then call its insertAfter method:

nnew = NodeConstructor; nnew.insertAfter(n1)

Because the node class defines the code that implements these operations, this code is:

- Implemented in an optimal way by the class author
- Always up to date with the current version of the class
- Properly tested
- Can automatically update old-versions of the objects when they are loaded from MAT-files.

The object methods enforce the rules for how the nodes interact. This design removes the responsibility for enforcing rules from the applications that use the objects. It also means that the application is less likely to generate errors in its own implementation of the process.

Fostering Modularity

As you decompose a system into objects (car -> engine -> fuel system -> oxygen sensor), you form modules around natural boundaries. Classes provide three levels of control over code modularity:

- Public Any code can access this particular property or call this method.
- Protected Only this object's methods and methods of objects derived from this object's class can access this property or call this method.
- Private Only the object's own methods can access this property or call this method.

Overloaded Functions and Operators

When you define a class, you can overload existing MATLAB functions to work with your new object. For example, the MATLAB serial port class overloads the fread function to read data from the device connected to the port represented by this object. You can define various operations, such as equality (eq) or addition (plus), for a class you have defined to represent your data.

See Also

More About

"Role of Classes in MATLAB" on page 3-2

Handle Object Behavior

In this section... "What Is a Handle?" on page 1-7 "Copies of Handles" on page 1-7 "Handle Objects Modified in Functions" on page 1-8 "Determine If an Object Is a Handle" on page 1-9

"Deleted Handle Objects" on page 1-9

More than one variable can refer to the same handle object. Therefore, users interact with instances of handle classes differently than instances of value classes. Understanding how handle objects behave can help you determine whether to implement a handle or a value class. This topic illustrates some of those interactions.

For more information on handle classes, see "Handle Classes".

What Is a Handle?

Certain kinds of MATLAB objects are handles. When a variable holds a handle, it actually holds a reference to the object.

Handle objects enable more than one variable to refer to the same object. Handle-object behavior affects what happens when you copy handle objects and when you pass them to functions.

Copies of Handles

All copies of a handle object variable refer to the same underlying object. This reference behavior means that if h identifies a handle object, then,

```
h2 = h;
```

Creates another variable, h2, that refers to the same object as h.

For example, the MATLAB audioplayer function creates a handle object that contains the audio source data to reproduce a specific sound segment. The variable returned by the audioplayer function identifies the audio data and enables you to access object functions to play the audio.

MATLAB software includes audio data that you can load and use to create an audioplayer object. This sample load audio data, creates the audio player, and plays the audio:

```
load gong Fs y
gongSound = audioplayer(y,Fs);
play(gongSound)
```

Suppose that you copy the gongSound object handle to another variable (gongSound2):

```
gongSound2 = gongSound;
```

The variables gongSound and gongSound2 are copies of the same handle and, therefore, refer to the same audio source. Access the audioplayer information using either variable.

For example, set the sample rate for the gong audio source by assigning a new value to the SampleRate property. First get the current sample rate and then set a new sample rate:

```
sr = gongSound.SampleRate;
disp(sr)
8192
gongSound.SampleRate = sr*2;
You can use gongSound2 to access the same audio source:
disp(gongSound2.SampleRate)
16384
Play the gong sound with the new sample rate:
play(gongSound2)
```

Handle Objects Modified in Functions

When you pass an argument to a function, the function copies the variable from the workspace in which you call the function into the parameter variable in the function's workspace.

Passing a nonhandle variable to a function does not affect the original variable that is in the caller's workspace. For example, myFunc modifies a local variable called var, but when the function ends, the local variable var no longer exists:

```
function myFunc(var)
   var = var + 1;
Define a variable and pass it to myfunc:
x = 12;
myFunc(x)
The value of x has not changed after executing myFunc(x):
disp(x)
12
```

The myFunc function can return the modified value, which you could assign to the same variable name (x) or another variable.

```
function out = myFunc(var)
   out = var + 1;
end
Modify a value in myfunc:
x = 12;
x = myFunc(x);
disp(x)
13
```

When the argument is a handle variable, the function copies only the handle, not the object identified by that handle. Both handles (original and local copy) refer to the same object.

When the function modifies the data referred to by the object handle, those changes are accessible from the handle variable in the calling workspace without the need to return the modified object.

For example, the modifySampleRate function changes the audioplayer sample rate:

```
function modifySampleRate(audioObj,sr)
  audioObj.SampleRate = sr;
end
```

Create an audioplayer object and pass it to the modifySampleRate function:

```
load gong Fs y
gongSound = audioplayer(y,Fs);
disp(gongSound.SampleRate)

8192

modifySampleRate(gongSound,16384)
disp(gongSound.SampleRate)

16384
```

The modifySampleRate function does not need to return a modified gongSound object because audioplayer objects are handle objects.

Determine If an Object Is a Handle

Handle objects are members of the handle class. Therefore, you can always identify an object as a handle using the isa function. isa returns logical true (1) when testing for a handle variable:

```
load gong Fs y
gongSound = audioplayer(y,Fs);
isa(gongSound,'handle')

To determine if a variable is a valid handle object, use isa and isvalid:
if isa(gongSound,'handle') && isvalid(gongSound)
...
end
```

Deleted Handle Objects

When a handle object has been deleted, the handle variables that referenced the object can still exist. These variables become invalid because the object they referred to no longer exists. Calling delete on the object removes the object, but does not clear handle variables.

For example, create an audioplayer object:

```
load gong Fs y
gongSound = audioplayer(y,Fs);
```

The output argument, gongSound, is a handle variable. Calling delete deletes the object along with the audio source information it contains:

delete(gongSound)

However, the handle variable still exists.

disp(gongSound)

```
handle to deleted audioplayer
```

The handle gongSound no longer refers to a valid object, as shown by the isvalid handle method:

isvalid(gongSound)

```
ans =
 logical
```

Calling delete on a deleted handle does nothing and does not cause an error. You can pass an array containing both valid and invalid handles to delete. MATLAB deletes the valid handles, but does not issue an error when encountering handles that are already invalid.

You cannot access properties with the invalid handle variable:

gongSound.SampleRate

```
Invalid or deleted object.
```

Functions and methods that access object properties cause an error:

play(gongSound)

```
Invalid or deleted object.
```

To remove the variable, gongSound, use clear:

clear gongSound whos

Name	Size	Bytes	Class	Attributes
Fs	1x1	8	double	
y	42028x1	336224	double	

See Also

More About

- "Handle Class Destructor" on page 7-13
- "Comparison of Handle and Value Classes" on page 7-2

Basic Example

Creating a Simple Class

```
In this section...

"Design Class" on page 2-2

"Create Object" on page 2-3

"Access Properties" on page 2-3

"Call Methods" on page 2-3

"Add Constructor" on page 2-4

"Vectorize Methods" on page 2-4

"Overload Functions" on page 2-5

"BasicClass Code Listing" on page 2-6
```

Design Class

The basic purpose of a class is to define an object that encapsulates data and the operations performed on that data. For example, BasicClass defines a property and two methods that operate on the data in that property:

- Value Property that contains the numeric data stored in an object of the class
- roundOff Method that rounds the value of the property to two decimal places
- multiplyBy Method that multiplies the value of the property by the specified number

Start a class definition with a classdef *ClassName...*end block, and then define the class properties and methods inside that block. Here is the definition of BasicClass:

```
classdef BasicClass
  properties
    Value {mustBeNumeric}
  end
  methods
    function r = roundOff(obj)
        r = round([obj.Value],2);
  end
    function r = multiplyBy(obj,n)
        r = [obj.Value]*n;
  end
  end
end
```

For a summary of class syntax, see classdef.

To use the class:

- Save the class definition in a .m file with the same name as the class.
- · Create an object of the class.
- Access the properties to assign data.
- Call methods to perform operation on the data.

Create Object

Create an object of the class using the class name:

```
a = BasicClass
a =
BasicClass with properties:
    Value: []
```

Initially, the property value is empty.

Access Properties

Assign a value to the Value property using the object variable and a dot before the property name:

```
a. Value = pi/3;
```

To return a property value, use dot notation without the assignment:

a.Value

```
ans = 1.0472
```

For information on class properties, see "Property Syntax" on page 8-4.

Call Methods

Call the roundOff method on object a:

```
roundOff(a)
ans =
    1.0500
```

Pass the object as the first argument to a method that takes multiple arguments, as in this call to the multiplyBy method:

```
multiplyBy(a,3)
ans =
     3.1416
```

You can also call a method using dot notation:

```
a.multiplyBy(3)
```

Passing the object as an explicit argument is not necessary when using dot notation. The notation uses the object to the left of the dot.

For information on class methods, see "Method Syntax" on page 5-7.

Add Constructor

Classes can define a special method to create objects of the class, called a constructor. Constructor methods enable you to pass arguments to the constructor, which you can assign as property values. The BasicClass Value property restricts its possible values using the mustBeNumeric function.

Here is a constructor for the BasicClass class. When you call the constructor with an input argument, it is assigned to the Value property. If you call the constructor without an input argument, the Value property has a default value of empty ([]).

```
methods
   function obj = BasicClass(val)
       if nargin == 1
       obj.Value = val;
   end
  end
end
```

By adding this constructor to the class definition, you can create an object and set the property value in one step:

```
a = BasicClass(pi/3)
a =
BasicClass with properties:
Value: 1.0472
```

The constructor can perform other operations related to creating objects of the class.

For information on constructors, see "Class Constructor Methods" on page 9-15.

Vectorize Methods

MATLAB enables you to vectorize operations. For example, you can add a number to a vector:

```
[1 2 3] + 2
ans =
```

MATLAB adds the number 2 to each of the elements in the array [1 2 3]. To vectorize the arithmetic operator methods, enclose the obj. Value property reference in brackets.

```
[obj.Value] + 2
```

This syntax enables the method to work with arrays of objects. For example, create an object array using indexed assignment.

```
obj(1) = BasicClass(2.7984);
obj(2) = BasicClass(sin(pi/3));
obj(3) = BasicClass(7);
```

These two expressions are equivalent.

```
[obj.Value] + 2
[obj(1).Value obj(2).Value obj(3).Value] + 2
The roundOff method is vectorized because the property reference is enclosed in brackets.
r = round([obj.Value],2);
Because roundOff is vectorized, it can operate on arrays.
roundOff(obj)
ans =
    2.8000    0.8700    7.0000
```

Overload Functions

Classes can implement existing functionality, such as addition, by defining a method with the same name as the existing MATLAB function. For example, suppose that you want to add two BasicClass objects. It makes sense to add the values of the Value properties of each object.

Here is an overloaded version of the MATLAB plus function. It defines addition for the BasicClass class as adding the property values:

```
methods
  function r = plus(o1,o2)
    r = [o1.Value] + [o2.Value];
  end
end
```

By implementing a method called plus, you can use the "+" operator with objects of BasicClass.

```
a = BasicClass(pi/3);
b = BasicClass(pi/4);
a + b
ans =
1.8326
```

By vectorizing the plus method, you can operate on object arrays.

```
a = BasicClass(pi/3);
b = BasicClass(pi/4);
c = BasicClass(pi/2);
ar = [a b];
ar + c
ans =
2.6180 2.3562
```

Related Information

For information on overloading functions, see "Overload Functions in Class Definitions" on page 9-26.

For information on overloading operators, see "Operator Overloading" on page 17-19.

BasicClass Code Listing

Here is the BasicClass definition after adding the features discussed in this topic:

```
classdef BasicClass
    properties
        Value {mustBeNumeric}
    methods
        function obj = BasicClass(val)
            if nargin == 1
                obj.Value = val;
            end
        end
        function r = roundOff(obj)
            r = round([obj.Value],2);
        function r = multiplyBy(obj,n)
            r = [obj.Value] * n;
        end
        function r = plus(o1,o2)
            r = [o1.Value] + [o2.Value];
        end
    end
end
```

See Also

Related Examples

- "Components of a Class" on page 5-2
- "Validate Property Values" on page 8-19

MATLAB Classes Overview

- "Role of Classes in MATLAB" on page 3-2
- "Developing Classes That Work Together" on page 3-6
- "Representing Structured Data with Classes" on page 3-14
- "Implementing Linked Lists with Classes" on page 3-23
- "Working with Objects in MATLAB" on page 3-37

Role of Classes in MATLAB

```
In this section...

"Classes" on page 3-2

"Some Basic Relationships" on page 3-3
```

Classes

In the MATLAB language, every value is assigned to a class. For example, creating a variable with an assignment statement constructs a variable of the appropriate class:

```
a = 7;
b = 'some text';
s.Name = 'Nancy';
s.Age = 64;
whos
whos
                           Bvtes Class
                                          Attributes
 Name
           Size
           1x1
                              8 double
 а
           1x9
                              18 char
 h
                             370 struct
```

Basic commands like whos display the class of each value in the workspace. This information helps MATLAB users recognize that some values are characters and display as text while other values are double precision numbers, and so on. Some variables can contain different classes of values like structures.

Predefined Classes

MATLAB defines fundamental classes that comprise the basic types used by the language. These classes include numeric, logical, char, cell, struct, and function handle.

User-Defined Classes

You can create your own MATLAB classes. For example, you could define a class to represent polynomials. This class could define the operations typically associated with MATLAB classes, like addition, subtraction, indexing, displaying in the command window, and so on. These operations would need to perform the equivalent of polynomial addition, polynomial subtraction, and so on. For example, when you add two polynomial objects:

```
p1 + p2
```

the plus operation must be able to add polynomial objects because the polynomial class defines this operation.

When you define a class, you can overload special MATLAB functions (such as plus.m for the addition operator). MATLAB calls these methods when users apply those operations to objects of your class.

See "Representing Polynomials with Classes" on page 19-2 for an example that creates just such a class.

MATLAB Classes — Key Terms

MATLAB classes use the following words to describe different parts of a class definition and related concepts.

- Class definition Description of what is common to every instance of a class.
- Properties Data storage for class instances
- Methods Special functions that implement operations that are usually performed only on instances of the class
- Events Messages defined by classes and broadcast by class instances when some specific action occurs
- Attributes Values that modify the behavior of properties, methods, events, and classes
- Listeners Objects that respond to a specific event by executing a callback function when the event notice is broadcast
- Objects Instances of classes, which contain actual data values stored in the objects' properties
- Subclasses Classes that are derived from other classes and that inherit the methods, properties, and events from those classes (subclasses facilitate the reuse of code defined in the superclass from which they are derived).
- Superclasses Classes that are used as a basis for the creation of more specifically defined classes (that is, subclasses).
- Namespaces Folders that define a scope for class and function naming

Some Basic Relationships

This section discusses some of the basic concepts used by MATLAB classes.

Classes


A class is a definition that specifies certain characteristics that all instances of the class share. These characteristics are determined by the properties, methods, and events that define the class and the values of attributes that modify the behavior of each of these class components. Class definitions describe how objects of the class are created and destroyed, what data the objects contain, and how you can manipulate this data.

Class Hierarchies

It sometimes makes sense to define a new class in terms of existing classes. This approach enables you to reuse the designs and techniques in a new class that represents a similar entity. You accomplish this reuse by creating a subclass. A subclass defines objects that are a subset of those objects defined by the superclass. A subclass is more specific than its superclass and might add new properties, methods, and events to those components inherited from the superclass.

Mathematical sets can help illustrate the relationships among classes. In the following diagram, the set of Positive Integers is a subset of the set of Integers and a subset of Positives. All three sets are subsets of Reals, which is a subset of All Numbers.

The definition of Positive Integers requires the additional specification that members of the set be greater than zero. Positive Integers combine the definitions from both Integers and Positives. The resulting subset is more specific, and therefore more narrowly defined, than the supersets, but still shares all the characteristics that define the supersets.



The "is a" relationship is a good way to determine if it is appropriate to define a particular subset in terms of existing supersets. For example, each of the following statements makes senses:

- · A Positive Integer is an Integer
- A Positive Integer is a Positive number

If the "is a" relationship holds, then it is likely you can define a new class from a class or classes that represent some more general case.

Reusing Solutions

Classes are usually organized into taxonomies to foster code reuse. For example, if you define a class to implement an interface to the serial port of a computer, it would probably be similar to a class designed to implement an interface to the parallel port. To reuse code, you could define a superclass that contains everything that is common to the two types of ports, and then derive subclasses from the superclass in which you implement only what is unique to each specific port. Then the subclasses would inherit all the common functionality from the superclass.

Objects

A class is like a template for the creation of a specific instance of the class. This instance or object contains actual data for a particular entity that is represented by the class. For example, an instance of a bank account class is an object that represents a specific bank account, with an actual account number and an actual balance. This object has built into it the ability to perform operations defined by the class, such as making deposits to and withdrawals from the account balance.

Objects are not just passive data containers. Objects actively manage the data contained by allowing only certain operations to be performed, by hiding data that does not need to be public, and by preventing external clients from misusing data by performing operations for which the object was not designed. Objects even control what happens when they are destroyed.

Encapsulating Information

An important aspect of objects is that you can write software that accesses the information stored in the object via its properties and methods without knowing anything about how that information is stored, or even whether it is stored or calculated when queried. The object isolates code that accesses the object from the internal implementation of methods and properties. You can define classes that hide both data and operations from any methods that are not part of the class. You can then implement whatever interface is most appropriate for the intended use.

References

- [1] Shalloway, A., J. R. Trott, Design Patterns Explained A New Perspective on Object-Oriented Design.. Boston, MA: Addison-Wesley 2002.
- [2] Gamma, E., R. Helm, R. Johnson, J. Vlissides, *Design Patterns Elements of Reusable Object-Oriented Software*. Boston, MA: Addison-Wesley 1995.
- [3] Freeman, E., Bert Bates, Kathy Sierra, Elisabeth Robson, *Head First Design Patterns*. O'Reilly Media, 2004.

See Also

Related Examples

- "Creating a Simple Class" on page 2-2
- "Developing Classes That Work Together" on page 3-6
- "Representing Structured Data with Classes" on page 3-14
- "Implementing Linked Lists with Classes" on page 3-23

Developing Classes That Work Together

In this section...

"Formulating a Class" on page 3-6

"Specifying Class Components" on page 3-7

"BankAccount Class Implementation" on page 3-7

"Formulating the AccountManager Class" on page 3-10

"Implementing the AccountManager Class" on page 3-11

"AccountManager Class Synopsis" on page 3-11

"Using BankAccount Objects" on page 3-12

Formulating a Class

This example discusses how to approach the design and implementation of two classes that interact through events and listeners. The two classes represent a bank account and an account manager.

To design a class that represents a bank account, first determine the elements of data and the operations that form your abstraction of a bank account. For example, a bank account has:

- · An account number
- An account balance
- A status (open, closed, etc.)

You must perform certain operations on a bank account:

- Create an object for each bank account
- · Deposit money
- Withdraw money
- · Generate a statement
- Save and load the BankAccount object

If the balance is too low and you attempt to withdraw money, the bank account broadcasts a notice. When this event occurs, the bank account broadcasts a notice to other entities that are designed to listen for these notices. In this example, a simplified version of an account manager program performs this task.

In this example, an account manager program determines the status of all bank accounts. This program monitors the account balance and assigns one of three values:

- open Account balance is a positive value
- overdrawn Account balance is overdrawn, but by \$200 or less.
- closed Account balance is overdrawn by more than \$200.

These features define the requirements of the BankAccount and AccountManager classes. Include only what functionality is required to meet your specific objectives. Support special types of accounts by subclassing BankAccount and adding more specific features to the subclasses. Extend the AccountManager as required to support new account types.

Specifying Class Components

Classes store data in properties, implement operations with methods, and support notifications with events and listeners. Here is how the BankAccount and AccountManager classes define these components.

Class Data

The class defines these properties to store the account number, account balance, and the account status:

- AccountNumber A property to store the number identifying the specific account. MATLAB assigns a value to this property when you create an instance of the class. Only BankAccount class methods can set this property. The SetAccess attribute is private.
- AccountBalance A property to store the current balance of the account. The class operation
 of depositing and withdrawing money assigns values to this property. Only BankAccount class
 methods can set this property. The SetAccess attribute is private.
- AccountStatus The BankAccount class defines a default value for this property. The
 AccountManager class methods change this value whenever the value of the AccountBalance
 falls below 0. The Access attribute specifies that only the AccountManager and BankAccount
 classes have access to this property.
- AccountListener Storage for the InsufficientFunds event listener. Saving a BankAccount object does not save this property because you must recreate the listener when loading the object.

Class Operations

These methods implement the operations defined in the class formulation:

- BankAccount Accepts an account number and an initial balance to create an object that represents an account.
- deposit Updates the AccountBalance property when a deposit transaction occurs
- withdraw Updates the AccountBalance property when a withdrawal transaction occurs
- getStatement Displays information about the account
- loadobj Recreates the account manager listener when you load the object from a MAT-file.

Class Events

The account manager program changes the status of bank accounts that have negative balances. To implement this action, the BankAccount class triggers an event when a withdrawal results in a negative balance. Therefore, the triggering of the InsufficientFunds event occurs from within the withdraw method.

To define an event, specify a name within an events block. Trigger the event by a call to the notify handle class method. Because InsufficientFunds is not a predefined event, you can name it with any char vector and trigger it with any action.

BankAccount Class Implementation

It is important to ensure that there is only one set of data associated with any object of a BankAccount class. You would not want independent copies of the object that could have, for

example, different values for the account balance. Therefore, implement the BankAccount class as a handle class. All copies of a given handle object refer to the same data.

BankAccount Class Synopsis

BankAccount Class	Discussion
<pre>classdef BankAccount < handle</pre>	Handle class because there should be only one copy of any instance of BankAccount. "Comparison of Handle and Value Classes" on page 7-2
<pre>properties (Access = ?AccountManager) AccountStatus = 'open' end</pre>	AccountStatus contains the status of the account determined by the current balance. Access is limited to the BankAccount and AccountManager classes. "Class Members Access" on page 12-23
<pre>properties (SetAccess = private) AccountNumber AccountBalance end</pre>	AccountStatus property access by AccountManager class methods.
properties (Transient) AccountListener end	AccountNumber and AccountBalance properties have private set access.
	AccountListener property is transient so the listener handle is not saved.
	See "Property Attributes" on page 8-8.
events InsufficientFunds end	Class defines event called InsufficientFunds. withdraw method triggers event when account balance becomes negative.
	For information on events and listeners, see "Events".
methods	Block of ordinary methods. See "Method Syntax" on page 5-7 for syntax.
<pre>function BA = BankAccount(AccountNumber,InitialBal BA.AccountNumber = AccountNumber; BA.AccountBlance = InitialBalance; BA.AccountBlatance = AccountManager; BA.AccountBlatance = AccountBlatance = AccountB</pre>	input arguments.
BA.AccountListener = AccountManager.addAccount(end	AccountManager.addAccount is static method of AccountManager class. Creates listener for InsufficientFunds event and stores listener handle in AccountListener property.
<pre>function deposit(BA,amt) BA.AccountBalance = BA.AccountBalance + amt; if BA.AccountBalance > 0 BA.AccountStatus = 'open';</pre>	deposit adjusts value of AccountBalance property.
end end	If AccountStatus is closed and subsequent deposit brings AccountBalance into positive range, then AccountStatus is reset to open.

Discussion BankAccount Class function withdraw(BA,amt) Updates AccountBalance property. If value if (strcmp(BA.AccountStatus,'closed')&& ... of account balance is negative as a result of BA.AccountBalance < 0) disp(['Account ',num2str(BA.AccountNumber),. the withdrawal, notify triggers has been closed.']) InsufficientFunds event. return end For more information on listeners, see "Events newbal = BA.AccountBalance - amt; BA.AccountBalance = newbal; and Listeners Syntax" on page 11-18. if newbal < 0 notify(BA,'InsufficientFunds') end end function getStatement(BA) Display selected information about the ----') account. This section also ends the ordinary disp(['Account: ',num2str(BA.AccountNumber)]) ab = sprintf('%0.2f',BA.AccountBalance); methods block. disp(['CurrentBalance: ',ab]) disp(['Account Status: ',BA.AccountStatus]) disp('----') end end Beginning of static methods block. See "Static methods (Static) Methods" on page 9-24 function obj = loadobj(s) loadobj method: if isstruct(s) accNum = s.AccountNumber; If the load operation fails, create the object initBal = s.AccountBalance; obj = BankAccount(accNum,initBal); from a struct. obj.AccountListener = AccountManager.addAccount(sRecreates the listener using the newly end created BankAccount object as the end source. For more information on saving and loading objects, see "Default Save and Load Process for Objects" on page 13-2 End of static methods block end end End of classdef

Expand for Class Code

```
classdef BankAccount < handle</pre>
  properties (Access = ?AccountManager)
     AccountStatus = 'open
   end
  properties (SetAccess = private)
      AccountNumber
      AccountBalance
  end
  properties (Transient)
      AccountListener
   events
     InsufficientFunds
   end
  methods
      function BA = BankAccount(accNum,initBal)
         BA.AccountNumber = accNum;
         BA.AccountBalance = initBal;
         BA.AccountListener = AccountManager.addAccount(BA);
      end
      function deposit(BA,amt)
```

```
BA.AccountBalance = BA.AccountBalance + amt;
         if BA.AccountBalance > 0
            BA.AccountStatus = 'open';
         end
      end
      function withdraw(BA,amt)
         if (strcmp(BA.AccountStatus,'closed')&& BA.AccountBalance <= 0)</pre>
            disp(['Account ',num2str(BA.AccountNumber),' has been closed.'])
         end
         newbal = BA.AccountBalance - amt;
         BA.AccountBalance = newbal;
         if newbal < 0</pre>
            notify(BA,'InsufficientFunds')
         end
      end
      function getStatement(BA)
                                      ----')
         disp(
         disp(['Account: ',num2str(BA.AccountNumber)])
         ab = sprintf('%0.2f', BA.AccountBalance);
         disp(['CurrentBalance: ',ab])
disp(['Account Status: ',BA.AccountStatus])
         disp('
      end
   end
   methods (Static)
      function obj = loadobj(s)
         if isstruct(s)
            accNum = s.AccountNumber;
            initBal = s.AccountBalance;
            obj = BankAccount(accNum,initBal);
         else
            obj.AccountListener = AccountManager.addAccount(s);
         end
      end
   end
end
```

Formulating the AccountManager Class

The purpose of the AccountManager class is to provide services to accounts. For the BankAccount class, the AccountManager class listens for withdrawals that cause the balance to drop into the negative range. When the BankAccount object triggers the InsufficientFunds event, the AccountManager resets the account status.

The AccountManager class stores no data so it does not need properties. The BankAccount object stores the handle of the listener object.

The AccountManager performs two operations:

- · Assign a status to each account as a result of a withdrawal
- Adds an account to the system by monitoring account balances.

Class Components

The AccountManager class implements two methods:

- assignStatus Method that assigns a status to a BankAccount object. Serves as the listener callback.
- addAccount Method that creates the InsufficientFunds listener.

Implementing the AccountManager Class

The AccountManager class implements both methods as static because there is no need for an AccountManager object. These methods operate on BankAccount objects.

The AccountManager is not intended to be instantiated. Separating the functionality of the AccountManager class from the BankAccount class provides greater flexibility and extensibility. For example, doing so enables you to:

- Extend the AccountManager class to support other types of accounts while keeping the individual account classes simple and specialized.
- Change the criteria for the account status without affecting the compatibility of saved and loaded BankAccount objects.
- Develop an Account superclass that factors out what is common to all accounts without requiring each subclass to implement the account management functionality

AccountManager Class Synopsis

AccountManager Class	Discussion
classdef AccountManager	This class defines the InsufficentFunds event listener and the listener callback.
methods (Static)	There is no need to create an instance of this class so the methods defined are static. See "Static Methods" on page 9-24.
<pre>function assignStatus(BA) if BA.AccountBalance < 0 if BA.AccountBalance < -200 BA.AccountStatus = 'closed'; else BA.AccountStatus = 'overdrawn'; end end</pre>	The assignStatus method is the callback for the InsufficentFunds event listener. It determines the value of a BankAccount object AccountStatus property based on the value of the AccountBalance property.
end	The BankAccount class constructor calls the AccountManager addAccount method to create and store this listener.
<pre>function lh = addAccount(BA) lh = addlistener(BA, 'InsufficientFunds', @(src, ~)AccountManager.assignStatus(src)); end</pre>	addAccount creates the listener for the InsufficentFunds event that the BankAccount class defines.
	See "Control Listener Lifecycle" on page 11- 23
end end	end statements for methods and for classdef.

Expand for Class Code

```
classdef AccountManager
  methods (Static)
   function assignStatus(BA)
    if BA.AccountBalance < 0
        if BA.AccountBalance < -200
        BA.AccountStatus = 'closed';
    else</pre>
```

```
BA.AccountStatus = 'overdrawn';
end
end
end
function lh = addAccount(BA)
lh = addlistener(BA, 'InsufficientFunds', ...
@(src, ~)AccountManager.assignStatus(src));
end
end
end
end
```

Using BankAccount Objects

The BankAccount class, while overly simple, demonstrates how MATLAB classes behave. For example, create a BankAccount object with an account number and an initial deposit of \$500:

```
BA = BankAccount(1234567,500)
BA =

BankAccount with properties:

    AccountNumber: 1234567
    AccountBalance: 500
    AccountListener: [1x1 event.listener]
```

Use the getStatement method to check the status:

```
getStatement(BA)
```

```
Account: 1234567
CurrentBalance: 500.00
Account Status: open
```

Make a withdrawal of \$600, which results in a negative account balance:

```
withdraw(BA,600)
getStatement(BA)

Account: 1234567
CurrentBalance: -100.00
Account Status: overdrawn
```

The \$600 withdrawal triggered the InsufficientFunds event. The current criteria defined by the AccountManager class results in a status of overdrawn.

Make another withdrawal of \$200:

```
Account Status: closed
```

Now the AccountStatus has been set to closed by the listener and further attempts to make withdrawals are blocked without triggering the event:

```
withdraw(BA, 100)
```

Account 1234567 has been closed.

If the AccountBalance is returned to a positive value by a deposit, then the AccountStatus is returned to open and withdrawals are allowed again:

deposit(BA,700)
getStatement(BA)

Account: 1234567

CurrentBalance: 400.00 Account Status: open

Representing Structured Data with Classes

In this section...

"Objects as Data Structures" on page 3-14

"Structure of the Data" on page 3-14

"The TensileData Class" on page 3-14

"Create an Instance and Assign Data" on page 3-15

"Restrict Properties to Specific Values" on page 3-15

"Simplifying the Interface with a Constructor" on page 3-16

"Calculate Data on Demand" on page 3-17

"Displaying TensileData Objects" on page 3-18

"Method to Plot Stress vs. Strain" on page 3-18

"TensileData Class Synopsis" on page 3-19

Objects as Data Structures

This example defines a class for storing data with a specific structure. Using a consistent structure for data storage makes it easier to create functions that operate on the data. A MATLAB struct with field names describing the particular data element is a useful way to organize data. However, a class can define both the data storage (properties) and operations that you can perform on that data (methods). This example illustrates these advantages.

Background for the Example

For this example, the data represents tensile stress/strain measurements. These data are used to calculate the elastic modulus of various materials. In simple terms, stress is the force applied to a material and strain is the resulting deformation. Their ratio defines a characteristic of the material. While this approach is an over simplification of the process, it suffices for this example.

Structure of the Data

This table describes the structure of the data.

Data	Description
Material	char vector identifying the type of material tested
SampleNumber	Number of a particular test sample
Stress	Vector of numbers representing the stress applied to the sample during the test.
Strain	Vector of numbers representing the strain at the corresponding values of the applied stress.
Modulus	Number defining an elastic modulus of the material under test, which is calculated from the stress and strain data

The TensileData Class

This example begins with a simple implementation of the class and builds on this implementation to illustrate how features enhance the usefulness of the class.

The first version of the class provides only data storage. The class defines a property for each of the required data elements.

```
classdef TensileData
  properties
    Material
    SampleNumber
    Stress
    Strain
    Modulus
  end
end
```

Create an Instance and Assign Data

The following statements create a TensileData object and assign data to it:

```
td = TensileData;
td.Material = 'Carbon Steel';
td.SampleNumber = 001;
td.Stress = [2e4 4e4 6e4 8e4];
td.Strain = [.12 .20 .31 .40];
td.Modulus = mean(td.Stress./td.Strain);
```

Advantages of a Class vs. a Structure

Treat the TensileData object (td in the previous statements) much as you would any MATLAB structure. However, defining a specialized data structure as a class has advantages over using a general-purpose data structure, like a MATLAB struct:

• Users cannot accidentally misspell a field name without getting an error. For example, typing the following:

```
td.Modulus = ...
```

would simply add a field to a structure. However, it returns an error when td is an instance of the TensileData class.

- A class is easy to reuse. Once you have defined the class, you can easily extend it with subclasses that add new properties.
- A class is easy to identify. A class has a name so that you can identify objects with the whos and class functions and the Workspace browser. The class name makes it easy to refer to records with a meaningful name.
- A class can validate individual field values when assigned, including class or value.
- A class can restrict access to fields, for example, allowing a particular field to be read, but not changed.

Restrict Properties to Specific Values

Restrict properties to specific values by defining a property set access method. MATLAB calls the set access method whenever setting a value for a property.

Material Property Set Function

The Material property set method restricts the assignment of the property to one of the following strings: aluminum, stainless steel, or carbon steel.

Add this function definition to the methods block.

```
classdef TensileData
   properties
      Material
      SampleNumber
       Stress
      Strain
      Modulus
   end
   methods
       function obj = set.Material(obj,material)
          if (strcmpi(material, 'aluminum') ||...
                 strcmpi(material, 'stainless steel') ||...
strcmpi(material, 'carbon steel'))
              obj.Material = material;
              error('Invalid Material')
          end
       end
   end
end
```

When there is an attempt to set the Material property, MATLAB calls the set.Material method before setting the property value.

If the value matches the acceptable values, the function set the property to that value. The code within set method can access the property directly to avoid calling the property set method recursively.

For example:

```
td = TensileData;
td.Material = 'brass';
Error using TensileData/set.Material
Invalid Material
```

Simplifying the Interface with a Constructor

Simplify the interface to the TensileData class by adding a constructor that:

- Enables you to pass the data as arguments to the constructor
- Assigns values to properties

The constructor is a method having the same name as the class.

```
methods
  function td = TensileData(material,samplenum,stress,strain)
  if nargin > 0
```

```
td.Material = material;
    td.SampleNumber = samplenum;
    td.Stress = stress;
    td.Strain = strain;
    end
    end
end
```

Create a TensileData object fully populated with data using the following statement:

```
td = TensileData('carbon steel',1,...

[2e4 4e4 6e4 8e4],...

[.12 .20 .31 .40]);
```

Calculate Data on Demand

If the value of a property depends on the values of other properties, define that property using the Dependent attribute. MATLAB does not store the values of dependent properties. The dependent property get method determines the property value when the property is accessed. Access can occur when displaying object properties or as the result of an explicit guery.

Calculating Modulus

TensileData objects do not store the value of the Modulus property. The constructor does not have an input argument for the value of the Modulus property. The value of the Modulus:

- Is calculated from the Stress and Strain property values
- Must change if the value of the Stress or Strain property changes

Therefore, it is better to calculate the value of the Modulus property only when its value is requested. Use a property get access method to calculate the value of the Modulus.

Modulus Property Get Method

The Modulus property depends on Stress and Strain, so its Dependent attribute is true. Place the Modulus property in a separate properties block and set the Dependent attribute.

The get. Modulus method calculates and returns the value of the Modulus property.

```
properties (Dependent)
   Modulus
end
```

Define the property get method in a methods block using only default attributes.

```
methods
  function modulus = get.Modulus(obj)
    ind = find(obj.Strain > 0);
    modulus = mean(obj.Stress(ind)./obj.Strain(ind));
  end
end
```

This method calculates the average ratio of stress to strain data after eliminating zeros in the denominator data.

MATLAB calls the get. Modulus method when the property is queried. For example,

```
td = TensileData('carbon steel',1,...
       [2e4 4e4 6e4 8e4],...
       [.12 .20 .31 .40]);
td.Modulus

ans =
    1.9005e+005
```

Modulus Property Set Method

To set the value of a Dependent property, the class must implement a property set method. There is no need to allow explicit setting of the Modulus property. However, a set method enables you to provide a customized error message. The Modulus set method references the current property value and then returns an error:

```
methods
  function obj = set.Modulus(obj,~)
    fprintf('%s%d\n','Modulus is: ',obj.Modulus)
    error('You cannot set the Modulus property');
  end
end
```

Displaying TensileData Objects

The TensileData class overloads the disp method. This method controls object display in the command window.

The disp method displays the value of the Material, SampleNumber, and Modulus properties. It does not display the Stress and Strain property data. These properties contain raw data that is not easily viewed in the command window.

The disp method uses fprintf to display formatted text in the command window:

Method to Plot Stress vs. Strain

It is useful to view a graph of the stress/strain data to determine the behavior of the material over a range of applied tension. The TensileData class overloads the MATLAB plot function.

The plot method creates a linear graph of the stress versus strain data and adds a title and axis labels to produce a standardized graph for the tensile data records:

```
methods
  function plot(td,varargin)
    plot(td.Strain,td.Stress,varargin{:})
    title(['Stress/Strain plot for Sample',...
```


```
num2str(td.SampleNumber)])
   ylabel('Stress (psi)')
   xlabel('Strain %')
  end
end
```

The first argument to this method is a TensileData object, which contains the data.

The method passes a variable list of arguments (varargin) directly to the built-in plot function. The TensileData plot method allows you to pass line specifier arguments or property name-value pairs.

For example:

```
td = TensileData('carbon steel',1,...
      [2e4 4e4 6e4 8e4],[.12 .20 .31 .40]);
plot(td,'-+b','LineWidth',2)
```



TensileData Class Synopsis

Example Code	Discussion

classdef TensileData

Value class enables independent copies of object. For more information, see "Comparison of Handle and Value Classes" on page 7-2

Example Code Discussion properties See "Structure of the Data" on page 3-14 Material SampleNumber Stress Strain properties (Dependent) Calculate Modulus when gueried. For Modulus information about this code, see "Calculate" end Data on Demand" on page 3-17. For general information, see "Get and Set Methods for Dependent Properties" on page 8methods For general information about methods, see "Ordinary Methods" on page 9-6 function td = TensileData(material,samplenum,... For information about this code, see stress.strain) "Simplifying the Interface with a Constructor" if nargin > 0on page 3-16. td.Material = material; td.SampleNumber = samplenum; td.Stress = stress; For general information about constructors, see td.Strain = strain; "Class Constructor Methods" on page 9-15 end function obj = set.Material(obj,material) Restrict possible values for Material property. if (strcmpi(material, 'aluminum') ||... strcmpi(material, 'stainless steel') ||... strcmpi(material, 'carbon steel')) For information about this code, see "Restrict obj.Material = material; Properties to Specific Values" on page 3-15. else error('Invalid Material') For general information about property set end end methods, see "Property Get and Set Methods" on page 8-39. function m = get.Modulus(obj) Calculate Modulus property when gueried. ind = find(obj.Strain > 0); m = mean(obj.Stress(ind)./obj.Strain(ind)); For information about this code, see "Modulus Property Get Method" on page 3-17. For general information about property get methods, see "Property Get and Set Methods" on page 8-39. function obj = set.Modulus(obj,~) Add set method for Dependent Modulus fprintf('%s%d\n','Modulus is: ',obj.Modulus) property. For information about this code, see error('You cannot set Modulus property'); "Modulus Property Set Method" on page 3-18. end For general information about property set methods, see "Property Get and Set Methods" on page 8-39.

Example Code Discussion function disp(td) Overload disp method to display certain fprintf(1, 'Material: %s\nSample Number: %g\nModul properties. td.Material,td.SampleNumber,td.Modulus) end For information about this code, see "Displaying TensileData Objects" on page 3-18 For general information about overloading disp, see "Overloading the disp Function" on page function plot(td,varargin) Overload plot function to accept plot(td.Strain,td.Stress,varargin{:}) TensileData objects and graph stress vs. title(['Stress/Strain plot for Sample',... num2str(td.SampleNumber)]) strain. ylabel('Stress (psi)') xlabel('Strain %') "Method to Plot Stress vs. Strain" on page 3-18 end end statements for methods and for end classdef.

Expand for Class Code

```
classdef TensileData
   properties
      Material
      SampleNumber
      Stress
      Strain
   end
   properties (Dependent)
      Modulus
   end
   methods
      function td = TensileData(material, samplenum, stress, strain)
         if nargin > 0
            td.Material = material;
            td.SampleNumber = samplenum;
            td.Stress = stress;
            td.Strain = strain;
         end
      end
      function obj = set.Material(obj,material)
         if (strcmpi(material, 'aluminum') ||...
               strcmpi(material, 'stainless steel') ||...
               strcmpi(material, 'carbon steel'))
            obj.Material = material;
         else
            error('Invalid Material')
         end
      end
      function m = get.Modulus(obj)
         ind = find(obj.Strain > 0);
         m = mean(obj.Stress(ind)./obj.Strain(ind));
      end
```

```
function obj = set.Modulus(obj,~)
         fprintf('%s%d\n','Modulus is: ',obj.Modulus)
         error('You cannot set Modulus property');
      end
      function disp(td)
         sprintf('Material: %s\nSample Number: %g\nModulus: %1.5g\n',...
            td.Material,td.SampleNumber,td.Modulus)
      end
      function plot(td,varargin)
         plot(td.Strain,td.Stress,varargin{:})
         title(['Stress/Strain plot for Sample ',...
            num2str(td.SampleNumber)])
         xlabel('Strain %')
         ylabel('Stress (psi)')
      end
   end
end
```

See Also

More About

"Components of a Class" on page 5-2

Implementing Linked Lists with Classes

In this section...

"Class Definition Code" on page 3-23

"dlnode Class Design" on page 3-23

"Create Doubly Linked List" on page 3-24

"Why Use a Handle Class for Linked Lists?" on page 3-25

"dlnode Class Synopsis" on page 3-25

"Specialize the dlnode Class" on page 3-34

Class Definition Code

For the class definition code listing, see "dlnode Class Synopsis" on page 3-25.

To use the class, create a folder named <code>@dlnode</code> and save <code>dlnode.m</code> to this folder. The parent folder of <code>@dlnode</code> must be on the MATLAB path. Alternatively, save <code>dlnode.m</code> to a path folder.

dlnode Class Design

dlnode is a class for creating doubly linked lists in which each node contains:

- Data array
- · Handle to the next node
- · Handle to the previous node

Each node has methods that enable the node to be:


- Inserted before a specified node in a linked list
- Inserted after a specific node in a linked list
- · Removed from a list

Class Properties

The dlnode class implements each node as a handle object with three properties:

- Data Contains the data for this node
- Next Contains the handle of the next node in the list (SetAccess = private)
- Prev Contains the handle of the previous node in the list (SetAccess = private)

This diagram shows a list with three-nodes n1, n2, and n3. It also shows how the nodes reference the next and previous nodes.



Class Methods

The dlnode class implements the following methods:

- dlnode Construct a node and assign the value passed as an input to the Data property
- insertAfter Insert this node after the specified node
- insertBefore Insert this node before the specified node
- removeNode Remove this node from the list and reconnect the remaining nodes
- clearList Remove large lists efficiently
- delete Private method called by MATLAB when deleting the list.

Create Doubly Linked List

Create a node by passing the node's data to the dlnode class constructor. For example, these statements create three nodes with data values 1, 2, and 3:

```
n1 = dlnode(1);
n2 = dlnode(2);
n3 = dlnode(3);
```

Build these nodes into a doubly linked list using the class methods designed for this purpose:

```
n2.insertAfter(n1) % Insert n2 after n1
n3.insertAfter(n2) % Insert n3 after n2
```

Now the three nodes are linked:

```
n1.Next % Points to n2
ans =
  dlnode with properties:
    Data: 2
    Next: [1x1 dlnode]
    Prev: [1x1 dlnode]
n2.Next.Prev % Points back to n2
ans =
  dlnode with properties:
    Data: 2
    Next: [1x1 dlnode]
    Prev: [1x1 dlnode]
n1.Next.Next % Points to n3
ans =
  dlnode with properties:
    Data: 3
    Next: []
    Prev: [1x1 dlnode]
```

```
n3.Prev.Prev % Points to n1
ans =
  dlnode with properties:
    Data: 1
    Next: [1x1 dlnode]
    Prev: []
```

Why Use a Handle Class for Linked Lists?

Each node is unique in that no two nodes can be previous to or next to the same node. For example, a node object, node, contains in its Next property the handle of the next node object, node.Next. Similarly, the Prev property contains the handle of the previous node, node.Prev. Using the three-node linked list defined in the previous section, you can demonstrate that the following statements are true:

```
n1.Next == n2
n2.Prev == n1
Now suppose that you assign n2 to x:
x = n2;
The following two equalities are then true:
```

But each instance of a node is unique so there is only one node in the list that can satisfy the conditions of being equal to n1.Next and having a Prev property that contains a handle to n1. Therefore, x must point to the same node as n2.

There has to be a way for multiple variables to refer to the same object. The MATLAB handle class provides a means for both x and n2 to refer to the same node.

The handle class defines the eq method (use methods ('handle') to list the handle class methods), which enables the use of the == operator with all handle objects.

Related Information

x == n1.Next
x.Prev == n1

For more information on handle classes, see "Comparison of Handle and Value Classes" on page 7-2.

dlnode Class Synopsis

This section describes the implementation of the dlnode class.

Example Code	Discussion
classdef dlnode < handle	"dlnode Class Design" on page 3-23
	"Why Use a Handle Class for Linked Lists?" on page 3-25
	"Comparison of Handle and Value Classes" on page 7-2
properties Data end	"dlnode Class Design" on page 3-23
<pre>properties (SetAccess = private) Next = dlnode.empty Prev = dlnode.empty end</pre>	"Property Attributes" on page 8-8: SetAccess.
end	Initialize these properties to empty dlnode objects.
	For general information about properties, see "Property Syntax" on page 8-4
methods	For general information about methods, see "Methods in Class Design" on page 9-2
<pre>function node = dlnode(Data) if (nargin > 0) node.Data = Data;</pre>	Creating an individual node (not connected) requires only the data.
end end	For general information about constructors, see "Guidelines for Constructors" on page 9-16
<pre>function insertAfter(newNode, nodeBefore) removeNode(newNode); newNode.Next = nodeBefore.Next; newNode.Prev = nodeBefore; if ~isempty(nodeBefore.Next)</pre>	Insert node into a doubly linked list after specified node, or link the two specified nodes if there is not already a list. Assigns the correct values for Next and Prev properties.
<pre>end nodeBefore.Next = newNode; end</pre>	"Insert Nodes" on page 3-29
<pre>function insertBefore(newNode, nodeAfter) removeNode(newNode); newNode.Next = nodeAfter; newNode.Prev = nodeAfter.Prev; if ~isempty(nodeAfter.Prev) nodeAfter.Prev.Next = newNode; end nodeAfter.Prev = newNode;</pre>	Insert node into doubly linked list before specified node, or link the two specified nodes if there is not already a list. This method assigns correct values for Next and Prev properties.
end	See "Insert Nodes" on page 3-29
<pre>function removeNode(node) if ~isscalar(node) error('Nodes must be scalar') end prevNode = node.Prev;</pre>	Remove node and fix the list so that remaining nodes are properly connected. node argument must be scalar.
<pre>nextNode = node.Next; if ~isempty(prevNode) prevNode.Next = nextNode; end</pre>	Once there are no references to node, MATLAB deletes it.
<pre>if ~isempty(nextNode) nextNode.Prev = prevNode; end node.Next = = dlnode.empty; node.Prev = = dlnode.empty; end</pre>	"Remove a Node" on page 3-30

Example Code	Discussion
<pre>function clearList(node) prev = node.Prev; next = node.Next; removeNode(node) while ~isempty(next) node = next; next = node.Next; removeNode(node); end while ~isempty(prev) node = prev; prev = node.Prev; removeNode(node) end end</pre>	Avoid recursive calls to destructor as a result of clearing the list variable. Loop through list to disconnect each node. When there are no references to a node, MATLAB calls the class destructor (see the delete method) before deleting it.
<pre>methods (Access = private) function delete(node) clearList(node) end</pre>	Class destructor method. MATLAB calls the delete method you delete a node that is still connected to the list.
end end	End of private methods and end of class definition.

Expand for Class Code

```
classdef dlnode < handle</pre>
   % dlnode A class to represent a doubly-linked node.
   % Link multiple dlnode objects together to create linked lists.
   properties
      Data
   end
   properties(SetAccess = private)
      Next = dlnode.empty
      Prev = dlnode.empty
   end
   methods
      function node = dlnode(Data)
         % Construct a dlnode object
         if nargin > 0
            node.Data = Data;
         end
      end
      function insertAfter(newNode, nodeBefore)
         % Insert newNode after nodeBefore.
         removeNode(newNode);
         newNode.Next = nodeBefore.Next;
         newNode.Prev = nodeBefore;
         if ~isempty(nodeBefore.Next)
            nodeBefore.Next.Prev = newNode;
         end
         nodeBefore.Next = newNode;
      end
      function insertBefore(newNode, nodeAfter)
         % Insert newNode before nodeAfter.
         removeNode(newNode);
         newNode.Next = nodeAfter;
         newNode.Prev = nodeAfter.Prev;
```

```
if ~isempty(nodeAfter.Prev)
            nodeAfter.Prev.Next = newNode;
         end
         nodeAfter.Prev = newNode;
      end
      function removeNode(node)
         % Remove a node from a linked list.
         if ~isscalar(node)
            error('Input must be scalar')
         prevNode = node.Prev;
         nextNode = node.Next;
         if ~isempty(prevNode)
            prevNode.Next = nextNode;
         end
         if ~isempty(nextNode)
            nextNode.Prev = prevNode;
         node.Next = dlnode.empty;
         node.Prev = dlnode.empty;
      function clearList(node)
         % Clear the list before
         % clearing list variable
         prev = node.Prev;
         next = node.Next;
         removeNode(node)
         while ~isempty(next)
            node = next;
            next = node.Next;
            removeNode(node);
         end
         while ~isempty(prev)
            node = prev;
            prev = node.Prev;
            removeNode(node)
         end
      end
   end
   methods (Access = private)
      function delete(node)
         clearList(node)
      end
   end
end
```

Class Properties

Only dlnode class methods can set the Next and Prev properties because these properties have private set access (SetAccess = private). Using private set access prevents client code from performing any incorrect operation with these properties. The dlnode class methods perform all the operations that are allowed on these nodes.

The Data property has public set and get access, allowing you to query and modify the value of Data as required.

Here is how the dlnode class defines the properties:

```
properties
   Data
end
properties(SetAccess = private)
   Next = dlnode.empty;
   Prev = dlnode.empty;
end
```

Construct a Node Object

To create a node object, specify the node's data as an argument to the constructor:

```
function node = dlnode(Data)
  if nargin > 0
     node.Data = Data;
  end
end
```

Insert Nodes

There are two methods for inserting nodes into the list — insertAfter and insertBefore. These methods perform similar operations, so this section describes only insertAfter in detail.

```
function insertAfter(newNode, nodeBefore)
  removeNode(newNode);
  newNode.Next = nodeBefore.Next;
  newNode.Prev = nodeBefore;
  if ~isempty(nodeBefore.Next)
        nodeBefore.Next.Prev = newNode;
  end
  nodeBefore.Next = newNode;
end
```

How insertAfter Works

First, insertAfter calls the removeNode method to ensure that the new node is not connected to any other nodes. Then, insertAfter assigns the newNode Next and Prev properties to the handles of the nodes that are after and before the newNode location in the list.

For example, suppose that you want to insert a new node, nnew, after an existing node, n1, in a list containing n1-n2-n3.

```
First, create nnew:
nnew = dlnode(rand(3));
Next, call insertAfter to insert nnew into the list after n1:
nnew.insertAfter(n1)
```

The insertAfter method performs the following steps to insert nnew in the list between n1 and n2:

• Set nnew.Next to n1.Next (n1.Next is n2):

```
nnew.Next = n1.Next;
```

• Set nnew.Prev to n1


```
nnew.Prev = n1:
```

• If n1.Next is not empty, then n1.Next is still n2, so n1.Next.Prev is n2.Prev, which is set to nnew

```
n1.Next.Prev = nnew:
```

n1.Next is now set to nnew

```
n1.Next = nnew;
```



Remove a Node


The removeNode method removes a node from a list and reconnects the remaining nodes. The insertBefore and insertAfter methods always call removeNode on the node to insert before attempting to connect it to a linked list.

Calling removeNode ensures that the node is in a known state before assigning it to the Next or Prev property:

```
function removeNode(node)
   if ~isscalar(node)
      error('Input must be scalar')
   end
   prevNode = node.Prev;
   nextNode = node.Next;
   if ~isempty(prevNode)
        prevNode.Next = nextNode;
   end
   if ~isempty(nextNode)
        nextNode.Prev = prevNode;
   end
   node.Next = dlnode.empty;
   node.Prev = dlnode.empty;
end
```

For example, suppose that you remove n2 from a three-node list (n1-n2-n3):

```
n2.removeNode;
```



removeNode removes n2 from the list and reconnects the remaining nodes with the following steps:

```
n1 = n2.Prev;
n3 = n2.Next;
if n1 exists, then
    n1.Next = n3;
if n3 exists, then
    n3.Prev = n1
```

The list is rejoined because n1 connects to n3 and n3 connects to n1. The final step is to ensure that n2.Next and n2.Prev are both empty (that is, n2 is not connected):

```
n2.Next = dlnode.empty;
n2.Prev = dlnode.empty;
```

Removing a Node from a List

Suppose that you create a list with 10 nodes and save the handle to the head of the list:

```
head = dlnode(1);
for i = 10:-1:2
   new = dlnode(i);
   insertAfter(new,head);
end
```

Now remove the third node (Data property assigned the value 3):

```
removeNode(head.Next.Next)
```

Now the third node in the list has a data value of 4:

head.Next.Next

```
ans =
  dlnode with properties:
  Data: 4
  Next: [1x1 dlnode]
  Prev: [1x1 dlnode]
```


And the previous node has a Data value of 2:

head.Next

```
ans =
  dlnode with properties:
  Data: 2
  Next: [1x1 dlnode]
  Prev: [1x1 dlnode]
```

Delete a Node

To delete a node, call the removeNode method on that node. The removeNode method disconnects the node and reconnects the list before allowing MATLAB to destroy the removed node. MATLAB destroys the node once references to it by other nodes are removed and the list is reconnected.



Delete the List

When you create a linked list and assign a variable that contains, for example, the head or tail of the list, clearing that variable causes the destructor to recurse through the entire list. With large enough list, clearing the list variable can result in MATLAB exceeding its recursion limit.

The clearList method avoids recursion and improves the performance of deleting large lists by looping over the list and disconnecting each node. clearList accepts the handle of any node in the list and removes the remaining nodes.

```
function clearList(node)
   if ~isscalar(node)
      error('Input must be scalar')
   end
   prev = node.Prev;
   next = node.Next;
   removeNode(node)
   while ~isempty(next)
      node = next;
      next = node.Next;
```

```
removeNode(node);
   end
   while ~isempty(prev)
      node = prev;
      prev = node.Prev;
      removeNode(node)
   end
end
For example, suppose that you create a list with many nodes:
head = dlnode(1);
for k = 100000:-1:2
   nextNode = dlnode(k);
   insertAfter(nextNode,head)
end
The variable head contains the handle to the node at the head of the list:
head
```

Data: 1 Next: [1x1 dlnode]

Prev: []

head =

head.Next

ans =

dlnode with properties:

dlnode with properties:

Data: 2 Next: [1x1 dlnode] Prev: [1x1 dlnode]

You can call clearList to remove the whole list:

```
clearList(head)
```

The only nodes that have not been deleted by MATLAB are those nodes for which there exists an explicit reference. In this case, those references are head and nextNode:

head

```
head =
  dlnode with properties:
    Data: 1
    Next: []
    Prev: []

nextNode
nextNode =
```

```
dlnode with properties:
  Data: 2
  Next: []
  Prev: []
```

You can remove these nodes by clearing the variables:

```
clear head nextNode
```

The delete Method

The delete method simply calls the clearList method:

```
methods (Access = private)
  function delete(node)
    clearList(node)
  end
end
```

The delete method has private access to prevent users from calling delete when intending to delete a single node. MATLAB calls delete implicitly when the list is destroyed.

To delete a single node from the list, use the removeNode method.

Specialize the dlnode Class

The dlnode class implements a doubly linked list and provides a convenient starting point for creating more specialized types of linked lists. For example, suppose that you want to create a list in which each node has a name.

Rather than copying the code used to implement the dlnode class, and then expanding upon it, you can derive a new class from dlnode (that is, subclass dlnode). You can create a class that has all the features of dlnode and also defines its own additional features. And because dlnode is a handle class, this new class is a handle class too.

NamedNode Class Definition

To use the class, create a folder named <code>@NamedNode</code> and save <code>NamedNode.m</code> to this folder. The parent folder of <code>@NamedNode</code> must be on the MATLAB path. Alternatively, save <code>NamedNode.m</code> to a path folder.

The following class definition shows how to derive the NamedNode class from the dlnode class:

```
classdef NamedNode < dlnode
  properties
    Name = ''
  end
  methods
    function n = NamedNode (name,data)
    if nargin == 0
        name = '';
        data = [];
  end
    n = n@dlnode(data);</pre>
```

```
n.Name = name;
end
end
end
```

The NamedNode class adds a Name property to store the node name.

The constructor calls the class constructor for the dlnode class, and then assigns a value to the Name property.

Use NamedNode to Create a Doubly Linked List

Use the NamedNode class like the dlnode class, except that you specify a name for each node object. For example:

```
n(1) = NamedNode('First Node',100);
n(2) = NamedNode('Second Node',200);
n(3) = NamedNode('Third Node',300);
```

Now use the insert methods inherited from dlnode to build the list:

```
n(2).insertAfter(n(1))
n(3).insertAfter(n(2))
```

A single node displays its name and data when you query its properties:

```
n(1).Next
ans =
 NamedNode with properties:
   Name: 'Second Node'
   Data: 200
   Next: [1x1 NamedNode]
   Prev: [1x1 NamedNode]
n(1).Next.Next
ans =
 NamedNode with properties:
   Name: 'Third Node'
   Data: 300
   Next: []
   Prev: [1x1 NamedNode]
n(3).Prev.Prev
ans =
 NamedNode with properties:
   Name: 'First Node'
   Data: 100
   Next: [1x1 NamedNode]
    Prev: []
```

See Also

More About

"The Handle Superclass" on page 7-11

Working with Objects in MATLAB

Some MATLAB® functions return *objects*. Objects combine data (*properties*) with functions and methods. Object properties contain data, including simple types like numbers or text, or other objects. The functions and methods perform actions on the objects themselves. These functions can act on the object properties or change the state of the object, for example.


Create an Object

When creating an object, you can assign a variable to that object. The variable provides access to the properties and methods of the object. For example, this syntax for the histogram function not only displays a histogram of the data in x but also returns the object as the output h.

```
h = histogram(x)
```

Create a histogram object that displays 1000 random numbers. Calling histogram with an output argument displays the graph, the type or class of the object (Histogram), and a partial list of the object properties and their values.

```
x = randn(1000,1);
h = histogram(x)
```




h =
 Histogram with properties:

```
Data: [1000x1 double]
    Values: [3 1 2 15 17 27 53 79 85 101 127 110 124 95 67 32 27 16 6 6 4 1 2]
    NumBins: 23
    BinEdges: [-3.3000 -3.0000 -2.7000 -2.4000 -2.1000 -1.8000 -1.5000 -1.2000 -0.9000 -0.60
    BinWidth: 0.3000
    BinLimits: [-3.3000 3.6000]
    Normalization: 'count'
    FaceColor: 'auto'
    EdgeColor: [0 0 0]

Use GET to show all properties
```

In the workspace, the histogram object is listed with the other active variables, including the dimensions and the type of object.



Get and Set Object Properties

Object properties contain data. By changing property values, you can modify certain aspects of an object. You can use dot notation with the variable assigned to the object to access and change its properties.


In the case of a histogram object, properties contain the raw data, the number of bins, the height of each bar, and other information that controls the appearance of the histogram. For example, Orientation is a property of histogram objects that determines whether the bars are displayed horizontally or vertically. You can access the value of the property by entering the name of the object (h), a dot, and the property name.

h.Orientation

```
ans =
'vertical'
```

You can change the value of the property using the same syntax, but with the addition of an equal sign and the new value.

```
h.Orientation = "horizontal"
```



```
h =
   Histogram with properties:
```

```
Data: [1000x1 double]
    Values: [3 1 2 15 17 27 53 79 85 101 127 110 124 95 67 32 27 16 6 6 4 1 2]
    NumBins: 23
    BinEdges: [-3.3000 -3.0000 -2.7000 -2.4000 -2.1000 -1.8000 -1.5000 -1.2000 -0.9000 -0.60
    BinWidth: 0.3000
    BinLimits: [-3.3000 3.6000]

Normalization: 'count'
    FaceColor: 'auto'
    EdgeColor: [0 0 0]
```

Use GET to show all properties

Not all object properties are writeable. A property can be read-only, meaning that it can be read, but trying to assign a new value to it returns an error. For example, the Values property of a histogram stores the height of each bar and is calculated when the object is created. It is a read-only property, so you cannot change Values directly.

Functions That Accept Objects

Some functions are designed to perform actions on an object. These functions can be *methods*, which are defined specifically for one class of objects, or can be functions that accept that object as an ordinary input argument. In either case, you can use the variable for the object as an input. For example, <code>Histogram</code> objects include the functions <code>morebins</code> and <code>fewerbins</code>, which increase and


decrease the number of histogram bins, respectively. Access the NumBins property to see how many bins are currently in the histogram.

h.NumBins

ans = 23

Call morebins to increase the number of bins in histogram h. The morebins function increases the number of bins by approximately 10%, so the number of bins increases from 23 to 26.

morebins(h)



ans = 26

Other object-oriented programming languages frequently use dot notation to call methods, such as h.morebins. That syntax also is supported for methods in MATLAB. However, for consistency in sample code, the documentation uses function form for most methods and functions that accept object inputs.

The morebins function does not have any additional input arguments, but that is not true of all functions that accept objects. Besides the object itself, object functions can have additional input arguments, which you can pass to the function with standard function syntax. For example, you can call to an object function that takes two input arguments with this syntax:

functionName(objectVariable,arg1,arg2)

Define Your Own Class-Based Objects

In addition to the objects provided in the MATLAB language, you can define your own class-based objects using object-oriented programming techniques. The language follows standard OO conventions. For more information, start with "Creating a Simple Class" on page 2-2.

See Also

"Fundamental MATLAB Classes" | "Creating a Simple Class" on page 2-2

Static Data

Static Data

```
In this section...

"What Is Static Data" on page 4-2

"Static Variable" on page 4-2

"Static Data Object" on page 4-3

"Constant Data" on page 4-4
```

What Is Static Data

Static data refers to data that all objects of the class share and that you can modify after creation. Use static data to define counters used by class instances or other data that is shared among all objects of a class. Unlike instance data, static data does not vary from one object to another. MATLAB provides several ways to define static data, depending on your requirements.

Static Variable

Classes can use a persistent variable to store static data. Define a static method or local function in which you create a persistent variable. The method or function provides access to this variable. Use this technique when you want to store one or two variables.

Saving an object of the class defining the persistent variable does not save the static data associated with the class. To save your static data in an object, or define more extensive data, use the static data object technique "Static Data Object" on page 4-3

Implementation

The StoreData class defines a static method that declares a persistent variable Var. The setgetVar method provides set and get access to the data in the persistent variable. Because the setgetVar method has public access, you can set and get the data stored in the persistent variable globally. Control the scope of access by setting the method Access attribute.

```
classdef StoreData
  methods (Static)
    function out = setgetVar(data)
        persistent Var;
        if nargin
            Var = data;
        end
        out = Var;
    end
end
end
```

Set the value of the variable by calling setgetVar with an input argument. The method assigns the input value to the persistent variable:

```
StoreData.setgetVar(10);
```

Get the value of the variable by calling setgetVar with no input argument:

```
a = StoreData.setgetVar
```

```
a =
```

Clear the persistent variable by calling clear on the StoreData class:

```
clear StoreData
a = StoreData.setgetVar
a =
[]
```

Add a method like setgetVar to any class in which you want the behavior of a static property.

Static Data Object

To store more extensive data, define a handle class with public properties. Assign an object of the class to a constant property of the class that uses the static data. This technique is useful when you want to:

- Add more properties or methods that modify the data.
- · Save objects of the data class and reload the static data.

Implementation

The SharedData class is a handle class, which enables you to reference the same object data from multiple handle variables:

```
classdef SharedData < handle
   properties
       Data1
       Data2
   end
end</pre>
```

The UseData class is the stub of a class that uses the data stored in the SharedData class. The UseData class stores the handle to a SharedData object in a constant property.

```
classdef UseData
  properties (Constant)
    Data = SharedData
  end
  % Class code here
end
```

The Data property contains the handle of the SharedData object. MATLAB constructs the SharedData object when loading the UseData class. All subsequently created instances of the UseData class refer to the same SharedData object.

To initialize the SharedData object properties, load the UseData class by referencing the constant property.

```
h = UseData.Data
h =
```

```
SharedData with properties:

Data1: []
Data2: []
```

Use the handle to the SharedData object to assign data to property values:

```
h.Data1 = 'MyData1';
h.Data2 = 'MyData2';
```

Each instance of the UseData class refers to the same handle object:

```
a1 = UseData;
a2 = UseData;
```

Reference the data using the object variable:

```
al.Data.Data1
ans =
MyData1
```

Assign a new value to the properties in the SharedData object:

```
al.Data.Data1 = rand(3);
```

All new and existing objects of the UseData class share the same SharedData object. a2 now has the rand(3) data that was assigned to a1 in the previous step:

```
a2.Data.Data1

ans =

0.8147   0.9134   0.2785
0.9058   0.6324   0.5469
0.1270   0.0975   0.9575
```

To reinitialize the constant property, clear all instances of the UseData class and then clear the class:

```
clear a1 a2
clear UseData
```

Constant Data

To store constant values that do not change, assign the data to a constant property. All instances of the class share the same value for that property. Control the scope of access to constant properties by setting the property Access attribute.

The only way to change the value of a constant property is to change the class definition. Use constant properties like public final static fields in Java $^{\circ}$.

See Also

```
persistent | clear
```

Related Examples

- "Define Class Properties with Constant Values" on page 15-2
- "Static Methods" on page 9-24

More About

- "Method Attributes" on page 9-4
- "Property Attributes" on page 8-8
- "Static Properties" on page 5-38

Class Definition—Syntax Reference

- "Components of a Class" on page 5-2
- "Method Syntax" on page 5-7
- "Call Superclass Methods on Subclass Objects" on page 5-11
- "Using a Class to Display Graphics" on page 5-13
- "MATLAB Code Analyzer Warnings" on page 5-18
- "Objects in Conditional Statements" on page 5-20
- "Use of Editor and Debugger with Classes" on page 5-25
- "Automatic Updates for Modified Classes" on page 5-27
- "Comparison of MATLAB and Other OO Languages" on page 5-34

Components of a Class

```
"Class Building Blocks" on page 5-2

"Class Definition Block" on page 5-2

"Properties Block" on page 5-3

"Methods Block" on page 5-3

"Events Block" on page 5-4

"Attribute Specification" on page 5-4

"Enumeration Classes" on page 5-5

"Related Information" on page 5-6
```

Class Building Blocks

MATLAB organizes class definition code into modular blocks, delimited by keywords. All keywords have an associated end statement:

- classdef...end Definition of all class components
- properties...end Declaration of property names, specification of property attributes, assignment of default values
- methods...end Declaration of method signatures, method attributes, and function code
- events...end Declaration of event name and attributes
- enumeration...end Declaration of enumeration members and enumeration values for enumeration classes

properties, methods, events, and enumeration are keywords only within a classdef block.

Class Definition Block

The classdef block contains the class definition within a file that starts with the classdef keyword and terminates with the end keyword.

```
classdef (ClassAttributes) ClassName < SuperClass
    ...
end</pre>
```

For example, this classdef defines a class called MyClass that subclasses the handle class. The class is also defined as sealed, so you cannot use inherit from this class.

```
classdef (Sealed) MyClass < handle
   ...
end</pre>
```

See classdef for more syntax information.

Properties Block

A properties block contains property definitions, including optional initial values. Use a separate block for each unique set of attribute specifications. Each properties block starts with the properties keyword and terminates with the end keyword.

```
properties (PropertyAttributes)
   PropertyName size class {validators} = DefaultValue
end
```

For example, this class defines a private property Prop1 of type double with a default value.

```
classdef MyClass
   properties (SetAccess = private)
      Prop1 double = 12
   end
   ...
end
```

See "Initialize Property Values" on page 8-14 for more information.

Methods Block

A methods block contains function definitions for the class methods. Use a separate block for each unique set of attribute specifications. Each methods block starts with the methods keyword and terminates with the end keyword.

For example, this class defines a protected method MyMethod.

```
classdef MyClass
  methods (Access = protected)
    function obj = myMethod(obj,argl)
    ...
  end
  end
end
end
```

See "Method Syntax" on page 5-7 for more information.

MATLAB differs from languages like C++ and Java in that you must explicitly pass an object of the class to the method.

Using the MyClass example, call MyMethod using the object obj of the class and either function or dot syntax:

```
obj = MyClass;
r = MyMethod(obj,arg1);
r = obj.MyMethod(arg1);
```

For more information, see "Method Invocation" on page 9-11.

Events Block

The events block (one for each unique set of attribute specifications) contains the names of events that this class declares. The events block starts with the events keyword and terminates with the end keyword.

```
classdef ClassName
  events (EventAttributes)
       EventName
  end
  ...
end
```

For example, this class defined an event called StateChange with ListenAccess set to protected.

```
classdef EventSource
   events (ListenAccess = protected)
      StateChanged
   end
   ...
end
```

See "Events" for more information.

Attribute Specification

Attribute Syntax

Attributes modify the behavior of classes and class components (properties, methods, and events). Attributes enable you to define useful behaviors without writing complicated code. For example, you can create a read-only property by setting its SetAccess attribute to private but leaving its GetAccess attribute set to public.

```
properties (SetAccess = private)
   ScreenSize = getScreenSize
end
```

All class definition blocks (classdef, properties, methods, and events) support specific attributes. All attributes have default values. Specify attribute values only in cases where you want to change from the default value.

Note Specify the value of a particular attribute only once in any component block.

Attribute Descriptions

For lists of supported attributes, see:

- "Class Attributes" on page 6-5
- "Property Attributes" on page 8-8
- "Method Attributes" on page 9-4
- "Event Attributes" on page 11-16

Attribute Values

When you specify attribute values, those values affect all the components defined within the defining block. Defining properties with different attribute settings requires multiple properties blocks. Specify multiple attributes in a comma-separated list.

```
properties (SetObservable = true)
   AccountBalance
end

properties (SetAccess = private, Hidden = true)
   SSNumber
   CreditCardNumber
end
```

Simpler Syntax for true/false Attributes

You can use a simpler syntax for attributes whose values are true or false. The attribute name alone implies true and adding the not operator (~) to the name implies false. For example, these two ways of defining a static methods block are equivalent.

```
methods (Static)
end

methods (Static = true)
...
end
```

Similarly, these three ways of defining a nonstatic methods block are equivalent. All attributes that take a logical value have a default value of false, so you can omit the attribute to get the default behavior.

```
methods
...
end

methods (~Static)
...
end

methods (Static = false)
...
end
```

Enumeration Classes

Enumeration classes are specialized classes that define a fixed set of names representing a single type of value. Enumeration classes use an enumeration block that contains the enumeration members defined by the class.

The enumeration block starts with the enumeration keyword and terminates with the end keyword.

```
end ...
```

For example, this class defines two enumeration members that represent the logical values false and true.

```
classdef Boolean < logical
   enumeration
    No (0)
    Yes (1)
   end
end</pre>
```

See "Define Enumeration Classes" on page 14-4 for more information.

Related Information

"Creating a Simple Class" on page 2-2

"Folders Containing Class Definitions" on page 6-14

Method Syntax

```
In this section...

"Methods Definition Block" on page 5-7

"Method Argument Validation" on page 5-8

"Special Considerations for Validation in Methods" on page 5-10
```

This topic describes how to define class methods in MATLAB using methods...end blocks, and it introduces method argument validation. This topic focuses on nonstatic, concrete methods, also referred to as ordinary methods. For other types of methods, see:

- "Class Constructor Methods" on page 9-15
- "Handle Class Destructor" on page 7-13
- "Static Methods" on page 9-24
- "Property Get and Set Methods" on page 8-39
- "Abstract Classes and Class Members" on page 12-68

Methods Definition Block

The methods and end keywords define one or more class methods that have the same attribute settings. The methods themselves are defined using MATLAB function blocks. The syntax for defining a block of ordinary methods is:

```
methods (attributes)
   function method1(obj,arg1,...)
     ...
   end
   function method2(obj,arg1,...)
     ...
   end
   ...
end
```

With the exception of static methods, you must pass an object of the class explicitly to a MATLAB method.

For example, this class defines one public property and two public methods. Each method takes two input arguments: the object itself and a user-provided argument inputArg. The methods calculate the product and quotient of the value of the class property, Property1, and the input argument.

```
classdef methodDemo
  properties
    Property1
  end
  methods
    function prod = propMultiply(obj,inputArg)
       prod = obj.Property1*inputArg;
  end
  function quotient = propDivide(obj,inputArg)
       quotient = obj.Property1/inputArg;
  end
```

```
end
end
```

You can also define multiple method blocks with different attributes. In this example, the first method is protected, and the second method is private. For more information, see "Method Attributes" on page 9-4.

```
classdef attributeDemo
  methods (Access = protected)
    function out = method1(obj,inputArg)
    ...
  end
end
methods (Access = private)
  function out = method2(obj,inputArg)
    ...
end
end
end
end
```

Method Argument Validation

You can define restrictions for method input and output arguments. To validate method arguments, add arguments blocks to your methods in the same way you would with a function. See arguments for more information.

Input Argument Validation

Input argument validation enables you to restrict the size, class, and other characteristics of a method input argument. The syntax for input argument validation is:

```
arguments
  argName1 (dimensions) class {validators} = defaultValue
  ...
end
```

- (dimensions) Input size, specified as a comma-separated list of two or more numbers, such as (1,2).
- class Class, specified as a class name, such as double or the name of a user-defined class.
- {validators} Comma-separated list of validation functions, such as mustBeNumeric and mustBeScalarOrEmpty, enclosed in curly brackets. For a list of validation functions, see "Argument Validation Functions".
- defaultValue Default values must conform to the specified size, type, and validation rules.

See arguments for the full description of elements in input argument validation syntax.

Input argument validation is useful for methods with public access. Restricting the types of argument values allowed from callers of the method can prevent errors before the body of the method is executed. For example, the Rectangle class represents a rectangle in the coordinate plane, with properties specifying its location (X and Y) as well as its width and height.

```
classdef Rectangle
    properties
        X (1,1) double {mustBeReal} = 0
        Y (1,1) double {mustBeReal} = 0
```

```
Width (1.1) double {mustBeReal} = 0
        Height (1,1) double {mustBeReal} = 0
    end
   methods
        function R = enlarge(R, x, y)
            arguments (Input)
                R (1,1) Rectangle
                x (1,1) {mustBeNonnegative}
                y (1,1) {mustBeNonnegative}
            arguments (Output)
                R (1,1) Rectangle
            R.Width = R.Width + x:
            R.Height = R.Height + y;
        end
    end
end
```

The enlarge method increases the height and width of the rectangle by adding the user inputs x and y to Width and Height, respectively. Because the intent of the method is to enlarge one rectangle, the validation restricts the input arguments to scalar values with a (1,1) size restriction and nonnegative numeric values with mustBeNonnegative.

Instantiate the class, and call enlarge with inputs 5 and -1 to enlarge. The argument validation returns an error.

Tip The (Input) attribute for an input arguments block is optional, but it is recommended for readability when defining both input and output argument blocks in a single method. MATLAB interprets an argument block with neither attribute as an input argument block.

Output Argument Validation

The syntax for output argument validation is the same as input validation, except that you must specify (Output) as an attribute of the arguments block, and you cannot set a default value.

```
arguments (Output)
  argName1 (dimensions) class {validators}
  ...
end
```

See arguments for the full description of the output argument validation syntax.

Output argument validation enables class authors to document what type of outputs a method returns, as well as acting as a fail-safe against future changes to the code that might alter the output types. For example, the enlarge method of Rectangle uses output argument validation to ensure that the object method returns a scalar instance of Rectangle.

```
arguments (Output)
R (1,1) Rectangle
end
```

If enlarge were later revised to return only the dimensions of the Rectangle and not the object itself, for example, the output validation would help catch this potential mistake.

Special Considerations for Validation in Methods

Argument validation for class methods works much like it does for functions, but some aspects of argument validation are unique to methods.

- If a classdef file includes method prototypes for methods defined in separate files, any arguments blocks you want to define for those methods must be defined in the separate files. For more information on defining methods in separate files, see "Methods in Separate Files" on page 9-8.
- Subclass methods do not inherit argument validation. To preserve argument validation in subclass methods that override superclass methods, repeat the argument validation from the superclass method in the subclass method.
- Abstract methods do not support argument validation because they cannot define arguments blocks. For more information, see "Abstract Classes and Class Members" on page 12-68.
- Handle class destructor methods cannot use argument validation. In handle classes, a destructor
 method named delete is called by MATLAB when a handle object becomes unreachable or is
 explicitly deleted with a call to delete. A destructor must have exactly one input, no outputs, and
 no argument validation. MATLAB treats a method defined in any other way as an ordinary method
 and does not use it as a destructor. For more information, see "Handle Class Destructor" on page
 7-13.

See Also

arguments

Related Examples

"Function Argument Validation"

Call Superclass Methods on Subclass Objects

```
In this section...

"Superclass Relation to Subclass" on page 5-11

"How to Call Superclass Methods" on page 5-11

"How to Call Superclass Constructor" on page 5-11
```

Superclass Relation to Subclass

Subclasses can override superclass methods to support the greater specialization defined by the subclass. Because of the relationship that a subclass object is a superclass object, it is often useful to call the superclass version of the method before executing the specialized subclass code.

How to Call Superclass Methods

Subclass methods can call superclass methods if both methods have the same name. From the subclass, reference the method name and superclass name with the @ symbol.

This is the syntax for calling a superMethod defined by MySuperClass:

```
superMethod@MySuperClass(obj,superMethodArguments)
```

For example, a subclass can call a superclass disp method to implement the display of the superclass part of the object. Then the subclass adds code to display the subclass part of the object:

```
classdef MySub < MySuperClass
    methods
        function disp(obj)
        disp@MySuperClass(obj)
        ...
    end
    end
end</pre>
```

How to Call Superclass Constructor

If you create a subclass object, MATLAB calls the superclass constructor to initialize the superclass part of the subclass object. By default, MATLAB calls the superclass constructor without arguments. If you want the superclass constructor called with specific arguments, explicitly call the superclass constructor from the subclass constructor. The call to the superclass constructor must come before any other references to the object.

The syntax for calling the superclass constructor uses an @ symbol:

```
obj = obj@MySuperClass(SuperClassArguments)
```

In this class, the MySub object is initialized by the MySuperClass constructor. The superclass constructor constructs the MySuperClass part of the object using the specified arguments.

```
classdef MySub < MySuperClass
   methods
    function obj = MySub(arg1,arg2,...)</pre>
```

See "Subclass Constructors" on page 9-19 for more information.

See Also

Related Examples

• "Modify Inherited Methods" on page 12-13

Using a Class to Display Graphics

```
In this section...

"Class Calculates Area" on page 5-13

"Description of Class Definition" on page 5-15
```

Class Calculates Area

The CircleArea class shows the syntax of a typical class definition. This class stores a value for the radius of a circle and calculates the area of the circle when you request this information. CircleArea also implements methods to graph, display, and create objects of the class.

To use the CircleArea class, copy this code into a file named CircleArea.m and save this file in a folder that is on the MATLAB path.

```
classdef CircleArea
   properties
      Radius
   properties (Constant)
      P = pi
   properties (Dependent)
      Area
   end
   methods
      function obj = CircleArea(r)
          if nargin > 0
             obj.Radius = r;
          end
      end
      function val = get.Area(obj)
          val = obj.P*obj.Radius^2;
      end
      function obj = set.Radius(obj,val)
          if val < 0
             error('Radius must be positive')
          obi.Radius = val;
      function plot(obj)
          r = obj.Radius;
          d = r*2;
          pos = [0 \ 0 \ d \ d];
          curv = [1 1];
          rectangle('Position',pos,'Curvature',curv,...
              'FaceColor',[.9 .9 .9])
          line([0,r],[r,r])
          text(r/2,r+.5,['r = ',num2str(r)])
title(['Area = ',num2str(obj.Area)])
          axis equal
      function disp(obj)
          rad = obj.Radius;
          disp(['Circle with radius: ',num2str(rad)])
```


```
end
end
methods (Static)
  function obj = createObj
    prompt = {'Enter the Radius'};
    dlgTitle = 'Radius';
    rad = inputdlg(prompt,dlgTitle);
    r = str2double(rad{:});
    obj = CircleArea(r);
  end
end
end
```

Use the CircleArea Class

Create an object using the dialog box:

```
ca = CircleArea.createObj
```

Add a value for radius and click **OK**.




Query the area of the defined circle:

```
ca.Area
```

```
ans = 164.2202
```

Call the overloaded plot method:

```
plot(ca)
```



Description of Class Definition

Class definition code begins with the classdef keyword followed by the class name:

```
classdef CircleArea
```

Define the Radius property within the properties-end keywords. Use default attributes:

```
properties
Radius
end
```

Define the P property as Constant ("Define Class Properties with Constant Values" on page 15-2). Call the pi function only once when class is initialized.

```
properties (Constant)
  P = pi
end
```

Define the Area property as Dependent because its value depends on the Radius property.

```
properties (Dependent)
   Area
end
```

The CircleArea class constructor method has the same name as the class and accepts the value of the circle radius as an argument. This method also allows no input arguments. ("Class Constructor Methods" on page 9-15)

```
methods
  function obj = CircleArea(r)
    if nargin > 0
        obj.Radius = r;
    else
        obj.Radius = 0;
    end
end
```

Because the Area property is Dependent, the class does not store its value. The get.Area method calculates the value of the Area property whenever it is queried. ("Get and Set Methods for Dependent Properties" on page 8-43)

```
function val = get.Area(obj)
  val = obj.P*obj.Radius^2;
end
```

The set.Radius method tests the value assigned to the Radius property to ensure that the value is not less than zero. MATLAB calls set.Radius to assign a value to Radius. ("Property Get and Set Methods" on page 8-39)

```
function obj = set.Radius(obj,val)
   if val < 0
      error('Radius must be positive')
   end
   obj.Radius = val;
end</pre>
```

The CircleArea class overloads the plot function. The plot method uses the rectangle function to create a circle and draws the radius. ("Overload Functions in Class Definitions" on page 9-26)

```
function plot(obj)
  r = obj.Radius;
  d = r*2;
  pos = [0 0 d d];
  curv = [1 1];
  rectangle('Position',pos,'Curvature',curv)
  line([0,r],[r,r])
  text(r/2,r+.5,['r = ',num2str(r)])
  axis equal
end
```

The CircleArea class overloads the disp function to change the way MATLAB displays objects in the command window.

```
function disp(obj)
    rad = obj.Radius;
    disp(['Circle with radius: ',num2str(rad)])
    end
end
methods (Static)
```

The CircleArea class defines a Static method that uses a dialog box to create an object. ("Static Methods" on page 9-24)

```
function obj = createObj
  prompt = {'Enter the Radius'};
  dlgTitle = 'Radius';
  rad = inputdlg(prompt,dlgTitle);
  r = str2double(rad{:});
  obj = CircleArea(r);
end
```

End of Static methods block and end of classdef block.

end end

MATLAB Code Analyzer Warnings

```
In this section...

"Syntax Warnings and Property Names" on page 5-18

"Variable/Property Name Conflict Warnings" on page 5-18

"Exception to Variable/Property Name Rule" on page 5-19
```

Syntax Warnings and Property Names

The MATLAB Code Analyzer helps you optimize your code and avoid syntax errors while you write code. It is useful to understand some of the rules that the Code Analyzer applies in its analysis of class definition code. This understanding helps you avoid situations in which MATLAB allows code that is undesirable.

Variable/Property Name Conflict Warnings

The Code Analyzer warns about the use of variable names in methods that match the names of properties. For example, suppose that a class defines a property called EmployeeName and in this class, there is a method that uses EmployeeName as a variable:

```
properties
    EmployeeName
end
methods
    function someMethod(obj,n)
        EmployeeName = n;
    end
end
```

While the previous function is legal MATLAB code, it results in Code Analyzer warnings for two reasons:

- The value of EmployeeName is never used.
- EmployeeName is the name of a property that is used as a variable.

If the function someMethod contained the following statement instead:

```
obj.EmployeeName = n;
```

The Code Analyzer generates no warnings.

If you change someMethod to:

```
function EN = someMethod(obj)
   EN = EmployeeName;
end
```

The Code Analyzer returns only one warning, suggesting that you might actually want to refer to the EmployeeName property.

While this version of someMethod is legal MATLAB code, it is confusing to give a property the same name as a function. Therefore, the Code Analyzer provides a warning suggesting that you might have intended the statement to be:

```
EN = obj.EmployeeName;
```

Exception to Variable/Property Name Rule

Suppose that you define a method that returns a value of a property and uses the name of the property for the output variable name. For example:

```
function EmployeeName = someMethod(obj)
   EmployeeName = obj.EmployeeName;
end
```

The Code Analyzer does not warn when a variable name is the same as a property name when the variable is:

- An input or output variable
- A global or persistent variable

In these particular cases, the Code Analyzer does not warn you that you are using a variable name that is also a property name. Therefore, a coding error like the following:

```
function EmployeeName = someMethod(obj)
   EmployeeName = EmployeeName; % Forgot to include obj.
end
```

does not trigger a warning from the Code Analyzer.

See Also

Related Examples

"Use of Editor and Debugger with Classes" on page 5-25

Objects in Conditional Statements

```
In this section...

"Enable Use of Objects in Conditional Statements" on page 5-20

"How MATLAB Evaluates Switch Statements" on page 5-20

"How to Define the eq Method" on page 5-21

"Enumerations in Switch Statements" on page 5-23
```

Enable Use of Objects in Conditional Statements

Enable the use of objects in conditional statements by defining relational operators for the class of the object. Classes that derive from the handle class inherit relational operators. Value classes can implement operators to support the use of conditional statements involving objects. For information on defining operators for your class, see "Operator Overloading" on page 17-19.

How MATLAB Evaluates Switch Statements

MATLAB enables you to use objects in switch statements when the object's class defines an eq method. The eq method implements the == operation on objects of that class.

For objects, case_expression == switch_expression defines how MATLAB evaluates switch and cases statements.

The values returned by the eq method must be of type logical or convertible to logical. MATLAB attempts to convert the output of eq to a logical value if the output of the eq method is a nonlogical value.

Note You do not need to define eq methods for enumeration classes. See "Enumerations in Switch Statements" on page 5-23.

Handle Objects in Switch Statements

All classes derived from the handle class inherit an eq method. The expression,

```
h1 == h2
```

is true if h1 and h2 are handles for the same object.

For example, the BasicHandle class derives from handle:

```
classdef BasicHandle < handle
  properties
    Prop1
end
methods
  function obj = BasicHandle(val)
    if nargin > 0
       obj.Prop1 = val;
    end
end
```

```
end
end
```

Create a BasicHandle object and use it in a switch statement:

```
h1 = BasicHandle('Handle Object');
h2 = h1;
Here is the switch statement code:
switch h1
    case h2
```

```
case h2
    disp('h2 is selected')
  otherwise
    disp('h2 not selected')
end
```

The result is:

h2 is selected

Object Must Be Scalar

The switch statements work only with scalar objects. For example:

```
h1(1) = BasicHandle('Handle Object');
h1(2) = BasicHandle('Handle Object');
h1(3) = BasicHandle('Handle Object');
h2 = h1;
switch h1
   case h2
       disp('h2 is selected')
   otherwise
       disp('h2 not selected')
end
```

The result is an error message.

SWITCH expression must be a scalar or string constant.

In this case, h1 is not scalar. Use isscalar to determine if an object is scalar before entering a switch statement.

How to Define the eq Method

To enable the use of value-class objects in switch statements, implement an eq method for the class. Use the eq method to determine what constitutes equality of two objects of the class.

Behave like a Built-in Type

Some MATLAB functions also use the built-in == operator in their implementation. Therefore, your implementation of eq should be replaceable with the built-in eq to enable objects of your class work like built-in types in MATLAB code.

Design of eq

Implement the eq method to return a logical array representing the result of the == comparison.

For example, the SwitchOnVer class implements an eq method that returns true for the == operation if the value of the Version property is the same for both objects. In addition, eq works with arrays the same way as the built-in eq. For the following expression:

```
obj1 == obj2
```

The eq method works as follows:

- If both obj1 and obj2 are scalar, eq returns a scalar value.
- If both obj1 and obj2 are nonscalar arrays, then these arrays must have the same dimensions, and eq returns an array of the same size.
- If one input argument is scalar and the other is a nonscalar array, then eq treats the scalar object as if it is an array having the same dimensions as the nonscalar array.

Implementation of eq

Here is a class that implements an eq method. Ensure that your implementation contains appropriate error checking for the intended use.

```
classdef SwitchOnVer
   properties
      Version
   end
   methods
      function obj = SwitchOnVer(ver)
         if nargin > 0
            obj.Version = ver;
         end
      end
      function bol = eq(obj1,obj2)
         if ~strcmp(class(obj1), class(obj2))
            error('Objects are not of the same class')
         end
         s1 = numel(obj1);
         s2 = numel(obj2);
         if s1 == s2
            bol = false(size(obj1));
            for k=1:s1
               if obj1(k).Version == obj2(k).Version
                  bol(k) = true;
                  bol(k) = false;
               end
            end
         elseif s1 == 1
            bol = scalarExpEq(obj2,obj1);
         elseif s2 == 1
            bol = scalarExpEq(obj1,obj2);
         else
            error('Dimension missmatch')
         function ret = scalarExpEq(ns,s)
            % ns is nonscalar array
            % s is scalar array
            ret = false(size(ns));
            n = numel(ns);
            for kk=1:n
```

```
ret(kk) = true;
               else
                   ret(kk) = false;
               end
            end
         end
      end
   end
end
Use SwitchOnVer objects in switch statements:
% Create known versions of objects
ov1 = SwitchOnVer(1.0);
ov2 = SwitchOnVer(2.0);
ov3 = SwitchOnVer(3.0);
. . .
if isscalar(objIn)
      switch(objIn)
         case ov1
            disp('This is version 1.0')
         case ov2
            disp('This is version 2.0')
         case ov3
            disp('This is version 3.0')
         otherwise
            disp('There is no version')
      end
   else
      error('Input object must be scalar')
   end
```

if ns(kk).Version == s.Version

Enumerations in Switch Statements

MATLAB enables you to use enumerations in switch statements without requiring an explicitly defined eq method for the enumeration class.

For example, the WeeklyPlanner class defines enumerations for five days of the week. The switch/case statements in the todaySchedule static method dispatch on the enumeration member corresponding to the current day of the week. The datetime, day, and string functions return a string containing the name of the current day.

```
disp("Tuesday schedule")
case WeeklyPlanner.Wednesday
disp("Wednesday schedule")
case WeeklyPlanner.Thursday
disp("Thursday schedule")
case WeeklyPlanner.Friday
disp("Friday schedule")
end
end
end
end
```

Call todaySchedule to display today's schedule:

WeeklyPlanner.todaySchedule

Enumerations Derived from Built-In Types

Enumeration classes that derived from built-in types inherit the superclass eq method. For example, the FlowRate class derives from int32:

```
classdef FlowRate < int32
  enumeration
    Low (10)
    Medium (50)
    High (100)
  end
end</pre>
```

The switchEnum function switches on the input argument, which can be a FlowRate enumeration value.

```
function switchEnum(inpt)
    switch inpt
    case 10
        disp('Flow = 10 cfm')
    case 50
        disp('Flow = 50 cfm')
    case 100
        disp('Flow = 100 cfm')
    end
end
```

Call switchEnum with an enumerated value:

```
switchEnum(FlowRate.Medium)
```

```
Flow = 50 cfm
```

Use of Editor and Debugger with Classes

In this section...

"Write Class Code in the Editor" on page 5-25

"How to Refer to Class Files" on page 5-25

"How to Debug Class Files" on page 5-25

Write Class Code in the Editor

The MATLAB code editor provides an effective environment for class development. The Code Analyzer, which is built into the editor, check code for problems and provides information on fixing these problems. For information on editor use and features, see edit.

How to Refer to Class Files

Define classes in files just like scripts and functions. To use the editor or debugger with a class file, use the full class name. For example, suppose the file for a class, myclass.m is in the following location:

```
+nspfld1/+nspfld2/@myclass/myclass.m
```

To open myclass.m in the MATLAB editor, you could reference the file using dot-separated namespace names:

```
edit nspfld1.nspfld2.myclass
```

You could also use path notation:

edit +nspfld1/+nspfld2/@myclass/myclass

If myclass.m is not in a class folder, then enter:

```
edit +nspfld1/+nspfld2/myclass
```

To refer to functions inside a namespace folder, use dot or path separators:

```
edit nspfld1.nspfld2.nspFunction
edit +nspfld1/+nspfld2/nspFunction
```

To refer to a method defined in its own file inside a class folder, use:

```
edit +nspfld1/+nspfld2/@myclass/myMethod
```

How to Debug Class Files

For debugging, dbstop enables you to set breakpoints in the class constructor by specifying the fully qualified class file name. To set a breakpoint at a method defined in the class file, specify the line number of the method with the dbstop command. For example, if the method begins on line 14 in the classdef file, myclass.m, use this command to put a breakpoint on the first executable line of the method.

```
dbstop in myclass at 14
```

See "Automatic Updates for Modified Classes" on page 5-27 for information about clearing class after modification.

See Also

dbstop

Related Examples

- "MATLAB Code Analyzer Warnings" on page 5-18
- "Debug MATLAB Code Files"

Automatic Updates for Modified Classes

In this section...

"When MATLAB Loads Class Definitions" on page 5-27

"Consequences of Automatic Update" on page 5-27

"What Happens When Class Definitions Change" on page 5-28

"Ensure Defining Folder Remains in Scope" on page 5-28

"Actions That Do Not Trigger Updates" on page 5-29

"Multiple Updates to Class Definitions" on page 5-29

"Object Validity with Deleted Class File" on page 5-29

"When Updates Are Not Possible" on page 5-29

"Potential Consequences of Class Updates" on page 5-29

"Interactions with the Debugger" on page 5-30

"Updates to Class Attributes" on page 5-30

"Updates to Property Definitions" on page 5-31

"Updates to Method Definitions" on page 5-31

"Updates to Event Definitions" on page 5-32

When MATLAB Loads Class Definitions

MATLAB loads a class definition:

- The first time the class is referenced, such as creating an instance, accessing a constant property, or calling a static method of the class.
- Whenever the definition of a loaded class changes and MATLAB returns to the command prompt.
- When you change the MATLAB path and cause a different definition of the class to be used. The change takes effect after MATLAB returns to the command prompt.
- Whenever you access the class metadata.

MATLAB allows only one definition for a class to exist at any time. Therefore, MATLAB attempts to update all existing objects of a class automatically to conform to the new class definition. You do not need to call clear classes to remove existing objects when you change their defining class.

Note Using an editor other than the MATLAB editor or using MATLAB Online $^{\text{TM}}$ can result in delays to automatic updating.

Consequences of Automatic Update

MATLAB follows a set of basic rules when updating existing objects. An automatic update can result in:

- Existing objects being updated to the new class definition.
- An error if MATLAB cannot convert the objects to the new class definition or if there is an error in the class definition itself.

Here is an example of what happens when you create an instance of a concrete class edit the class definition to make the class abstract.

```
a = MyClass;
% Edit MyClass to make it Abstract
a
Error using MyClass/display
Cannot update object because the class 'MyClass' is now abstract.
```

Note MATLAB does not update metaclass instances when you change the definition of a class. You must get new metaclass data after updating a class definition.

What Happens When Class Definitions Change

MATLAB updates existing objects when a class definition changes, including the following situations:

- Value change to handle Existing objects become independent handles referring to different objects.
- Enumeration member added Existing objects preserve the enumeration members they had previously, even if the underlying values have changed.
- Enumeration member removed Existing objects that are not using the removed member have the same enumeration members that they had previously. Existing objects that use the removed member replace the removed member with the default member of the enumeration.
- Enumeration block removed Enumeration members are taken out of use.
- Superclass definition changed Changes applied to all subclasses in the hierarchy of that superclass.
- Superclass added or removed Change of superclass applied to all existing objects.

Ensure Defining Folder Remains in Scope

Changes to the MATLAB path that result in removing the class definition file from the path, even temporarily, can produce side effects. If a function changes from the current folder, which contains the class definition, and that folder is not on the path, then the function cannot call methods of the class that is now out of scope. To avoid potential problems, add the class defining folder to the path before changing to another folder.

For example, suppose the class of the input obj is defined in the current folder, which is not on the path. Before changing the current folder to another folder, add the current folder to the path using the addpath function.

```
function runFromTempFolder(obj)
    % Add current folder to path
    addpath(pwd)
    definingFolder = cd('myTempFolder');
    obj.myMethod;
    cd(definingFolder)
end
```

Actions That Do Not Trigger Updates

These actions do not update existing objects:

- Calling the class function on an out-of-date object
- · Assigning an out-of-date object to a variable
- · Calling a method that does not access class data
- Changing property validation in the class definition ("Validate Property Values" on page 8-19)

Objects do not update until referenced in a way that exposes the change, such as invoking the object display or assigning to a property.

Multiple Updates to Class Definitions

Updates do not occur incrementally. Updates conform to the latest version of the class.

Object Validity with Deleted Class File

Deleting a class definition file does not make instances of that class invalid. However, you cannot call methods on existing objects of that class.

When Updates Are Not Possible

Some class updates result in an invalid class definition. In these cases, objects do not update until the error is resolved:

- Adding a superclass can result in a property or method being defined twice.
- Changing a superclass to be **Sealed** when objects of one of its subclasses exists results in an invalid subclass definition.

Some class updates cause situations in which MATLAB cannot update existing objects to conform to a modified class definition. These cases result in errors until you delete the objects:

- Adding an enumeration block to a non-enumeration class
- · Redefining a class to be abstract
- Removing a class from a heterogeneous hierarchy that results in there being no default object to replace existing objects in a heterogeneous array
- Updating a class to restrict array formation behavior, such as overloading array indexing and concatenation.
- Inheriting a subsref, subsasgn, cat, vertcat, or horzcat method
- Redefining a handle class to be a value class.

Potential Consequences of Class Updates

- Following an update, existing objects can be incompatible with the new class definition. For example, a newly added property can require execution of the constructor to be valid.
- Removing or renaming properties can lose the data held in the property. For example, if a property holds the only reference to another object and you remove that property from the class, the MATLAB deletes the object because there are no longer any references to it.

• Removing a class from a heterogeneous class hierarchy can result in invalid heterogeneous array elements. In this case, the default object for the heterogeneous hierarchy replaces these array elements.

Interactions with the Debugger

Since R2021a.

MATLAB disables the debugger during class updates. Before R2021a, a breakpoint could potentially interrupt the class update process and allow for the introduction of errors when the update resumes. For example, the breakpoint allows a class author to introduce invalid syntax into the class definition or remove the class from the path entirely, potentially causing MATLAB to crash.

Example of a Disabled Breakpoint

This class defines a property validation function:

```
classdef ClassWithBreakpoint
    properties (Constant)
        Prop1 (1,1) {myPropertyValidator} = 32
    end
end

function myPropertyValidator(~)
end % Add breakpoint here
```

Create an instance of this class. Then add a breakpoint where indicated, and update the definition of Prop1 to a different initial value:

```
Prop1 (1,1) {myPropertyValidator} = 10
```

In version R2020b and earlier, MATLAB hits the breakpoint, and the class update is interrupted. In R2021a, the debugger is disabled, and the breakpoint does not interrupt the update.

Updates to Class Attributes

Changing class attributes can change existing object behavior or make the objects invalid. MATLAB returns an error when you access the invalid objects.

Change	Effect
Make Abstract = true	Accessing existing objects returns an error.
Change AllowedSubclasses	Newly created objects can inherit from different superclasses than existing objects.
Change ConstructOnLoad	Loading classes obeys the current value of ConstructOnLoad.
Change HandleCompatible	Newly created objects can have different class hierarchy than existing objects.
Change Hidden	Appearance of class in list of superclasses and access by help function can change
Change InferiorClasses	Method dispatching for existing objects can change.
Make Sealed = true	Existing subclass objects return errors when accessed.

Updates to Property Definitions

When you change the definition of class properties, MATLAB applies the changes to existing objects of the class.

Change	Effect	
Add property	Adds the new property to existing objects of the class. Sets the property values to the default value (which is [] if the class definition does not specify a default).	
Remove property	Removes the property from existing objects of the class. Attempts to access the removed property fail.	
Change property default value	Does not apply the new default value to existing objects of the class.	
Move property between subclass and superclass	Does not apply different default value when property definition moves between superclass and subclass.	
Change property attribute value	 Applies changes to existing objects of the class. Some cases require transitional steps: Abstract — Existing objects of a class that becomes abstract cannot be updated. Delete these objects. Access — Changes to the public, protected, or private property access settings affect access to existing objects. Changes to the access lists do not change existing objects. However, if you add classes to the access list, instances of those classes have access to this property. If you remove classes from the access list, objects of those classes no longer have access to this property. Dependent — If changed to true, existing objects no longer store property values. If you want to query the property value, add a property get method for the property. Transient — If changed to true, objects already saved, reload this property value. If changed to false, objects already saved reload this property using the default value. 	

Updates to Method Definitions

When you change the definition of class methods, MATLAB changes the affected class member in existing objects as follows.

Change	Effect	
Add method	You can call the new method on existing objects of the class.	
Modify method	Modifications are available to existing objects.	
Remove method	You can on longer call deleted method on existing objects.	

Change	Effect		
Change method attribute value	Apply changes to existing objects of the class. Some cases require transitional steps:		
	Abstract — Existing objects of a class that becomes abstract cannot be updated. Delete these objects.		
	• Access — Changes to method public, protected, or private access settings affect access to existing objects.		
	Changes to the access lists do not change existing instances. However, if you add classes to the access list, instances of those classes have access to this method. If you remove classes from the access list, objects of those classes no longer have access to this method.		
	Sealed — If changed to true and existing subclasses already have defined the method, MATLAB returns an error because the new class definition cannot be applied to existing subclasses.		

Updates to Event Definitions

Change	Effect	
Add event	Existing objects of the class support the new event.	
Change event name	New event name is visible to existing objects of the class. MATLAB: Does not update existing metaclass objects Does update newly acquired metaclass objects	
	Does not update listeners to use new event name	
Remove event	Existing objects no longer support deleted event.	

Change	Effect		
Change event attribute value	Apply changes to existing objects of the class.		
	Some cases require transitional steps:		
	• ListenAccess — Changes to event public, protected, or private listen access settings affect access to existing objects.		
	Changes to the access list do not change existing objects. However, if you add classes to the access list, objects of those classes can create listeners for this event. If you remove classes from the access list, objects of those classes are not allowed to create listeners for this event.		
	NotifyAccess — Changes to event public, protected, or private notify access settings affect access to existing objects.		
	Changes to the access list do not change existing objects. However, if you add classes to the access list, instances of those classes can trigger this event. If you remove classes, objects of those classes are not able to trigger this event.		

See Also

Related Examples

• "Use of Editor and Debugger with Classes" on page 5-25

Comparison of MATLAB and Other OO Languages

In this section...

"Some Differences from C++ and Java Code" on page 5-34

"Object Modification" on page 5-35

"Static Properties" on page 5-38

"Common Object-Oriented Techniques" on page 5-38

Some Differences from C++ and Java Code

The MATLAB programming language differs from other object-oriented languages, such as C++ or Java in some important ways.

Public Properties

Unlike fields in C++ or the Java language, you can use MATLAB properties to define a public interface separate from the implementation of data storage. You can provide public access to properties because you can define set and get access methods that execute automatically when assigning or querying property values. For example, the following statement:

```
myobj.Material = 'plastic';
```

assigns the char vector plastic to the Material property of myobj. Before making the actual assignment, myobj executes a method called set.Material (assuming the class of myobj defines this method), which can perform any necessary operations. See "Property Get and Set Methods" on page 8-39 for more information on property access methods.

You can also control access to properties by setting attributes, which enable public, protected, or private access. See "Property Attributes" on page 8-8 for a full list of property attributes.

No Implicit Parameters

In some languages, one object parameter to a method is always implicit. In MATLAB, objects are explicit parameters to the methods that act on them.

Dispatching

In MATLAB classes, method dispatching is not based on method signature, as it is in C++ and Java code. When the argument list contains objects of equal precedence, MATLAB uses the leftmost object to select the method to call.

However, if the class of an argument is superior to the class of the other arguments, MATLAB dispatches to the method of the superior argument, regardless of its position within the argument list.

See "Class Precedence" on page 6-18 for more information.

Calling Superclass Method

- In C++, you call a superclass method using the scoping operator: superclass::method
- In Java code, you use: *superclass.method*

The equivalent MATLAB operation is method@superclass.

Other Differences

In MATLAB classes, there is no equivalent to C++ templates or Java generics. However, MATLAB is weakly typed and it is possible to write functions and classes that work with different types of data.

MATLAB classes do not support overloading functions using different signatures for the same function name.

Object Modification

MATLAB classes can define public properties, which you can modify by explicitly assigning values to those properties on a given instance of the class. However, only classes derived from the handle class exhibit reference behavior. Modifying a property value on an instance of a value classes (classes not derived from handle), changes the value only within the context in which the modification is made.

The sections that follow describe this behavior in more detail.

Objects Passed to Functions

MATLAB passes all variables by value. When you pass an object to a function, MATLAB copies the value from the caller into the parameter variable in the called function.

However, MATLAB supports two kinds of classes that behave differently when copied:

- Handle classes a handle class instance variable refers to an object. A copy of a handle class
 instance variable refers to the same object as the original variable. If a function modifies a handle
 object passed as an input argument, the modification affects the object referenced by both the
 original and copied handles.
- Value classes the property data in an instance of a value class are independent of the property data in copies of that instance (although, a value class property could contain a handle). A function can modify a value object that is passed as an input argument, but this modification does not affect the original object.

See "Comparison of Handle and Value Classes" on page 7-2 for more information on the behavior and use of both kinds of classes.

Passing Value Objects

When you pass a value object to a function, the function creates a local copy of the argument variable. The function can modify only the copy. If you want to modify the original object, return the modified object and assign it to the original variable name. For example, consider the value class, SimpleClass:

```
classdef SimpleClass
  properties
    Color
end
methods
  function obj = SimpleClass(c)
    if nargin > 0
        obj.Color = c;
end
```

```
end
end
end
```

Create an instance of SimpleClass, assigning a value of red to its Color property:

```
obj = SimpleClass('red');
```

Pass the object to the function **q**, which assigns **blue** to the **Color** property:

```
function y = g(x)
    x.Color = 'blue';
    y = x;
end
y = g(obj);
```

The function g modifies its copy of the input object and returns that copy, but does not change the original object.

```
y.Color
ans =
    blue
obj.Color
ans =
    red
```

If the function g did not return a value, the modification of the object Color property would have occurred only on the copy of obj within the function workspace. This copy would have gone out of scope when the function execution ended.

Overwriting the original variable actually replaces it with a new object:

```
obj = g(obj);
```

Passing Handle Objects

When you pass a handle to a function, the function makes a copy of the handle variable, just like when passing a value object. However, because a copy of a handle object refers to the same object as the original handle, the function can modify the object without having to return the modified object.

For example, suppose that you modify the SimpleClass class definition to make a class derived from the handle class:

```
classdef SimpleHandleClass < handle
  properties
    Color
end
methods
  function obj = SimpleHandleClass(c)
    if nargin > 0
        obj.Color = c;
    end
end
```

```
end
end
```

Create an instance of SimpleHandleClass, assigning a value of red to its Color property:

```
obj = SimpleHandleClass('red');
```

Pass the object to the function g, which assigns blue to the Color property:

```
y = g(obj);
```

The function g sets the Color property of the object referred to by both the returned handle and the original handle:

```
y.Color
ans =
blue
obj.Color
ans =
blue
The variables y and obj refer to the same object:
y.Color = 'yellow';
obj.Color
ans =
yellow
```

The function g modified the object referred to by the input argument (obj) and returned a handle to that object in y.

MATLAB Passes Handles by Value

A handle variable is a reference to an object. MATLAB passes this reference by value.

Handles do not behave like references in C++. If you pass an object handle to a function and that function assigns a different object to that handle variable, the variable in the caller is not affected. For example, suppose you define a function q2:

```
function y = g2(x)
    x = SimpleHandleClass('green');
    y = x;
end

Pass a handle object to g2:
obj = SimpleHandleClass('red');
y = g2(obj);
y.Color
ans =
green
```

```
obj.Color
```

ans =

The function overwrites the handle passed in as an argument, but does not overwrite the object referred to by the handle. The original handle obj still references the original object.

Static Properties

In MATLAB, classes can define constant properties, but not "static" properties in the sense of other languages like C++. You cannot change constant properties from the initial value specified in the class definition.

MATLAB has long-standing rules that variables always take precedence over the names of functions and classes. Assignment statements introduce a variable if one does not exist.

Expressions of this form

A.B = C

Introduce a new variable, A, that is a struct containing a field B whose value is C. If A.B = C could refer to a static property of class A, then class A would take precedence over variable A.

This behavior would be a significant incompatibility with prior releases of MATLAB. For example, the introduction of a class named A on the MATLAB path could change the meaning of an assignment statement like A.B = C inside a .m code file.

In other languages, classes rarely use static data, except as private data within the class or as public constants. In MATLAB, you can use constant properties the same way you use public final static fields in Java. To use data that is internal to a class in MATLAB, create persistent variables in private or protected methods or local functions used privately by the class.

Avoid static data in MATLAB. If a class has static data, using the same class in multiple applications causes conflicts among applications. Conflicts are less of an issue in some other languages. These languages compile applications into executables that run in different processes. Each process has its own copy of the class static data. MATLAB, frequently runs many different applications in the same process and environment with a single copy of each class.

For ways to define and use static data in MATLAB, see "Static Data" on page 4-2.

Common Object-Oriented Techniques

This table provides links to sections that discuss object-oriented techniques commonly used by other object-oriented languages.

Technique	How to Use in MATLAB	
Operator overloading	"Operator Overloading" on page 17-19	
Multiple inheritance	"Subclassing Multiple Classes" on page 12-19	
Subclassing	"Design Subclass Constructors" on page 12-7	
Destructor	"Handle Class Destructor" on page 7-13	

Technique	How to Use in MATLAB	
Data member scoping	"Property Attributes" on page 8-8	
Namespaces (scoping classes)	"Create Namespaces" on page 6-20	
Named constants	See "Define Class Properties with Constant Values" on page 15-2 and "Named Values" on page 14-2	
Enumerations	"Define Enumeration Classes" on page 14-4	
Static methods	"Static Methods" on page 9-24	
Static properties	Not supported. See persistent variables. For the equivalent of Java static final or C++ static const properties, use Constant properties. See "Define Class Properties with Constant Values" on page 15-2 For mutable static data, see "Static Data" on page 4-2	
Constructor	"Class Constructor Methods" on page 9-15	
Copy constructor	No direct equivalent	
Reference/reference classes	"Comparison of Handle and Value Classes" on page 7-2	
Abstract class/Interface	"Abstract Classes and Class Members" on page 12-68	
Garbage collection	"Object Lifecycle" on page 7-16	
Instance properties	"Dynamic Properties — Adding Properties to an Instance" on page 8-48	
Importing classes	"Import Namespace Members into Functions" on page 6-24	
Events and Listeners	"Event and Listener Concepts" on page 11-12	

Defining and Organizing Classes

- "User-Defined Classes" on page 6-2
- "Class Attributes" on page 6-5
- "Functions Inside Class Definition Files" on page 6-8
- "Evaluation of Expressions in Class Definitions" on page 6-9
- "Folders Containing Class Definitions" on page 6-14
- "Class Precedence" on page 6-18
- "Create Namespaces" on page 6-20
- "Import Namespace Members into Functions" on page 6-24
- "Creating and Managing Class Aliases" on page 6-26

User-Defined Classes

In this section...

"What Is a Class Definition" on page 6-2

"Attributes for Class Members" on page 6-2

"Kinds of Classes" on page 6-2

"Constructing Objects" on page 6-3

"Class Hierarchies" on page 6-3

"classdef Syntax" on page 6-3

"Class Code" on page 6-3

What Is a Class Definition

A MATLAB class definition is a template whose purpose is to provide a description of all the elements that are common to all instances of the class. Class members are the properties, methods, and events that define the class.

Define MATLAB classes in code blocks, with subblocks delineating the definitions of various class members. For syntax information on these blocks, see "Components of a Class" on page 5-2.

Attributes for Class Members

Attributes modify the behavior of classes and the members defined in the class-definition block. For example, you can specify that methods are static or that properties are private. The following sections describe these attributes:

- "Class Attributes" on page 6-5
- "Method Attributes" on page 9-4
- "Property Attributes" on page 8-8
- "Event Attributes" on page 11-16

Class definitions can provide information, such as inheritance relationships or the names of class members without actually constructing the class. See "Class Metadata" on page 16-2.

See "Specifying Attributes" on page 6-7 for more on attribute syntax.

Kinds of Classes

There are two kinds of MATLAB classes—handle classes and value classes.

- Value classes represent independent values. Value objects contain the object data and do not share this data with copies of the object. MATLAB numeric types are value classes. Values objects passed to and modified by functions must return a modified object to the caller.
- Handle classes create objects that reference the object data. Copies of the instance variable refer to the same object. Handle objects passed to and modified by functions affect the object in the caller's workspace without returning the object.

For more information, see "Comparison of Handle and Value Classes" on page 7-2.

Constructing Objects

For information on class constructors, see "Class Constructor Methods" on page 9-15.

For information on creating arrays of objects, see "Create and Initialize Object Arrays" on page 10-2.


Class Hierarchies

For more information on how to define class hierarchies, see "Hierarchies of Classes — Concepts" on page 12-2.

classdef Syntax

Class definitions are blocks of code that are delineated by the classdef keyword at the beginning and the end keyword at the end. Files can contain only one class definition.

The following diagram shows the syntax of a classdef block. Only comments and blank lines can precede the classdef keyword.



Class Code

Here is a simple class definition with one property and a constructor method that sets the value of the property when there is an input argument supplied.

```
classdef MyClass
  properties
    Prop
  end
  methods
    function obj = MyClass(val)
       if nargin > 0
         obj.Prop = val;
    end
```

```
end
end
end
```

To create an object of MyClass, save the class definition in a .m file having the same name as the class and call the constructor with any necessary arguments:

```
d = datestr(now);
o = MyClass(d);
```

Use dot notation to access the property value:

```
o.Prop
ans =
10-Nov-2005 10:38:14
```

The constructor should support a no argument syntax so MATLAB can create default objects. For more information, see "No Input Argument Constructor Requirement" on page 9-19.

For more information on the components of a class definition, see "Components of a Class" on page 5-2.

See Also

Related Examples

- "Creating a Simple Class" on page 2-2
- "Developing Classes That Work Together" on page 3-6
- "Representing Structured Data with Classes" on page 3-14

Class Attributes

In this section...

"Specifying Class Attributes" on page 6-5

"Specifying Attributes" on page 6-7

"Class-Specific Attributes" on page 6-7

Specifying Class Attributes

All classes support the attributes listed in the following table. Attributes enable you to modify the behavior of class. Attribute values apply to the class defined within the classdef block.

```
classdef (Attribute1 = value1, Attribute2 = value2,...) ClassName
    ...
end
```

Class Attributes

Attribute Name	Class	Description
	logical (default =	If specified as true, this class is an abstract class (cannot be instantiated).
false)		See "Abstract Classes and Class Members" on page 12-68 for more information.
ata	matlab.metad ata.Class object or cell	List classes that can subclass this class. Specify subclasses as matlab.metadata.Class objects in the form:
	array of	A single matlab.metadata.Class object
	matlab.metad ata.Class objects	• A cell array of matlab.metadata.Class objects. An empty cell array, {}, is the same as a Sealed class (no subclasses).
		Specify matlab.metadata.Class objects using the ?ClassName syntax only.
		See "Specify Allowed Subclasses" on page 12-21 for more information.
ConstructOnLoad	logical (default = false)	If true, MATLAB calls the class constructor when loading an object from a MAT file. Classes defined with this attribute must have a noargument constructor.
	racse)	See "Default Save and Load Process for Objects" on page 13-2 for more information.
HandleCompatible	logical (default = false) for value classes	If specified as true, this class can be used as a superclass for handle classes. All handle classes are HandleCompatible by definition. See "Handle Compatible Classes" on page 12-31 for more information.
Hidden	logical	If true, this class does not appear in the output of the superclasses or help functions.
	(default = false)	
ata	matlab.metad ata.Class object or cell array of	Use this attribute to establish a precedence relationship among classes. Specify a cell array of matlab.metadata.Class objects using the ? operator.
	matlab.metad ata.Class	The fundamental classes are always inferior to user-defined classes and do not show up in this list.
	objects	See "Class Precedence" on page 6-18.
Sealed	logical	If true, this class cannot be subclassed.
	(default = false)	
Framework attributes		certain framework base classes have framework-specific attributes. ntation for the specific base class you are using for information on

Specifying Attributes

Attributes are specified for class members in the classdef, properties, methods, and events definition blocks. The particular attribute setting applies to all members defined within that particular block. You can use multiple properties, methods, and events definition blocks to apply different attribute setting to different class members.

Superclass Attribute Values Are Not Inherited

Class attributes settings are not inherited, so superclass attribute values do not affect subclasses.

Attribute Syntax

Specify class attribute values in parentheses, separating each attribute name/attribute value pair with a comma. The attribute list always follows the classdef or class member keyword, as shown:

Class-Specific Attributes

Some MATLAB classes define additional attributes that you can use only with the class hierarchies that define these attributes. See the specific documentation for the classes you are using for information on any additional attributes supported by those classes.

See Also

More About

• "Expressions in Attribute Specifications" on page 6-10

Functions Inside Class Definition Files

Just as you can define local functions in a script file or function file, you can also define local functions inside a classdef file. Define these functions outside of the classdef block, but in the same file as the class definition. You can call these functions from anywhere in the same file, but they are not visible outside of the file in which you define them.

Local functions in classdef files are useful for utility functions that you use only within that file. For example, this code defines myUtilityFcn outside the classdef block.

```
classdef MyClass
   properties
        PropName
   end
   methods
        function obj = method1(val)
            adjustedVal = myUtilityFcn(val)
            ...
   end
   end
end
end % End of classdef

function out = myUtilityFcn(in)
   ...
end
```

When you call method1 of MyClass, the method first uses myUtilityFcn to perform some preprocessing on the input argument before performing any other actions.

Unlike methods, these functions do not require an instance of the class as an input, but they can take or return arguments that are instances of the class and access the members of those instances, including private members. However, if a function inside a class definition file needs direct access to class members, consider defining the function as a method of the class instead.

See Also

classdef

More About

• "Folders Containing Class Definitions" on page 6-14

Evaluation of Expressions in Class Definitions

```
"Why Use Expressions" on page 6-9

"Where to Use Expressions in Class Definitions" on page 6-9

"How MATLAB Evaluates Expressions" on page 6-11

"When MATLAB Evaluates Expressions" on page 6-11

"Expression Evaluation in Handle and Value Classes" on page 6-11
```

Why Use Expressions

An expression used in a class definition can be any valid MATLAB statement that evaluates to a single array. Use expressions to define property default values and in attribute specifications. Expressions are useful to derive values in terms of other values. For example, suppose that you want to define a constant property with the full precision value of 2π . You can assign the property the value returned by the expression 2*pi. MATLAB evaluates the function when first loading the class.

For information on assigning property default values and attribute values, see "Initialize Property Values" on page 8-14 and "Property Attributes" on page 8-8.

Where to Use Expressions in Class Definitions

Here are some examples of expressions used in a class definition:

```
classdef MyClass
   % Some attributes are set to logical values
   properties (Constant = true)
      CnstProp = 2*pi
   properties
      % Static method of this class
      Prop1 = MyClass.setupAccount
      % Constant property from this class
      Prop2 = MyClass.CnstProp
      % Function that returns a value
      Prop3 = datestr(now)
      % A class constructor
      Prop4 = AccountManager
   end
   methods (Static)
      function accNum = setupAccount
         accNum = randi(9,[1,12]);
      end
   end
end
```

MATLAB does not call property set methods when assigning the result of default value expressions to properties. (See "Property Get and Set Methods" on page 8-39 for information about these special methods.)

Enumerations that derived from MATLAB types can use expressions to assign a value:

```
classdef FlowRate < int32
   enumeration
     Low (10)
     Medium (FlowRate.Low*5)
     High (FlowRate.Low*10)
   end
end</pre>
```

MATLAB evaluates these expressions only once when enumeration members are first accessed.

Expressions in Attribute Specifications

For attributes values that are logical true or false, class definitions can specify attribute values using expressions. For example, this assignment makes MyClass sealed (cannot be subclassed) for versions of MATLAB before R2014b (verLessThan)

```
classdef (Sealed = verLessThan('matlab', '8.4')) MyClass
```

The expression on the right side of the equal sign (=) must evaluate to true or false. You cannot use any definitions from the class file in this expression, including any constant properties, static methods, and local functions.

While you can use conditional expression to set attribute values, doing so can cause the class definition to change based on external conditions. Ensure that this behavior is consistent with your class design.

Note The AllowedSubclasses and the InferiorClasses attributes require an explicit specification of a cell array of matlab.metadata.Class objects as their values. You cannot use expressions to return these values.

Expressions That Specify Default Property Values

Property definitions allow you to specify default values for properties using any expression that has no reference to variables. For example, VectorAngle defines a constant property (Rad2Deg) and uses it in an expression that defines the default value of another property (Angle). The default value expression also uses a static method (getAngle) defined by the class:

```
classdef VectorAngle
  properties (Constant)
      Rad2Deg = 180/pi
  end
  properties
      Angle = VectorAngle.Rad2Deg*VectorAngle.getAngle([1 0],[0 1])
  end
  methods
      function obj = VectorAngle(vx,vy)
         obj.Angle = VectorAngle.getAngle(vx,vy);
      end
  end
  methods (Static)
      function r = getAngle(vx,vy)
         % Calculate angle between 2D vectors
         cr = vx(1)*vy(1) + vx(2)*vy(2)/sqrt(vx(1)^2 + vx(2)^2) * ...
            sqrt(vy(1)^2 + vy(2)^2);
```

```
r = acos(cr);
    end
    end
end
```

You cannot use the input variables to the constructor to define the default value of the Angle property. For example, this definition for the Angle property is not valid:

Attempting to create an instance causes an error:

```
\label{eq:absolute} a = VectorAngle([1,0],[0,1]) 
 Error \ using \ VectorAngle \\ Unable \ to \ update \ the \ class \ 'VectorAngle' \ because \ the \ new \ definition \ contains \ an \ error: \\ Undefined \ function \ or \ variable \ 'vx'.
```

Expressions in Class Methods

Expression in class methods execute like expressions in any function. MATLAB evaluates an expression within the function workspace when the method executes. Therefore, expressions used in class methods are not considered part of the class definition and are not discussed in this section.

How MATLAB Evaluates Expressions

MATLAB evaluates the expressions used in the class definition without any workspace. Therefore, these expressions cannot reference variables of any kind.

MATLAB evaluates expressions in the context of the class file, so these expressions can access any functions, static methods, and constant properties of other classes that are on your path at the time MATLAB initializes the class. Expressions defining property default values can access constant properties defined in their own class.

When MATLAB Evaluates Expressions

MATLAB evaluates the expressions in class definitions only when initializing the class. Initialization occurs before the first use of the class.

After initialization, the values returned by these expressions are part of the class definition and are constant for all instances of the class. Each instance of the class uses the results of the initial evaluation of the expressions without re-evaluation.

If you clear a class, then MATLAB reinitializes the class by reevaluating the expressions that are part of the class definition. (see "Automatic Updates for Modified Classes" on page 5-27)

Expression Evaluation in Handle and Value Classes

The following example shows how value and handle object behave when assigned to properties as default values. Suppose that you have the following classes.

Expressions in Value Classes

The ClassExp class has a property that contains a ContClass object:

```
classdef ContClass
  properties
    % Assign current date and time
    TimeProp = datestr(now)
  end
end

classdef ClassExp
  properties
    ObjProp = ContClass
  end
end
```

When you first use the ClassExp class, MATLAB creates an instance of the ContClass class. MATLAB initializes both classes at this time. All instances of ClassExp include a copy of this same instance of ContClass.

```
a = ClassExp;
a.ObjProp.TimeProp
ans =
08-Oct-2003 17:16:08
```

The TimeProp property of the ContClass object contains the date and time when MATLAB initialized the class. Creating additional instances of the ClassExp class shows that the date string has not changed:

```
b = ClassExp;
b.ObjProp.TimeProp
ans =
08-Oct-2003 17:16:08
```

Because this example uses a value class for the contained object, each instance of the ClassExp has its own copy of the object. For example, suppose that you change the value of the TimeProp property on the object contained by ClassExp objectb:

```
b.ObjProp.TimeProp = datestr(now)
ans =
08-Oct-2003 17:22:49
```

The copy of the object contained by object a is unchanged:

```
a.ObjProp.TimeProp
ans =
08-0ct-2003 17:16:08
```

Expressions in Handle Classes

Now consider the behavior if the contained object is a handle object:

```
classdef ContClass < handle
   properties
      TimeProp = datestr(now)
   end
end</pre>
```

Creating two instances of the ClassExp class shows that MATLAB created an object when it initialized the ContClass. MATLAB used a copy of the object's *handle* for each instance of the ClassExp class. Therefore, there is one ContClass object and the ObjProp property of each ClassExp object contains a copy of its handle.

Create an instance of the ClassExp class and note the time of creation:

```
a = ClassExp;
a.ObjProp.TimeProp
ans =
08-Oct-2003 17:46:01
```

Create a second instance of the ClassExp class. The ObjProp contains the handle of the same object:

```
b = ClassExp;
b.ObjProp.TimeProp
ans =
08-0ct-2003 17:46:01
```

Reassign the value of the contained object TimeProp property:

```
b.ObjProp.TimeProp = datestr(now);
b.ObjProp.TimeProp

ans =
08-0ct-2003 17:47:34
```

The ObjProp property of object b contains a handle to the same object as the ObjProp property of object a. The value of the TimeProp property has changed on this object as well:

```
a.ObjProp.TimeProp
ans =
08-Oct-2003 17:47:34
```

See Also

More About

• "Comparison of Handle and Value Classes" on page 7-2

Folders Containing Class Definitions

In this section... "Using Path Folders" on page 6-14 "Using Class Folders" on page 6-14 "Functions in Private Folders Within Class Folders" on page 6-15 "Class Precedence and MATLAB Path" on page 6-15 "Changing the Path to Update Class Definitions" on page 6-16

You can use different types of folders to define and organize classes in MATLAB.

- Path folders This type of folder is on the MATLAB path, and the folder name does not begin with a + or @ character. Use this type of folder when you want to include multiple classes and functions in one folder. In a path folder, each class definition must be contained in one file.
- Class folders The folder name begins with an @ character followed by the class name. This type of folder is not on the MATLAB path, but its parent folder is on the path. Use this type of folder when you want to use multiple files for one class definition.
- Namespace folders The folder name begins with a + character followed by the class name.
 Namespaces are special folders that can contain class folders, class definition files, function files, and other namespaces (referred to as inner namespaces). Because the folder names become part of the class name, a namespace creates more robust names for the items contained inside it.

This topic covers the use of path and class folders. For more information on namespaces, see "Create Namespaces" on page 6-20.

Using Path Folders

Because path folders are on the MATLAB path, class definitions placed in path folders behave like any ordinary function with respect to precedence. The first occurrence of a name on the MATLAB path takes precedence over all subsequent occurrences of the same name.

The name of each class definition file must match the name of the class that is specified with the classdef keyword. You can define multiple classes in the same path folder, but each class definition, including all methods, must be contained within one file.

Suppose that you have three classes defined in a single folder:

```
.../path_folder/MyClass1.m
.../path_folder/MyClass2.m
.../path_folder/MyClass3.m
```

To use these classes, add path folder to your MATLAB path.

```
addpath path_folder
```

Using Class Folders

The name of a class folder always begins with the @ character followed by the class name that the folder contains. A class folder must be contained in a path folder. Place the class definition file inside the class folder, which also can contain separate method files. For example, MyClass and two of its methods are defined inside the @MyClass folder.

```
.../parent_folder/@MyClass/MyClass.m
.../parent_folder/@MyClass/myMethod1.m
.../parent_folder/@MyClass/myMethod2.m
```

To use these classes, add path folder to your MATLAB path.

Use a class folder when you want to use more than one file for your class definition. Define only one class per class folder. MATLAB treats any function file in the class folder as a method of the class. Class definition files can have a .m or .p extension. Function files can be MATLAB code (.m), live code (.mlx), MEX functions (platform-dependent extensions), and P-code (.p).

Functions in Private Folders Within Class Folders

Private folders contain functions that are accessible only from functions defined in folders immediately above the private folder. Any functions defined in a private folder inside a class folder can only be called from the methods of the class. The functions have access to the private members of the class but are not themselves methods. They do not require an object to be passed as an input and can only be called using function notation. Use functions in private folders when you need helper functions that can be called from multiple methods of your class.

If a class folder contains a private folder, only the class defined in that folder can access functions defined in the private folder. Subclasses do not have access to superclass private functions. For more information on private folders, see "Private Functions".

If you want a subclass to have access to the private functions of the superclass, define the functions as protected methods of the superclass. Specify the methods with the Access attribute set to protected.

Dispatching to Methods in Private Folders

If a class defines functions in a private folder that is in a class folder, then MATLAB follows these precedence rules when dispatching to the private functions versus the methods of the classdef file:

- Using dot notation (*obj.methodName*), a method defined in the classdef file takes precedence over a function of the same name in the private folder.
- Using function notation (methodName(obj)), a function in a private folder takes precedence over a method of the same name defined in the classdef file.

Note You cannot put class definitions inside private folders.

Class Precedence and MATLAB Path

When there are multiple class definitions with the same name, the file location on the MATLAB path determines precedence. The class definition in the folder that comes first on the MATLAB path takes precedence over any classes that are later on the path.

A function with the same name as a class in a path folder takes precedence over the class if the function is in a folder that is earlier on the path. However, a class defined in a class folder (@-folder) takes precedence over a function of the same name, even if the function is defined in a folder that is earlier on the path.

For example, this path has a function and a class with the same name. Even though the function Foo in fldr1 is earlier in the path, the class Foo in fldr2 takes precedence because it is defined in a class folder.

Order in Path	Folder and File	File Defines
1	fldr1/Foo.m	Function Foo
2	fldr2/@Foo/Foo.m	Class Foo

Precedence of Classes in @-folders over Functions of the Same Name Will Be Removed in a Future Release

In a future release, the rule giving precedence to a class defined in a class folder (@-folder) over a function of the same name, regardless of position on the path, will be removed. Starting in R2024a, MATLAB issues a warning when these three conditions are met:

- You have a class defined in a class folder and a function with the same name on your path.
- The function appears earlier in the path order than the class.
- · You use the name of the function and class.

To ensure the class still has precedence after the rule change and avoid the warning, use one of these options:

- Update your path configuration to place the class earlier than the function on the path. For more information on working with the path, see "What Is the MATLAB Search Path?"
- Remove the function from the path.
- Rename the function.

To permanently give the function precedence and avoid the warning, use one of these options:

- Remove the class from the path.
- · Rename the class.

Changing the Path to Update Class Definitions

MATLAB can only recognize one definition of a class as the current definition. Changing your MATLAB path can change the definition file for a class (see path). MATLAB follows these rules for updating class definitions after a change to the path:

- When a class definition is removed from the path, MATLAB clears the class definition unless there are existing instances of that class in the workspace.
- When a new class definition is added to the path and it takes precedence over an old definition of the same name, MATLAB uses the new definition. MATLAB updates existing instances of the class the next time those instances are accessed.
- If you change the path in the middle of a script or function and a class is updated during that change, MATLAB does not update or clear any class definitions until the script or function finishes executing.

Note Changing the current folder is also a path change, and class definitions in the current folder always take precedence over definitions in the path.

The type of folder a class definition is contained in affects how MATLAB updates class definitions after path changes. MATLAB immediately updates class definitions when the new definition is in a class folder (@-folder), but for classes defined in path folders, you must clear the old definition before MATLAB recognizes the new definition.

See Also

More About

- "What Is the MATLAB Search Path?"
- "Create Namespaces" on page 6-20
- "Automatic Updates for Modified Classes" on page 5-27
- "Live Code File Format (.mlx)"
- "Call MEX Functions"
- "Use MEX Functions for MATLAB Class Methods"
- "Security Considerations to Protect Your Source Code"

Class Precedence

In this section...

"Use of Class Precedence" on page 6-18

"Why Mark Classes as Inferior" on page 6-18

"InferiorClasses Attribute" on page 6-18

Use of Class Precedence

MATLAB uses class precedence to determine which method to call when multiple classes have the same method. You can specify the relative precedence of user-defined classes with the class InferiorClasses attribute.

Why Mark Classes as Inferior

When more than one class defines methods with the same name or when classes overload functions, MATLAB determines which method or function to call based on the dominant argument. Here is how MATLAB determines the dominant argument:

- **1** Determine the dominant argument based on the class of arguments.
- 2 If there is a dominant argument, call the method of the dominant class.
- **3** If arguments are of equal precedence, use the leftmost argument as the dominant argument.
- If the class of the dominant argument does not define a method with the name of the called function, call the first function on the path with that name.

InferiorClasses Attribute

Specify the relative precedence of user-defined classes using the class InferiorClasses attribute. To specify classes that are inferior to the class you are defining, assign a cell array of class matlab.metadata.Class objects to this attribute.

For example, the following classdef declares that MyClass is dominant over *ClassName1* and *ClassName2*.

```
classdef (InferiorClasses = {?ClassName1,?ClassName2}) MyClass
   ...
end
```

The ? operator combined with a class name creates a matlab.metadata.Class object. See metaclass.

The following MATLAB classes are always inferior to classes defined using the classdef syntax and cannot be used in this list.

double, single, int64, uint64, int32, uint32, int16, uint16, int8, uint8, char, string, logical, cell, struct, and function_handle.

Dominant Class

MATLAB uses class dominance when evaluating expressions involving objects of more than one class. The dominant class determines:

- Which class method to call when more than one class defines methods with the same names.
- The class of arrays that are formed by combining objects of different classes, assuming MATLAB can convert the inferior objects to the dominant class.

No Attribute Inheritance

Subclasses do not inherit a superclass InferiorClasses attribute. Only classes specified in the subclass InferiorClasses attribute are inferior to subclass objects.

See Also

More About

"Class Precedence and MATLAB Path" on page 6-15

Create Namespaces

In this section...

"Namespace Folders" on page 6-20

"Define Code in Namespaces" on page 6-20

"Reference Namespace Members" on page 6-21

"Namespaces and the MATLAB Path" on page 6-22

"How MATLAB Handles Duplicate Names" on page 6-22

"The internal Namespace" on page 6-22

Namespaces are special folders that can contain class folders, class definition files, function files, and other namespaces (referred to as inner namespaces). Using a namespace helps organize code and creates more robust names for the items contained inside it. Function and class names must be unique inside a given namespace. The functions and classes are scoped to the namespace, so you can reuse those names in a different namespace.

Namespace Folders

Define a namespace by adding the + character at the beginning of the folder name. For example, the namespace folder +mynamesp contains a class, an enumeration class, a function, an inner namespace, and a second class in a class folder inside the inner namespace.

```
+mynamesp
+mynamesp/MyClass.m
+mynamesp/WeekdaysEnum.m
+mynamesp/myFunction.m
+mynamesp/+innernamesp/@MySecondClass/MySecondClass.m
```

Note This folder hierarchy is for example purposes only. It is not part of the MATLAB installation. To experiment with the functionality, define these folders and code on your own path.

To be accessible to MATLAB, the parent folder of the namespace folder must be on the path. Trying to add the namespace folder itself to the path causes an error. For more information, see "Namespaces and the MATLAB Path" on page 6-22.

Define Code in Namespaces

Define members of the namespace as you would any other code. Do not include the namespace name in the definitions. For example, in the sample hierarchy shown in "Namespace Folders" on page 6-20, the definition of myFunction includes only the function name.

```
function z = myFunction(x)
...
end
```

Similarly, the definition of MyClass includes only the class name.

```
classdef MyClass
    ...
end
```

Reference Namespace Members

To reference most namespace members, add the namespace name to the beginning of the member name, followed by a dot. For example, this statement creates an instance of MyClass, which is contained in mynamesp. (See the sample hierarchy shown in "Namespace Folders" on page 6-20.)

```
obj = mynamesp.MyClass(arg1,arg2);
```

A call to code defined in the namespace, even if the call is inside the namespace itself, must include the namespace name. For example, if myFunction is used as a property validation function by MyClass, the function name must include the namespace.

```
classdef MyClass
   properties
     myProp {mynamesp.myFunction}
   end
end
```

To simplify outside access to namespace code, you can import code from a namespace. Calling imported code does not require the namespace name. For more information, see "Import Namespace Members into Functions" on page 6-24.

Class Folders

When a class is defined in a class folder (@-folder), the class folder name is not part of the namespace name. For example, constructing an object of MySecondClass uses this syntax.

```
obj = mynamesp.innernamesp.MySecondClass(arg1,arg2);
```

Methods

Calling nonstatic methods of a class does not require the namespace name because you have an object of the class, which is already scoped to the namespace. Calling the myMethod method of obj, an instance of MyClass follows the usual syntax.

```
obj.myMethod(arg)
myMethod(obj,arg)
```

A static method always requires the full class name and the namespace.

```
mynamesp.myClass.stMethod(arg)
```

Properties

Like nonstatic methods, you can access the public properties of an instance without using the full namespace. However, accessing a constant property of a class without a specific instance of that class requires the full namespace. For example, if MyClass defines a constant property ConstProp, access it using the full namespace.

```
x = mynamesp.MyClass.ConstProp;
```

If you already have an instance of MyClass, you can access ConstProp without using the full namespace.

```
y = mynamesp.MyClass;
c = y.ConstProp;
```

Enumerations

To reference an enumeration member in a namespace, use the full namespace name. For example, this is a possible definition of WeekdaysEnum inside mynamesp.

```
classdef WeekdaysEnum
   enumeration
     Monday, Tuesday, Wednesday, Thursday, Friday
   end
end
```

Assign the enumeration member Monday to a variable using the full namespace.

```
day = mynamesp.WeekdaysEnum.Monday;
```

Namespaces and the MATLAB Path

You must add the parent folder of the top-level namespace to the MATLAB path to call code in the namespace. Namespace members are not accessible if the parent folder is not on the MATLAB path, even if the namespace folder is the current folder.

How MATLAB Handles Duplicate Names

Namespaces with the Same Name

Namespace folders do not take precedence over other namespace folders with the same name positioned later on the path. If two or more top-level namespaces have the same name, MATLAB treats them as one namespace. If two namespaces with the same name in different path folders define the same function name, then MATLAB finds only one of these functions.

Namespace Functions and Static Methods

When a namespace function and a static method have the same name, the namespace function takes precedence over the static method. For example, path folder fldrA contains a namespace function bar, and path folder fldrB contains a static method bar of class foo.

```
fldrA/+foo/bar.m % bar is a function in namespace foo
fldrB/@foo/bar.m % bar is a static method of class foo
```

Use the which command to show that the namespace function has precedence.

```
which foo.bar
fldrA\+foo\bar.m
```

The internal Namespace

MathWorks® reserves the use of namespaces named internal. Code contained in namespaces named internal is intended for MathWorks use only, and use of this code is discouraged. This code is not guaranteed to work in a consistent manner from one release to the next. Any of these functions and classes can be removed from the MATLAB software in any subsequent release without notice.

See Also

More About

- "Folders Containing Class Definitions" on page 6-14
- "Class Precedence" on page 6-18

Import Namespace Members into Functions

```
In this section...

"Import Classes, Namespace Functions, and Static Methods" on page 6-24

"Importing Namespace Members with the Same Name" on page 6-24

"Clear an Import List" on page 6-25
```

When referencing namespace members inside a function, you can simplify access to namespace members by importing them into the function. Once you have imported the code, you do not need to use the namespace name.

Note The namespace names and members used here are for example purposes only. They are not part of the MATLAB installation. To experiment with the functionality, define these folders and code on your own path.

Import Classes, Namespace Functions, and Static Methods

For example, use the import command to import MyClass from the namespace mynamesp. You can then reference MyClass inside the function without the namespace name.

The same process works for namespace functions and static methods, as shown in these examples. Importing the code into the function enables you to call the code without the namespace.

```
function myFuncA
   import mynamesp.myFunction
   myFunction(arg,...); % call imported namespace function
end

function myFuncB
   import mynamesp.MyClass.myStaticMethod
   myStaticMethod(arg,...); % call static method
end
```

You can import all code in a namespace using the syntax mynamesp.*. However, you should avoid doing so because of potential naming conflicts. See "Importing Namespace Members with the Same Name" on page 6-24 for more information.

Importing Namespace Members with the Same Name

Use caution when importing namespace members to avoid name conflicts. For example, this folder hierarchy contains a namespace function and a class method with the same name, timedata.

```
+mynamesp/timedata.m % namespace function
+mynamesp/@MyClass/MyClass.m % class definition file
+mynamesp/@MyClass/timedata.m % class method
```

Import the namespace and attempt to call timedata on an instance of MyClass.

```
import mynamesp.*
myobj = MyClass;
timedata(myobj)
```

Calling timedata using the function syntax instead of the dot syntax calls the namespace function because MATLAB finds the imported function first.

Clear an Import List

You cannot clear the import list from a function workspace. However, you can clear the base workspace using clear import.

See Also

import

More About

• "Create Namespaces" on page 6-20

Creating and Managing Class Aliases

A *class alias definition* is a mapping of one or more old class names to a new name. Creating alias definitions enables you to rename classes while maintaining backward compatibility with code and MAT-files that use one or more older class names. In effect, MATLAB recognizes more than one name for the same class. This functionality enables you to update class names when the older names no longer reflect your current design.

Creating an Alias Definition File

The matlab.alias.AliasFileManager class provides an API for creating and maintaining alias definitions. Aliases are not part of class definitions. Instead, alias definition files are stored in resources folders that are located in the same folder as the latest class file.

The recommended process for creating and maintaining alias files is to use functions to automate the process. To create a class alias definition, the function must:

- 1 Create an instance of matlab.alias.AliasFileManager.
- 2 Call the addAlias method on the instance with the new class name and the old class names as arguments.
- 3 Call the writeAliasFile method on the instance to write the alias definition file. The method writes the definition file to a folder called resources. The method creates the resources folder if one does not already exist.

Run the function from the same folder that contains the new class definition. For example, a class named FirstName is defined in a folder named Work. Update the name of the class from FirstName to SecondName using a function called createAliasFile with this folder structure:

The FirstName class file is not needed to create the alias. In fact, you must remove the original definition from the path so that MATLAB finds the newer alias instead of the older definition.

The final folder structure after running createAliasFile looks like this:



MATLAB recognizes both FirstName and SecondName as the same class as long as SecondName.m and the associated alias resources folder are in the same folder on the MATLAB path.

See the example "Rename Class" for more details.

Renaming a Class Multiple Times

You can define multiple aliases for the same class. When doing so, you must pass in all of the old aliases to the addAlias method. The aliases must be listed in order from newest to oldest. Keeping the original function used to define the alias can help you avoid errors by maintaining a record of the alias definitions. addAlias returns an error if all of the previous aliases are not included as part of the OldNames input argument.

For an example, see "Rename Class That Has Existing Aliases".

Renaming a Namespace

Renaming the entire contents of a namespace in one step is not supported. To rename a namespace, you must define aliases for all the classes in the namespace. For an example, see "Rename Namespace of Two Classes".

Note You cannot create aliases for namespace functions. To rename a namespace that contains functions, keep the old namespace in place and redefine the namespace functions to redirect to the functions in the new namespace.

Viewing Alias Definitions

There are two ways to view alias definitions:

- Create a matlab.metadata.Class instance for the class you want to investigate. The Aliases property of matlab.metadata.Class returns all of the defined class aliases in a string array, in order from newest to oldest. For more information, see matlab.metadata.Class.
- Create a matlab.alias.AliasFileManager instance with the location input argument, where location points to the folder that contains the resources folder of the class alias definition file. The Aliases property of the matlab.alias.AliasFileManager instance returns an array of all alias definitions in that given definition file. For an example of accessing the Aliases property, see "Rename Namespace of Two Classes".

Note that reading in an existing alias definition file does not validate that the current class names in that file exist.

Backward and Forward Compatibility of Aliases

To share code that includes classes that have been renamed using aliasing, include one of these two items with your code:

- The alias-creating function in the setup script of your application or toolbox
- The resources folder that contains the class alias definition file

The alias definition enables MATLAB to recognize both names as the same class. Including or creating an alias definition in your new code ensures backward compatibility:

- New code can work with code that uses old class names because the old names are recognized as aliases.
- New code can load and work with MAT-files containing serialized objects that were created using the old names.

When serializing objects, using the oldest defined alias for the objects allows the greatest range of compatibility. Objects serialized using the oldest alias can be used by any code back to the original definition and any future code that maintains the full alias definition. Deleting alias definitions or deleting old names from existing definitions is not recommended because backward and forward compatibility can be limited.

See Also

matlab.alias.AliasFileManager

Value or Handle Class — Which to Use

- "Comparison of Handle and Value Classes" on page 7-2
- "Which Kind of Class to Use" on page 7-9
- "The Handle Superclass" on page 7-11
- "Handle Class Destructor" on page 7-13
- "Find Handle Objects and Properties" on page 7-21
- "Implement Set/Get Interface for Properties" on page 7-22
- "Implement Copy for Handle Classes" on page 7-30
- "Weak Reference Handles" on page 7-36

Comparison of Handle and Value Classes

```
In this section...

"Basic Difference" on page 7-2

"Behavior of MATLAB Built-In Classes" on page 7-2

"User-Defined Value Classes" on page 7-3

"User-Defined Handle Classes" on page 7-4

"Determining Equality of Objects" on page 7-6

"Functionality Supported by Handle Classes" on page 7-7
```

Basic Difference

A value class constructor returns an object that is associated with the variable to which it is assigned. If you reassign this variable, MATLAB creates an independent copy of the original object. If you pass this variable to a function to modify it, the function must return the modified object as an output argument. For information on value-class behavior, see "Avoid Unnecessary Copies of Data".

A handle class constructor returns a handle object that is a reference to the object created. You can assign the handle object to multiple variables or pass it to functions without causing MATLAB to make a copy of the original object. A function that modifies a handle object passed as an input argument does not need to return the object.

All handle classes are derived from the abstract handle class.

Create a Value Class

By default, MATLAB classes are value classes. The following definition creates a value class named MyValueClass:

```
classdef MyValueClass
    ...
end
```

Create a Handle Class

To create a handle class, derive the class from the handle class.

```
classdef MyHandleClass < handle
   ...
end</pre>
```

Behavior of MATLAB Built-In Classes

MATLAB fundamental classes are value classes (numeric, logical, char, cell, struct, and function handle). For example, if you create an object of the class int32 and make a copy of this object, the result is two independent objects. When you change the value of a, the value of b does not change. This behavior is typical of classes that represent values.

```
a = int32(7);
b = a;
a = a^4;
```

```
b 7
```

MATLAB graphics objects are implemented as handle objects because they represent visual elements. For example, create a graphics line object and copy its handle to another variable. Both variables refer to the same line object.

```
x = 1:10; y = sin(x);
l1 = line(x,y);
l2 = l1;
```

Set the properties of the line object using either copy of the handle.

Calling the delete function on the 12 handle destroys the line object. If you attempt to set the Color property on the line 11, the set function returns an error.

```
delete(l2)
set(l1,'Color','blue')
Error using matlab.graphics.primitive.Line/set
Invalid or deleted object.
```

If you delete the object by deleting any one of the existing handles, all copies are now invalid because you deleted the single object to which all handles refer.

Deleting a handle object is not the same as clearing the handle variable. In the graphics object hierarchy, the parent of the object holds a reference to the object. For example, the parent axes hold a reference to the line object referred to by 11 and 12. If you clear both variables from the workspace, the object still exists.

For more information on the behavior of handle objects, see "Handle Object Behavior" on page 1-7.

User-Defined Value Classes

MATLAB associates objects of value classes with the variables to which you assign the object. When you copy a value object to another variable or pass a value object to a function, MATLAB creates an independent copy of the object and all the data contained by the object. The new object is independent of changes to the original object. Value objects behave like MATLAB numeric and struct classes. Each property behaves essentially like a MATLAB array.

Value objects are always associated with one workspace or temporary variable. Value objects go out of scope when their variable goes out of scope or is cleared. There are no references to value objects, only copies that are independent objects.

Value Object Behavior

Here is a value class that stores a value in its Number property. The default property value is the number 1.

```
classdef NumValue
   properties
     Number = 1
   end
end
```

Create a NumValue object assigned to the variable a.

```
a = NumValue
a =
  NumValue with properties:
    Number: 1
```

Assign the value of a to another variable, b.

```
b = a
b =
  NumValue with properties:
    Number: 1
```

The variables a and b are independent. Changing the value of the Number property of a does not affect the Number property of b.

```
a.Number = 7
a =
   NumValue with properties:
       Number: 7
b
b =
   NumValue with properties:
   NumValue with properties:
```

Modifying Value Objects in Functions

When you pass a value object to a function, MATLAB creates a copy of that object in the function workspace. Because copies of value objects are independent, the function does not modify the object in the caller's workspace. Therefore, functions that modify value objects must return the modified object to be reassigned in the caller's workspace.

For more information, see "Object Modification" on page 5-35.

User-Defined Handle Classes

Instances of classes that derive from the handle class are references to the underlying object data. When you copy a handle object, MATLAB copies the handle, but does not copy the data stored in the

object properties. The copy refers to the same object as the original handle. If you change a property value on the original object, the copied handle references the same change.

Handle Object Behavior

Here is a handle class that stores a value in its Number property. The default property value is the number 1.

```
classdef NumHandle < handle
   properties
      Number = 1
   end
end</pre>
```

Create a NumHandle objects assigned to the variable a.

```
a = NumHandle
a =
  NumHandle with properties:
    Number: 1
```

Assign the value of a to another variable, b.

```
b = a
b =
   NumHandle with properties:
    Number: 1
```

The variables a and b refer to the same underlying object. Changing the value of the Number property of a also changes the Number property of b. That is, a and b refer to the same object.

```
a.Number = 7
a =
   NumHandle with properties:
        Number: 7
b
b =
   NumHandle with properties:
        NumHandle with properties:
```

Modifying Handle Objects in Functions

When you pass a handle object to a function, MATLAB creates a copy of the handle in the function workspace. Because copies of handles reference the same underlying object, functions that modify the handle object effectively modify the object in the caller's workspace as well. Therefore, it is not

necessary for functions that modify handle objects passed as input arguments to return the modified object to the caller.

For more information, see "Object Modification" on page 5-35.

Deleting Handles

You can destroy handle objects by explicitly calling the handle delete method. Deleting the handle of a handle class object makes all handles invalid. For example:

```
a = NumHandle;
b = a;
delete(a)
b.Number
Invalid or deleted object.
```

Calling delete on a handle object invokes the destructor function or functions for that object. See "Handle Class Destructor" on page 7-13 for more information.

Initialize Properties to Contain Handle Objects

For information on the differences between initializing properties to default values in the properties block and initializing properties from within the constructor, see "Initialize Property Values" on page 8-14 and "Create and Initialize Object Arrays" on page 10-2.

Determining Equality of Objects

Equality for value objects means that the objects are of the same class and have the same state.

Equality for handle objects means that the handle variables refer to the same object. You also can identify handle variables that refer to different objects of the same class that have the same state.

Equality of Value Objects

To determine if value objects are the same size and their contents are of equal value, use isequal. For example, use the previously defined NumValue class to create two instances and test for equality:

```
a = NumValue;
b = NumValue;
isequal(a,b)
ans =
```

a and b are independent and therefore are not the same object. However each represents the same value.

If you change the value represented by a value object, the objects are no longer equal.

```
a = NumValue;
b = NumValue;
b.Number = 7;
isequal(a,b)
```

```
ans =
```

Value classes do not have a default eq method to implement the == operation.

Equality of Handle Objects

Handle objects inherit an eq method from the handle base class. You can use == and isequal to test for two different relationships among handle objects:

- The handles refer to the same object: == and isequal return true.
- The handles refer to objects of the same class that have the same values, but are not the same objects only isequal returns true.

Use the previously defined NumHandle class to create an object and copy the handle.

```
a = NumHandle;
b = a;
Test for equality using == and isequal.
a == b
ans =
    1
isequal(a,b)
ans =
    1
Create two instances of the NumHandle class using the default values.
a = NumHandle;
b = NumHandle;
```

Determine if \boldsymbol{a} and \boldsymbol{b} refer to the same object.

```
a == b
ans =
```

Determine if a and b have the same values.

```
isequal(a,b)
ans =
1
```

Functionality Supported by Handle Classes

Deriving from the handle class enables your class to:

- Inherit several useful methods ("Handle Class Methods" on page 7-11)
- Define events and listeners ("Events and Listeners Syntax" on page 11-18)
- Define dynamic properties ("Dynamic Properties Adding Properties to an Instance" on page 8-48)
- Implement set and get methods ("Implement Set/Get Interface for Properties" on page 7-22)
- Customize copy behavior ("Implement Copy for Handle Classes" on page 7-30)
- Weak references ("Weak Reference Handles" on page 7-36)

See "The Handle Superclass" on page 7-11 for more information on the handle class and its methods.

See Also

Related Examples

- "Which Kind of Class to Use" on page 7-9
- "Implement Copy for Handle Classes" on page 7-30
- "Handle Object Behavior" on page 1-7

Which Kind of Class to Use

In this section...

"Examples of Value and Handle Classes" on page 7-9

"When to Use Value Classes" on page 7-9

"When to Use Handle Classes" on page 7-9

Examples of Value and Handle Classes

Handle and value classes are useful in different situations. For example, value classes enable you to create array classes that have the same behavior as MATLAB numeric classes. "Representing Polynomials with Classes" on page 19-2 and "Representing Structured Data with Classes" on page 3-14 provides examples of value classes.

Handle classes enable you to create objects that more than one function or object can share. Handle objects allow more complex interactions among objects because they allow objects to reference each other. "Implementing Linked Lists with Classes" on page 3-23 and "Developing Classes That Work Together" on page 3-6 provides examples of a handle class.

When to Use Value Classes

Value class objects behave like normal MATLAB variables. A typical use of value classes is to define data structures. For example, suppose that you want to define a class to represent polynomials. This class can define a property to contain a list of coefficients for the polynomial. It can implement methods that enable you to perform various operations on the polynomial object. For example, implement addition and multiplication without converting the object to another class.

A value class is suitable because you can copy a polynomial object and have two objects that are identical representations of the same polynomial. For an example of value classes, see "Subclasses of MATLAB Built-In Types" on page 12-40.

For information on MATLAB pass-by-value semantics, see "Avoid Unnecessary Copies of Data".

When to Use Handle Classes

Handle objects are useful in specialized circumstances where an object represents a physical object such as a graph or an external device rather than a mathematical object like a number or matrix. Handle objects are derivations of the handle class, which provides functionality such as events and listeners, destructor method, and support for dynamic properties.

Use a handle class when:

- No two instances of a class can have the same state, making it impossible to have exact copies. For example:
 - A copy of a graphics object (such as a line) has a different position in its parents list of children than the object from which it was copied. Therefore, the two objects are not identical.
 - Nodes in lists or trees having specific connectivity to other nodes. No two nodes can have the same connectivity.

- The class represents physical and unique objects like serial ports and printers.
- The class represents visible objects like graphics components.
- The class defines events and notifies listeners when an event occurs (notify is a handle class method).
- The class creates listeners by calling the handle class addlistener method.
- The class subclasses the dynamicprops class (a subclass of handle) so that instances can define dynamic properties.
- The class subclasses the matlab.mixin.SetGet class (a subclass of handle) so that it can implement a graphics object style set/get interface to access property values.
- You want to create a singleton class or a class in which you track the number of instances from within the constructor.

See Also

Related Examples

"Handle Compatible Classes" on page 12-31

The Handle Superclass

In this section...

"Building on the Handle Class" on page 7-11

"Handle Class Methods" on page 7-11

"Event and Listener Methods" on page 7-11

"Relational Methods" on page 7-12

"Test Handle Validity" on page 7-12

"When MATLAB Destroys Objects" on page 7-12

Building on the Handle Class

The handle class is an abstract class. Therefore, you cannot create objects of this class directly. Use the handle class as a superclass to implement subclasses that inherit handle behavior. MATLAB defines several classes that derive from the handle class. These classes provide specialized functionality to subclasses.

Specialized Handle Base Classes

To add both handle behavior and specific functionality to your class, derive your class from these handle classes:

- matlab.mixin.SetGet Provides set and get methods to access property values.
- dynamicprops Enables you to define properties that are associated with an object, but not the class in general.
- matlab.mixin.Copyable Provides a copy method that you can customize for your class.

For information on how to define subclasses, see "Design Subclass Constructors" on page 12-7.

Handle Class Methods

When you derive a class from the handle class, the subclass inherits methods that enable you to work more effectively with handle objects.

List the methods of a class by passing the class name to the methods function:

```
methods('handle')

Methods for class handle:

addlistener findobj gt lt
delete findprop isvalid ne
eq ge le notify
```

Event and Listener Methods

For information on how to use the notify and addlistener methods, see "Events and Listeners Syntax" on page 11-18.

Relational Methods

```
TF = eq(H1,H2)
TF = ne(H1,H2)
TF = lt(H1,H2)
TF = le(H1,H2)
TF = gt(H1,H2)
TF = ge(H1,H2)
```

The handle class overloads these functions to support equality tests and sorting on handles. For each pair of input arrays, these functions return a logical array of the same size. Each element is an element-wise equality or comparison test result. The input arrays must be the same size or one (or both) can be scalar. The method performs scalar expansion as required. For more information on handle class relational methods, see relational operators.

Test Handle Validity

Use the isvalid handle class method to determine if a variable is a valid handle object. For example, in the statement:

```
B = isvalid(H)
```

B is a logical array in which each element is true if, and only if, the corresponding element of H is a valid handle. B is always the same size as H.

When MATLAB Destroys Objects

MATLAB destroys objects in the workspace of a function when the function:

- · Reassigns an object variable to a new value
- Does not use an object variable for the remainder of a function
- · Function execution ends

When MATLAB destroys an object, it also destroys values stored in the properties of the object. MATLAB frees computer memory associated with the object for use by MATLAB or the operating system.

You do not need to free memory in handle classes. However, there can be other operations that you want to perform when destroying an object. For example, closing a file or shutting down an external program that the object constructor started. Define a delete method in your handle subclass for these purposes.

See "Handle Class Destructor" on page 7-13 for more information.

See Also

Related Examples

• "Comparison of Handle and Value Classes" on page 7-2

Handle Class Destructor

In this section...

"Basic Knowledge" on page 7-13

"Syntax of Handle Class Destructor Method" on page 7-13

"Handle Object During delete Method Execution" on page 7-14

"Support Destruction of Partially Constructed Objects" on page 7-15

"When to Define a Destructor Method" on page 7-15

"Destructors in Class Hierarchies" on page 7-16

"Object Lifecycle" on page 7-16

"Restrict Access to Object Delete Method" on page 7-17

"Nondestructor Delete Methods" on page 7-18

"External References to MATLAB Objects" on page 7-18

Basic Knowledge

Class destructor – a method named delete that MATLAB calls implicitly before destroying an object of a handle class. Also, user-defined code can call delete explicitly to destroy an object.

Nondestructor - a method named delete that does not meet the syntax requirements of a valid destructor. Therefore, MATLAB does not call this method implicitly when destroying handle objects. A method named delete in a value class is not a destructor. A method named delete in a value class that sets the HandleCompatible attribute to true is not a destructor.

"Object Lifecycle" on page 7-16

"Method Attributes" on page 9-4

Syntax of Handle Class Destructor Method

MATLAB calls the destructor of a handle class when destroying objects of the class. MATLAB recognizes a method named delete as the class destructor only if you define delete as an ordinary method with the appropriate syntax.

To be a valid class destructor, the delete method:

- Must define one, scalar input argument, which is an object of the class.
- Must not define output arguments
- Cannot be Sealed, Static, or Abstract
- Cannot use arguments blocks for input argument validation.

In addition, the delete method should not:

- Throw errors, even if the object is invalid.
- Create new handles to the object being destroyed

· Call methods or access properties of subclasses

MATLAB does not call a noncompliant delete method when destroying objects of the class. A noncompliant delete method can prevent the destruction of the object by shadowing the handle class delete method.

A delete method defined by a value class that is handle compatible is not a destructor, even if the delete method is inherited by a handle subclass. For information on handle compatible classes, see "Handle Compatible Classes" on page 12-31.

Declare delete as an ordinary method:

```
methods
   function delete(obj)
    % obj is always scalar
   ...
   end
end
```

delete Called Element-Wise on Array

MATLAB calls the delete method separately for each element in an array. Therefore, a delete method is passed only one scalar argument with each invocation.

Calling delete on a deleted handle should not error and can take no action. This design enables delete to work on object arrays containing a mix of valid and invalid objects.

Handle Object During delete Method Execution

Calling the delete method on an object always results in the destruction of the object. The object is destroyed when the call to delete is made explicitly in MATLAB code or when called by MATLAB because an object is no longer reachable from any workspace. Once called, a delete method cannot abort or prevent object destruction.

A delete method can access properties of the object being deleted. MATLAB does not destroy these properties until after the delete methods for the class of the object and all superclasses finish executing.

If a delete method creates new variables that contain a handle to the object being deleted, those handles are invalid. After the delete method finishes execution, handles to the deleted object in any variables in any workspace are invalid.

The isvalid method returns false for the handle object within the delete method because object destruction begins when the method is called.

MATLAB calls delete methods in the inverse of the construction order. That is, MATLAB invokes subclass delete methods before superclass delete methods.

If a superclass expects a property to be managed by subclasses, then the superclass should not access that property in its delete method. For example, if a subclass uses an inherited abstract property to store an object handle, then the subclass should destroy this object in its delete method, but the superclass should not access that property in its delete method.

Support Destruction of Partially Constructed Objects

Errors that occur while constructing an object can result in a call to delete before the object is fully created. Therefore, class delete methods must be able to work with partially constructed objects.

For example, the PartialObject class delete method determines if the Data property is empty before accessing the data this property contains. If an error occurs while assigning the constructor argument to the Name property, MATLAB passes the partially constructed object to delete.

```
classdef PartialObject < handle</pre>
   properties
      % Restrict the Name property
      % to a cell array
      Name cell
      Data
   end
   methods
      function h = PartialObject(name)
         if nargin > 0
            h.Name = name;
            h.Data.a = rand(10,1);
         end
      end
      function delete(h)
         % Protect against accessing properties
         % of partially constructed objects
         if ~isempty(h.Data)
            t = h.Data.a;
            disp(t)
         else
            disp('Data is empty')
         end
      end
   end
end
```

An error occurs if you call the constructor with a char vector, instead of the required cell array:

```
obj = PartialObject('Test')
```

MATLAB passes the partially constructed object to the delete method. The constructor did not set the value of the Data property because the error occurred when setting the Name property.

```
Data is empty
Error setting 'Name' property of 'PartialObject' class:
```

When to Define a Destructor Method

Use a delete method to perform cleanup operations before MATLAB destroys the object. MATLAB calls the delete method reliably, even if execution is interrupted with Ctrl-c or an error.

If an error occurs during the construction of a handle class, MATLAB calls the class destructor on the object along with the destructors for any objects contained in properties and any initialized base classes.

For example, suppose that a method opens a file for writing and you want to close the file in your delete method. The delete method can call fclose on a file identifier that the object stores in its FileID property:

```
function delete(obj)
  fclose(obj.FileID);
end
```

Destructors in Class Hierarchies

If you create a hierarchy of classes, each class can define its own delete method. When destroying an object, MATLAB calls the delete method of each class in the hierarchy. Defining a delete method in a handle subclass does not override the handle class delete method. Subclass delete methods augment the superclass delete methods.

Inheriting a Sealed Delete Method

Classes cannot define a valid destructor that is Sealed. MATLAB returns an error when you attempt to instantiate a class that defines a Sealed delete method.

Normally, declaring a method as Sealed prevents subclasses from overriding that method. However, a Sealed method named delete that is not a valid destructor does not prevent a subclass from defining its own destructor.

For example, if a superclass defines a method named delete that is not a valid destructor, but is Sealed, then subclasses:

- Can define valid destructors (which are always named delete).
- Cannot define methods named delete that are not valid destructors.

Destructors in Heterogeneous Hierarchies

Heterogeneous class hierarchies require that all methods to which heterogeneous arrays are passed must be sealed. However, the rule does not apply to class destructor methods. Because destructor methods cannot be sealed, you can define a valid destructor in a heterogeneous hierarchy that is not sealed, but does function as a destructor.

For information on heterogeneous hierarchies, see "Designing Heterogeneous Class Hierarchies" on page 10-19

Object Lifecycle

MATLAB invokes the delete method when the lifecycle of an object ends. The lifecycle of an object ends when the object is:

- · No longer referenced anywhere
- · Only referenced by weak handles
- Explicitly deleted by calling delete on the handle

Inside a Function

The lifecycle of an object referenced by a local variable or input argument exists from the time the variable is assigned until the time it is reassigned, cleared, or no longer referenced within that function or in any handle array.

A variable goes out of scope when you explicitly clear it or when its function ends. When a variable goes out of scope and its value belongs to a handle class that defines a delete method, MATLAB calls that method. MATLAB defines no ordering among variables in a function. Do not assume that MATLAB destroys one value before another value when the same function contains multiple values.

Sequence During Handle Object Destruction

MATLAB invokes the delete methods in the following sequence when destroying an object:

- 1 The delete method for the class of the object
- 2 The delete method of each superclass class, starting with the immediate superclasses and working up the hierarchy to the most general superclasses

MATLAB invokes the delete methods of superclasses at the same level in the hierarchy in the order specified in the class definition. For example, the following class definition specifies supclass1 before supclass2. MATLAB calls the delete method of supclass1 before the delete method of supclass2.

classdef myClass < supclass1 & supclass2</pre>

After calling each delete method, MATLAB destroys the property values belonging exclusively to the class whose method was called. However, if the property values contain handle objects that are still referenced outside the scope of the class, calling delete on the containing object does not delete the property handle objects themselves. They can still be accessed by other existing references.

Superclass delete methods cannot call methods or access properties belonging to a subclass.

Destruction of Objects with Cyclic References

Consider a set of objects that reference other objects of the set such that the references form a cyclic graph. In this case, MATLAB:

- Destroys the objects if they are referenced only within the cycle
- Does not destroy the objects as long as there is an external reference to any of the objects from a MATLAB variable outside the cycle

MATLAB destroys the objects in the reverse of the order of construction. for more information, see "Handle Object During delete Method Execution" on page 7-14.

Restrict Access to Object Delete Method

Destroy handle objects by explicitly calling delete on the object:

delete(obj)

A class can prevent explicit destruction of an object by setting its delete method Access attribute to private. However, a method of the class can call the private delete method.

If the class delete method Access attribute is protected, only methods of the class and of subclasses can explicitly delete objects of that class.

However, when an object lifecycle ends, MATLAB calls the object's delete method when destroying the object regardless of the method's Access attribute.

Inherited Private Delete Methods

Class destructor behavior differs from the normal behavior of an overridden method. MATLAB executes each delete method of each superclass upon destruction, even if that delete method is not public.

When you explicitly call an object's delete method, MATLAB checks the delete method Access attribute in the class defining the object, but not in the superclasses of the object. A superclass with a private delete method cannot prevent the destruction of subclass objects.

Declaring a private delete method makes most sense for sealed classes. In the case where classes are not sealed, subclasses can define their own delete methods with public access. MATLAB calls a private superclass delete method as a result of an explicit call to a public subclass delete method.

Nondestructor Delete Methods

A class can implement a method named delete that is not a valid class destructor. MATLAB does not call this method implicitly when destroying an object. In this case, delete behaves like an ordinary method.

For example, if the superclass implements a Sealed method named delete that is not a valid destructor, then MATLAB does not allow subclasses to override this method.

A delete method defined by a value class cannot be a class destructor.

External References to MATLAB Objects

MATLAB does not manage object lifecycles that involve external languages that perform their own object lifecycle management (aka, garbage collection). MATLAB cannot detect when it is safe to destroy objects used in cyclic references because the external environment does not notify MATLAB when external reference have been destroyed.

If you cannot avoid external references to MATLAB objects, explicitly break the cyclic reference by destroying the objects in MATLAB.

The following section describes how to manage this situation when using Java objects that reference MATLAB objects.

Java References Can Prevent Destructor Execution

Java does not support the object destructors that MATLAB objects use. Therefore, it is important to manage the lifecycle of all objects used in applications that include both Java and MATLAB objects.

Java objects that hold references to MATLAB objects can prevent deletion of the MATLAB objects. In these cases, MATLAB does not call the handle object delete method even when there is no handle variable referring to that object. To ensure your delete method executes, call delete on the object explicitly before the handle variable goes out of scope.

Problems can occur when you define callbacks for Java objects that reference MATLAB objects.

For example, the CallbackWithJava class creates a Java com.mathworks.jmi.Callback object and assigns a class method as the callback function. The result is a Java object that has a reference to a handle object via the function-handle callback.

```
classdef CallbackWithJava < handle</pre>
   methods
      function obj = CallbackWithJava
         jo = com.mathworks.jmi.Callback;
         set(jo,'DelayedCallback',@obj.cbFunc); % Assign method as callback
         jo.postCallback
      end
      function cbFunc(obj,varargin)
         c = class(obj);
         disp(['Java object callback on class ',c])
      end
      function delete(obj)
         c = class(obj);
         disp(['ML object destructor called for class ',c])
      end
  end
end
```

Suppose that you create a CallbackWithJava object from within a function:

```
function testDestructor
   cwj = CallbackWithJava
   ...
end
```

Creating an instance of the CallbackWithJava class creates the com.mathworks.jmi.Callback object and executes the callback function:

testDestructor

```
cwj =
  CallbackWithJava with no properties.
Java object callback on class CallbackWithJava
```

The handle variable, cwj, exists only in the function workspace. However, MATLAB does not call the class delete method when the function ends. The com.mathworks.jmi.Callback object still exists and holds a reference to the object of the CallbackWithJava class, which prevents destruction of the MATLAB object.

```
clear classes
Warning: Objects of 'CallbackWithJava' class exist. Cannot clear this class or
any of its superclasses.
```

To avoid causing inaccessible objects, call delete explicitly before losing the handle to the MATLAB object.

```
function testDestructor
   cwj = CallbackWithJava
   ...
   delete(cwj)
end
```

Manage Object Lifecycle in Applications

MATLAB applications that use Java or other external-language objects should manage the lifecycle of the objects involved. A typical user interface application references Java objects from MATLAB objects and creates callbacks on Java objects that reference MATLAB objects.

You can break these cyclic references in various ways:

- Explicitly call delete on the MATLAB objects when they are no longer needed
- Unregister the Java object callbacks that reference MATLAB objects
- Use intermediate handle objects that reference both the Java callbacks and the MATLAB objects.

See Also

More About

• "Handle Object Behavior" on page 1-7

Find Handle Objects and Properties

```
In this section...

"Find Handle Objects" on page 7-21

"Find Handle Object Properties" on page 7-21
```

Find Handle Objects

The findobj method enables you to locate handle objects that meet certain conditions.

```
function HM = findobj(H, <conditions>)
```

The findobj method returns an array of handles matching the conditions specified. You can use regular expressions with findobj. For more information, see regexp.

Find Handle Object Properties

The findprop method returns the matlab.metadata.Property object for the specified object and property.

```
function mp = findprop(h,'PropertyName')
```

The property can also be a dynamic property created by the addprop method of the dynamicprops class.

Use the returned matlab.metadata.Property object to obtain information about the property, such as the settings of any of its attributes. For example, the following statements determine that the setting of the AccountStatus property Dependent attribute is false.

```
ba = BankAccount(007,50,'open');
mp = findprop(ba,'AccountStatus');
mp.Dependent
ans =
0
```

See Also

handle

Related Examples

• "Class Metadata" on page 16-2

Implement Set/Get Interface for Properties

In this section...

"The Standard Set/Get Interface" on page 7-22

"Subclass Syntax" on page 7-22

"Get Method Syntax" on page 7-22

"Set Method Syntax" on page 7-23

"Class Derived from matlab.mixin.SetGet" on page 7-24

"Set Priority for Matching Partial Property Names" on page 7-27

The Standard Set/Get Interface

Some MATLAB objects, such as graphics objects, implement an interface based on set and get functions. These functions enable access to multiple properties on arrays of objects in a single function call.

You can add set and get functionality to your class by deriving from one of these classes:

- matlab.mixin.SetGet use when you want support for case-insensitive, partial property name matching. Deriving from matlab.mixin.SetGet does not affect the exact property name required by the use of dot notation reference to properties.
- matlab.mixin.SetGetExactNames use when you want to support only case-sensitive full property name matching.

Note The set and get methods referred to in this section are different from property set access and property get access methods. See "Property Get and Set Methods" on page 8-39 for information on property access methods.

Subclass Syntax

Use the abstract class matlab.mixin.SetGet or matlab.mixin.SetGetExactNames as a superclass:

```
classdef MyClass < matlab.mixin.SetGet
   ...
end</pre>
```

Because matlab.mixin.SetGet and matlab.mixin.SetGetExactNames derive from the handle class, your subclass is also a handle class.

Get Method Syntax

The get method returns the value of an object property using the object handle and the property name. For example, assume H is the handle to an object:

```
v = get(H,'PropertyName');
```

If you specify an array of handles with a single property name, get returns the property value for each object as a cell array of values:

```
CV = get(H,'PropertyName');
```

The CV array is always a column regardless of the shape of H.

If you specify a cell array of char vector property names and an array of handles, **get** returns a cell array of property values. Each row in the cell corresponds to an object in the handle array. Each column in the cell corresponds to a property name.

```
props = {'PropertyName1','PropertyName2'};
CV = get(H,props);
get returns an m-by-n cell array, where m = length(H) and n = length(props).
```

If you specify a handle array, but no property names, get returns an array of type struct in which each structure in the array corresponds to an object in H. Each field in each structure corresponds to a property defined by the class of H. The value of each field is the value of the corresponding property.

```
SV = get(H);
```

If you do not assign an output variable, then H must be scalar.

For an example, see "Using get with Arrays of Handles" on page 7-25.

Set Method Syntax

The set method assigns the specified value to the specified property for the object with handle H. If H is an array of handles, MATLAB assigns the value to the property for each object in the array H.

```
set(H, 'PropertyName', PropertyValue)
```

You can pass a cell array of property names and a cell array of property values to set:

```
props = {'PropertyName1','PropertyName2'};
vals = {Property1Value,Property2Value};
set(H,props,vals)
```

If length(H) is greater than one, then the property value cell array (vals) can have values for each property in each object. For example, suppose length(H) is 2 (two object handles). You want to assign two property values on each object:

```
props = {'PropertyName1','PropertyName2'};
vals = {Property11Value,Property12Value;Property21Value,Property22Value};
set(H,props,vals))
```

The preceding statement is equivalent to the follow two statements:

```
set(H(1),'PropertyName1',Property11Value,'PropertyName2',Property12Value)
set(H(2),'PropertyName1',Property21Value,'PropertyName2',Property22Value)
```

If you specify a scalar handle, but no property names, set returns a struct with one field for each property in the class of H. Each field contains an empty cell array.

```
SV = set(h);
```

Tip You can use any combination of property name/property value cell arrays, structure arrays (with the field names as property names and field values as property values), and cell arrays in one call to set.

Class Derived from matlab.mixin.SetGet

This sample class defines a set/get interface and illustrates the behavior of the inherited methods:

```
classdef LineType < matlab.mixin.SetGet</pre>
   properties
      Style = '-'
      Marker = 'o'
   properties (SetAccess = protected)
      Units = 'points'
   end
   methods
      function obj = LineType(s,m)
         if nargin > 0
            obj.Style = s;
             obj.Marker = m;
         end
      end
      function set.Style(obj,val)
         if ~(strcmpi(val,'-') ||...
                strcmpi(val,'--') ||...
                strcmpi(val,'..'))
             error('Invalid line style ')
         obj.Style = val;
      function set.Marker(obj,val)
         if ~isstrprop(val, 'graphic')
             error('Marker must be a visible character')
         obj.Marker = val;
      end
   end
end
Create an instance of the class and save its handle:
h = LineType('--','*');
Query the value of any object property using the inherited get method:
get(h, 'Marker')
ans =
1 * 1
Set the value of any property using the inherited set method:
set(h,'Marker','Q')
```

Property Access Methods Called with set and get

MATLAB calls property access methods (set.Style or set.Marker in the LineType class) when you use the set and get methods.

```
set(h, 'Style', '-.-')
```

```
Error using LineType/set.Style (line 20)
Invalid line style
```

For more information on property access methods, see "Property Get and Set Methods" on page 8-39

List All Properties

Return a struct containing object properties and their current values using get:

```
h = LineType('--','*');
SV = get(h)

SV =
    struct with fields:
        Style: '--'
        Marker: '*'
        Units: 'points'
```

Return a struct containing the properties that have public SetAccess using set:

```
S = set(h)
S =
   struct with fields:
       Style: {}
       Marker: {}
```

The LineType class defines the Units property with SetAccess = protected. Therefore, S = set(h) does not create a field for Units in S.

set cannot return possible values for properties that have nonpublic set access.

Using get with Arrays of Handles

Suppose that you create an array of LineType objects:

```
H = [LineType('..','z'),LineType('--','q')]
H =
    1x2 LineType with properties:
    Style
    Marker
    Units
```

When H is an array of handles, get returns a (length(H)-by-1) cell array of property values:

```
CV = get(H,'Style')
CV =
  2×1 cell array
```

```
{'..'}
{'--'}
```

When H is an array of handles and you do not specify a property name, get returns a struct array containing fields with names corresponding to property-names. Assign the output of get to a variable when H is not scalar.

```
SV = get(H)
SV =

2x1 struct array with fields:
    Style
    Marker
    Units
```

Get the value of the Marker property from the second array element in the SV array of structures:

```
SV(2).Marker
ans =
```

Arrays of Handles, Names, and Values

You can pass an array of handles, a cell array of property names, and a cell array of property values to set. The property value cell array must have one row of property values for each object in H. Each row must have a value for each property in the property name array:

```
set(H, {'Style', 'Marker'}, {'...', 'o'; '--', 'x'})
The result of this call to set is:
H(1)
ans =
   LineType with properties:
        Style: '...'
        Marker: 'o'
        Units: 'points

H(2)
ans =
   LineType with properties:
        Style: '--'
```

H = [LineType('..', 'z'), LineType('--', 'q')];

Customize the Property List

Marker: 'x'
Units: 'points'

Customize the way property lists display by redefining the following methods in your subclass:

- setdisp When you call set with no output argument and a single scalar handle input, set calls setdisp to determine how to display the property list.
- getdisp When you call get with no output argument and a single scalar handle input, get calls getdisp to determine how to display the property list.

Set Priority for Matching Partial Property Names

Classes that derive from matlab.mixin.SetGet can use the PartialMatchPriority property attribute to specify a relative priority for partial name matching. MATLAB applies this attribute when resolving incomplete and case-insensitive text strings that match more than one property name.

The inherited set and get methods can resolve inexact property names when there are no ambiguities resulting from inexact name strings. When a partial property name is ambiguous because the name matches more than one property, the PartialMatchPriority attribute value can determine which property MATLAB matches.

The default priority is equivalent to PartialMatchPriority = 1. To reduce the relative priority of a property, set PartialMatchPriority to a positive integer value of 2 or greater. The priority of a property decreases as the value of PartialMatchPriority increases.

For example, in this class the Verbosity property has a higher priority for name matching than the Version property.

```
classdef MyClass < matlab.mixin.SetGet
    properties
        Verbosity
    end
    properties (PartialMatchPriority = 2)
        Version
    end
end</pre>
```

Calling the set method with the potentially ambiguous inexact name Ver sets the Verbosity property because of its higher relative priority. Without setting the PartialMatchPriority attribute, the ambiguous name would cause an error.

```
a = MyClass;
set(a,"Ver",10)
disp(a)

MyClass with properties:
    Verbosity: 10
    Version: []
```

The same name selection applies to the get method.

```
v = get(a,"Ver")
v =
    10
```

Case and Name Matching

A full name match with nonmatching case takes precedence over a partial match with a higher priority property. For example, this class defines the BaseLine property with a priority of 1 (the default) and a Base property with a priority of 2 (lower than 1).

```
classdef MyClass < matlab.mixin.SetGet
    properties
        BaseLine
    end
    properties (PartialMatchPriority = 2)
        Base
    end
end</pre>
```

Calling the set method with the string base sets the Base property. BaseLine has a higher priority, but the full name match with incorrect case takes precedence.

```
a = MyClass;
set(a, "base", -2)
disp(a)

MyClass with properties:

BaseLine: []
Base: -2
```

Reduce Incompatibilities When Adding New Properties

You can use the PartialMatchPriority attribute to avoid introducing code incompatibilities when adding a new property. For example, this class enables the set and get methods to refer to the Distance property with the string Dis because the DiscreteSamples property has a lower priority.

```
classdef Planet < matlab.mixin.SetGet
% Version 1.0
    properties
        Distance
    end
    properties(PartialMatchPriority = 2)
        DiscreteSamples
    end
end</pre>
```

Version 2.0 of the class introduces a property named Discontinuities. To prevent the possibility of causing an ambiguous partial property name in existing code, use PartialMatchPriority to set the priority of Discontinuities lower than that of previously existing properties.

```
classdef Planet < matlab.mixin.SetGet
% Version 2.0
    properties
        Diameter;
        NumMoons = 0
        ApparentMagnitude;
        DistanceFromSun;
end
properties(PartialMatchPriority = 2)
        DiscreteSamples;</pre>
```

For version 1.0 of the Planet class, this call to the set method was not ambiguous.

```
p = Planet;
set(p,"Disc",true)
```

However, with the introduction of the Discontinuities property, the string Disc becomes ambiguous. By giving the Discontinuities property a lower priority, the string Disc continues to match the DiscreteSamples property.

Note When writing reusable code, using complete, case-sensitive property names avoids ambiguities, prevents incompatibilities with subsequent software releases, and produces more readable code.

See Also

set|get|matlab.mixin.SetGet|matlab.mixin.SetGetExactNames

More About

• "Ways to Use Properties" on page 8-2

Implement Copy for Handle Classes

```
In this section...

"Copy Method for Handle Classes" on page 7-30

"Customize Copy Operation" on page 7-31

"Copy Properties That Contain Handles" on page 7-32

"Exclude Properties from Copy" on page 7-33
```

Copy Method for Handle Classes

Copying a handle variable results in another handle variable that refers to the same object. You can add copy functionality to your handle class by subclassing matlab.mixin.Copyable. The inherited copy method enables you to make shallow copies of objects of the class. The CopyObj class shows the behavior of copy operations.

```
classdef CopyObj < matlab.mixin.Copyable
   properties
       Prop
   end
end</pre>
```

Create an object of the CopyObj class and assign the handle of a line object to the property Prop.

```
a = CopyObj;
a.Prop = line;
Copy the object.
b = copy(a);
```

Confirm that the handle variables a and b refer to different objects.

```
a == b
ans =
logical
0
```

However, the line object referred to by a.Prop has not been copied. The handle in a.Prop refers to the same object as the handle in b.Prop.

```
a.Prop == b.Prop
ans =
  logical
1
```

For more detailed information on the behavior of the copy operation, see copy.

Customize Copy Operation

Customize handle object copy behavior by deriving your class from matlab.mixin.Copyable. The matlab.mixin.Copyable class is an abstract base class that derives from the handle class. matlab.mixin.Copyable provides a template for customizing object copy operations by defining:

- copy Sealed method that defines the interface for copying objects
- copyElement Protected method that subclasses can override to customize object copy operations for the subclass

The matlab.mixin.Copyable copy method, calls the copyElement method. Your subclass customizes the copy operation by defining its own version of copyElement.

The default implementation of copyElement makes shallow copies of all the nondependent properties. copyElement copies each property value and assigns it to the new (copied) property. If a property value is a handle object, copyElement copies the handle, but not the underlying data.

To implement different copy behavior for different properties, override copyElement. For example, the copyElement method of the SpecializedCopy class:

- · Creates a new class object
- Copies the value of Prop1 to the new object
- Reinitializes the default value of Prop2 by adding a timestamp when the copy is made

```
classdef SpecializedCopy < matlab.mixin.Copyable
    properties
        Prop1
        Prop2 = datestr(now)
    end
    methods(Access = protected)
        function cp = copyElement(obj)
        cp = SpecializedCopy;
        cp.Prop1 = obj.Prop1;
        cp.Prop2 = datestr(now);
    end
end</pre>
```

Create an object of the class and assign a value to Prop1:

```
a = SpecializedCopy;
a.Prop1 = 7

a =
   SpecializedCopy with properties:
    Prop1: 7
    Prop2: '17-Feb-2015 17:51:23'
```

Use the inherited copy method to create a copy of a:

```
b = copy(a)
b =
```

```
SpecializedCopy with properties:
    Prop1: 7
    Prop2: '17-Feb-2015 17:51:58'
```

The copy (object b) has the same value for Prop1, but the subclass copyElement method assigned a new value to Prop2. Notice the different timestamp.

Copy Properties That Contain Handles

Copying an object also copies the values of object properties. Object properties can contain other objects, including handle objects. If you simply copy the value of a property that contains a handle object, you are actually copying the handle, not the object itself. Therefore, your copy references the same object as the original object. Classes that derive from the matlab.mixin.Copyable class can customize the way the copy method copies objects of the class.

Class to Support Handle Copying

Suppose that you define a class that stores a handle in an object property. You want to be able to copy objects of the class and want each copy of an object to refer to a new handle object. Customize the class copy behavior using these steps:

- Create a subclass of matlab.mixin.Copyable.
- Override copyElement to control how the property containing the handle is copied.
- Because the property value is a handle, create a new default object of the same class.
- Copy property values from the original handle object to the new handle object.

The "HandleCopy" on page 7-32 class customizes copy operations for the property that contains a handle object. The "ColorProp" on page 7-33 class defines the handle object to assign to Prop2:

Create an object and assign property values:

```
a = HandleCopy;
a.Prop1 = 7;
a.Prop2 = ColorProp;
```

Make a copy of the object using the copy method inherited from matlab.mixin.Copyable:

```
b = copy(a);
```

Demonstrate that the handle objects contained by objects a and b are independent. Changing the value on object a does not affect object b:

```
a.Prop2.Color = 'red';
b.Prop2.Color
ans =
blue
```

HandleCopy

The HandleCopy class customizes the copy operation for objects of this class.

```
classdef HandleCopy < matlab.mixin.Copyable
  properties</pre>
```

```
Prop1 % Shallow copy
      Prop2 % Handle copy
   end
   methods (Access = protected)
      function cp = copyElement(obj)
         % Shallow copy object
         cp = copyElement@matlab.mixin.Copyable(obj);
         % Get handle from Prop2
         hobi = obi.Prop2;
         % Create default object
         new hobj = eval(class(hobj));
         % Add public property values from orig object
         HandleCopy.propValues(new_hobj,hobj);
         % Assign the new object to property
         cp.Prop2 = new hobj;
      end
   end
   methods (Static)
      function propValues(newObj,orgObj)
         pl = properties(org0bj);
         for k = 1:length(pl)
            if isprop(newObj,pl{k})
               new0bj.(pl\{k\}) = org0bj.(pl\{k\});
            end
         end
      end
   end
end
```

ColorProp

The ColorProp class defines a color by assigning an RGB value to its Color property.

```
classdef ColorProp < handle
  properties
      Color = 'blue';
  end
end</pre>
```

Exclude Properties from Copy

Use the NonCopyable property attribute to indicate that you do not want a copy operation to copy a particular property value. By default, NonCopyable is false, indicating that the property value is copyable. You can set NonCopyable to true only on properties of handle classes.

For classes that derive from matlab.mixin.Copyable, the default implementation of copyElement honors the NonCopyable attribute. Therefore, if a property has its NonCopyable attribute set to true, then copyElement does not copy the value of that property. If you override copyElement in your subclass, you can choose how to use the NonCopyable attribute.

Set the Attribute to Not Copy

Set NonCopyable to true in a property block:

```
properties (NonCopyable)
   Prop1
end
```

Default Values

If a property that is not copyable has a default value assigned in the class definition, the copy operation assigns the default value to the property. For example, the CopiedClass assigns a default value to Prop2.

```
classdef CopiedClass < matlab.mixin.Copyable
    properties (NonCopyable)
        Prop1
        Prop2 = datestr(now) % Assign current time
    end
end</pre>
```

Create an object to copy and assign a value to Prop1:

```
a = CopiedClass;
a.Prop1 = 7
a =
CopiedClass with properties:
    Prop1: 7
    Prop2: '17-Feb-2015 15:19:34'
```

Copy a to b using the copy method inherited from matlab.mixin.Copyable:

```
b = copy(a)
b =
CopiedClass with properties:
    Prop1: []
    Prop2: '17-Feb-2015 15:19:34'
```

In the copy b, the value of Prop1 is not copied. The value of Prop2 is set to its default value, which MATLAB determined when first loading the class. The timestamp does not change.

Objects with Dynamic Properties

Subclasses of the dynamic props class allow you to add properties to an object of the class. When a class derived from dynamic props is also a subclass of matlab.mixin.Copyable, the default implementation of copyElement does not copy dynamic properties. The default value of NonCopyable is true for dynamic properties.

The default implementation of copyElement honors the value of a dynamic property NonCopyable attribute. If you want to allow copying of a dynamic property, set its NonCopyable attribute to false. Copying a dynamic property copies the property value and the values of the property attributes.

For example, this copy operation copies the dynamic property, DynoProp, because its NonCopyable attribute is set to false. The object obj must be an instance of a class that derives from both dynamicprops and matlab.mixin.Copyable:

```
obj = MyDynamicClass;
p = addprop(obj,'DynoProp');
```

```
p.NonCopyable = false;
obj2 = copy(obj);
```

See Also

matlab.mixin.Copyable

Related Examples

• "Dynamic Properties — Adding Properties to an Instance" on page 8-48

Weak Reference Handles

A weak reference to a handle object works much like a regular handle, but a weak reference does not prevent the object it references from being deleted. You can use weak references to manage object lifecycles more efficiently.

Create Weak References

For example, this class defines a property using the WeakHandle property attribute. (See "Property Attributes" on page 8-8 for more information.)

```
classdef Example < handle
    properties (WeakHandle)
        Prop Example
    end
end</pre>
```

Create two instances of the class, and use the second instance as the value of Prop in the first.

```
x = Example;
y = Example;
x.Prop = y;
```

The second instance of Example is referenced by two handles: y and x.Prop, and x.Prop is a weak reference. Clear y.

```
clear("y");
```

If x.Prop were a strong reference, the object it referenced would still exist. However, x.Prop is a weak reference, so MATLAB deletes the object. Verify this by accessing x.Prop.

```
x.Prop
ans =
  handle to deleted Example
```

Outside of the context of a property definition, you can also create weak references using the matlab.lang.WeakReference wrapper class. See matlab.lang.WeakReference for an example.

Create Back Pointers Using Properties Defined with WeakHandle Attribute

Data structures like trees or lists can contain objects with back pointers to objects above them in a hierarchy. Back pointers that are strong reference handles force MATLAB to do extra work when checking to see which objects can be deleted. Replacing strong references with weak references provides more efficient management of handle objects.

For example, the class Car contains properties that reference parts of a car. The class Engine represents one part that Car can reference.

```
classdef Car < handle
    properties
    VIN string
    EngineInstalled Engine</pre>
```

```
end
end

classdef Engine < handle
   properties (WeakHandle)
        InstalledIn Car
   end
   properties
        SerialNumber string = "00000"
        LastService datetime = "today"
  end
end</pre>
```

The Engine class defines a weak reference, InstalledIn, back to the car that the engine is installed in. All properties defined with the WeakHandle attribute must use class validation. In this case, InstalledIn must be of type Car.

Construct myCar and myCarEngine. Assign myCarEngine to the EngineInstalled property of myCar, and set the InstalledIn property of myCarEngine to myCar.

```
myCar = Car;
myCarEngine = Engine;
myCar.EngineInstalled = myCarEngine;
myCarEngine.InstalledIn = myCar;
```

Now, both myCar and myCarEngine reference each other, although the reference from myCarEngine to myCar is a weak reference. Clear myCar.

```
clear("myCar")
```

If the handle in the InstalledIn property of myCarEngine were a strong reference, the object pointed to by myCar would still exist because it would be strongly referenced by myCarEngine.InstalledIn However, the myCarEngine.InstalledIn property is now the only reference to myCar. Because myCarEngine.InstalledIn is a weak reference, it does not prevent MATLAB from deleting the myCar object. Confirm this by accessing myCarEngine.InstalledIn.

```
myCarEngine.InstalledIn
ans =
    handle to deleted Car
```

Create a Cache Using the matlab.lang.WeakReference Class

You can use weak references to design a cache. Because caches are usually intended for quick access to data without necessarily preserving that data, you can use weak references to help manage lifecycles of data objects. Each object in the cache can have a weak reference, but the weak references do not prevent the code that manages the cache from deleting objects.

First, define a basic class TrialData that represents experimental data.

```
classdef TrialData < handle
    properties
        trialNumber string = "A001"
        trialResults double = 0
    end
end</pre>
```

Create the basis for a cache by defining a dictionary, workingData. The dictionary maps a string-valued key to a weak reference to the data object. You cannot use the WeakHandle property attribute here, so instead use an empty array of the matlab.lang.WeakReference wrapper class as the initial value.

```
workingData = dictionary(string.empty,matlab.lang.WeakReference.empty)
workingData =
dictionary (string □ matlab.lang.WeakReference) with no entries.
```

Construct two instances of TrialData and add them to workingData. Use the trialNumber property of the TrialData instances as the keys for the entries in the dictionary. The dictionary values are weak references to first and second because the dictionary values were initially defined as type matlab.lang.WeakReference.

```
first = TrialData;
second = TrialData;
second.trialNumber = "A002";
second.trialResults = 1;
workingData(first.trialNumber) = first;
workingData(second.trialNumber) = second

workingData =

dictionary (string [] matlab.lang.WeakReference) with 2 entries:
    "A001" [] 1×1 matlab.lang.WeakReference
    "A002" [] 1×1 matlab.lang.WeakReference
```

The instance referenced by each dictionary value is held by the Handle property of matlab.lang.WeakReference. Access the property values of the object referenced by "A002" through the Handle property.

```
result2 = workingData("A002").Handle.trialResults
result2 =
1
```

Because the dictionary values are weak references, they do not prevent any of the objects referenced from being cleared from memory. Clear second, and confirm that the reference in the dictionary now points to a deleted object.

```
clear("second")
workingData("A002").Handle
ans =
  handle to deleted TrialData
```

Immediate Destruction of Weak References

MATLAB immediately deletes an object that has only weak references to it. For example, construct an instance of Example from the introduction to "Create Weak References" on page 7-36. Set Propusing the Example constructor instead of creating a separate instance as a strong reference.

```
classdef Example < handle
    properties (WeakHandle)
        Prop Example
    end
end

x = Example;
x.Prop = Example;</pre>
```

Because the object referenced by x.Prop has only a weak reference, MATLAB deletes it immediately after it is created.

```
x.Prop
ans =
  handle to deleted Example
```

To avoid this behavior, define a strong reference first so that MATLAB does not immediately delete the object, as shown in the "Create Back Pointers Using Properties Defined with WeakHandle Attribute" on page 7-36 example.

See Also

matlab.lang.WeakReference|matlab.lang.HandlePlaceholder|
matlab.lang.invalidHandle

Related Examples

- "Property Attributes" on page 8-8
- "Validate Property Values" on page 8-19

Properties — Storing Class Data

- "Ways to Use Properties" on page 8-2
- "Property Syntax" on page 8-4
- "Property Attributes" on page 8-8
- "Initialize Property Values" on page 8-14
- "Mutable and Immutable Properties" on page 8-17
- "Validate Property Values" on page 8-19
- "Property Class and Size Validation" on page 8-24
- "Property Validation Functions" on page 8-30
- "Metadata Interface to Property Validation" on page 8-37
- "Property Get and Set Methods" on page 8-39
- "Get and Set Methods for Dependent Properties" on page 8-43
- "Properties Containing Objects" on page 8-46
- "Dynamic Properties Adding Properties to an Instance" on page 8-48
- "Set and Get Methods for Dynamic Properties" on page 8-52
- "Dynamic Property Events" on page 8-54
- "Dynamic Properties and ConstructOnLoad" on page 8-58

Ways to Use Properties

In this section...

"What Are Properties" on page 8-2

"Types of Properties" on page 8-2

What Are Properties

Properties encapsulate the data that belongs to instances of classes. Data contained in properties can be public, protected, or private. This data can be a fixed set of constant values, or it can depend on other values and calculated only when queried. You control these aspects of property behaviors by setting property attributes and by defining property-specific access methods.

Flexibility of Object Properties

In some ways, properties are like fields of a struct object. However, storing data in an object property provides more flexibility. Properties can:

- Define a constant value that you cannot change outside the class definition. See "Define Class Properties with Constant Values" on page 15-2.
- Calculate its own value based on the current value of other data. See "Features of Dependent Properties" on page 8-3.
- Execute a function to determine if an attempt to assign a value meets a certain criteria. See "Property Get and Set Methods" on page 8-39.
- Trigger an event notification when any attempt is made to get or set its value. See "Property-Set and Query Events" on page 11-14.
- Control access by code to the property values. See the SetAccess and GetAccess attributes "Property Attributes" on page 8-8.
- Control whether its value is saved with the object in a MAT-file. See "Save and Load Functions" on page 13-2.

For an example of a class that defines and uses a class, see "Creating a Simple Class" on page 2-2.

Types of Properties

There are two types of properties:

- Stored properties Use memory and are part of the object
- Dependent properties No allocated memory and the get access method calculates the value when queried

Features of Stored Properties

- Property value is stored when you save the object to a MAT-file
- Can assign a default value in the class definition
- Can restrict property value to a specific class and size
- Can execute validation functions to control allowed property value (default and assigned)

• Can use a set access method to control possible values when set

When to Use Stored Properties

- You want to be able to save the property value in a MAT-file
- The property value is not dependent on other property values

Features of Dependent Properties

Dependent properties save memory because property values that depend on other values are calculated only when needed.

When to Use Dependent Properties

Define properties as dependent when you want to:

- Compute the value of a property from other values (for example, you can compute area from Width and Height properties).
- Provide a value in different formats depending on other values. For example, the size of a push button in values determined by the current setting of its Units property.
- Provide a standard interface where a particular property is or is not used, depending on other values. For example, different computer platforms can have different components on a toolbar).

For examples of classes that use dependent properties, see "Calculate Data on Demand" on page 3-17 and "A Class Hierarchy for Heterogeneous Arrays" on page 20-2.

See Also

Related Examples

- "Property Attributes" on page 8-8
- "Validate Property Values" on page 8-19
- "Property Get and Set Methods" on page 8-39
- "Static Properties" on page 5-38

Property Syntax

```
In this section...

"Property Definition Block" on page 8-4

"Property Validation Syntax" on page 8-5

"Property Access Syntax" on page 8-6
```

This topic describes how to define class properties in MATLAB using properties...end blocks, and it introduces property validation syntax and concepts. It also covers the basics of getting and setting property values from a class instance.

Property Definition Block

The properties and end keywords define one or more class properties that have the same attribute settings. This is the general syntax for defining a property block:

```
properties (attributes)
  propName1
  ...
  propNameN
end
```

Note Properties cannot have the same name as the class or any of the other members defined by the class.

For example, this properties block defines two properties with the SetAccess attribute set to private. This attribute setting means that the property values can be set only by members of the PrivateProps class.

```
classdef PrivateProps
   properties (SetAccess = private)
        Property1
        Property2
   end
end
```

You can also define multiple property blocks for properties with different attributes. In this example, one properties block defines properties with private SetAccess, and the second block defines an abstract property. Property blocks with different attributes can appear in any order in the class definition.

```
classdef MultiplePropBlocks
  properties (SetAccess = private)
     Property1
     Property2
  end
  properties (Abstract)
     Property3
  end
end
```

For a full listing of property attributes, see "Property Attributes" on page 8-8.

Property Validation Syntax

Within a properties block, you can use property validation. Property validation enables you to place one or more restrictions on each property value, including size and class. You can also define a default value for each property. The general syntax for property validation is:

```
properties (attributes)
    propName1 (dimensions) class {validators} = defaultValue
    ...
end
```

- (dimensions) Size of property value, specified as a comma-separated list of two or more numbers enclosed in parentheses, such as (1,2) or (1,:). A colon allows any length in that dimension. The dimensions of the value must match (dimensions) exactly or be compatible. See "Compatible Array Sizes for Basic Operations" for more information. (dimensions) cannot include expressions.
- class Class of property value, specified as the name of the class, such as double. The value
 must be the specified class or a class that can be converted. For example, a property that specifies
 double accepts values of type single and converts them to double. Beyond the classes already
 available in MATLAB, you can use your own classes as property validators. For user-defined
 classes, property validation allows a subclass of the specified class to pass without error, but it
 does not convert the subclass to the superclass.
- {validators} Validation functions, specified as a comma-separated list enclosed in curly brackets, such as mustBePositive and mustBeScalarOrEmpty. Unlike class, validation functions do not modify property values. Validation functions error when the property values do not match their conditions. For a list of validation functions, see "Property Validation Functions" on page 8-30. You can also define your own validation functions.
- defaultValue Default property values must conform to the specified size, class, and validation rules. A default value can also be an expression. See "Define Properties with Default Values" on page 8-14 for more information about how MATLAB evaluates default value expressions.

This class defines one property. The properties block has no explicit attribute defined, which is equivalent to defining a block of public properties. MyPublicData must also be a vector of positive doubles, and it has a default value of [1 1 1].

```
classdef ValidationExample
   properties
      MyPublicData (1,:) double {mustBePositive} = [1 1 1]
   end
end
```

Not all validation options must be used at once, and different properties in the same block can use different combinations of validators. In this example, the RestrictedByClass property uses class validation only, while RestrictedByFunction uses a validation function and assigns a default value.

```
classdef DifferentValidation
  properties
    RestrictedByClass uint32
    RestrictedByFunction {mustBeInteger} = 0
```

```
end
end
```

For more information, see "Property Class and Size Validation" on page 8-24 and "Property Validation Functions" on page 8-30.

Property Access Syntax

Property access syntax is like MATLAB structure field syntax. For example, if obj is an object of a class, then you can get the value of a property by referencing the property name.

```
val = obj.PropertyName
```

Assign values to properties by putting the property reference on the left side of the equal sign.

```
obj.PropertyName = val
```

For example, instantiate the ValidationExample class and read the value of MyPublicData.

Assign a new value to the property that satisfies the validators defined for it.

```
x.MyPublicData = [2 3 5 7];
```

You can optionally define get and set methods that MATLAB automatically calls when you use this structure field syntax. For more information, see "Property Get and Set Methods" on page 8-39.

Reference Properties Using Variables

MATLAB can resolve a property name from a string or char variable using an expression of the form:

```
object.(PropertyNameVar)
```

PropertyNameVar is a variable containing the name of a valid object property. Use this syntax when passing property names as arguments. For example, the getPropValue function returns the value of the KeyType property.

```
PropName = "KeyType";
function o = getPropValue(obj,PropName)
    o = obj.(PropName);
end
```

See Also

Related Examples

- "Property Attributes" on page 8-8
- "Validate Property Values" on page 8-19
- "Initialize Property Values" on page 8-14

Property Attributes

```
In this section...

"Purpose of Property Attributes" on page 8-8

"Specify Property Attributes" on page 8-8

"Table of Property Attributes" on page 8-8

"Property Access Lists" on page 8-12
```

Purpose of Property Attributes

You can specify attributes in the class definition to customize the behavior of properties for specific purposes. Control characteristics like access, data storage, and visibility of properties by setting attributes. Subclasses do not inherit superclass member attributes.

Specify Property Attributes

Assign property attributes on the same line as the properties keyword.

```
properties (Attribute1 = value1, Attribute2 = value2,...)
    ...
end
```

For example, define a property Data with private access.

```
properties (Access = private)
  Data
end
```

You can use a simpler syntax for attributes whose values are true. The attribute name by itself implies true, and adding the not operator (~) to the name implies false. For example, this block defines abstract properties.

```
properties (Abstract)
...
end
```

Table of Property Attributes

All properties support the attributes listed in this table. Attribute values apply to all properties defined within the properties...end code block that specifies the nondefault values. Attributes that you do not explicitly defined take their default values.

Property Attributes

Attribute	Values	Additional Information
AbortSet		For handle classes only. Setting AbortSet to true also prevents the triggering of property PreSet and PostSet events.
	• false (default) - MATLAB sets the property value regardless of the current value.	For more information, see "Assignment When Property Value Is Unchanged" on page 11-35.
Abstract	true - The property has no implementation, but a concrete subclass must override this property without	Abstract properties cannot define set or get access methods. See "Property Get and Set Methods" on page 8-39.
	Abstract set to true. • false (default) - The	Abstract properties cannot define initial values.
	property is concrete and does not need to be overridden in a subclass.	A sealed class cannot define abstract members.
Access	• public (default) - The property can be accessed from any code.	Use Access to set SetAccess and GetAccess to the same value.
	• protected - The property can be accessed from the	Specifying Access as an empty cell array, {}, is the same as private access.
	defining class or its subclasses.	See "Class Members Access" on page 12-23 for more information.
	 private - The property can be accessed only by members of the defining class. 	
	• List of classes that have get and set access to this property. Specify classes as a single matlab.metadata.Class object or a cell array of matlab.metadata.Class objects. See "Property Access Lists" on page 8-12 for more information.	
	IIIIUI IIIauuii.	

Attribute	Values	Additional Information
Constant	• true - The property has the same value in all instances of the class.	Subclasses inherit constant properties but cannot change them.
	false (default) - The property value can vary between instances.	Constant properties cannot also be defined as dependent.
		The value of SetAccess is ignored for constant properties.
		See "Define Class Properties with Constant Values" on page 15-2 for more information.
Dependent	true - The property value is not stored in the object. The value is calculated when the property is accessed.	You can define set methods for dependent properties, but the set method cannot actually set the value of the property. It can take other actions, such as setting the value
	• false (default) - The property value is stored in the object.	of another property. See "When to Use Set Methods with Dependent Properties" on page 8-44 for an example.
		Values returned by dependent property get methods are not considered when testing for object equality using isequal.
GetAccess	• public (default) - The property can be read from any code.	Specifying GetAccess as an empty cell array, {}, is the same as private access.
	• protected - The property can be read from the defining class or its subclasses.	In the Command Window, MATLAB does not display the names and values of properties with protected or private GetAccess.
	 private - The property can be read only by members of the defining class. 	All subclasses must specify the same values as the superclass for the property SetAccess and GetAccess attributes.
	• List of classes that can read this property. Specify classes as a single matlab.metadata.Class object or a cell array of matlab.metadata.Class objects. See "Property Access Lists" on page 8-12 for more information.	See "Class Members Access" on page 12-23 for more information.

Attribute	Values	Additional Information	
GetObservable	• true - You can create listeners for handle class properties. The listeners are called whenever property values are queried.	See "Property-Set and Query Events" on page 11-14 for more information.	
	 false (default) - Listeners do not have access to this property. 		
Hidden •	 true - The property is not visible in property lists or in results from calls to get, set, or the properties functions. 	In the Command Window, MATLAB does no display the names and values of properties whose Hidden attribute is true. However, hidden properties are visible in the Class	
	 false (default) - The property is visible. 	Diagram Viewer app.	
NonCopyable	 true - The property value is not copied when the object that defines it is copied. 	You can set NonCopyable to true only in handle classes.	
	• false (default) - The property value is copied when the object is copied.	For more information, see "Exclude Properties from Copy" on page 7-33.	
PartialMatchPriority	Positive integer - Defines the relative priority of partial	Use only with subclasses of matlab.mixin.SetGet.	
	property name matches used in get and set methods. The default value is 1.	For more information, see "Set Priority for Matching Partial Property Names" on page 7-27.	
SetAccess	• public (default) - The property can be set from any code.	All subclasses must specify the same values as the superclass for the property SetAccess and GetAccess attributes.	
	 protected - The property can be set from the defining class or its subclasses. 	For more information, see "Class Members Access" on page 12-23, "Properties Containing Objects" on page 8-46, and	
	• private - The property can be set only by members of the defining class.	"Mutable and Immutable Properties" on page 8-17.	
	• immutable - The property can be set only in the constructor.		
	• List of classes that have set access to this property. Specify classes as a single matlab.metadata.Class object or a cell array of matlab.metadata.Class objects. See "Property Access Lists" on page 8-12 for more information.		

Attribute	Values	Additional Information
SetObservable	true - You can create listeners for handle class properties. The listeners are called whenever property values are set.	See "Property-Set and Query Events" on page 11-14 for more information.
	• false (default) - Listeners do not have access to this property.	
Transient	• true - The property value is not saved when the object is saved to a file or sent from MATLAB to another program, such as a MATLAB Engine application.	See "Default Save and Load Process for Objects" on page 13-2 for more information.
	 false (default) - The property value is saved when the object is saved. 	
WeakHandle	 true - The property holds a weak reference to a handle object. Weak references to an object do not prevent that object from being deleted. false (default) - The property holds a value class object or a strong reference to a handle object. 	Properties defined as WeakHandle can only take handle object arrays as values. All properties defined with the WeakHandle attribute must use class validation. Default values are supported, but they must be empty or an array of invalid handles. WeakHandle cannot be used for properties containing classes that inherit from matlab.indexing.RedefinesParen or that customize indexing by overriding
		subsref or subsasgn. See "Weak Reference Handles" on page 7-36 for examples and more information.
Framework attributes		k base classes have framework-specific for the specific base class you are using for

Property Access Lists

You can use lists of matlab.metadata.Class instances for the Access, GetAccess, and SetAccess attributes. For example, this class declares access lists for the Prop1 and Prop2 properties.

For Prop1:

- Classes ClassA and ClassB have get access to Prop1.
- All subclasses of ClassA and ClassB have get access to Prop1.
- Access lists are not inherited, so subclasses of PropertyAccess do not have get access to Prop1 unless they explicitly define that access.

For Prop2:

- ClassC has get and set access to Prop2.
- All subclasses of ClassC have get and set access to Prop2.
- Access lists are not inherited, so subclasses of PropertyAccess do not have access to Prop2 unless they explicitly define that access.

See Also

Related Examples

- "Property Syntax" on page 8-4
- "Initialize Property Values" on page 8-14

Initialize Property Values

```
In this section...

"Define Properties with Default Values" on page 8-14

"Set Property Values in the Constructor" on page 8-15
```

There are two basic ways to initialize property values:

- Define properties with default values MATLAB assigns the same initial value to the property
 of every instance.
- **Set property values in the constructor** The constructor evaluates the assignment statement for each instance, which enables instances to have unique initial property values.

Define Properties with Default Values

You can assign a default value to an individual property using a value or an expression. Expressions cannot include variables. This example shows several ways to define a default value for a property.

```
classdef PropExample
  properties
    Prop1
    Prop2 = "some text"
    Prop3 = sin(pi/12)
    Prop4 = datetime.empty
    Prop5 (1,1) double {mustBePositive} = 1
  end
end
```

- Prop1 The property definition does not specify a default value, so MATLAB initializes the property value to an empty double ([]).
- Prop2 The default value is the string scalar "some text".
- Prop3 The default value is the value of sin(pi/12). Reading this property returns the evaluated expression (0.2588), not the expression itself.

For more information on the evaluation of expressions that you assign as default values, see "Evaluation of Expressions in Class Definitions" on page 6-9 and "Properties Containing Objects" on page 8-46.

- Prop4 The default value is an empty datetime object.
- Prop5 The default value is 1, and the property value in general is restricted to scalar, positive doubles. When a property definition specifies any size, class, or validation function restrictions on the property value, then the default value must satisfy those conditions. For example, a default value of 0 would cause an error during instantiation because it does not satisfy mustBePositive.

For information on property restrictions based on size, class, and validation functions, see "Validate Property Values" on page 8-19.

Note MATLAB evaluates a default expression when the property value is first needed (for example, when the class is first instantiated). The same default value is then used for all instances of a class.

MATLAB does not reevaluate the default expression unless the class definition is cleared from memory.

Handle Objects as Default Property Values

When you use a handle class constructor to create a default property value, MATLAB calls the constructor only when the class is first used, and then uses the same object handle as the default for the property in all instances. Because all of the object handles reference the same object, any changes you make to the handle object in one instance are reflected in the handle object in all instances. To initialize a property value with a new instance of a handle object each time you instantiate your class, assign the property value in the constructor.

Set Property Values in the Constructor

To assign a value to a property from within the class constructor, refer to the object that the constructor returns (the output variable obj) and the property name using dot notation.

```
classdef MyClass
   properties
      Prop1
   end
   methods
      function obj = MyClass(intval)
      obj.Prop1 = intval;
   end
   end
end
```

When you assign a value to a property in the class constructor, MATLAB evaluates the assignment statement for each object you create. Assign property values in the constructor if you want each object to contain a unique value for that property.

For example, ContainsHandle assigns a unique handle object of class MyHandleClass to Prop1 for each instance. ContainsHandle does this by calling the MyHandleClass constructor from its own constructor.

```
classdef ContainsHandle
  properties
     Prop1
  end
  methods
     function obj = ContainsHandle(keySet,valueSet)
        obj.Prop1 = MyHandleClass(keySet,valueSet);
  end
  end
end
```

For more information on constructor methods, see "Referencing the Object in a Constructor" on page 9-18.

Property Validation Before Construction

MATLAB validates default property values before the assignment of values in the constructor. The default value assigned in the properties block and any value set for the property in the class constructor must satisfy the specified validation. For example, PropInit restricts Prop to a scalar

positive double, but it does not assign a default value. By default, MATLAB assigns an initial value of empty double.

```
classdef PropInit
  properties
        Prop (1,1) double {mustBePositive}
  end
  methods
      function obj = PropInit(positiveInput)
        obj.Prop = positiveInput;
  end
  end
end
```

Calling the class constructor with a valid value for Prop still causes an error because of the initial empty double in Prop. An empty double does not satisfy the validation function mustBePositive.

```
obj = PropInit(2);
Error using implicit default value of property 'Prop' of class 'PropInit':
Value must be positive.
```

To avoid this problem, ensure that your properties have default values that satisfy your validation, even when you intend to overwrite those values in the constructor.

See Also

Related Examples

- "Evaluation of Expressions in Class Definitions" on page 6-9
- "Ways to Use Properties" on page 8-2
- "Validate Property Values" on page 8-19

Mutable and Immutable Properties

```
In this section...

"Set Access to Property Values" on page 8-17

"Define Immutable Property" on page 8-17
```

Set Access to Property Values

The property SetAccess attribute enables you to determine under what conditions code can modify object property values. There are four levels of set access that provide varying degrees of access to object property values:

- SetAccess = public Any code with access to an object can set public property values. There are differences between the behavior of handle and value classes with respect to modifying object properties.
- SetAccess = protected Only code executing from within class methods or methods of subclasses can set property values. You cannot change the value of an object property unless the class or any of its subclasses defines a method to do so.
- SetAccess = private Only the defining class can set property values. You can change the value of an object property only if the class defines a method that sets the property.
- SetAccess = immutable Property value is set in the constructor. You cannot change the value of an immutable property after the object is created. Set the value of the property as a default or in the class constructor. You cannot define a property set method (set. *PropertyName*) for an immutable property.

For related information, see "Properties Containing Objects" on page 8-46.

Define Immutable Property

In this class definition, only the Immute class constructor can set the value of the CurrentDate property:

```
classdef Immute
   properties (SetAccess = immutable)
       CurrentDate
   end
   methods
       function obj = Immute
       obj.CurrentDate = datetime("today");
   end
   end
end

a = Immute

a =
   Immute with properties:
   CurrentDate: 09-Jun-2022
```

See Also

Related Examples

- "Property Attributes" on page 8-8
- "Object Modification" on page 5-35

Validate Property Values

In this section...

"Property Validation in Class Definitions" on page 8-19

"Sample Class Using Property Validation" on page 8-20

"Order of Validation" on page 8-21

"Abstract Property Validation" on page 8-22

"Objects Not Updated When Changing Validation" on page 8-22

"Validation During Load Operation" on page 8-22

Property Validation in Class Definitions

MATLAB property validation enables you to place specific restrictions on property values. You can use validation to constrain the class and size of property values. Also, you can use functions to establish criteria that the property value must conform to. MATLAB defines a set of validation functions and you can write your own validation functions.

The use of property validation is optional in class definitions.

Additional Information on Property Validation

For more information on property validation, see "Property Class and Size Validation" on page 8-24, "Property Validation Functions" on page 8-30, and "Metadata Interface to Property Validation" on page 8-37.

Validation Syntax

The highlighted area in the following code shows the syntax for property validation.

Property validation includes any of the following:

- Size The length of each dimension, specified as a positive integer or a colon. A colon indicates that any length is allowed in that dimension. The value assigned to the property must conform to the specified size or be compatible with the specified size. For more information, see "Property Size Validation" on page 8-24.
- Class The name of a single MATLAB class. The value assigned to the property must be of the specified class or convertible to the specified class. Use any MATLAB class or externally defined class that is supported by MATLAB, except for Java and COM classes. For more information, see "Property Class Validation" on page 8-25.

• Functions — A comma-separated list of validation function names. MATLAB passes the value assigned to the property to each the validation functions after applying any possible class and size conversions. Validator functions throw errors if the validation fails, but do not return values. For more information, see "Property Validation Functions" on page 8-30.

For a list of MATLAB validation functions, see "Property Validation Functions" on page 8-30.

Using Property Validation

Use property validation for public properties to control the values user code assigns to the properties.

If you want to restrict property values to a fixed set of identifiers, create an enumeration class for these identifiers and constrain the property to this class. For information on enumeration classes, see "Define Enumeration Classes" on page 14-4.

MATLAB type conversion rules apply to property validation. For example, MATLAB can coerce from one to another numeric type. Therefore, restricting a property value to a specific numeric type, such as double does not prevent the assignment of other numeric types to the property.

To ensure that a property can be assigned only a specific type of value, restrict the property to a type that supports only the desired type conversions or use a validation function to specify the exact class allowed for the property instead of specifying the property type. MATLAB evaluates the type specification before executing any validation functions. For more information, see "Order of Validation" on page 8-21.

Specify Valid Default

Ensure that any default value assigned to the property meets the restrictions imposed by the specified validation. If you do not specify a default value, MATLAB creates a default value by assigning an empty object of the specified class or by calling the default constructor if size restriction does not allow the use of an empty default value. The default constructor must return an object of the correct size.

Sample Class Using Property Validation

The ValidateProps class defines three properties with validation.

```
classdef ValidateProps
    properties
        Location(1,3) double {mustBeReal, mustBeFinite}
        Label(1,1) string {mustBeMember(Label,["High","Medium","Low"])} = "Low"
        State(1,1) matlab.lang.OnOffSwitchState
    end
end
```

- Location must be a 1-by-3 array of class double whose values are real, finite numbers.
- Label must be a string scalar that is either "High", "Medium", or "Low".
- State must be an enumeration member of the matlab.lang.OnOffSwitchState class (off or on).

Validation at Instantiation

Creating an object of the ValidateProps class performs the validation on implicit and explicit default values:

```
a = ValidateProps
```

```
a =
  ValidateProps with properties:
  Location: [0 0 0]
    Label: "Low"
    State: off
```

When creating the object, MATLAB:

- Initializes the Location property value to [0 0 0] to satisfy the size and class requirements.
- Sets the Label property to its default value, "Low". The default value must be a member of the allowed set of values. The empty string default value would cause an error.
- Sets the State property to the off enumeration member defined by the matlab.lang.OnOffSwitchState class.

For information on how MATLAB selects default values, see "Default Values Per Size and Class" on page 8-29.

Order of Validation

When a value is assigned to the property, including default values that are specified in the class definition, MATLAB performs validation in this order:

- Class validation This validation can cause conversion to a different class, such as conversion of a char to string. Assignment to properties follows MATLAB conversion rules for arrays.
- Size validation This validation can cause size conversion, such as scalar expansion or
 conversion of a column vector to a row vector. Assignment to a property that specifies a size
 validation behaves the same as assignment to any MATLAB array. For information on indexed
 assignment, see "Array Indexing".
- Validator functions MATLAB passes the result of the class and size validation to each validation function, in left to right order. An error can occur before all validation functions have been called, which ends the validation process.
- Set method MATLAB performs property validation before calling a property set method, if one
 is defined for that property. Assignment to the property within a property set or get method does
 not apply the validation again. Often, you can replace property set methods using property
 validation.

Property Validation Errors

The ValueProp class uses size, class, and function validation to ensure that an assignment to the Value property is a double scalar that is not negative.

```
classdef ValueProp
  properties
     Value(1,1) double {mustBeNonnegative} = 0
  end
end
```

This statement attempts to assign a cell array to the property. This assignment violates the class validation.

```
a. Value = \{10,20\};
```

```
Error setting property 'Value' of class 'ValueProp':
Invalid data type. Value must be double or be convertible to double.
```

This statement attempts to assign a 1-by-2 double array to the property. This assignment violates the size validation.

```
a.Value = [10 20];
Error setting property 'Value' of class 'ValueProp':
Size of value must be scalar.
```

This statement attempts to assign a scalar double to the property. This assignment fails the function validation, which requires a nonnegative number.

```
a.Value = -10;
Error setting property 'Value' of class 'ValueProp':
Value must be nonnegative.
```

The validation process ends with the first error encountered.

Abstract Property Validation

You can define property validation for abstract properties. The validation applies to all subclasses that implement the property. However, subclasses cannot use any validation on their implementation of the property. When inheriting validation for a property from multiple classes, only a single abstract property in one superclass can define the validation. None of the superclasses can define the property as concrete.

Objects Not Updated When Changing Validation

If you change the property validation while objects of the class exist, MATLAB does not attempt to apply the new validation to existing property values. However, MATLAB does apply the new validation when you make assignments to the properties of existing objects.

Validation During Load Operation

When saving an object to a MAT file, MATLAB saves all nondefault property values with the object. When loading the object, MATLAB restores these property values in the newly created object.

If a class definition changes the property validation such that the loaded property value is no longer valid, MATLAB substitutes the currently defined default value for that property. However, the load function suppresses the validation errors that occur before assigning the default value from the current class definition. Therefore, validation errors are silently ignored during load operations.

To illustrate this behavior, this example creates, saves, and loads an object of the MonthTemp class. This class restricts the AveTemp property to a cell array.

```
classdef MonthTemp
  properties
      AveTemp cell
  end
end
```

Create a MonthTemp object and assign a value to the AveTemp property.

```
a = MonthTemp;
a.AveTemp = {'May',70};
Save the object using save.
save TemperatureFile a
```

Edit the property definition to change the validation class for the AveTemp property from cell array to containers.Map.

```
classdef MonthTemp
  properties
      AveTemp containers.Map
  end
end
```

Load the saved object with the new class definition on the MATLAB path. MATLAB cannot assign the saved value to the AveTemp property because the cell array, {'May', 70}, is not compatible with the current requirement that the property value be a containers.Map object. MATLAB cannot convert a cell array to a containers.Map.

To address the incompatibility, MATLAB sets the AveTemp property of the loaded object to the current default value, which is an empty containers.Map object.

The loaded object has a different value assigned to the AveTemp property because the saved value is now invalid. However, the load process suppresses the validation error.

To prevent loss of data when changing class definitions and reloading objects, implement a loadobj method or class converter method that enables the saved values to satisfy the current property validation.

For more information on saving and loading objects, see "Default Save and Load Process for Objects" on page 13-2.

See Also

Related Examples

- "Property Class and Size Validation" on page 8-24
- "Property Validation Functions" on page 8-30

Property Class and Size Validation

```
In this section...

"Property Class and Size" on page 8-24

"Property Size Validation" on page 8-24

"Property Class Validation" on page 8-25

"Default Values Per Size and Class" on page 8-29
```

Property Class and Size

MATLAB applies any class and size validation defined for a property before calling validation functions. Assignment to a property that defines size or class validation is analogous to assignment to a MATLAB object array. MATLAB can apply class and size conversions to the right side of the assignment to satisfy class and size validation.

For more information, see "Order of Validation" on page 8-21 and "Property Validation Functions" on page 8-30.

Property Size Validation

Specify the property size as the row, column, and additional dimension following the property name.

```
classdef MyClass
   properties
     Prop(dim1,dim2,...) = defaultValue
   end
end
```

Assignment and Size Validation

This class defines the size of the Location property as 1-by-3. Any value assigned to this property must conform to that size or must be convertible to that size.

```
classdef ValidateProps
   properties
      Location(1,3)
   end
end
```

The implicit default value assigned by MATLAB, [0 0], conforms to the specified size:

```
a = ValidateProps
a =
  ValidateProps with properties:
    Location: [0 0 0]
```

MATLAB applies scalar expansion when you assign a scalar the Location property.

```
a = ValidateProps;
a.Location = 1
```

```
ValidateProps with properties:
    Location: [1 1 1]

MATLAB converts columns to rows to match the size specification:
col = [1;1;1]

col =
    1
    1
    1
a.Location = col
```

Colon in Size Specification

Location: [1 1 1]

ValidateProps with properties:

a =

A colon in the size specification indicates that the corresponding dimension can have any length. For example, you can assign a row vector with any number of columns to the Data property in this class.

```
classdef ValidateProps
   properties
      Data(1,:)
   end
end
a = ValidateProps;
a.Data = [1:10]
a =
   ValidateProps with properties:
   Data: [1 2 3 4 5 6 7 8 9 10]
```

Assignment to a property that defines size validation follows the same rules as the equivalent indexed array assignment. For information on indexing behavior of multidimensional arrays, see "Compatible Array Sizes for Basic Operations".

Property Class Validation

Defining the class of a property can reduce the need to test the values assigned to the property in your code. In general, the value assigned to the property must be of the specified class or convertible to the specified class. An exception to this rule is for subclasses. If you specify a user-defined class as part of validation, subclasses of that class pass validation without error, but they are not converted.

You can specify only one class per property. Use validation functions like mustBeNumeric or mustBeInteger to restrict properties to a broader category of classes. For more information on validation functions, see "Property Validation Functions" on page 8-30.

You can use any MATLAB class or externally defined class that is supported by MATLAB, except Java and COM classes.

Place the name of the class in the property definition block following the property name and optional size specification.

```
classdef MyClass
   properties
     Prop ClassName = defaultValue
   end
end
```

If you do not specify a default value, MATLAB assigns an empty object of the specified class to the property. If you define a size and a class, MATLAB attempts to create a default value for the property that satisfies both the size and class requirement.

MATLAB creates the default value by calling the class constructor with no arguments. The class must have a constructor that returns an object of the specified size when called with no input arguments or you must specify a default value for the property that satisfies the property size restriction. For more information, see "Default Values Per Size and Class" on page 8-29.

Using Class Validation

The PropsWithClass class defines two properties with class definitions:

- Number Values must be of class double or convertible to double.
- Today Values must be of class string or convertible to string. The default value is the current date, returned by the datetime function.

```
classdef PropsWithClass
   properties
     Number double
     Today string = datetime("today")
   end
end
```

Create an object of the PropsWithClass class.

```
p = PropsWithClass
p =
   PropsWithClass with properties:
    Number: []
    Today: "09-Jun-2022"
```

MATLAB performs conversions from any compatible class to the property class. For example, assign a uint8 value to the Number property.

```
p.Number = uint8(5);
disp(class(p.Number))
ans =
double
```

Because the uint8 value can be converted to double, you can assign that uint8 value to the Number property.

Assigning an incompatible value to a property that uses class validation causes an error.

```
p.Number = datetime("today");
Error setting property 'Number' of class 'PropsWithClass':
Value must be double or be convertible to double.
```

User-Defined Class for Validation

You can define a class to control the values assigned to a property. Enumeration classes enable users to set property values to character vectors or string scalars with inexact name matching.

For example, suppose that there is a class that represents a three-speed mechanical pump. You can define an enumeration class to represent the three flow rates.

```
classdef FlowRate < int32
  enumeration
    Low (10)
    Medium (50)
    High (100)
  end
end</pre>
```

The Pump class has a method to return the current flow rate in gallons per minute. Define the Speed property as a FlowRate class.

```
classdef Pump
  properties
    Speed FlowRate
  end
  methods
    function getGPM(p)
       if isempty(p.Speed)
            gpm = 0;
       else
            gpm = int32(p.Speed);
       end
            fprintf('Flow rate is: %i GPM\n',gpm);
       end
  end
end
```

Users can set the Speed property using inexact text.

```
p = Pump;
p.Speed = 'm'
p =
  Pump with properties:
    Speed: Medium
```

The numerical value is available from the property.

```
getGPM(p)
```

```
Flow rate is: 50 GPM
```

For information about enumeration classes, see "Define Enumeration Classes" on page 14-4.

Integer Class Validation

MATLAB supports several integer classes (see "Integers"). However, restricting a property to an integer class can result in integer overflow. The resulting value can saturate at the maximum or minimum value in the integer's range.

When integer overflow occurs, the value that is assigned to a property can be a value that is different from the value from the right side of the assignment statement.

For example, suppose that you want to restrict a property value to a scalar uint8.

```
classdef IntProperty
  properties
     Value(1,1) uint8
  end
end
```

Assigning a numeric value to the Value property effectively casts the numeric value to uint8, but does not result in an error for out-of-range values.

```
a = IntProperty;
a.Value = -10;
disp(a.Value)
```

Assignment to the Value property is equivalent to indexed assignment of an array. If the assigned value is out of the range of values that uint8 can represent, MATLAB sets the value to the closest value that it can represent using uint8.

```
a = uint8.empty;
a(1) = -10

a =

uint8
```

To avoid the potential for integer overflow, use a combination of validation functions that restrict the value to the intended range instead of an integer class.

```
classdef IntProperty
  properties
    Value(1,1) {mustBeInteger, mustBeNonnegative,...
        mustBeLessThan(Value, 256)}
  end
end
```

Because there is no conversion of the assigned value by the uint8 class, the validators catch out of range values and throw an appropriate error.

```
a = IntProperty;
a.Value = -10;
```

Error setting property 'Value' of class 'IntProperty': Value must be nonnegative.

Default Values Per Size and Class

Any default property value that you assign in the class definition must conform to the specified validation.

Implicit Default Values

MATLAB defines a default value implicitly if you do not specify a default value in the class definition. This table shows how size and class determine the implicit default value of MATLAB classes.

Size	Class	Implicit Default Assigned by MATLAB
(m,n)	Any numeric	m-by-n array of zeros of specified class.
(m,:) or (:,n)	Any class	m-by-0 or 0-by-n of specified class.
(m,n)	char	m-by-n char array of spaces.
(m,n)	cell	m-by-n cell array with each cell containing a 0-by-0 double.
(m,n)	struct	m-by-n struct
(m,n)	string	m-by-n string
(m,n)	enumeration class	First enumeration member defined in the class.
(1,1)	function_handle	Runtime error — define a default value in the class.

To determine the implicit default value for nonzero and explicit size specifications, MATLAB calls the default class constructor and builds an array of the specified size using the instance returned by the constructor call. If the class does not support a default constructor (that is, a constructor called with no arguments), then MATLAB throws an error when instantiating the class containing the validation.

If the specified size has any zero or unrestricted (:) dimensions, MATLAB creates a default value that is an empty array with the unrestricted dimension set to zero.

For heterogeneous arrays, MATLAB calls the matlab.mixin.Heterogeneous.getDefaultScalarElement method to get the default object.

See Also

Related Examples

- "Validate Property Values" on page 8-19
- "Property Validation Functions" on page 8-30
- "Enumerations for Property Values" on page 14-14

Property Validation Functions

In this section...

"MATLAB Validation Functions" on page 8-30

"Validate Property Using Functions" on page 8-32

"Define Validation Functions" on page 8-35

MATLAB Validation Functions

MATLAB defines functions for use in property validation. These functions support common use patterns for validation and provide descriptive error messages. The following tables categorize the MATLAB validation functions and describe their use.

Numeric Value Attributes

Name	Meaning	Functions Called on Inputs
mustBePositive(value)	value > 0	gt,isreal, isnumeric, islogical
mustBeNonpositive(value)	value <= 0	ge, isreal, isnumeric, islogical
mustBeNonnegative(value)	value >= 0	ge, isreal, isnumeric, islogical
mustBeNegative(value)	value < 0	lt,isreal, isnumeric, islogical
mustBeFinite(value)	value has no NaN and no Inf elements.	isfinite
mustBeNonNan(value)	value has no NaN elements.	isnan
mustBeNonzero(value)	value ~= 0	eq, isnumeric, islogical
mustBeNonsparse(value)	value is not sparse.	issparse
mustBeSparse(value)	value is sparse.	issparse
mustBeReal(value)	value has no imaginary part.	isreal
mustBeInteger(value)	<pre>value == floor(value)</pre>	isreal, isfinite, floor, isnumeric, islogical
mustBeNonmissing(value)	value cannot contain missing values.	ismissing

Comparison with Other Values

Name	Meaning	Functions Called on Inputs
<pre>mustBeGreaterThan(valu e,c)</pre>	value > c	gt,isreal, isnumeric, islogical
<pre>mustBeLessThan(value,c)</pre>	value < c	lt,isreal, isnumeric, islogical
<pre>mustBeGreaterThanOrEqu al(value,c)</pre>	value >= c	ge, isreal, isnumeric, islogical
<pre>mustBeLessThanOrEqual(value,c)</pre>	value <= c	le, isreal, isnumeric, islogical

Data Types

Name	Meaning	Functions Called on Inputs
<pre>mustBeA(value,classnam es)</pre>	value must be of specific class.	Uses class definition relationships
mustBeNumeric(value)	value must be numeric.	isnumeric
<pre>mustBeNumericOrLogical (value)</pre>	value must be numeric or logical.	isnumeric, islogical
mustBeFloat(value)	value must be floating-point array.	isfloat
<pre>mustBeUnderlyingType(v alue,typename)</pre>	value must have specified underlying type.	isUnderlyingTyp e

Size

Name	Meaning	Functions Called on Inputs
mustBeNonempty(value)	value is not empty.	isempty
mustBeScalarOrEmpty(value)	value must be a scalar or be empty.	isscalar, isempty
mustBeVector(value)	value must be a vector.	isvector
mustBeRow(value)	value must be a 1-by- N row vector.	isrow

Name	Meaning	Functions Called on Inputs
mustBeColumn(value)	value must be an M- by-1 column vector.	iscolumn
mustBeMatrix(value)	value must be an M- by-N matrix.	ismatrix

Membership and Range

Name	Meaning	Functions Called on Inputs
mustBeMember(value,S)	value is an exact match for a member of S.	ismember
<pre>mustBeInRange(value, lo wer, upper, boundflags)</pre>	value must be within range.	gt, ge, lt, le

Text

Name	Meaning	Functions Called on Inputs
mustBeFile(path)	path must refer to a file.	isfile
mustBeFolder(folder)	path must refer to a folder.	isfolder
mustBeNonzeroLengthTex t(value)	value must be a piece of text with nonzero length.	Not applicable
mustBeText(value)	value must be a string array, character vector, or cell array of character vectors.	Not applicable
<pre>mustBeTextScalar(value)</pre>	value must be a single piece of text.	Not applicable
<pre>mustBeValidVariableNam e(varname)</pre>	varname must be a valid variable name.	isvarname

Validate Property Using Functions

Use property validation functions in class definitions to impose specific restrictions on property values. A validation function accepts a potential property value as an argument and issues an error if the value does not meet the specific requirement imposed by the function.

During the validation process, MATLAB passes the value to each validation function listed in the class definition. MATLAB calls each function from left to right and throws the first error encountered. The value passed to the validation functions is the result of any conversion applied by the class and size specifications. For more information on class and size validation, see "Property Class and Size Validation" on page 8-24.

For a list of MATLAB validation functions, see "MATLAB Validation Functions" on page 8-30.

Validation Function Syntax

Specify validation functions as a comma-separated list of function names or function calls with arguments, enclosed in braces.

```
classdef MyClass
   properties
      Prop {fcn1,fcn2} = defaultValue
   end
end
```

MATLAB passes the potential property value to the validation function implicitly. However, if the validation function requires input arguments in addition to the potential property value, then you must include both the property and the additional arguments. Additional arguments must be literal values and cannot reference variables. Literal values are nonsymbolic representations, such as numbers and text.

For example, consider the function mustBeGreaterThan. It requires a limiting value as an input parameter. This validation function requires that a property value must be greater than this limiting value.

Pass the property as the first argument. Use the property name, but do not enclose the name in quotation marks. This property definition restricts Prop to values greater than 10.

```
properties
   Prop {mustBeGreaterThan(Prop,10)}
end
```

Using Validation Functions

The following class specifies validation functions for each property.

- Data must be numeric and finite.
- Interp must be one of the three options listed. Specify a default value for this property to satisfy this requirement.

```
classdef ValidatorFunction
    properties
        Data {mustBeNumeric, mustBeFinite}
        Interp {mustBeMember(Interp,{'linear','cubic','spline'})} = 'linear'
    end
end
```

Creating a default object of the class shows the initial values.

```
a = ValidatorFunction
a =
  ValidatorFunction with properties:
       Data: []
       Interp: 'linear'
```

Assigning values to properties calls the validation functions.

```
a.Data = 'cubic'
```

```
Error setting property 'Data' of class 'ValidatorFunction': Value must be numeric.
```

Because the Data property validation does not include a numeric class, there is no conversion of the char vector to a numeric value. If you change the validation of the Data property to specify the class as double, MATLAB converts the char vector to a double array.

```
properties
   Data double {mustBeNumeric, mustBeFinite}
end
```

The assignment to the char vector does not produce an error because MATLAB converts the char vector to class double.

```
a.Data = 'cubic'
a =

ValidatorFunction with properties:

Data: [99 117 98 105 99]
Interp: 'linear'
```

Assignment to the Interp property requires an exact match.

```
a = ValidatorFunction;
a.Interp = 'cu'

Error setting property 'Interp' of class 'ValidatorFunction':
Value must be a member of this set
    linear
    cubic
    spline
```

Using an enumeration class provides inexact matching and case insensitivity.

Enumeration Class for Inexact Matching

Property validation using an enumeration class provides these advantages:

- Inexact, case-insensitive matching for unambiguous char vectors or string scalars
- Conversion of inexact matches to correct values

For example, suppose that you define the InterpMethod enumeration class for the Interp property validation.

```
classdef InterpMethod
    enumeration
        linear
        cubic
        spline
    end
end
```

Change the Interp property validation to use the InterpMethod class.

```
classdef ValidatorFunction
   properties
```

```
Data {mustBeNumeric, mustBeFinite}
    Interp InterpMethod
    end
end

Assign a value matching the first few letters of 'cubic'.

a = ValidatorFunction;
a.Interp = 'cu'

a =

ValidatorFunction with properties:

Data: []
Interp: cubic
```

Define Validation Functions

Validation functions are ordinary MATLAB functions that are designed for the specific purpose of validating property and function argument values. Functions used to validate properties:

- · Accept the potential property value as an input argument
- Do not return values
- Display error messages if the validation fails

Creating your own validation function is useful when you want to provide specific validation that is not available using the MATLAB validation functions. You can create local functions within the class file or place the function on the MATLAB path to be available for use in any class.

For example, the ImgData class uses a local function to define a validator that restricts the Data property to only uint8 or uint16 values, excluding subclasses and not allowing conversion from other numeric classes. The predefined validation function mustBeInRange restricts the range of allowed values.

```
classdef ImgData
    properties
        Data {mustBeImData(Data),mustBeInRange(Data,0,255)} = uint8(0)
    end
end
function mustBeImData(a)
    if ~(isa(a,'uint8') || isa(a,'uint16'))
        error("Value of Data property must be uint8 or uint16 data.")
    end
end
```

When you create an instance of the ImgData class, MATLAB validates that the default value is a uint8 or uint16 value, in the range 0...255, and not empty. Note that the default value must satisfy the validation requirements like any other value assigned to the property.

```
a = ImgData
a =
  ImgData with properties:
  Data: 0
```

Property assignment invokes the validators in left-to-right order. Assigning a char vector to the Data property causes an error thrown by mustBeImData.

```
a.Data = 'red';
Error setting property 'Data' of class 'ImgData'.
Value of Data property must be uint8 or uint16 data.
```

Assigning a numeric value that is out of range causes an error thrown by mustBeInRange.

```
a.Data = uint16(312); 
 Error setting property 'Data' of class 'ImgData'. Value must be greater than or equal to 0, and less than or equal to 255.
```

For related functions, see mustBeInteger, mustBeNumeric, and mustBePositive.

See Also

Related Examples

- "Validate Property Values" on page 8-19
- "Property Class and Size Validation" on page 8-24

Metadata Interface to Property Validation

For information on property validation, see "Validate Property Values" on page 8-19.

You can determine what validation applies to a property by accessing the validation metadata. Instances of the matlab.metadata.Validation class provide the following information about property validation.

- Class requirement of the property specified as a matlab.metadata.Class object
- Size requirements of the property value specified as an array of matlab.metadata.FixedDimension and matlab.metadata.UnrestrictedDimension objects
- Function handles referencing validation functions applied to property values specified as a cell array of function handles.

For example, the ValidationExample class defines a property that must be an array of doubles that is 1-by-any number of elements and must be a real number that is greater than 10.

```
classdef ValidationExample
  properties
     Prop (1,:) double {mustBeReal,mustBeGreaterThan(Prop,10)} = 200;
  end
end
```

Access the matlab.metadata.Validation object from the property's matlab.metadata.Property object. Get the validation information from the matlab.metadata.Validation object properties. Collect this information into a cell array and display it.

- Get the size information from the Size property
- Get the class name from the Class property
- Get a cell array of function handles for the validation functions from the ValidatorFunctions property.

```
mc = ?ValidationExample;
mp = findobj(mc.PropertyList, 'Name', 'Prop');
sz = mp.Validation.Size;
len = length(sz);
dim = cell(1:len);
for k = 1:len
   if isa(sz(k), 'matlab.metadata.FixedDimension')
         dim\{k\} = sz(k).Length;
   else
         dim\{k\} = ':';
   end
end
dim{end+1} = mp.Validation.Class.Name;
dim{end+1} = mp.Validation.ValidatorFunctions;
dim
dim =
 1×4 cell array
    {[1]} {':'} {'double'} {1×2 cell}
```

See Also

matlab.metadata.Property | matlab.metadata.Validation

Related Examples

- "Validate Property Values" on page 8-19
- "Property Class and Size Validation" on page 8-24
- "Property Validation Functions" on page 8-30

Property Get and Set Methods

```
In this section...

"Property Get Methods" on page 8-39

"Property Set Methods" on page 8-40
```

You can define property get and set methods that MATLAB calls automatically whenever the associated property is accessed. To associate a get or set method with a given property, name the get and set methods using the forms get. *PropertyName* and set. *PropertyName*, respectively.

Get and set methods can perform extra steps beyond just accessing the property. Use get methods to:

- Calculate the value of dependent properties.
- Store data in a different format than what you present to users.

Use set methods to:

- Design property validation that is more complex than what the built-in validation techniques support.
- Issue custom error messages.
- Perform actions that are a direct result of a property value change, such as establishing or updating connections with hardware devices or opening files, ensuring access to resources.

Get and set methods do add overhead to your classes. Avoid complex and computation-heavy operations in the get and set methods of frequently accessed properties.

Note You cannot call the get and set methods described in this topic directly. MATLAB automatically calls these methods when you access property values. For information on implementing user-callable get and set methods, see "Implement Set/Get Interface for Properties" on page 7-22.

Property Get Methods

You can define a get method that MATLAB automatically calls whenever the associated property value is queried. The get method must return the property value. Get methods use this syntax, where <code>PropertyName</code> is the name of the property.

```
methods
   function value = get.PropertyName(obj)
     ...
   end
end
```

Method blocks defining get or set methods cannot specify attributes.

For example, the triangleArea class defines a get method for the Area property. Area is defined as a dependent property, which means that it does not store values. The get method for Area calculates the value on demand. (For more information on dependent properties, see "Get and Set Methods for Dependent Properties" on page 8-43.)

```
classdef triangleArea
  properties
```

```
Base = 1
      Height = 1
   properties (Dependent)
      Area
   end
   methods
      function a = get.Area(obj)
         disp("Executing get.Area method.")
         a = 0.5*obj.Base*obj.Height;
      end
  end
end
```

Create an instance of triangleArea.

```
a = triangleArea
a =
Executing get.Area method.
 triangleArea with properties:
      Base: 1
   Height: 1
      Area: 0.5000
```

When displaying an object, MATLAB calls any defined get methods for the properties it displays. In this case, it calls get. Area and calculates the value of Area based on the default values for Base and Height. If a get method errors, MATLAB suppresses the error and omits that property from the display.

Change the values of Base and Height and access Area again.

```
a.Base = 3;
a.Height = 4;
a.Area
Executing get.Area method.
ans =
     6
```

Get Method Usage

- Get methods are not called recursively.
- When copying a value object (that is, not derived from the handle class), get methods are not called when copying property values from one object to another.

Property Set Methods

You can define a set method that MATLAB automatically calls whenever the associated property is assigned a value. Set methods use these syntaxes, depending on whether the class is a value or handle class:

• Value class set methods must return the modified object.

```
methods
   function obj = set.PropertyName(obj,value)
    ...
   end
end
```

Handle class set methods do not need to return the modified object.

```
methods
   function set.PropertyName(obj,value)
     ...
   end
end
```

Method blocks defining get or set methods cannot specify attributes.

For example, symPosDef uses a set method for property validation. When the inputMatrix property is set to a new value, the set method calls the chol function to determine if the input matrix is symmetric positive definite. If it is, the method sets inputMatrix to that value. If not, the method returns a custom error message.

```
classdef symPosDef
  properties
    inputMatrix = [1 0; 0 1]
  end
  methods
    function obj = set.inputMatrix(obj,val)
        try chol(val)
        obj.inputMatrix = val;
    catch ME
        error("inputMatrix must be symmetric positive definite.")
    end
  end
  end
end
end
```

Create an instance of symPosDef and try to set inputMatrix to a value that is not a symmetric positive definite matrix.

```
s = symPosDef;
s.inputMatrix = [1 2; 1 1]
Error using symPosDef/set.inputMatrix
inputMatrix must be symmetric positive definite.
```

Set Method Usage

- · Set methods are not called recursively.
- MATLAB does not call set methods when it assigns default values to the properties during initialization of an object. However, setting property values in the constructor does call set methods.
- MATLAB calls set methods when an object is loaded.
- When MATLAB copies a value object (any object that is not a handle), set methods are not called when copying property values from one object to another.

• When a property is defined with the AbortSet attribute equal to true, the set method of the property is not called when assigning a value that is the same as the current value. However, if the property has a get method, that method is called so that the values can be compared. See "Assignment When Property Value Is Unchanged" on page 11-35 for more information on this attribute.

See Also

Related Examples

- "Get and Set Methods for Dependent Properties" on page 8-43
- "Listen for Changes to Property Values" on page 11-32

Get and Set Methods for Dependent Properties

```
In this section...

"Define a Get Method for a Dependent Property" on page 8-43

"When to Use Set Methods with Dependent Properties" on page 8-44
```

Dependent properties do not store data. The value of a dependent property depends on other values, such as the values of nondependent properties. Define a dependent property using this syntax:

```
properties (Dependent)
  PropertyName
end
```

Because dependent properties do not store data, you must define get methods (get. *PropertyName*) to determine the value for the properties when the properties are queried.

Dependent properties can also have set methods (set. *PropertyName*), but these methods cannot actually set the value of the dependent property. However, a set method can contain other code. For example, it can set values of properties related to the dependent property.

For an introduction to defining get and set methods, see "Property Get and Set Methods" on page 8-39

Define a Get Method for a Dependent Property

The Account class stores an amount in US dollars, and it can return that value in one of three currencies: US dollars, euros, or Japanese yen. That converted value is represented by the dependent Balance property. The get.Balance method uses USDollarAmount and Currency to determine a conversion rate to calculate the Balance property.

```
classdef Account
   properties
      Currency {mustBeMember(Currency,["USD","EUR","JPY"])} = "USD"
      USDollarAmount = 0
   properties (Dependent)
      Balance
   end
   methods
      function value = get.Balance(obj)
         c = obj.Currency;
         switch c
            case "EUR"
               v = obj.USDollarAmount/0.98;
            case "JPY"
               v = obj.USDollarAmount/0.0069;
            otherwise
               v = obj.USDollarAmount;
         end
         value = v;
      end
   end
end
```

Create an instance of Account. Set the USDollarAmount and Currency properties.

```
a = Account;
a.USDollarAmount = 100;
a.Currency = "JPY";
```

You cannot explicitly call get methods. When you access Balance, MATLAB calls the get method to return the initial amount converted to yen.

```
a.Balance
ans =
1.4493e+04
```

MATLAB also calls get methods when it displays the object. When you set Currency to euros without ending the statement with a semicolon, MATLAB calls the Balance get method to display the updated value.

```
a.Currency = "EUR"

a =

Account with properties:

    Currency: "EUR"
    USDollarAmount: 100
         Balance: 102.0400
```

When to Use Set Methods with Dependent Properties

Although dependent properties do not store values, you can still define set methods for them. The set methods cannot set the value of a dependent property, but they can execute other code.

For example, propertyChange is a value class that initially defined a property named OldPropName. You can use a set method to change the property name from the perspective of a class user:

- Redefine OldPropName as dependent and hidden.
- Define a new property with the name you would like to replace OldPropName.
- Define a set method for OldPropName that stores the value in NewPropName.
- Define a get method for OldPropName that returns the value stored in NewPropName.

```
classdef propertyChange
    properties
        NewPropName
    end
    properties (Dependent, Hidden)
        OldPropName
    end

methods
    function obj = set.OldPropName(obj, val)
        obj.NewPropName = val;
    end
    function value = get.OldPropName(obj)
        value = obj.NewPropName;
    end
```

end end

Code that accesses OldPropName continues to work as expected, and making OldPropName hidden helps prevent new users from seeing the old property name.

For example, create an instance of propertyChange. Set the property value using the old property name and then display the object. MATLAB sets the value to the property with the new name and displays it.

```
a = propertyChange;
a.OldPropName = "hello"
p =
  propertyChange with properties:
    NewPropName: "hello"
```

See Also

Related Examples

- "Property Attributes" on page 8-8
- "Calculate Data on Demand" on page 3-17

Properties Containing Objects

```
In this section...

"Assigning Objects as Default Property Values" on page 8-46

"Assigning to Read-Only Properties Containing Objects" on page 8-46

"Assignment Behavior" on page 8-46
```

Assigning Objects as Default Property Values

MATLAB evaluates property default values only once when loading the class. MATLAB does not reevaluate the assignment each time you create an object of that class. If you assign an object as a default property value in the class definition, MATLAB calls the constructor for that object only once when loading the class.

Note Evaluation of property default values occurs only when the value is first needed, and only once when MATLAB first initializes the class. MATLAB does not reevaluate the expression each time you create an instance of the class.

For more information on the evaluation of expressions that you assign as property default values, see "When MATLAB Evaluates Expressions" on page 6-11.

Assigning to Read-Only Properties Containing Objects

When a class defines a property with private or protected SetAccess, and that property contains an object which itself has properties, assignment behavior depends on whether the property contains a handle or a value object:

- Handle object you can set properties on handle objects contained in read-only properties
- Value object you cannot set properties on value object contained in read-only properties.

Assignment Behavior

These classes illustrate the assignment behavior:

- ReadOnlyProps class with two read-only properties. The class constructor assigns a handle object of type HanClass to the PropHandle property and a value object of type ValClass to the PropValue property.
- HanClass handle class with public property
- ValClass value class with public property

```
classdef ReadOnlyProps
  properties(SetAccess = private)
    PropHandle
    PropValue
  end
  methods
    function obj = ReadOnlyProps
    obj.PropHandle = HanClass;
```

```
obj.PropValue = ValClass;
      end
   end
end
classdef HanClass < handle</pre>
   properties
      Hprop
   end
end
classdef ValClass
   properties
      Vprop
   end
end
Create an instance of the ReadOnlyProps class:
a = ReadOnlyProps
a =
 ReadOnlyProps with properties:
    PropHandle: [1x1 HanClass]
     PropValue: [1x1 ValClass]
Use the private PropHandle property to set the property of the HanClass object it contains:
class(a.PropHandle.Hprop)
ans =
double
a.PropHandle.Hprop = 7;
Attempting to make an assignment to the value class object property is not allowed:
a.PropValue.Vprop = 11;
You cannot set the read-only property 'PropValue' of ReadOnlyProps.
```

See Also

More About

"Mutable and Immutable Properties" on page 8-17

Dynamic Properties — Adding Properties to an Instance

In this section...

"What Are Dynamic Properties" on page 8-48

"Define Dynamic Properties" on page 8-48

"List Object Dynamic Properties" on page 8-50

What Are Dynamic Properties

You can add properties to instances of classes that derive from the dynamicprops class. These dynamic properties are sometimes referred to as instance properties. Use dynamic properties to attach temporary data to objects or to assign data that you want to associate with an instance of a class, but not all objects of that class.

It is possible for more than one program to define dynamic properties on the same object. In these cases, avoid name conflicts. Dynamic property names must be valid MATLAB identifiers (see "Variable Names") and cannot be the same name as a method of the class.

Characteristics of Dynamic Properties

Once defined, dynamic properties behave much like class-defined properties:

- Set and query the values of dynamic properties using dot notation. (See "Assign Data to the Dynamic Property" on page 8-49.)
- MATLAB saves and loads dynamic properties when you save and load the objects to which they are attached. (See "Dynamic Properties and ConstructOnLoad" on page 8-58.)
- Define attributes for dynamic property. (See "Set Dynamic Property Attributes" on page 8-49.)
- By default, dynamic properties have their NonCopyable attribute set to true. If you copy an object containing a dynamic property, the dynamic property is not copied. (See "Objects with Dynamic Properties" on page 7-34.)
- Add property set and get access methods. (See "Set and Get Methods for Dynamic Properties" on page 8-52.)
- Listen for dynamic property events. (See "Dynamic Property Events" on page 8-54.)
- Access dynamic property values from object arrays, with restricted syntax. (See "Accessing Properties and Methods in Object Arrays" on page 10-7.)
- The isequal function always returns false when comparing objects that have dynamic properties, even if the properties have the same name and value. To compare objects that contain dynamic properties, overload isequal for your class.

Define Dynamic Properties

Any class that is a subclass of the dynamicprops class (which is itself a subclass of the handle class) can define dynamic properties using the addprop method. The syntax is:

P = addprop(H,'PropertyName')

where:

P is an array of matlab.metadata.DynamicProperty objects

H is an array of handles

PropertyName is the name of the dynamic property you are adding to each object

Naming Dynamic Properties

Use only valid names when naming dynamic properties (see "Variable Names"). In addition, do not use names that:

- Are the same as the name of a class method
- Are the same as the name of a class event
- Contain a period (.)
- Are the names of function that support array functionality: empty, transpose, ctranspose, permute, reshape, display, disp, details, or sort.

Set Dynamic Property Attributes

To set property attributes, use the matlab.metadata.DynamicProperty object associated with the dynamic property. For example, if P is the object returned by addprop, this statement sets the property's Hidden attribute to true:

```
P.Hidden = true;
```

The property attributes Constant and Abstract have no meaning for dynamic properties. Setting the value of these attributes to true has no effect.

Remove a Dynamic Property

Remove the dynamic property by deleting its matlab.metadata.DynamicProperty object:

```
delete(P);
```

Assign Data to the Dynamic Property

Suppose, you are using a predefined set of user interface widget classes (buttons, sliders, check boxes, etc.). You want to store the location of each instance of the widget class. Assume that the widget classes are not designed to store location data for your particular layout scheme. You want to avoid creating a map or hash table to maintain this information separately.

Assuming the button class is a subclass of dynamicprops, add a dynamic property to store your layout data. Here is a simple class to create a uicontrol button:

```
end
end
end
```

Create an instance of the button class, add a dynamic property, and set its value:

```
b1 = button([20 40 80 20]);
b1.addprop('myCoord');
b1.myCoord = [2,3];
```

Access the dynamic property just like any other property, but only on the object on which you defined it:

Access Attribute for Dynamic Properties

Using nonpublic Access with dynamic properties is not recommended because these properties belong to specific instances that are often created outside of class methods. The Access attribute of a dynamic property applies to the class of the instance that contains the dynamic property. The dynamic property Access attribute does not necessarily apply to the class whose method adds the dynamic property.

For example, if a base class method adds a dynamic property with private access to an instance, the private access applies only to the class of the instance.

For more information on dynamic property attributes, see matlab.metadata.DynamicProperty. Use the handle findprop method to get the matlab.metadata.DynamicProperty object.

List Object Dynamic Properties

You can list the dynamic properties for an object using the handle findprop method. Here are the steps:

- Get the names of the object's properties using the properties function.
- Get the metadata object for each property using findprop.
- Use the isa function to determine if the metadata object is a matlab.metadata.DynamicProperty object. If so, then the property is a dynamic property.

The getDynamicPropNames function shows how to display the names of any dynamic properties defined for the input obj.

See Also

Related Examples

- "Set and Get Methods for Dynamic Properties" on page 8-52
- "Dynamic Property Events" on page 8-54
- "Dynamic Properties and ConstructOnLoad" on page 8-58

Set and Get Methods for Dynamic Properties

You can define property set access or get access methods for dynamic properties without creating additional class methods. For general information on the use of access methods, see "Property Get and Set Methods" on page 8-39.

Create Access Methods for Dynamic Properties

Use these steps to create a property access method:

- Define a function that implements the operations you want to perform before the property set or get occurs. These methods must have the following signatures: mySet(obj,val) or val = myGet(obj)
- Obtain the dynamic property's corresponding matlab.metadata.DynamicProperty object.
- Assign a function handle referencing your set or get property function to the matlab.metadata.DynamicProperty object's GetMethod or SetMethod property. This function does not need to be a method of the class. You cannot use a naming scheme like set.PropertyName. Instead, use any other valid function name.

Suppose that you want to create a property set function for the myCoord dynamic property of the button class created in "Define Dynamic Properties" on page 8-48.

Write the function as follows.

```
function set_myCoord(obj,val)
  if ~(length(val) == 2)
    error('myCoords require two values')
  end
  obj.myCoord = val;
end
```

Because button is a handle class, the property set function does not need to return the object as an output argument.

To get the matlab.metadata.DynamicProperty object, use the handle class findprop method:

```
mb1 = b1.findprop('myCoord');
mb1.SetMethod = @set myCoord;
```

MATLAB calls the property set function whenever you set this property:

```
b1.myCoord = [1 2 3] % length must be two
Error using button.set_myCoord
myCoords require two values
```

You can set and get the property values only from within your property access methods. You cannot call another function from the set or get method, and then attempt to access the property value from that function.

See Also

Related Examples

• "Dynamic Properties — Adding Properties to an Instance" on page 8-48

Dynamic Property Events

In this section...

"Dynamic Properties and Ordinary Property Events" on page 8-54

"Dynamic-Property Events" on page 8-54

"Listen for a Specific Property Name" on page 8-55

"PropertyAdded Event Callback Execution" on page 8-56

"PropertyRemoved Event Callback Execution" on page 8-56

"How to Find matlab.metadata.DynamicProperty Objects" on page 8-56

Dynamic Properties and Ordinary Property Events

Dynamic properties support property set and get events so you can define listeners for these properties. Listeners are bound to the particular dynamic property for which they are defined.

If you delete a dynamic property, and then create another dynamic property with the same name, the listeners do not respond to events generated by the new property. A listener defined for a dynamic property that has been deleted does not cause an error, but the listener callback is never executed.

"Property-Set and Query Events" on page 11-14 provides more information on how to define listeners for these events.

Dynamic-Property Events

To respond to the addition and removal of dynamic properties, attach listeners to objects containing the dynamic properties. The dynamic props class defines events for this purpose:

- PropertyAdded Triggered when you add a dynamic property to an object derived from the dynamic props class.
- PropertyRemoved Triggered when you delete the object or the matlab.metadata.DynamicProperty object associated with a dynamic property.
- ObjectBeingDestroyed Triggered when the object is destroyed. This event is inherited from the handle class.

These events have public listen access (ListenAccess attribute) and private notify access (NotifyAccess attribute).

The PropertyAdded and PropertyRemoved events pass an event.DynamicPropertyEvent object to listener callbacks. The event data object has three properties:

- PropertyName Name of the dynamic property that is added or removed
- Source Handle to the object that is the source of the event
- EventName Name of the event (PropertyAdded, PropertyRemoved, or ObjectBeingDestroyed)

Listen for a Specific Property Name

Suppose that you have an application that creates a dynamic property under certain conditions. You want to:

- Set the value of a hidden property to true when a property named SpecialProp is added.
- Set the value of the hidden property to false when SpecialProp is removed.

Use the event.DynamicPropertyEvent event data to determine the name of the property and whether it is added or deleted.

The DynamTest class derives from dynamicprops. It defines a hidden property, HiddenProp.

```
classdef DynamTest < dynamicprops
  properties (Hidden)
      HiddenProp
  end
end</pre>
```

Define a callback function that uses the EventName property of the event data to determine if a property is added or removed. Obtain the name of the property from the PropertyName property of the event data. If a dynamic property is named SpecialProp, change the value of the hidden property.

```
function DyPropEvtCb(src,evt)
   switch evt.EventName
      case 'PropertyAdded'
         switch evt.PropertyName
            case 'SpecialProp'
               % Take action based on the addition of this property
               %...
               %...
               src.HiddenProp = true;
               disp('SpecialProp added')
            otherwise
               % Other property added
               disp([evt.PropertyName, ' added'])
         end
      case 'PropertyRemoved'
         switch evt.PropertyName
            case 'SpecialProp'
               % Take action based on the removal of this property
               %...
               src.HiddenProp = false;
               disp('SpecialProp removed')
            otherwise
               % Other property removed
               disp([evt.PropertyName, ' removed'])
         end
   end
end
```

Create an object of the DynamTest class.

```
dt = DynamTest;
Add a listener for both PropertyAdded and PropertyRemoved events.
lad = addlistener(dt,'PropertyAdded',@DyPropEvtCb);
lrm = addlistener(dt,'PropertyRemoved',@DyPropEvtCb);
```

PropertyAdded Event Callback Execution

Adding a dynamic property triggers the PropertyAdded event. This statement adds a dynamic property to the object and saves the returned matlab.metadata.DynamicProperty object.

```
ad = addprop(dt, 'SpecialProp');
```

The addition of the dynamic property causes the listener to execute its callback function, DyPropEvtCb. The callback function assigns a value of true to the HiddenProp property.

```
dt.HiddenProp
ans =
1
```

PropertyRemoved Event Callback Execution

Remove a dynamic property by calling delete on the matlab.metadata.DynamicProperty object that is returned by the addprop method. Removing the matlab.metadata.DynamicProperty object triggers the PropertyRemoved event.

Delete the matlab.metadata.DynamicProperty object returned when adding the dynamic property SpecialProp.

```
delete(ad)
The callback executes:
SpecialProp removed
The value of HiddenProp is now false.
dt.HiddenProp
ans =
0
```

How to Find matlab.metadata.DynamicProperty Objects

You can obtain the matlab.metadata.DynamicProperty object for a dynamic property using findprop. Use findprop if you do not have the object returned by addprop.

```
ad = findprop(dt, 'SpecialProp');
```

See Also

Related Examples

• "Dynamic Properties — Adding Properties to an Instance" on page 8-48

Dynamic Properties and ConstructOnLoad

Setting the class ConstructOnLoad attribute to true causes MATLAB to call the class constructor when loading the class. MATLAB saves and restores dynamic properties when loading an object.

If you create dynamic properties from the class constructor, you can cause a conflict if you also set the class ConstructOnLoad attribute to true. Here is the sequence:

- A saved object saves the names and values of properties, including dynamic properties
- When loaded, a new object is created and all properties are restored to the values at the time the object was saved
- Then, the ConstructOnLoad attribute causes a call to the class constructor, which would create another dynamic property with the same name as the loaded property. See "Save and Load Functions" on page 13-2 for more on the load sequence.
- MATLAB prevents a conflict by loading the saved dynamic property, and does not execute addprop when calling the constructor.

If you use ConstructOnLoad, add dynamic properties from the class constructor, and want the constructor to call addprop at load time, then set the dynamic property Transient attribute to true. This setting prevents the property from being saved. For example:

```
classdef (ConstructOnLoad) MyClass < dynamicprops
  function obj = MyClass
    P = addprop(obj,'DynProp');
    P.Transient = true;
    ...
  end
end</pre>
```

See Also

Related Examples

• "Dynamic Properties — Adding Properties to an Instance" on page 8-48

Methods — **Defining Class Operations**

- "Methods in Class Design" on page 9-2
- "Method Attributes" on page 9-4
- "Ordinary Methods" on page 9-6
- "Methods in Separate Files" on page 9-8
- "Method Invocation" on page 9-11
- "Class Constructor Methods" on page 9-15
- "Static Methods" on page 9-24
- "Overload Functions in Class Definitions" on page 9-26
- "Class Support for Array-Creation Functions" on page 9-29
- "Class Methods for Graphics Callbacks" on page 9-37

Methods in Class Design

In this section...

"Class Methods" on page 9-2

"Examples and Syntax" on page 9-2

"Kinds of Methods" on page 9-2

"Method Naming" on page 9-3

Class Methods

Methods are functions that implement the operations performed on objects of a class. Methods, along with other class members support the concept of encapsulation—class instances contain data in properties and class methods operate on that data. This design allows the internal workings of classes to be hidden from code outside of the class, and thereby enabling the class implementation to change without affecting code that is external to the class.

Methods have access to private members of their class including other methods and properties. This encapsulation enables you to hide data and create special interfaces that must be used to access the data stored in objects.

Examples and Syntax

For an example to get started writing classes, see "Creating a Simple Class" on page 2-2.

For sample code and syntax, see "Method Syntax" on page 5-7.

For a discussion of how to create classes that modify standard MATLAB behavior, see "Methods That Modify Default Behavior" on page 17-2.

For information on the use of @ and path directors and namespaces to organize your class files, see "Class File Organization".

For the syntax to use when defining classes in more than one file, see "Methods in Separate Files" on page 9-8.

Kinds of Methods

There are specialized kinds of methods that perform certain functions or behave in particular ways:

- Ordinary methods are functions that act on one or more objects and return some new object or some computed value. These methods are like ordinary MATLAB functions that cannot modify input arguments. Ordinary methods enable classes to implement arithmetic operators and computational functions. These methods require an object of the class on which to operate. See "Ordinary Methods" on page 9-6.
- Constructor methods are specialized methods that create objects of the class. A constructor method must have the same name as the class and typically initializes property values with data obtained from input arguments. The class constructor method must declare at least one output argument, which is the object being constructed. The first output is always the object being constructed. See "Class Constructor Methods" on page 9-15.

- Destructor methods are called automatically when the object is destroyed, for example if you call delete(object) or there are no longer any references to the object. See "Handle Class Destructor" on page 7-13.
- *Property access methods* enable a class to define code to execute whenever a property value is queried or set. See "Property Get and Set Methods" on page 8-39.
- Static methods are functions that are associated with a class, but do not necessarily operate on class objects. These methods do not require an instance of the class to be referenced during invocation of the method, but typically perform operations in a way specific to the class. See "Static Methods" on page 9-24.
- Conversion methods are overloaded constructor methods from other classes that enable your class
 to convert its own objects to the class of the overloaded constructor. For example, if your class
 implements a double method, then this method is called instead of the double class constructor
 to convert your class object to a MATLAB double object. See "Object Converters" on page 17-5
 for more information.
- Abstract methods define a class that cannot be instantiated itself, but serves as a way to define a
 common interface used by numerous subclasses. Classes that contain abstract methods are often
 referred to as interfaces. See "Abstract Classes and Class Members" on page 12-68 for more
 information and examples.

Method Naming

The name of a function that implements a method can contain dots (for example, set.PropertyName) only if the method is one of the following:

- Property set/get access method (see "Property Get and Set Methods" on page 8-39)
- Conversion method that converts to a namespace-qualified class, which requires the use of the namespace name (see "Create Namespaces" on page 6-20)

You cannot define property access or conversion methods as local functions, nested functions, or separately in their own files. Class constructors and namespace-scoped functions must use the unqualified name in the function definition; do not include the namespace name in the function definition statement.

See Also

Related Examples

- "Method Attributes" on page 9-4
- "Rules for Naming to Avoid Conflicts" on page 9-28

Method Attributes

In this section...

"Purpose of Method Attributes" on page 9-4

"Specifying Method Attributes" on page 9-4

"Table of Method Attributes" on page 9-4

Purpose of Method Attributes

Specifying attributes in the class definition enables you to customize the behavior of methods for specific purposes. Control characteristics like access, visibility, and implementation by setting method attributes. Subclasses do not inherit superclass member attributes.

Specifying Method Attributes

Assign method attributes on the same line as the methods keyword:

```
methods (Attribute1 = value1, Attribute2 = value2,...)
    ...
end
```

Table of Method Attributes

Attributes enable you to modify the behavior of methods. All methods support the attributes listed in the following table.

Attribute values apply to all methods defined within the methods...end code block that specifies the nondefault values.

Method Attributes

Attribute Name	Class	Description
Abstract	logical Default = false	If true, the method has no implementation. The method has a syntax line that can include arguments that subclasses use when implementing the method:
		• Subclasses are not required to define the same number of input and output arguments. However, subclasses generally use the same signature when implementing their version of the method.
		 The method does not contain function or end keywords, only the function syntax (for example, [a,b] = myMethod(x,y)).
		• The method can include comments after the signature line.
Access	 enumeration, 	Determines what code can call this method:
	default = public	• public — Unrestricted access
	 matlab.metadata .Class object 	• protected — Access from methods in class or subclasses
	• cell array of matlab.metadata .Class objects	• private — Access by class methods only (not from subclasses)
		• List classes that have access to this method. Specify classes as matlab.metadata.Class objects in the form:
		• A single matlab.metadata.Class object
		 A cell array of matlab.metadata.Class objects. An empty cell array, {}, is the same as private access.
		See "Class Members Access" on page 12-23
Hidden	logical Default = false	When false, the method name shows in the list of methods displayed using the methods or methodsview commands. If set to true, the method name is not included in these listings and ismethod does not return true for this method name.
Sealed	logical Default = false	If true, the method cannot be redefined in a subclass. Attempting to define a method with the same name in a subclass causes an error.
Static	logical Default = false	Specify as true to define a method that does not depend on an object of the class and does not require an object argument. Use the class name to call the method: <code>classname.methodname</code> or an instance of the class: <code>obj.methodname</code>
		"Static Methods" on page 9-24 provides more information.
Framework attributes		n framework base classes have framework-specific attributes. See the specific base class you are using for information on these attributes.

See Also

metaclass|matlab.metadata.Method

More About

• "Methods"

Ordinary Methods

```
In this section...

"Ordinary Methods Operate on Objects" on page 9-6

"Methods Inside classdef Block" on page 9-6

"Method Files" on page 9-7
```

Ordinary Methods Operate on Objects

Ordinary methods define functions that operate on objects of the class. Therefore, one of the input arguments must be an object or array of objects of the defining class. These methods can compute values based on object data, can overload MATLAB built-in functions, and can call other methods and functions. Ordinary methods can return modified objects.

Methods Inside classdef Block

This example shows the definition of a method (methodName) within the classdef and methods blocks:

```
classdef ClassName
  methods (AttributeName = value,...)
    function methodName(obj,args)
    % method code
    ...
  end
  ...
  end % end of method block
  ...
end
```

Method attributes apply only to that particular methods block, which is terminated by the end statement.

Note Nonstatic methods must include an explicit object variable as a function argument. The MATLAB language does not support an implicit reference in the method function definition.

Example of a Method

The addData method adds a value to the Data property of MyData objects. The mustBeNumeric function restricts the value of the Data property to numeric values. The property has a default value of θ .

The addData method returns the modified object, which you can reassign to the same variable.

```
classdef MyData
  properties
    Data {mustBeNumeric} = 0
  end
  methods
    function obj = addData(obj,val)
    if isnumeric(val)
```

```
newData = obj.Data + val;
obj.Data = newData;
end
end
end
end

a = MyData;
a = addData(a,75)

a =

MyData with properties:
Data: 75
```

Method Files

You can define methods:

- · Inside the class definition block
- In a separate file in the class folder (that is, @ClassName folder)

For more information on class folders, see "Folders Containing Class Definitions" on page 6-14.

See Also

More About

- "Methods in Separate Files" on page 9-8
- "Method Invocation" on page 9-11
- "Operator Overloading" on page 17-19

Methods in Separate Files

In this section...

"Class Folders" on page 9-8

"Define Method in Function File" on page 9-8

"Specify Method Attributes in classdef File" on page 9-9

"Methods You Must Define in the classdef File" on page 9-10

Class Folders

You can define class methods in files that are separate from the class definition file, with certain exceptions (see "Methods You Must Define in the classdef File" on page 9-10).

To use multiple files for class definitions, put the class files in a folder having a name beginning with the @ character followed by the name of the class (this is called a class folder). Ensure that the parent folder of the class folder is on the MATLAB path.

If the class folder is contained in one or more namespace folders, then the folder containing the toplevel namespace folder must be on the MATLAB path.

For example, the folder @MyClass must contain the file MyClass.m (which contains the classdef block) and contains other methods and function defined in files having a .m extension. The folder @MyClass can contain a number of files:

```
@MyClass/MyClass.m
@MyClass/subsref.m
@MyClass/subsasgn.m
@MyClass/horzcat.m
@MyClass/vertcat.m
@MyClass/myFunc.m
```

Types of Method Files

MATLAB treats any function file in the class folder as a method of the class. Function files can be MATLAB code (.m), Live Code file format (.mlx), MEX functions (platform dependent extensions), and P-code files (.p). The base name of the file must be a valid MATLAB function name. Valid function names begin with an alphabetic character, and can contain letters, numbers, or underscores.

For information on defining methods as C++ MEX functions, see "Use MEX Functions for MATLAB Class Methods".

Define Method in Function File

To define a method in a separate file in the class folder, create the function in a file. Do not use the method-end keywords in that file. Name the file with the function name, as with any function.

In the myFunc.m file, implement the method:

```
function output = myFunc(obj,arg1,arg2)
% code here
end
```

For code readability, declaring the function signature in the classdef file in a methods block is good practice. You also must declare the function signature to set method attributes. If you do not declare the function signature in the classdef file, all attributes of the method take their default values. For example, a method without a signature in classdef has Access set to public, Sealed set to false, and so on.

Specify Method Attributes in classdef File

If you need to specify method attributes for a method that you define in a separate function file, include the method signature in a methods block in the classdef file. This methods block specifies the attributes that apply to the method.

For example, the following code shows a method with Access set to private in the methods block. The method implementation resides in a separate file. Do not include the function or end keywords in the methods block. Include only the function signature showing input and output arguments.

```
classdef MyClass
  methods (Access = private)
     output = myFunc(obj,arg1,arg2)
  end
end
```

In a file named myFunc.m, in the @MyClass folder, define the function:

```
function output = myFunc(obj,arg1,arg2)
   ...
end
```

Static Methods in Separate Files

To create a static method, set the method Static attribute to true and list the function signature in a static methods block in the classdef file. Include the input and output arguments with the function name. For example:

```
classdef MyClass
...
  methods (Static)
    output = staticFunc1(arg1,arg2)
    staticFunc2
  end
  ...
end
```

Define the functions in separate files using the same function signature. For example, in the file @MyClass/staticFunc1.m:

```
function output = staticFunc1(arg1,arg2)
...
end

and in @Myclass/staticFunc2.m:
function staticFunc2
...
end
```

Methods You Must Define in the classdef File

Define the following methods in the classdef file. You cannot define these methods in separate files:

- Class constructor
- All functions that use dots in their names, including:
 - Converter methods that must use the namespace name as part of the class name because the class is contained in namespaces
 - Property set and get access methods

Related Information

- "Converters for Namespace Classes" on page 17-5
- "Property Get and Set Methods" on page 8-39

See Also

Related Examples

- "Folders Containing Class Definitions" on page 6-14
- "Live Code File Format (.mlx)"
- "Call MEX Functions"
- "Use MEX Functions for MATLAB Class Methods"
- "Security Considerations to Protect Your Source Code"

Method Invocation

```
In this section...

"Dot and Function Syntaxes" on page 9-11

"Determining Which Method Is Invoked" on page 9-12
```

MATLAB classes support both dot and function syntaxes for invoking methods. This topic demonstrates both syntaxes and describes how MATLAB determines what method to invoke.

Dot and Function Syntaxes

To invoke a nonstatic method with one argument arg, where obj is an object of the class that defines the method, use dot syntax or function syntax.

```
obj.methodName(arg)
methodName(obj,arg)
```

For example, dataSetSummary stores a set of numeric data along with the mean, median, and range of that data. The class defines two methods: showDataSet displays the current data stored in the data property, and newDataSet replaces the current value of data and calculates the mean, median, and range of that data.

```
classdef dataSetSummary
    properties (SetAccess=private)
        data {mustBeNumeric}
        dataMean
        dataMedian
        dataRange
    end
    methods
        function showDataSet(obj)
            disp(obj.data)
        function obj = newDataSet(obj,inputData)
            obj.data = inputData;
            obj.dataMean = mean(inputData);
            obj.dataMedian = median(inputData);
            obj.dataRange = range(inputData);
        end
    end
end
```

Create an instance of dataSetSummary and invoke newDataSet to add data to the object. Use dot syntax to call newDataSet. Because dataSetSummary is a value class, assign the result back to the original variable to preserve the change.

```
dataMean: 2.5000
dataMedian: 2.5000
dataRange: 3
```

Invoke the showDataSet method, but use function syntax for this call.

```
showDataSet(a)
     1 2 3 4
```

Referencing Method Names with Expressions

You can invoke a class method dynamically by enclosing an expression in parentheses.

```
obj.(expression)
```

The expression must evaluate to a character vector or string that is the name of a method. For example, these two statements are equivalent for an object a of class dataSetSummary.

```
a.showDataSet
a.("showDataSet")
```

This technique does not work when used with function syntax.

Indexing into the Result of Method Call

You can dot index into the result of any method that returns a value for which dot indexing is defined, such as an object property or structure field name. For example, add a new method returnSummary to the dataSetSummary class that returns all of the stored data in a struct.

Call returnSummary and use dot indexing to return the median of the data set.

```
a.returnSummary.Median
ans =
    2.5000
```

For more information on indexing into the result of function calls, see "Indexing into Function Call Results".

Determining Which Method Is Invoked

When dot syntax is used to invoke a method, MATLAB calls the method defined by the class of the object to the left of the dot. For example, if classA and classB both define a method called plus, then this code always invokes the plus method defined by classA.

```
A = classA;
B = classB;
A.plus(B)
```

No other arguments are considered. Methods of other arguments are never called, nor are functions.

In other syntaxes, MATLAB must determine which of possibly many versions of an operator or function to call in a given situation. The default behavior is to call the method associated with the leftmost argument. In both of these statements, the plus method defined by classA is called.

```
objA + objB
plus(objA,objB)
```

However, this default behavior can be changed when one object has precedence over another.

Object Precedence

Depending on how classes are defined, the objects of those classes can take precedence over other objects when it comes to method dispatching:

- Classes defined with the classdef syntax have precedence over these MATLAB classes:
 - double, single, int64, uint64, int32, uint32, int16, uint16, int8, uint8, char, string, logical, cell, struct, and function handle.
- Classes defined with the classdef syntax can specify their relative precedence to other classes using the InferiorClasses attribute.

In "Representing Polynomials with Classes" on page 19-2, the DocPolynom class defines a plus method that enables the addition of DocPolynom objects. Construct a DocPolynom instance.

This statement adds a double to the DocPolynom instance. The DocPolynom class is dominant over the built-in double class, even though the double is the leftmost argument in 1 + p. This code invokes the DocPolynom plus method to add the polynomials.

```
1 + p

ans =
    x^3 - 2*x - 4
```

You can also specify the relative precedence of classes defined with the classdef syntax by listing inferior classes in a class attribute. The InferiorClasses attribute gives the class higher precedence than the classes listed as arguments for the attribute. Define the InferiorClasses attribute in the classdef statement:

```
classdef (InferiorClasses = {?class1,?class2}) myClass
```

This attribute establishes a relative priority of the class being defined with the order of the classes listed. For more information, see "Class Precedence" on page 6-18.

See Also

More About

"Class Attributes" on page 6-5

- "Method Attributes" on page 9-4
- "Class Precedence" on page 6-18
- "Call Superclass Methods on Subclass Objects" on page 5-11

Class Constructor Methods

```
In this section...

"Purpose of Class Constructor Methods" on page 9-15

"Basic Structure of Constructor Methods" on page 9-15

"Guidelines for Constructors" on page 9-16

"Default Constructor" on page 9-17

"When to Define Constructors" on page 9-17

"Related Information" on page 9-17

"Initializing Objects in Constructor" on page 9-17

"No Input Argument Constructor Requirement" on page 9-19

"Subclass Constructors" on page 9-19

"Implicit Call to Inherited Constructor" on page 9-21

"Errors During Class Construction" on page 9-22
```

Purpose of Class Constructor Methods

"Output Object Suppressed" on page 9-22

A constructor method is a special function that creates an instance of the class. Typically, constructor methods accept input arguments to assign the data stored in properties and return an initialized object.

For a basic example, see "Creating a Simple Class" on page 2-2.

MATLAB classes that do not explicitly define any class constructors have a default constructor method. This method returns an object of the class that is created with no input arguments. A class can define a constructor method that overrides the default constructor. An explicitly defined constructor can accept input arguments, initialize property values, call other methods, and perform other operations necessary to create objects of the class.

Basic Structure of Constructor Methods

Constructor methods can be structured into three basic sections:

- Pre-initialization Compute arguments for superclass constructors.
- Object initialization Call superclass constructors.
- Post initialization Perform any operations related to the subclass, including referencing and assigning to the object, call class methods, passing the object to functions, and so on.

This code illustrates the basic operations performed in each section:

```
classdef ConstructorDesign < BaseClass1
  properties
     ComputedValue
  end
  methods</pre>
```

```
function obj = ConstructorDesign(a,b,c)
         %% Pre Initialization %%
         % Any code not using output argument (obj)
         if nargin == 0
            % Provide values for superclass constructor
            % and initialize other inputs
            a = someDefaultValue;
            args{1} = someDefaultValue;
            args{2} = someDefaultValue;
            % When nargin ~= 0, assign to cell array,
            % which is passed to supclass constructor
            args{1} = b;
            args{2} = c;
         end
         compvalue = myClass.staticMethod(a);
         %% Object Initialization %%
         % Call superclass constructor before accessing object
         % You cannot conditionalize this statement
         obj = obj@BaseClass1(args{:});
         %% Post Initialization %%
         % Any code, including access to object
         obj.classMethod(arg);
         obj.ComputedValue = compvalue;
      end
   . . .
   end
end
```

Call the constructor like any function, passing arguments and returning an object of the class.

```
obj = ConstructorDesign(a,b,c);
```

Guidelines for Constructors

- The constructor has the same name as the class.
- The constructor can return multiple arguments, but the first output must be the object created.
- If you do not want to assign the output argument, you can clear the object variable in the constructor (see "Output Object Suppressed" on page 9-22).
- If you create a class constructor, ensure it can be called with no input arguments. See "No Input Argument Constructor Requirement" on page 9-19.
- If your constructor makes an explicit call to a superclass constructor, this call must occur before any other reference to the constructed object and cannot occur after a return statement.
- Calls to superclass constructors cannot be conditional. You cannot place superclass construction
 calls in loops, conditions, switches, try/catch, or nested functions. See "No Conditional Calls to
 Superclass Constructors" on page 9-20 for more information.

Default Constructor

If a class does not define a constructor, MATLAB supplies a default constructor that takes no arguments and returns a scalar object whose properties are initialized to property default values. The default constructor supplied by MATLAB also calls all superclass constructors with no arguments or with any argument passed to the default subclass constructor.

When a subclass does not define a constructor, the default constructor passes its inputs to the direct superclass constructor. This behavior is useful when there is no need for a subclass to define a constructor, but the superclass constructor does require input arguments.

When to Define Constructors

Define a constructor method to perform object initialization that a default constructor cannot perform. For example, when creating an object of the class requires:

- Input arguments
- Initializing object state, such as property values, for each instance of the class
- Calling the superclass constructor with values that are determined by the subclass constructor

Related Information

For information specific to constructing enumerations, see "Enumeration Class Constructor Calling Sequence" on page 14-7.

For information on creating object arrays in the constructor, see "Create and Initialize Object Arrays" on page 10-2.

If the class being created is a subclass, MATLAB calls the constructor of each superclass class to initialize the object. Implicit calls to the superclass constructor are made with no arguments. If superclass constructors require arguments, call them from the subclass constructor explicitly. See "Control Sequence of Constructor Calls" on page 12-11

Initializing Objects in Constructor

Constructor methods return an initialized object as an output argument. The output argument is created when the constructor executes, before executing the first line of code.

For example, the following constructor can assign the value of the object's property A as the first statement because the object obj has already been assigned to an instance of MyClass.

```
function obj = MyClass(a,b,c)
  obj.A = a;
...
end
```

You can call other class methods from the constructor because the object is already initialized.

The constructor also creates an object whose properties have their default values — either empty ([]) or the default value specified in the property definition block.

For example, this constructor operates on the input arguments to assign the value of the \mbox{Value} property.

```
function obj = MyClass(a,b,c)
  obj.Value = (a + b) / c;
  ...
end
```

Referencing the Object in a Constructor

When initializing the object, for example, by assigning values to properties, use the name of the output argument to refer to the object within the constructor. For example, in the following code the output argument is obj and the object is reference as obj:

```
% obj is the object being constructed
function obj = MyClass(arg)
  obj.property1 = arg*10;
  obj.method1;
  ...
end
```

For more information on defining default property values, see "Define Properties with Default Values" on page 8-14.

Setting Properties Using Name-Value Arguments

When initializing an object, you can use the *structName*.?ClassName syntax to enable passing in property values as name-value arguments. For example, NameValueClass, the constructor collects any passed arguments into the struct opts, then uses a for-loop to set the property values.

```
classdef NameValueClass
    properties
        Property1
        Property2
   end
   properties (SetAccess=immutable)
        ImmProperty
   end
   methods
        function obj = NameValueClass(opts)
            arguments
                opts.?NameValueClass
            end
            for prop = string(fieldnames(opts))'
                obj.(prop) = opts.(prop);
            end
        end
    end
end
```

Call the class constructor and set ImmProperty using the name-value syntax.

```
x = NameValueClass(ImmProperty=1)
x =
   NameValueClass with properties:
        Property1: []
```

```
Property2: [] ImmProperty: 1
```

For more information on using class properties as name-value arguments in a function, see "Name-Value Arguments from Class Properties".

The *structName*.?*ClassName* syntax did not work with immutable properties. To use this technique in earlier releases, use a separate line to define a name-value argument that matches the immutable property. For example, in NameValueClass:

```
arguments
  opts.ImmProperty
  opts.?NameValueClass
end
```

No Input Argument Constructor Requirement

There are cases where the constructor must be able to be called with no input argument:

- When loading objects into the workspace, if the class ConstructOnLoad attribute is set to true, the load function calls the class constructor with no arguments.
- When creating or expanding an object array such that not all elements are given specific values, the class constructor is called with no arguments to fill in unspecified elements (for example, x(10,1) = MyClass(a,b,c);). In this case, the constructor is called once with no arguments to populate the empty array elements (x(1:9,1)) with copies of this one object.

If there are no input arguments, the constructor creates an object using only default properties values. A good practice is to add a check for zero arguments to the class constructor to prevent an error if either of these two cases occur:

```
function obj = MyClass(a,b,c)
  if nargin > 0
    obj.A = a;
    obj.B = b;
    obj.C = c;
    end
end
```

For ways to handle superclass constructors, see "Basic Structure of Constructor Methods" on page 9-15.

Subclass Constructors

Subclass constructors can call superclass constructors explicitly to pass arguments to the superclass constructor. The subclass constructor must specify these arguments in the call to the superclass constructor and must use the constructor output argument to form the call. Here is the syntax:

```
classdef MyClass < SuperClass
   methods
    function obj = MyClass(a,b,c,d)
       obj@SuperClass(a,b);
    ...
end</pre>
```

```
end
end
```

The subclass constructor must make all calls to superclass constructors before any other references to the object (obj). This restriction includes assigning property values or calling ordinary class methods. Also, a subclass constructor can call a superclass constructor only once.

Reference Only Specified Superclasses

If the classdef does not specify the class as a superclass, the constructor cannot call a superclass constructor with this syntax. That is, subclass constructor can call only direct superclass constructors listed in the classdef line.

```
classdef MyClass < SuperClass1 & SuperClass2</pre>
```

MATLAB calls any uncalled constructors in the left-to-right order in which they are specified in the classdef line. MATLAB passes no arguments with these calls.

No Conditional Calls to Superclass Constructors

Calls to superclass constructors must be unconditional. There can be only one call for a given superclass. Initialize the superclass portion of the object by calling the superclass constructors before using the object (for example, to assign property values or call class methods).

To call a superclass constructor with different arguments that depend on some condition, build a cell array of arguments and provide one call to the constructor.

For example, the Cube class constructor calls the superclass Shape constructor using default values when the Cube constructor is called with no arguments. If the Cube constructor is called with four input arguments, then pass upvector and viewangle to the superclass constructor:

```
classdef Cube < Shape</pre>
   properties
      SideLength = 0
      Color = [0 \ 0 \ 0]
   end
   methods
      function cubeObj = Cube(length,color,upvector,viewangle)
         % Assemble superclass constructor arguments
         if nargin == 0
            super_args{1} = [0 \ 0 \ 1];
            super_args{2} = 10;
         elseif nargin == 4
            super args{1} = upvector;
            super_args{2} = viewangle;
         else
            error('Wrong number of input arguments')
         end
         % Call superclass constructor
         cubeObj@Shape(super_args{:});
         % Assign property values if provided
         if nargin > 0
            cubeObj.SideLength = length;
```

```
cubeObj.Color = color;
end
end
end
end
end
```

Zero or More Superclass Arguments

To support a syntax that calls the superclass constructor with no arguments, provide this syntax explicitly.

Suppose in the case of the Cube class example, all property values in the Shape superclass and the Cube subclass have default values specified in the class definitions. Then you can create an instance of Cube without specifying any arguments for the superclass or subclass constructors.

Here is how you can implement this behavior in the Cube constructor:

```
methods
```

```
function cubeObj = Cube(length,color,upvector,viewangle)
      % Assemble superclass constructor arguments
      if nargin == 0
         super_args = {};
      elseif nargin == 4
         super_args{1} = upvector;
         super_args{2} = viewangle;
      else
         error('Wrong number of input arguments')
      end
      % Call superclass constructor
      cubeObj@Shape(super args{:});
      % Assign property values if provided
      if nargin > 0
         cubeObj.SideLength = length;
         cubeObj.Color = color;
      end
   end
end
```

More on Subclasses

See "Design Subclass Constructors" on page 12-7 for information on creating subclasses.

Implicit Call to Inherited Constructor

MATLAB passes arguments implicitly from a default subclass constructor to the superclass constructor. This behavior eliminates the need to implement a constructor method for a subclass only to pass arguments to the superclass constructor.

For example, the following class constructor requires one input argument (a datetime object), which the constructor assigns to the CurrentDate property.

```
classdef BaseClassWithConstr
  properties
        CurrentDate datetime
  end
  methods
      function obj = BaseClassWithConstr(dt)
        obj.CurrentDate = dt;
  end
  end
end
```

Suppose that you create a subclass of BaseClassWithConstr, but your subclass does not require an explicit constructor method.

```
classdef SubclassDefaultConstr < BaseClassWithConstr
    ...
end</pre>
```

You can construct an object of the SubclassDefaultConstr by calling its default constructor with the superclass argument:

```
obj = SubclassDefaultConstr(datetime);
```

For information on subclass constructors, see "Subclass Constructors" on page 9-19 and "Default Constructor" on page 9-17.

Errors During Class Construction

For handle classes, MATLAB calls the delete method when an error occurs under the following conditions:

- A reference to the object is present in the code prior to the error.
- An early return statement is present in the code before the error.

MATLAB calls the delete method on the object, the delete methods for any objects contained in properties, and the delete methods for any initialized base classes.

Depending on when the error occurs, MATLAB can call the class destructor before the object is fully constructed. Therefore class delete methods must be able to operate on partially constructed objects that might not have values for all properties. For more information, see "Support Destruction of Partially Constructed Objects" on page 7-15.

For information on how objects are destroyed, see "Handle Class Destructor" on page 7-13.

Output Object Suppressed

You can suppress the assignment of the class instance to the ans variable when no output variable is assigned in a call to the constructor. This technique is useful for apps that creates graphical interface windows that hold onto the constructed objects. These apps do not need to return the object.

Use nargout to determine if the constructor has been called with an output argument. For example, the class constructor for the MyApp class clears the object variable, obj, if called with no output assigned:

```
classdef MyApp
  methods
```

When a class constructor does not return an object, MATLAB does not trigger the matlab.metadata.Class InstanceCreated event.

See Also

Related Examples

- "Simplifying the Interface with a Constructor" on page 3-16
- "Subclass Constructor Implementation" on page 12-8

Static Methods

```
In this section...

"What Are Static Methods" on page 9-24

"Why Define Static Methods" on page 9-24

"Defining Static Methods" on page 9-24

"Calling Static Methods" on page 9-24

"Inheriting Static Methods" on page 9-25
```

What Are Static Methods

Static methods are associated with a class, but not with specific instances of that class. These methods do not require an object of the class as an input argument. Therefore, you can call static methods without creating an object of the class.

Why Define Static Methods

Static methods are useful when you do not want to create an instance of the class before executing some code. For example, suppose you want to set up the MATLAB environment or use the static method to calculate data required to create class instances.

Suppose that a class needs a value for pi calculated to particular tolerances. The class could define its own version of the built-in pi function for use within the class. This approach maintains the encapsulation of the class's internal workings, but does not require an instance of the class to return a value.

Defining Static Methods

To define a method as static, set the methods block Static attribute to true. For example:

```
classdef MyClass
  methods(Static)
    function p = pi(tol)
        [n d] = rat(pi,tol);
        p = n/d;
    end
end
end
```

Calling Static Methods

Invoke static methods using the name of the class followed by dot (.), then the name of the method:

```
classname.staticMethodName(args,...)
```

Calling the pi method of MyClass in the previous section would require this statement:

```
value = MyClass.pi(.001);
```

You can also invoke static methods using an instance of the class, like any method:

```
obj = MyClass;
value = obj.pi(.001);
```

Inheriting Static Methods

Subclasses can redefine static methods unless the method's Sealed attribute is also set to true in the superclass.

See Also

Related Examples

• "Implementing the AccountManager Class" on page 3-11

Overload Functions in Class Definitions

In this section...

"Why Overload Functions" on page 9-26

"Implementing Overloaded MATLAB Functions" on page 9-26

"Rules for Naming to Avoid Conflicts" on page 9-28

Why Overload Functions

Classes can redefine MATLAB functions by implementing methods having the same name. Overloading is useful when defining specialized types that you want to behave like existing MATLAB types. For example, you can implement relational operations, plotting functions, and other commonly used MATLAB functions to work with objects of your class.

You can also modify default behaviors by implementing specific functions that control these behaviors. For more information on functions that modify default behaviors, see "Methods That Modify Default Behavior" on page 17-2.

Implementing Overloaded MATLAB Functions

Class methods can provide implementations of MATLAB functions that operate only on instances of the class. This restriction is possible because MATLAB can always identify to which class an object belongs.

MATLAB uses the dominant argument to determine which version of a function to call. If the dominant argument is an object, then MATLAB calls the method defined by the object's class, if one exists.

In cases where a class defines a method with the same name as a global function, the class's implementation of the function is said to *overload* the original global implementation.

To overload a MATLAB function:

- Define a method with the same name as the function you want to overload.
- Ensure that the method argument list accepts an object of the class, which MATLAB uses to determine which version to call.
- Perform the necessary steps in the method to implement the function. For example, access the object properties to manipulate data.

Generally, the method that overloads a function produces results similar to the MATLAB function. However, there are no requirements regarding how you implement the overloading method. The overloading method does not need to match the signature of the overloaded function.

Note MATLAB does not support defining multiple methods with the same name but different signatures in the same class.

Overload the bar Function

It is convenient to overload commonly used functions to work with objects of your class. For example, suppose that a class defines a property that stores data that you often graph. The MyData class overrides the bar function and adds a title to the graph:

```
classdef MyData
   properties
      Data
   end
   methods
      function obj = MyData(d)
         if nargin > 0
            obj.Data = d;
         end
      end
      function bar(obj)
         y = obj.Data;
         bar(y, 'EdgeColor', 'r');
         title('My Data Graph')
      end
   end
end
```

The MyData bar method has the same name as the MATLAB bar function. However, the MyData bar method requires a MyData object as input. Because the method is specialized for MyData objects, it can extract the data from the Data property and create a specialized graph.

To use the bar method, create an object:

```
y = rand(1,10);
md = MyData(y);

Call the method using the object:
bar(md)

You can also use dot notation:
md.bar
```

Implementing MATLAB Operators

Classes designed to implement new MATLAB data types typically define certain operators, such as addition, subtraction, or equality.

For example, standard MATLAB addition (+) cannot add two polynomials because this operation is not defined by simple addition. However, a polynomial class can define its own plus method that the MATLAB language calls to perform addition of polynomial objects when you use the + symbol:

```
p1 + p2
```

For information on overloading operators, see "Operator Overloading" on page 17-19.

Rules for Naming to Avoid Conflicts

The names of methods, properties, and events are scoped to the class. Therefore, adhere to the following rules to avoid naming conflicts:

- You can reuse names that you have used in unrelated classes.
- You can reuse names in subclasses if the member does not have public or protected access. These
 names then refer to entirely different methods, properties, and events without affecting the
 superclass definitions
- Within a class, all names exist in the same name space and must be unique. A class cannot define
 two methods with the same name and a class cannot define a local function with the same name as
 a method.
- The name of a static method is considered without its class prefix. Thus, a static method name without its class prefix cannot match the name of any other method.

See Also

Related Examples

• "Class Support for Array-Creation Functions" on page 9-29

Class Support for Array-Creation Functions

#Extend Array-Creation Functions for Your Class" on page 9-29 "Which Syntax to Use" on page 9-30 "Implement Support for Array-Creation Functions" on page 9-31

Extend Array-Creation Functions for Your Class

There are several MATLAB functions that create arrays of a specific size and type, such as ones and zeros. You can overload many of these functions to work specifically with your classes. That process is described in this topic. For options for creating object arrays without overloading existing functions, see "Create and Initialize Object Arrays" on page 10-2.

Note createArray supports array creation for many classes without the need for overloading. For more information, see createArray. For information about cases when overloading createArray might be useful, see createArray Methods to Implement.

Class support for any of the array-creation functions enables you to develop code that you can share with built-in and user-defined data types. For example, the class of the variable x in the following code can be a built-in type during initial development, and then be replaced by a user-defined class that transparently overloads zeros:

```
cls = class(x);
zArray = zeros(m,n,cls);
```

Array-creation functions create arrays of a specific type in two ways:

- Class name syntax Specify class name that determines the type of array elements.
- Prototype object syntax Provide a prototype object that the function uses to determine the type and other characteristics of the array elements.

For example:

```
zArray = zeros(2,3,'uint8');
p = uint8([1 3 5; 2 4 6]);
zArray = zeros(2,3,'like',p);
```

After adding support for these functions to a class named MyClass, you can use a similar syntax with that class:

```
zArray = zeros(2,3,'MyClass');
Or pass an object of your class:
p = MyClass(...);
zArray = zeros(size(p),'like',p);
```

MATLAB uses these arguments to dispatch to the appropriate method in your class.

Array-Creation Functions That Support Overloading

These functions support this kind of overloading:

Array-Creation Functions
ones
zeros
eye
NaN
Inf
true
false
cast
rand
randn
randi
createArray

Scalar Functions That Support Overloading

These functions also support similar overloading, with the exception that the output is always a scalar (or a 1-by-1 sparse matrix):

```
Scalar Functions

eps
realmax
realmin
intmax
intmin
flintmax
```

For these functions, you do not need to specify the size when creating scalars of a specific type. For example:

```
d = eps('single');
p = single([1 3 5; 2 4 6]);
d = eps('like',p);
```

After adding support for these functions to a user-defined class, you can use similar syntax with that class as well.

Which Syntax to Use

Classes can support both the class name and the prototype object syntax. To create an array of default objects, use the class name syntax. To create an array of objects with the same type, complexity, and other properties as an existing object, use the prototype syntax.

Implement Support for Array-Creation Functions

Use two separate methods to support an array-creation function. One method implements the class name syntax and the other implements the prototype object syntax.

For example, to support the zeros function:

• Implement the class name syntax:

```
zeros(...,'ClassName')
As a Static method:
methods (Static)
  function z = zeros(varargin)
    ...
  end
end
```

• Implement the prototype object syntax:

```
zeros(...,'like',obj)
As a Hidden method with the char vector 'Like' appended to the name.
methods (Hidden)
   function z = zerosLike(obj,varargin)
        ...
   end
end
```

How MATLAB Interprets the Function Call

The special support for array-creation functions results from the interpretation of the syntax.

• A call to the zeros function of this form:

```
zeros(...,'ClassName')
Calls the class static method with this syntax:
ClassName.zeros(varargin{1:end-1})
• A call to the zeros function of this form:
zeros(...,'like',obj)
Calls the class method with this syntax:
zerosLike(obj,varargin{1:end-2})
```

Class Name Method Called If Prototype Method Does Not Exist

If your class implements a class name syntax, but does not implement a prototype object syntax for a particular function, you can still call both syntaxes. For example, if you implement a static zeros method only, you can call:

```
zeros(...,'like',MyClass(...))
```

In the case in which you call the prototype object syntax, MATLAB first searches for a method named zerosLike. If MATLAB cannot find this method, it calls for the zeros static method.

This feature is useful if you only need the class name to create the array. You do not need to implement both methods to support the complete array-creation function syntax. When you implement only the class name syntax, a call to a prototype object syntax is the same as the call to the class name syntax.

Support All Function Inputs

The input arguments to an array-creation function can include the dimensions of the array the function returns and possibly other arguments. In general, there are three cases that your methods must support:

• No dimension input arguments resulting in the return of a scalar. For example:

```
z = zeros('MyClass');
```

• One or more dimensions equal to or less than zero, resulting in an empty array. For example:

```
z = zeros(2,0,'MyClass');
```

Any number of valid array dimensions specifying the size of the array. For example:

```
z = zeros(2,3,5, 'MyClass');
```

When the array-creation function calls your class method, it passes the input arguments, excluding the class name or the literal 'like' and the object variable to your method. You can implement your methods with these signatures:

- zeros(varargin) for "class name" methods
- zeros(obj, varargin) for "like prototype object" methods

Sample Class

The Color class represents a color in a specific color space, such as, RGB, HSV, and so on. The discussions in "Class Name Method Implementations" on page 9-33 and "Prototype Object Method Implementation" on page 9-34 use this class as a basis for the overloaded method implementations.

```
classdef Color
  properties
      ColorValues = [0,0,0]
      ColorSpace = 'RGB'
  end
  methods
     function obj = Color(cSpace,values)
      if nargin > 0
          obj.ColorSpace = cSpace;
          obj.ColorValues = values;
      end
  end
  end
end
```

Class Name Method Implementations

The zeros function strips the final *ClassName* char vector and uses it to form the call to the static method in the Color class. The arguments passed to the static method are the array dimension arguments.

Here is an implementation of a zeros method for the Color class. This implementation:

- Defines the zeros method as Static (required)
- Returns a scalar Color object if the call to zeros has no dimension arguments
- Returns an empty array if the call to zeros has any dimensions arguments equal to 0.
- Returns an array of default Color objects. Use repmat to create an array of the dimensions specified by the call to zeros.

```
classdef Color
   methods (Static)
      function z = zeros(varargin)
         if (nargin == 0)
         % For zeros('Color')
             z = Color;
         elseif any([varargin{:}] <= 0)</pre>
         % For zeros with any dimension <= 0</pre>
            z = Color.empty(varargin{:});
         else
         % For zeros(m,n,...,'Color')
         % Use property default values
            z = repmat(Color, varargin{:});
         end
      end
   end
end
```

The zeros method uses default values for the ColorValues property because these values are appropriate for this application. An implementation of a ones method can set the ColorValues property to [1,1,1], for example.

Suppose that you want to overload the randi function to achieve the following objectives:

- Define each ColorValue property as a 1-by-3 array in the range of 1 to a specified maximum value (for example, 1-255).
- · Accommodate scalar, empty, and multidimensional array sizes.
- Return an array of Color objects of the specified dimensions, each with random ColorValues.

```
classdef Color
...
methods (Static)
function r = randi(varargin)
if (nargin == 0)
% For randi('ClassName')
r = Color('RGB', randi(255,[1,3]));
elseif any([varargin{2:end}] <= 0)
% For randi with any dimension <= 0
r = Color.empty(varargin{2:end});
else</pre>
```

```
% For randi(max,m,n,...,'ClassName')
if numel([varargin{:}]) < 2
        error('Not enough input arguments')
end
    dims = [varargin{2:end}];
    r = zeros(dims,'Color');
    for k = 1:prod(dims)
        r(k) = Color('RGB',randi(varargin{1},[1,3]));
    end
end
end
end
end
end</pre>
```

Prototype Object Method Implementation

The objective of a method that returns an array of objects that are "like a prototype object" depends on the requirements of the class. For the Color class, the zerosLike method creates objects that have the ColorSpace property value of the prototype object, but the ColorValues are all zero.

Here is an implementation of a zerosLike method for the Color class. This implementation:

- Defines the zerosLike method as Hidden
- Returns a scalar Color object if the call to the zeros function has no dimension arguments
- Returns an empty array if the call to the zeros function has any dimension arguments that are negative or equal to 0.
- Returns an array of Color objects of the dimensions specified by the call to the zeros function.

```
classdef Color
   methods (Hidden)
      function z = zerosLike(obj,varargin)
         if nargin == 1
            % For zeros('like',obj)
            cSpace = obj.ColorSpace;
            z = Color;
            z.ColorSpace = cSpace;
         elseif any([varargin{:}] <= 0)</pre>
            % For zeros with any dimension <= 0
            z = Color.empty(varargin{:});
            % For zeros(m,n,...,'like',obj)
            if ~isscalar(obj)
               error('Prototype object must be scalar')
            obj = Color(obj.ColorSpace,zeros(1,3,'like',obj.ColorValues));
            z = repmat(obj,varargin{:});
         end
      end
   end
end
```

Full Class Listing

Here is the Color class definition with the overloaded methods.

Note In actual practice, the Color class requires error checking, color space conversions, and so on. This overly simplified version illustrates the implementation of the overloaded methods.

```
classdef Color
   properties
      ColorValues = [0,0,0]
      ColorSpace = 'RGB'
   end
   methods
      function obj = Color(cSpace,values)
         if nargin > 0
            obj.ColorSpace = cSpace;
            obj.ColorValues = values;
         end
      end
   end
   methods (Static)
      function z = zeros(varargin)
         if (nargin == 0)
            % For zeros('ClassName')
            z = Color;
         elseif any([varargin{:}] <= 0)</pre>
            % For zeros with any dimension <= 0
            z = Color.empty(varargin{:});
         else
            % For zeros(m,n,...,'ClassName')
            % Use property default values
            z = repmat(Color, varargin{:});
         end
      end
      function r = randi(varargin)
         if (nargin == 0)
            % For randi('ClassName')
            r = Color('RGB', randi(255, [1,3]));
         elseif any([varargin{2:end}] <= 0)</pre>
            % For randi with any dimension <= 0
            r = Color.empty(varargin{2:end});
         else
            % For randi(max,m,n,...,'ClassName')
            if numel([varargin{:}]) < 2</pre>
               error('Not enough input arguments')
            dims = [varargin{2:end}];
            r = zeros(dims, 'Color');
            for k = 1:prod(dims)
               r(k) = Color('RGB', randi(varargin{1},[1,3]));
            end
         end
      end
   end
   methods (Hidden)
      function z = zerosLike(obj,varargin)
         if nargin == 1
            % For zeros('like',obj)
            cSpace = obj.ColorSpace;
            z = Color;
            z.ColorSpace = cSpace;
         elseif any([varargin{:}] <= 0)</pre>
            \% For zeros with any dimension <= 0
            z = Color.empty(varargin{:});
         else
            % For zeros(m,n,...,'like',obj)
            if ~isscalar(obj)
               error('Prototype object must be scalar')
            obj = Color(obj.ColorSpace,zeros(1,3,'like',obj.ColorValues));
            z = repmat(obj,varargin{:});
         end
      end
   end
end
```

Overloading createArray

createArray supports most classes without the need for overloading. However, if your class meets
one or more of these conditions, implement the static createArray method:

- · Your class does not have a default constructor.
- Your class has a default constructor that returns an empty array.
- Your class has properties that need to be dynamically initialized for each instance in the array.

Implement the createArrayLike method if your class does not support creating an array from an existing object through indexed assignment. However, most classes do not need to overload createArrayLike because createArray usually supports the preservation of property values.

The process of overloading the createArray function is similar to zeros, but the syntaxes are slightly different because of the FillValue name-value arguments for createArray.

createArray Methods to Implement

Method	Function Signature	When the Method Is Called
static createArray	<pre>function obj = createArray(dims,F), where dims is a row vector of two or more nonnegative integers, and F is the FillValue (optional)</pre>	<pre>createArray(dims, "ClassName") createArray(dims, "ClassName", FillValue=F)</pre>
createArrayLik e	<pre>function obj = createArrayLike(L, dims,F), where dims is a row vector of two or more nonnegative integers, L is the prototype and F is the FillValue (optional)</pre>	<pre>createArrayLike(dims,Like=L) createArrayLike(dims,Like=L,FillValue=F)</pre>

See Also

Related Examples

• "Create and Initialize Object Arrays" on page 10-2

Class Methods for Graphics Callbacks

In this section...

"Referencing the Method" on page 9-37

"Syntax for Method Callbacks" on page 9-37

"Use a Class Method for a Slider Callback" on page 9-38

Referencing the Method

To use an ordinary class method as callback for a graphics object, specify the callback property as a function handle referencing the method. For example,

```
uicontrol('Style','slider','Callback',@obj.sliderCallback)
```

Where your class defines a method called sliderCallback and obj is an instance of your class.

To use a static method as a callback, specify the callback property as a function handle that includes the class name that is required to refer to a static method:

```
uicontrol('Style','slider','Callback',@MyClass.sliderCallback)
```

Syntax for Method Callbacks

For ordinary methods, use dot notation to pass an instance of the class defining the callback as the first argument:

@obj.methodName

Define the callback method with the following input arguments:

- An instance of the defining class as the first argument
- The event source handle
- The event data

The function signature would be of this form:

```
function methodName(obj,src,eventData)
    ...
end
```

For static methods, the required class name ensures MATLAB dispatches to the method of the specified class:

```
@MyClass.methodName
```

Define the static callback method with two input arguments — the event source handle and the event data

The function signature would be of this form:

```
function methodName(src,eventData)
```

Passing Extra Arguments

If you want to pass arguments to your callback in addition to the source and event data arguments passed by MATLAB, you can use an anonymous function. The basic syntax for an anonymous function that you assign to the graphic object's Callback property includes the object as the first argument:

```
@(src,event)callbackMethod(object,src,eventData,arg1,...argn)
The function signature would be of this form:
function methodName(obj,src,eventData,varargin)
...
end
```

Use a Class Method for a Slider Callback

This example shows how to use a method of your class as a callback for an uicontrol slider.

The SeaLevelSlider class creates a slider that varies the color limits of an indexed image to give the illusion of varying the sea level.

Class Definition

Define SeaLevelSlider as a handle class with the following members:

- The class properties store figure and axes handles and the calculated color limits.
- The class constructor creates the graphics objects and assigns the slider callback.
- The callback function for the slider accepts the three required arguments a class instance, the handle of the event source, and the event data. The event data argument is empty and not used.
- The uicontrol callback uses dot notation to reference the callback method: . . . 'Callback', @obj.sliderCallback.

```
classdef SeaLevelSlider < handle</pre>
   properties
      Figure
      Axes
      CLimit
   end
   methods
      function obj = SeaLevelSlider(x,map)
         obj.Figure = figure('Colormap',map,...
             'Position',[100,100,560,580],...
             'Resize', 'off');
         obj.Axes = axes('DataAspectRatio',[1,1,1],...
             'XLimMode', 'manual', 'YLimMode', 'manual',...
             'Parent', obj. Figure);
         image(x,'CDataMapping','scaled',...
             'Parent', obj.Axes);
         obj.CLimit = get(obj.Axes, 'CLim');
         uicontrol('Style','slider',...
             'Parent',obj.Figure,...
             'Max',obj.CLimit(2)-10,...
             'Min', obj.CLimit(1)-1,...
             'Value', obj.CLimit(1),...
```

```
'Units','normalized',...
'Position',[0.9286,0.1724,0.0357,0.6897],...
'SliderStep',[0.003,0.005],...
'Callback',@obj.sliderCallback);
end

function sliderCallback(obj,src,~)
    minVal = get(src,'Value');
    maxVal = obj.CLimit(2);
    obj.Axes.CLim = [minVal maxVal];
end
end
end
```

Using the SeaLevelAdjuster Class


The class uses the cape image that is included with the MATLAB product. To obtain the image data, use the load command:

```
load cape X map
```

After loading the data, create a SeaLevelSlider object for the image:

```
slaObj = SeaLevelSlider(X,map);
```

Move the slider to change the color mapping and visualize a rise in sea level.



See Also

More About

• "Listener Callback Syntax" on page 11-24

Object Arrays

- "Create and Initialize Object Arrays" on page 10-2
- "Accessing Properties and Methods in Object Arrays" on page 10-7
- "Implicit Class Conversion" on page 10-10
- "Concatenating Objects of Different Classes" on page 10-14
- "Designing Heterogeneous Class Hierarchies" on page 10-19
- "Heterogeneous Array Constructors" on page 10-26

Create and Initialize Object Arrays

```
"Create an Object Array Using a Loop" on page 10-2

"Create an Object Array Using createArray" on page 10-3

"Create an Object Array by Constructing the Last Element" on page 10-5

"Create an Object Array in the Constructor" on page 10-6
```

MATLAB provides different ways of creating object arrays. These different methods vary in how the objects in the array are created. Choose a method of array creation based on your end goal:

- "Create an Object Array Using a Loop" on page 10-2 Use a for-loop to create arrays when you
 need to initialize objects with different values.
- "Create an Object Array Using createArray (since R2024a)" on page 10-3 Use createArray to create an array of objects with the same initial values.
- "Create an Object Array by Constructing the Last Element" on page 10-5 Use when you want to construct only one element of an array. MATLAB fills the rest of the array with copies of the default object of the class of the last element.

Create an Object Array Using a Loop

Define the class SimpleValue, which has one property with a default value and a constructor that can be called with no arguments.

```
classdef SimpleValue
  properties
    prop1 = 0
  end
  methods
    function obj = SimpleValue(v)
        if nargin > 0
            obj.prop1 = v;
        end
        end
    end
end
end
```

Create an array of SimpleValue objects using a loop. Set the value of prop1 of each element of the array to a different value.

```
initValues = [3 -1 0 4 5];
for k = 1:5
  objArray(k) = SimpleValue(initValues(k));
end
```

Verify that the values of prop1 are set to initValues.

```
p = [objArray.prop1]
p =
3   -1   0   4   5
```

For more information on accessing properties and methods of an object array, see "Accessing Properties and Methods in Object Arrays" on page 10-7.

Create an Object Array Using createArray

You can also use createArray to generate object arrays of your class. createArray enables you to specify the size of the array, as well as combinations of class, prototype, and fill value to generate arrays of objects. For the full descriptions of syntaxes and options, see createArray.

classname Argument

Use the class name argument to specify the class of the array:

```
X = createArray(dims,"classname")
```

Create a 1-by-5 array of the SimpleValue class from "Create an Object Array Using a Loop" on page 10-2. MATLAB calls the constructor once with no arguments and populates the array with copies of that instance.

```
X = createArray(1,5,"SimpleValue")
X =
   1×5 SimpleValue array with properties:
   prop1
```

The value of prop1 in all elements of the array is the default value defined by the class.

```
[X.prop1]
ans =
0 0 0 0 0
```

Like Argument

Use the Like name-value argument to create an object array with an existing instance or array as a prototype:

```
X = createArray(dims,Like=prototype)
```

Create an instance phi of SimpleValue with 1.618 assigned to prop1. Use Like with phi to create a 2-by-2 object array of the class. The returned array L has the same class as phi.

```
phi = SimpleValue(1.618);
L = createArray(2,2,Like=phi)
L =
   2×2 SimpleValue array with properties:
    prop1
```

createArray used with Like does not preserve the property value of phi because it does not use copies of the prototype to fill the array. The elements in L are copies of one call to the default constructor of the class of the prototype, so they have the default value for prop1.

```
[L.prop1]
ans =
0 0 0 0
```

FillValue Argument

To create an array with objects other than the default, create an instance using input arguments to the constructor and then use that as a fill value for createArray:

```
X = createArray(dims,FillValue=instance)
```

Create an instance of SimpleValue with 7 assigned to prop1, and use that instance with the FillValue name-value argument to create a 3-by-1 array.

```
s = SimpleValue(7);
F = createArray(3,1,FillValue=s)
F =
  3×1 SimpleValue array with properties:
    prop1
```

Unlike in the case of specifying classname, createArray does not call the class constructor when you specify a fill value. The fill value is copied to each element of the array. Verify that the value of prop1 of each instance is 7.

```
[F.prop1]
ans =
7 7 7
```

Handle Classes

The previous sections focused on value classes. For handle classes, createArray creates unique handles for each element of the array. For example, define a handle class with a constructor that generates a random number for a class property.

```
classdef InitHandleArray < handle
    properties
        Num
    end
    methods
        function obj = InitHandleArray(varargin)
            if nargin == 1
                obj.Num = randi(varargin{1});
            else
                obj.Num = -4;
            end
        end
    end
end</pre>
```

Use createArray to return a 2-by-2 array of the default InitHandleArray object.

```
Y = createArray(2,2,"InitHandleArray")
```

```
Y =
  2×2 InitHandleArray array with properties:
    Num
```

Although the handles are unique, MATLAB calls the constructor only once and populates the array with copies of that instance. Verify that the no-argument constructor was called by checking the values of property Num.

```
[Y.Num]
ans =
-4 -4 -4 -4
```

Create an Object Array by Constructing the Last Element

In the SimpleValue example in "Create an Object Array Using a Loop" on page 10-2, the objects in objArray are created inside a loop. You can also create an array of SimpleValue objects by constructing the last element of the array.

For example, create a 2-by-2 array of SimpleValue objects by constructing the last element in the array.

```
a(2,2) = SimpleValue
a =
  2×2 SimpleValue array with properties:
    prop1
```

Value Class Arrays

After you construct the last element in an array of value class objects, MATLAB:

- Calls the no-argument constructor
- Fills in the rest of the elements with copies of that instance

Create a 1-by-5 array of SimpleValue by constructing b(5) with input argument 7.

```
b(5) = SimpleValue(7);
```

Return all of the prop1 values and assign them to a vector y. The object in b(5) has a prop1 value of 7. MATLAB calls the no-argument constructor once and copies that value to all the remaining elements in the array. Those elements have the default prop1 value of 0.

```
y = [b.prop1]
y =
0     0     0     7
```

If the SimpleValue constructor cannot handle no-argument calls, MATLAB errors when trying to populate b(1) through b(4).

Handle Class Arrays

After you construct the last element in an array of handle class objects, MATLAB:

- Creates unique handles for each element of the array
- Calls the no-argument constructor
- Fills in the rest of the elements with copies of that instance

Create a new 1-by-5 array of the InitHandleArray class (see "Handle Classes" on page 10-4) by constructing c(5) with an input argument of 3, and verify the Num values. MATLAB calls the constructor again and assigns copies of the result of that call to c(1) through c(4).

```
c(5) = InitHandleArray(3);
z = [c.Num]
z =
```

Create an Object Array in the Constructor

You can also use the class constructor itself to create and return an object array. For example, the ObjectArray class creates an object array that is the same size and shape as the input array F. The constructor then initializes the Value property of each object to the corresponding input array value.

```
classdef ObjectArray
   properties
      Value
   end
   methods
      function obj = ObjectArray(F)
         if nargin ~= 0
            n = numel(F);
            p(n) = obi;
            for i = 1:n
               p(i) = F(i);
            obj = reshape(p,size(F));
         end
      end
   end
end
```

This pattern for the constructor works for both value and handle objects as long as the no-argument option is included.

See Also

Related Examples

- "Accessing Properties and Methods in Object Arrays" on page 10-7
- "Class Constructor Methods" on page 9-15

Accessing Properties and Methods in Object Arrays

You can access properties and invoke methods of object arrays as a whole or work with individual elements of the array. The examples in this topic use a modified version of BasicClass from "Creating a Simple Class" on page 2-2:

```
classdef BasicClass
  properties
    prop1 {mustBeNumeric} = 0
  end
  methods
    function r = roundOff(obj)
        r = round([obj.prop1],2);
  end
    function r = multiplyBy(obj,n)
        r = [obj.prop1]*n;
  end
  end
end
```

Create a BasicClass object array with a loop. The loop assigns the value of i to prop1 of each array element a(i). For more information, see "Create and Initialize Object Arrays" on page 10-2.

```
for i = 1:4
a(i) = BasicClass;
a(i).prop1 = i;
end
```

Reference Properties in an Object Array

You can retrieve all values of the same property in an object array using dot notation. This command returns a comma-separated list of all the property values.

To collect the comma-separated list in a vector and assign it to a variable, enclose the object array expression in brackets.

```
prop1Values = [a.prop1]
prop1Values =
    1    2    3    4
```

Note Dynamic properties are defined per object and are therefore not properties of the class. Because of this distinction, even if every element of the array defines the same dynamic property, MATLAB returns an error if you try to access the dynamic properties of an entire array in a single statement. Index into each object individually to access dynamic property values. For information about classes that can define dynamic properties, see "Dynamic Properties — Adding Properties to an Instance" on page 8-48.

You can reference the property values of individual elements in an object array using standard MATLAB indexing syntax. For example, return the value of prop1 for the object a(2).

```
a(2).prop1
ans =
```

You can also return a subset of prop1 values from the object array.

```
proplpartialValues = [a(2:3).prop1]
proplpartialValues =
2  3
```

Assigning Values to Properties in an Object Array

You cannot assign new values to prop1 of all elements in an object array with a simple assignment statement, but you can use a loop to assign values to all properties in one step. Assign new values to prop1 of all four elements in the array and verify the results.

```
newValues = [1.4142 1.6180 2.7183 3.1415];
for i = 1:4
a(i).prop1 = newValues(i);
end
propValues = [a.prop1]
propValues =
    1.4142    1.6180    2.7183    3.1415
```

Assign property values of individual array elements using standard indexing syntax. For example, assign a new value to a(2).prop1 and verify the result.

```
a(2).prop1 = 1.7321;
a(2).prop1
ans =
```

Invoking Methods on an Object Array

When you pass an object array to a method, MATLAB invokes the method on the entire array. Call the roundOff method of BasicClass on the object array a from the previous section.

```
roundOff(a)
ans =
1.4100 1.7300 2.7200 3.1400
```

Class methods must be designed to handle the size and shape of the object arrays you need to create. In BasicClass, the roundOff and multiplyBy methods are designed to handle arrays of any size by enclosing the property references in square brackets.

```
r = round([obj.prop1],2);
r = [obj.prop1]*n;
```

A method that only works on scalar instances errors if passed a nonscalar array. For more information, see "Vectorize Methods" on page 2-4.

You can also use standard function notation to invoke a method for one element of the object array. For example, call the roundOff method on a(3).

```
roundOff(a(3))
ans =
    2.7200
```

Use a similar syntax for a method that takes one or more input arguments.

See Also

Related Examples

- "Creating a Simple Class" on page 2-2
- "Property Syntax" on page 8-4
- "Method Invocation" on page 9-11

Implicit Class Conversion

In this section...

"Concatenation" on page 10-10

"Subscripted Assignment" on page 10-10

"Property Validation" on page 10-11

"Function and Method Argument Validation" on page 10-12

MATLAB can implicitly convert classes in these situations:

- Creation or modification of object arrays using concatenation
- Creation or modification of object arrays using subscripted assignment
- Property validation
- Argument validation in function and method calls

To perform the conversion, MATLAB attempts to use a converter method, the constructor of the destination class, or the cast function, depending on the context of the conversion.

Concatenation

In concatenation operations, the dominant object determines the class of the resulting array. MATLAB determines the dominant object according to these rules:

- User-defined classes are dominant over built-in classes such as double.
- If there is no defined dominance relationship between any two classes, then the leftmost object in the concatenation statement is dominant. For more information on class dominance, see "Method Invocation" on page 9-11.

For example, A is an instance of ClassA, and B is an instance of ClassB. In the statement C = [A,B], if A is the dominant object, MATLAB attempts to convert B to the class of A.

MATLAB first tries to call a converter method. If no converter method is found, it calls the constructor for ClassA. The concatenation statement is equivalent to:

```
C = [A,ClassA(B)]
```

If the call to the ClassA constructor fails to convert B to ClassA, MATLAB issues an error. If the conversion succeeds, MATLAB concatenates A with the converted B.

Subscripted Assignment

In subscripted assignment, the left side of the assignment statement defines the class of the array. If you assign array elements when the right side is a different class than the left side, MATLAB attempts to convert the right side to the class of the left side.

For example, assigning an object of ClassB to an element of array A requires conversion.

```
A = ClassA:
B = ClassB;
A(2) = B;
```

MATLAB attempts to perform the conversion by first looking for a converter method. If no converter method is found, it calls the ClassA constructor. The assignment is then equivalent to:

```
A(2) = ClassA(B)
```

If calling the constructor fails, MATLAB calls cast:

```
A(2) = cast(B, "like", A)
```

If the conversion still fails after these steps, MATLAB issues an error. If the conversion succeeds, MATLAB assigns the converted value to A(2).

Property Validation

When you assign a value to a property that specifies a class restriction as part of its validation, MATLAB uses the built-in function <code>isa</code> to check the relationship between the value and the class. If the value is not the specified class or one of its subclasses, MATLAB attempts to convert the value to the specified class.

To demonstrate the conversion process, refer to these class definitions.

```
classdef ClassA
   properties
    Prop ClassB
   end
end

classdef ClassB
end

classdef SubClassB < ClassB
end

classdef ClassC
end</pre>
```

This script shows when MATLAB attempts conversions during property assignments.

```
A = ClassA;
B = ClassB;
SB = SubClassB;
C = ClassC;

A.Prop = B; % no conversion
A.Prop = SB; % no conversion
A.Prop = C; % conversion required
```

In this script:

- A.Prop = B does not require conversion because B belongs to ClassB, which satisfies the property validation for Prop defined in ClassA.
- A.Prop = SB does not require conversion because SB belongs to SubClassB, which is a subclass of ClassB.
- A.Prop = C requires conversion because C does not belong to ClassB or its subclass SubClassB.

MATLAB attempts to convert C to ClassB or its subclass SubClassB by first calling ClassB(C). This call can invoke a converter method called ClassB (defined by ClassC) or the ClassB constructor. If calling ClassB(C) does not yield an instance of ClassB or SubClassB, MATLAB attempts to cast the result of ClassB(C) to ClassB as a final step.

If these steps fail to convert C to ClassB or SubClassB, MATLAB issues an error. If the conversion succeeds, MATLAB writes the converted value to A.Prop.

Note Property class validation does not support implicit conversion of any built-in types to cell arrays, even if you provide your own conversion method.

Function and Method Argument Validation

When you assign a value to a function or method argument that specifies a class restriction as part of its validation, MATLAB uses the built-in function isa to check the relationship between the value and the class. If the value is not the specified class or one of its subclasses, MATLAB attempts to convert the value to the specified class.

To demonstrate the conversion process, refer to these class and function definitions.

```
classdef ClassA
end

classdef SubClassA < ClassA
end

classdef ClassB
end

function test(x)
    arguments
    x ClassA
    end
end</pre>
```

This script shows when MATLAB attempts conversions during argument validation.

```
A = ClassA;
SA = SubClassA;
B = ClassB;

test(A); % no conversion
test(SA); % no conversion
test(B); % conversion required
```

In this script:

- test(A) does not require conversion because A belongs to ClassA, which satisfies the argument validation for x defined in test.
- test(SA) does not require conversion because SA belongs to SubClassA, which is a subclass of ClassA.
- test(B) requires conversion because B does not belong to ClassA or its subclass SubClassA.

MATLAB attempts to convert B to ClassA or its subclass SubClassA by first calling ClassA(B). This call can invoke a converter method called ClassA (defined by ClassB) or the ClassA

constructor. If calling ClassA(B) does not yield an instance of ClassA or SubClassA, MATLAB attempts to cast the result of ClassA(B) to ClassA as a final step.

If these steps fail to convert B to ClassA or SubClassA, MATLAB issues an error. If the conversion succeeds, MATLAB uses the converted value for the function call.

Note Argument validation does not support implicit conversion of any built-in types to cell arrays, even if you provide your own conversion method.

See Also

Related Examples

- "Valid Combinations of Unlike Classes"
- "Concatenating Objects of Different Classes" on page 10-14
- "Object Converters" on page 17-5
- "Function Argument Validation"

Concatenating Objects of Different Classes

In this section...

"Basic Knowledge" on page 10-14

"MATLAB Concatenation Rules" on page 10-14

"Concatenating Objects" on page 10-14

"Calling the Dominant-Class Constructor" on page 10-15

"Converter Methods" on page 10-16

Basic Knowledge

The material presented in this section builds on an understanding of the information presented in the following sections.

- "Create and Initialize Object Arrays" on page 10-2
- "Valid Combinations of Unlike Classes"

MATLAB Concatenation Rules

MATLAB follows these rules for concatenating objects:

- MATLAB always attempts to convert all objects to the dominant class.
- User-defined classes take precedence over built-in classes like double.
- If there is no defined dominance relationship between any two objects, then the leftmost object dominates (see "Class Precedence" on page 6-18).

When converting to a dominant class during concatenation or subscripted assignment, MATLAB searches the non-dominant class for a conversion method that is the same name as the dominant class. If such a conversion method exists, MATLAB calls it. If a conversion method does not exist, MATLAB calls the dominant class constructor on the non-dominant object.

It is possible for the dominant class to define horzcat, vertcat, or cat methods that modify the default concatenation process.

Note MATLAB does not convert objects to a common superclass unless those objects are part of a heterogeneous hierarchy. For more information, see "Designing Heterogeneous Class Hierarchies" on page 10-19.

Concatenating Objects

Concatenation combines objects into arrays. For example:

```
ary = [obj1,obj2,obj3];
```

The size of ary is 1-by-3.

The class of the arrays is the same as the class of the objects being concatenated. Concatenating objects of different classes is possible if MATLAB can convert objects to the dominant class. MATLAB attempts to convert unlike objects by:

- Calling the inferior object converter method, if one exists.
- Passing an inferior object to the dominant class constructor to create an object of the dominant class.

If conversion of the inferior object is successful, MATLAB returns an array that is of the dominant class. If conversion is not possible, MATLAB returns an error.

Calling the Dominant-Class Constructor

MATLAB calls the dominant class constructor to convert an object of an inferior class to the dominant class. MATLAB passes the inferior object to the constructor as an argument. If the class design enables the dominant class constructor to accept objects of inferior classes as input arguments, then concatenation is possible without implementing a separate converter method.

If the constructor simply assigns this argument to a property, the result is an object of the dominant class with an object of an inferior class stored in a property. If this assignment is not a desired result, then ensure that class constructors include adequate error checking.

For example, consider the class ColorClass and two subclasses, RGBColor and HSVColor:

```
classdef ColorClass
   properties
        Color
   end
end
```

The class RGBColor inherits the Color property from ColorClass. RGBColor stores a color value defined as a three-element vector of red, green, and blue (RGB) values. The constructor does not restrict the value of the input argument. It assigns this value directly to the Color property.

```
classdef RGBColor < ColorClass
  methods
    function obj = RGBColor(rgb)
    if nargin > 0
        obj.Color = rgb;
    end
    end
end
end
```

The class HSVColor also inherits the Color property from ColorClass. HSVColor stores a color value defined as a three-element vector of hue, saturation, brightness value (HSV) values.

```
classdef HSVColor < ColorClass
   methods
    function obj = HSVColor(hsv)
        if nargin > 0
            obj.Color = hsv;
        end
    end
end
end
```

Create an instance of each class and concatenate them into an array. The RGBColor object is dominant because it is the leftmost object and neither class defines a dominance relationship:

```
crgb = RGBColor([1 0 0]);
chsv = HSVColor([0 1 1]);
ary = [crgb,chsv];
class(ary)
ans =
RGBColor
```

You can combine these objects into an array because MATLAB can pass the inferior object of class HSVColor to the constructor of the dominant class. However, notice that the Color property of the second RGBColor object in the array actually contains an HSVColor object, not an RGB color specification:

```
ary(2).Color
ans =
  HSVColor with properties:
    Color: [0 1 1]
```

Avoid this undesirable behavior by:

- Implementing converter methods
- Performing argument checking in class constructors before assigning values to properties

Converter Methods

If your class design requires object conversion, implement converter methods for this purpose.

The ColorClass class defines converter methods for RGBColor and HSVColor objects:

```
classdef ColorClass
   properties
      Color
   end
   methods
      function rgb0bj = RGBColor(obj)
         if isa(obj,'HSVColor')
            rgb0bj = RGBColor(hsv2rgb(obj.Color));
         end
      end
      function hsv0bj = HSVColor(obj)
         if isa(obj,'RGBColor')
            hsv0bj = HSVColor(rgb2hsv(obj.Color));
         end
      end
   end
end
```

Create an array of RGBColor and HSVColor objects with the revised superclass:

```
crgb = RGBColor([1 0 0]);
chsv = HSVColor([0 1 1]);
```

```
ary = [crgb,chsv];
class(ary)
ans =
RGBColor
```

MATLAB calls the converter method for the HSVColor object, which it inherits from the superclass. The second array element is now an RGBColor object with an RGB color specification assigned to the Color property:

```
ary(2)
ans =
   RGBColor with properties:
        Color: [1 0 0]
ary(2).Color
ans =
        1 0 0
```

If the leftmost object is of class HSVColor, the array ary is also of class HSVColor, and MATLAB converts the Color property data to HSV color specification.

Defining a converter method in the superclass and adding better argument checking in the subclass constructors produces more predictable results. Here is the RGBColor class constructor with argument checking:

```
classdef RGBColor < ColorClass
  methods
  function obj = RGBColor(rgb)
  if nargin == 0
    rgb = [0 0 0];
  else
    if ~(isa(rgb,'double')...
        && size(rgb,2) == 3 ...
        && max(rgb) <= 1 && min(rgb) >= 0)
        error('Specify color as RGB values')
    end
end
```

```
obj.Color = rgb;
      end
   end
end
```

Your applications can require additional error checking and other coding techniques. The classes in these examples are designed only to demonstrate concepts.

See Also

More About

- "Implicit Class Conversion" on page 10-10
- "Object Converters" on page 17-5
- "Hierarchies of Classes Concepts" on page 12-2

Designing Heterogeneous Class Hierarchies

In this section...

"Creating Classes That Support Heterogeneous Arrays" on page 10-19

"MATLAB Arrays" on page 10-19

"Heterogeneous Hierarchies" on page 10-19

"Heterogeneous Arrays" on page 10-20

"Heterogeneous Array Concepts" on page 10-20

"Nature of Heterogeneous Arrays" on page 10-21

"Unsupported Hierarchies" on page 10-23

"Default Object" on page 10-24

"Conversion During Assignment and Concatenation" on page 10-25

"Empty Arrays of Heterogeneous Abstract Classes" on page 10-25

Creating Classes That Support Heterogeneous Arrays

This topic describes the concepts involved in defining classes that support the formation of heterogeneous arrays. For information on the concatenation of existing MATLAB objects, see these topics.

- "Concatenating Objects of Different Classes" on page 10-14
- "Valid Combinations of Unlike Classes"

For an example that uses heterogeneous arrays, see "A Class Hierarchy for Heterogeneous Arrays" on page 20-2.

MATLAB Arrays

MATLAB determines the class of an array by the class of the objects contained in the array. MATLAB is unlike some languages in which you define an array of object pointers or references. In these other languages, the type of the array is different from the type of an object in the array. You can access the elements of the array and dispatch to methods on those elements, but you cannot call an object method on the whole array, as you can in MATLAB.

Object arrays in MATLAB are homogeneous in class. Because of this homogeneity, you can perform operations on whole arrays, such as multiplying numeric matrices. You can form heterogeneous arrays by defining a hierarchy of classes that derive from a common superclass. Cell arrays provide option for an array type that can hold different kinds of unrelated objects.


Heterogeneous Hierarchies

You can form arrays of objects that are subclasses of a common superclass when these classes are part of a heterogeneous hierarchy. A MATLAB heterogeneous class hierarchy:

• Derives from matlab.mixin.Heterogeneous

- Defines a single root superclass that derives directly from matlab.mixin.Heterogeneous
- Seals methods that are inherited by subclasses.

For example, in the following diagram, Shape is the root of the heterogeneous hierarchy.



Heterogeneous Arrays

A heterogeneous array is an array of objects that differ in their specific class, but all objects derive from or are instances of a common superclass. The common superclass forms the root of the hierarchy of classes that you can combine into heterogeneous arrays.

The common superclass must derive from matlab.mixin.Heterogeneous. Methods that you can call on the array as a whole must have the same definitions for all subclasses.

Heterogeneous hierarchies are useful to:

- Create arrays of objects that are of different classes, but part of a related hierarchy.
- Call methods of the most specific common superclass on the array as a whole
- Access properties of the most specific common superclass using dot notation with the array
- Use common operators that are supported for object arrays
- Support array indexing (scalar or nonscalar) that returns arrays of the most specific class


Heterogeneous Array Concepts

- Heterogeneous array An array in which two or more elements belong to different specific classes. All elements derive from the same root superclass.
- Root superclass Class derived directly from matlab.mixin.Heterogeneous. The root superclass can be abstract or concrete. Only concrete subclasses of the root superclass can form heterogeneous arrays.
- Most specific common superclass The most specific class in the inheritance hierarchy from
 which all the objects in a heterogeneous array derive. The most specific common superclass can
 be the root superclass or a more specific superclass shared by the objects currently in the array.
- Class of a heterogeneous array The most specific common superclass from which all objects in the heterogeneous array derive. Adding and removing objects from a heterogeneous array can change the most specific superclass shared by the instances. This change results in a change in the class of a heterogeneous array. The most specific common superclass can be abstract.

Nature of Heterogeneous Arrays

The heterogeneous hierarchy in this diagram illustrates the characteristics of heterogeneous arrays concerning:

- Array class
- Property access
- Method invocation



Class of Heterogeneous Arrays

The class of a heterogeneous array is that of the most specific superclass shared by the objects of the array.

If the following conditions are true, the concatenation and subscripted assignment operations return a heterogeneous array:

- The objects on the right side of the assignment statement are of different classes
- All objects on the right side of the assignment statement derive from a common subclass of matlab.mixin.Heterogeneous

For example, form an array by concatenating objects of these classes. The class of al is ClassA:

```
a1 = [SpecificA, SpecificB];
class(a1)
```

```
ans =
ClassA
```

If the array includes an object of the class SpecificC, the class of a2 is RootSuperclass:

```
a2 = [SpecificA,SpecificB,SpecificC];
class(a2)
ans =
```

RootSuperclass

If you assigned an object of the class SpecificC to array all using indexing, the class of all becomes RootSuperclass:

```
a1(3) = SpecificC;
class(a1)
ans =
RootSuperclass
```

If the array contains objects of only one class, then the array is not heterogeneous. For example, the class of a is SpecificA.

```
a = [SpecificA, SpecificA];
class(a)
ans =
SpecificA
```

Property Access

Access array properties with dot notation when the class of the array defines the properties. The class of the array is the most specific common superclass, which ensures all objects inherit the same properties.

For example, suppose ClassA defines a property called Prop1.

```
a1 = [SpecificA, SpecificB];
al.Prop1
```

Referring to Prop1 using dot notation returns the value of Prop1 for each object in the array.

Invoking Methods

To invoke a method on a heterogeneous array, the class of the array must define or inherit the method as Sealed. For example, suppose RootSuperclass defines a Sealed method called superMethod.

Call the method on all objects in the array a2:


```
a2 = [SpecificA,SpecificB,SpecificC];
a2.superMethod
```

Sealing the method (so that it cannot be overridden in a subclass) ensures that the same method definition exists for all elements of the array. Calling that method on a single element of the array invokes the same method implementation as calling the method on the whole array.

Unsupported Hierarchies


Heterogeneous hierarchies cannot have ambiguities when obtaining default objects, determining the class of the array, and converting class objects to other types. Members of the hierarchy can derive from only one root superclass (that is, from only one direct subclass of matlab.mixin.Heterogeneous).

This diagram shows a hierarchy that is not allowed:



ClassA derives from two classes that are subclasses of matlab.mixin.Heterogeneous.

The next diagram shows two separate heterogeneous hierarchies. ClassA has only one root superclass (called OtherBaseClass). The heterogeneous hierarchy is no longer ambiguous:



Default Object

A default object is the object returned by calling the class constructor with no arguments. MATLAB uses default objects in these situations:

• Indexed assignment creates an array with gaps in array elements. For example, assign the first element of array h to index 5:

```
h(5) = ClassA(arg1, arg2);
```

MATLAB fills the unassigned positions with default objects.

 Loading a heterogeneous array from a MAT-file when the class definition of a specific object in the array is not available. MATLAB replaces the object with the default object.

Heterogeneous hierarchies enable you to define the default object for that hierarchy. The matlab.mixin.Heterogeneous class provides a default implementation of a method called getDefaultScalarElement. This method returns an instance of the root class of the heterogeneous hierarchy, unless the root superclass is abstract.

If the root superclass is abstract or is not appropriate for a default object, override the getDefaultScalarElement method. Implement the getDefaultScalarElement override in the root superclass, which derives directly from matlab.mixin.Heterogeneous.

getDefaultScalarElement must return a scalar object that is derived from the root superclass.
For specific information on how to implement this method, see
matlab.mixin.Heterogeneous.getDefaultScalarElement.

Conversion During Assignment and Concatenation

If you create a heterogeneous array that contains objects that are not derived from the same root superclass, MATLAB attempts to call a method called convertObject. Implement convertObject to convert objects to the appropriate class. There is no default implementation of this method.

To support the formation of heterogeneous arrays using objects that are not part of the heterogeneous hierarchy, implement a convertObject method in the root superclass. The convertObject method must convert the nonmember object to a valid member of the heterogeneous hierarchy.

For details on implementing the convertObject method, see matlab.mixin.Heterogeneous.

Empty Arrays of Heterogeneous Abstract Classes

For homogeneous arrays, MATLAB does not allow you to initialize an empty array of an abstract class. However, if the class is part of a heterogeneous hierarchy, you can initialize empty arrays of an abstract class. Initializing an empty heterogeneous array is useful in cases in which you do not know the class of the concrete elements in advance.

For example, suppose RootSuperclass is an abstract class that is the root of a heterogeneous hierarchy. Initialize an array using the empty static method:

ary = RootSuperclass.empty;

See Also

Related Examples

- "A Class Hierarchy for Heterogeneous Arrays" on page 20-2
- "Handle-Compatible Classes and Heterogeneous Arrays" on page 12-38

Heterogeneous Array Constructors

In this section...

"Building Arrays in Superclass Constructors" on page 10-26

"When Errors Can Occur" on page 10-26

"Initialize Array in Superclass Constructor" on page 10-26

"Sample Implementation" on page 10-27

"Potential Error" on page 10-29

Building Arrays in Superclass Constructors

When a subclass in a heterogeneous class hierarchy calls its superclass to construct an array of objects, you must ensure that the superclass constructor does not return a heterogeneous array to the subclass. The following programming patterns show how to avoid the errors caused by returning the wrong class to the subclass constructor.

When Errors Can Occur

Constructors must return objects that are the same class as the defining class. When working with objects from a heterogeneous class hierarchy, the class of an object array can change as you add array elements of different classes. As a result, heterogeneous superclass constructors can change the class of object arrays when the class design requires all of these techniques:

- Building object arrays in subclass constructors
- Calling superclass constructors from subclass constructors to pass arguments
- Creating object arrays in the superclass constructor

In addition, either of the following is true:

- The root superclass is not abstract and does not implement a matlab.mixin.Heterogeneous.getDefaultScalarElement method.
- The root superclass implements a getDefaultScalarElement method that returns an object that is not the same class as the subclass.

When assigning to object arrays, MATLAB uses the default object to fill in unassigned array elements. In a heterogeneous hierarchy, the default object can be the superclass that is called by the subclass constructor. Therefore, building an array in the superclass constructor can create a heterogeneous array.

If a superclass constructor returns a heterogeneous array to the subclass constructor, MATLAB generates an error (see "Potential Error" on page 10-29).

Initialize Array in Superclass Constructor

To avoid errors, initialize the object array explicitly in the superclass constructor. For example, use repelem in the superclass constructor to initialize the array before initializing the superclass part of the objects. Initializing the array ensures that all elements assigned into the array are of the same class as the obj argument.

In this code, the superclass constructor creates one object for each element in the input argument, arg:

```
methods
  function obj = SuperClass(arg)
    ...
    n = numel(arg);
    obj = repelem(obj,1,n);
    for k = 1:n
        obj(k).SuperProp = arg(k);
    end
    ...
end
end
```

The subclass constructor calls the superclass constructor to pass the required argument array, a:


```
methods
  function obj = SubClass(a)
   obj = obj@SuperClass(a);
  for k = 1:numel(a)
    obj(k).SubProp = a(k);
  end
  end
end
```

Sample Implementation

The following class hierarchy defines a subclass that builds object arrays in its constructor. The root superclass of the hierarchy initializes the superclass part of the objects in the array.

This class hierarchy represents members of an engineering team. The classes in the hierarchy include:

- TeamMembers Superclass for specific team member classes, like ProjectEngineer.
 TeamMembers defines the Name and PhoneX properties and derives from matlab.mixin.Heterogeneous.
- ProjectEngineer Team members that are engineers. Each instance inherits a Name and PhoneX property and defines a billing Rate property.
- Other members Other types of team members not implemented for this example for simplicity.



The TeamMembers class is the root of the heterogeneous hierarchy and is a concrete class. Before assigning values to the Name and PhoneX properties, the constructor initializes an array of subclass (ProjectEngineer) objects.

The ProjectEngineer constructor provides the obj argument for the call to repelem with this statement:

```
obj = obj@TeamMembers(varargin{1:2});
```

Here is the TeamMembers class:

```
classdef TeamMembers < matlab.mixin.Heterogeneous</pre>
   properties
      Name
      PhoneX
   end
   methods
      function obj = TeamMembers(nme,ext)
         if nargin > 0
            n = numel(nme);
            obj = repelem(obj,1,n);
             for k = 1:n
                obj(k).Name = nme{k};
                obj(k).PhoneX = ext(k);
            end
         else
            obj.Name = '';
         end
      end
   end
end
```

The ProjectEngineer class represents one type of team member. This class supports array inputs and returns an array of objects.

```
classdef ProjectEngineer < TeamMembers
% Inputs: {Name}, [PhoneX], {Rate}
properties
   Rate
end
methods
   function obj = ProjectEngineer(varargin)
      obj = obj@TeamMembers(varargin{1:2});
   for k = 1:numel(varargin{1})
      obj(k).Rate = varargin{3}{k};
   end
end
end</pre>
```

The ProjectEngineer class requires a cell array of names, a numeric array of phone extensions, and a cell array of billing rates for each engineer in the team.

```
nm = {'Fred','Nancy','Claudette'};
px = [8112,8113,8114];
rt = {'C2','B1','A2'};
tm = ProjectEngineer(nm,px,rt)

tm =
    1x3 ProjectEngineer array with properties:
    Rate
    Name
    PhoneX
```

Potential Error

The TeamMembers constructor initializes the object array with this statement:

```
obj = repelem(obj,1,n);
```

Because the obj argument to repelem is a ProjectEngineer object, the array returned is of the same class.

Without this statement, the TeamMembers constructor would create default objects to fill in array elements in the for loop. The resulting heterogeneous array would be of the class of the common superclass (TeamMembers in this case). If the superclass returns this heterogeneous array to the subclass constructor, it is a violation of the rule that class constructors must preserve the class of the returned object.

MATLAB issues this error:

See Also

More About

"Designing Heterogeneous Class Hierarchies" on page 10-19

Events — Sending and Responding to Messages

- "Overview Events and Listeners" on page 11-2
- "Define Custom Event Data" on page 11-5
- "Observe Changes to Property Values" on page 11-8
- "Implement Property Set Listener" on page 11-10
- "Event and Listener Concepts" on page 11-12
- "Event Attributes" on page 11-16
- "Events and Listeners Syntax" on page 11-18
- "Listener Lifecycle" on page 11-23
- "Listener Callback Syntax" on page 11-24
- "Callback Execution" on page 11-27
- "Determine If Event Has Listeners" on page 11-29
- "Listen for Changes to Property Values" on page 11-32
- "Assignment When Property Value Is Unchanged" on page 11-35
- "Techniques for Using Events and Listeners" on page 11-40

Overview Events and Listeners

In this section...

"Why Use Events and Listeners" on page 11-2

"Events and Listeners Basics" on page 11-2

"Event Syntax" on page 11-2

"Create Listener" on page 11-3

Why Use Events and Listeners

Events are notices that objects broadcast in response to something that happens, such as a property value changing or a user interaction with an application program. Listeners execute functions when notified that the event of interest occurs. Use events to communicate changes to objects. Listeners respond by executing the callback function.

For more information, see "Event and Listener Concepts" on page 11-12.

Events and Listeners Basics

When using events and listeners:

- Only handle classes can define events and listeners.
- Define event names in the events block of a class definition ("Events and Listeners Syntax" on page 11-18).
- Use event attributes to specify access to the event ("Event Attributes" on page 11-16).
- Call the handle notify method to trigger the event. The event notification broadcasts the named event to all listeners registered for this event.
- Use the handle addlistener method to couple a listener to the event source object. MATLAB destroys the listener when the source of the event is destroyed.
- Use the handle listener method to create listeners that are not coupled to the lifecycle of the event source object. This approach is useful when the event source and the listeners are defined in different components that you want to be able to add, remove, or modify independently. Your application code controls the listener object lifecycle.
- Listener callback functions must define at least two input arguments the event source object handle and the event data (See "Listener Callback Syntax" on page 11-24 for more information).
- Modify the data passed to each listener callback by subclassing the event. EventData class.

Predefined Events

MATLAB defines events for listening to property sets and queries. For more information, see "Listen for Changes to Property Values" on page 11-32.

All handle objects define an event named ObjectBeingDestroyed. MATLAB triggers this event before calling the class destructor.

Event Syntax

Define an event name in the events code block:

```
classdef ClassName < handle
   events
      FventName
   end
end
For example, MyClass defines an event named StateChange:
classdef MyClass < handle</pre>
   events
      StateChange
   end
end
Trigger an event using the handle class notify method:
classdef ClassName < handle
   events
      EventName
   end
   methods
      function anyMethod(obj)
         notify(obj,'EventName');
      end
   end
end
```

Any function or method can trigger the event for a specific instance of the class defining the event. For example, the triggerEvent method calls notify to trigger the StateChange event:

```
classdef MyClass < handle
    events
        StateChange
    end
    methods
        function triggerEvent(obj)
            notify(obj,'StateChange')
    end
    end
end</pre>
```

Trigger the StateChange event with the triggerEvent method:

```
obj = MyClass;
obj.triggerEvent
```

For more information, see "Events and Listeners Syntax" on page 11-18.

Create Listener

Define a listener using the handle class addlistener or listener method. Pass a function handle for the listener callback function using one of these syntaxes:

- addlistener(SourceOfEvent, 'EventName', @functionName) for an ordinary function.
- addlistener(SourceOfEvent, 'EventName',@Obj.methodName) for a method of Obj.

• addlistener(SourceOfEvent, 'EventName', @ClassName.methodName) — for a static method of the class ClassName.

```
ListenerObject = addlistener(SourceOfEvent, 'EventName',@listenerCallback);
```

addlistener returns the listener object. The input arguments are:

- SourceOfEvent An object of the class that defines the event. The event is triggered on this object.
- EventName The name of the event defined in the class events code block.
- @listenerCallback a function handle referencing the function that executes in response to the event.

For example, create a listener object for the StateChange event:

```
function lh = createListener(src)
   lh = addlistener(src, 'StateChange',@handleStateChange)
end
```

Define the callback function for the listener. The callback function must accept as the first two arguments the event source object and an event data object: Use the event source argument to access the object that triggered the event. Find information about the event using the event data object.

```
function handleStateChange(src,eventData)
   % src - handle to object that triggered the event
   % eventData - event.EventData object containing
                 information about the event.
end
```

For more information, see "Listener Callback Syntax" on page 11-24.

See Also

event.EventData | handle

Related Examples

- "Listener Lifecycle" on page 11-23
- "Implement Property Set Listener" on page 11-10

Define Custom Event Data

```
In this section...

"Class Event Data Requirements" on page 11-5

"Define and Trigger Event" on page 11-5

"Define Event Data" on page 11-6

"Create Listener for Overflow Event" on page 11-6
```

Class Event Data Requirements

Suppose that you want to create a listener callback function that has access to specific information when the event occurs. This example shows how by creating custom event data.

Events provide information to listener callback functions by passing an event data argument to the specified function. By default, MATLAB passes an event. EventData object to the listener callback. This object has two properties:

- EventName Name of the event triggered by this object.
- Source Handle of the object triggering the event.

Provide additional information to the listener callback by subclassing the event. EventData class.

- Define properties in the subclass to contain the additional data.
- Define a constructor that accepts the additional data as arguments.
- Set the ConstructOnLoad class attribute.
- Use the subclass constructor as an argument to the notify method to trigger the event.

Define and Trigger Event

The SimpleEventClass defines a property set method (see "Property Get and Set Methods" on page 8-39) from which it triggers an event if the property is set to a value exceeding a certain limit. The property set method performs these operations:

- Saves the original property value
- Sets the property to the specified value
- If the specified value is greater than 10, the set method triggers an Overflow event
- Passes the original property value, and other event data, in a SpecialEventDataClass object to the notify method.

```
classdef SimpleEventClass < handle
  properties
     Prop1 = 0
  end
  events
     Overflow
  end
  methods
     function set.Prop1(obj,value)
          orgvalue = obj.Prop1;</pre>
```

```
obj.Prop1 = value;
         if (obj.Prop1 > 10)
            % Trigger the event using custom event data
            notify(obj,'Overflow',SpecialEventDataClass(orgvalue));
         end
      end
   end
end
```

Define Event Data

Event data is always contained in an event. EventData object. The SpecialEventDataClass adds the original property value to the event data by subclassing event. EventData:

```
classdef (ConstructOnLoad) SpecialEventDataClass < event.EventData</pre>
   properties
      OrgValue = 0
   end
   methods
      function eventData = SpecialEventDataClass(value)
         eventData.OrgValue = value;
      end
   end
end
```

Create Listener for Overflow Event

To listen for the Overflow event, attach a listener to an instance of the SimpleEventClass class. Use the addlistener method to create the listener. Also, you must define a callback function for the listener to execute when the event is triggered.

The function setupSEC instantiates the SimpleEventClass class and adds a listener to the object. In this example, the listener callback function displays information that is contained in the eventData argument (which is a SpecialEventDataClass object).

```
function sec = setupSEC
   sec = SimpleEventClass;
   addlistener(sec, 'Overflow',@overflowHandler)
   function overflowHandler(eventSrc,eventData)
      disp('The value of Prop1 is overflowing!')
      disp(['Its value was: ' num2str(eventData.OrgValue)])
      disp(['Its current value is: ' num2str(eventSrc.Prop1)])
   end
end
Create the SimpleEventClass object and add the listener:
sec = setupSEC;
sec.Prop1 = 5;
sec.Prop1 = 15; % listener triggers callback
The value of Prop1 is overflowing!
Its value was: 5
Its current value is: 15
```

See Also

Related Examples

• "Observe Changes to Property Values" on page 11-8

Observe Changes to Property Values

This example shows how to listen for changes to a property value. This example uses:

- PostSet event predefined by MATLAB
- SetObservable property attribute to enable triggering the property PostSet event.
- addlistener handle class method to create the listener

```
classdef PropLis < handle</pre>
   % Define a property that is SetObservable
   properties (SetObservable)
      ObservedProp = 1
   methods
      function attachListener(obj)
         %Attach a listener to a PropListener object
         addlistener(obj,'ObservedProp','PostSet',@PropLis.propChange);
      end
   end
   methods (Static)
      function propChange(metaProp,eventData)
         % Callback for PostSet event
         % Inputs: matlab.metadata.Property object, event.PropertyEvent
         h = eventData.AffectedObject;
         propName = metaProp.Name;
         disp(['The ',propName,' property has changed.'])
         disp(['The new value is: ',num2str(h.ObservedProp)])
         disp(['Its default value is: ',num2str(metaProp.DefaultValue)])
      end
  end
end
```

The PropLis class uses an ordinary method (attachListener) to add the listener for the ObservedProp property. If the PropLis class defines a constructor, the constructor can contain the call to addlistener.

The listener callback is a static method (propChange). MATLAB passes two arguments when calling this function:

- metaProp a matlab.metadata.Property object for ObservedProp
- eventData an event.PropertyEvent object contain event-specific data.

These arguments provide information about the property and the event.

Use the PropLis class by creating an instance and calling its attachListener method:

```
plObj = PropLis;
plObj.ObservedProp
ans =
     1
plObj.attachListener
pl0bj.0bservedProp = 2;
```

```
The ObservedProp property has changed. The new value is: 2
Its default value is: 1
```

See Also

event.proplistener|addlistener|listener

Related Examples

- "Listener Lifecycle" on page 11-23
- "Implement Property Set Listener" on page 11-10

Implement Property Set Listener

This example shows how to define a listener for a property set event. The listener callback triggers when the value of a specific property changes. The class defined for this example uses a method for a push-button callback and a static method for the listener callback. When the push-button callback changes the value of a property, the listener executes its callback on the PreSet event.

This example defines a class (PushButton) with these design elements:

- ResultNumber Observable property
- uicontrol pushbutton Push-button object used to generate a new graph when its callback executes
- A listener that responds to a change in the observable property

PushButton Class Design

The PushButton class creates figure, uicontrol, axes graphics objects, and a listener object in the class constructor.


The push button's callback is a class method (named pressed). When the push button is activated, the following sequence occurs:

- MATLAB executes the pressed method, which graphs a new set of data and increments the ResultNumber property.
- Attempting to set the value of the ResultNumber property triggers the PreSet event, which executes the listener callback before setting the property value.
- The listener callback uses the event data to obtain the handle of the callback object (an instance of the PushButton class), which then provides the handle of the axes object that is stored in its AxHandle property.
- The listener callback updates the axes Title property, after the callback completes execution, MATLAB sets the ResultsNumber property to its new value.

```
classdef PushButton < handle</pre>
   properties (SetObservable)
      ResultNumber = 1
   end
   properties
      AxHandle
   end
   methods
      function buttonObj = PushButton
          myFig = figure;
          buttonObj.AxHandle = axes('Parent', myFig);
          uicontrol('Parent',myFig,...
             'Style', 'pushbutton',...
'String', 'Plot Data',...
             'Callback',@(src,evnt)pressed(buttonObj));
          addlistener(buttonObj,'ResultNumber','PreSet',...
             @PushButton.updateTitle);
      end
   end
   methods
      function pressed(obj)
```

The scatter graph looks similar to this graph after three push-button clicks.

buttonObj = PushButton;



See Also

Related Examples

• "Listen for Changes to Property Values" on page 11-32

Event and Listener Concepts

In this section...

"The Event Model" on page 11-12

"Limitations" on page 11-13

"Default Event Data" on page 11-13

"Events Only in Handle Classes" on page 11-14

"Property-Set and Query Events" on page 11-14

"Listeners" on page 11-15

The Event Model

Events represent changes or actions that occur within objects. For example,


- · Modification of class data
- · Execution of a method
- Querying or setting a property value
- Destruction of an object

Basically, any activity that you can detect programmatically can generate an event and communicate information to other objects.

MATLAB classes define a process that communicates the occurrence of events to other objects that respond to the events. The event model works this way:

- A handle class declares a name used to represent an event. "Name Events" on page 11-18
- After creating an object of the event-declaring class, attach listener to that object. "Control Listener Lifecycle" on page 11-23
- A call to the handle class notify method broadcasts a notice of the event to listeners. The class user determines when to trigger the event. "Trigger Events" on page 11-18
- Listeners execute a callback function when notified that the event has occurred. "Specifying Listener Callbacks" on page 11-24
- You can bind listeners to the lifecycle of the object that defines the event, or limit listeners to the existence and scope of the listener object. "Control Listener Lifecycle" on page 11-23

This diagram illustrates the event model.



Limitations

There are certain limitations to the use of events:

- The event source cannot guarantee that listeners exist when triggering the event.
- A listener cannot prevent other listeners from being notified that the event occurred.
- The order in which listeners execute is not defined.
- Listeners should not modify the event data object passed to the listener callback, because other listeners are passed this same handle object.

Default Event Data

Events provide information to listener callbacks by passing an event data argument to the callback function. By default, MATLAB passes an event. EventData object to the listener callback. This object has two properties:

- EventName The event name as defined in the class event block
- Source The object that is the source of the event

MATLAB passes the source object to the listener callback in the required event data argument. Use the source object to access any of the object's public properties from within your listener callback function.

Customize Event Data

You can create a subclass of the event. EventData class to provide additional information to listener callback functions. The subclass would define properties to contain the additional data and provide a method to construct the derived event data object so it can be passed to the notify method.

"Define Event-Specific Data" on page 11-21 provides an example showing how to customize this

Events Only in Handle Classes

You can define events only in handle classes. This restriction exists because a value class is visible only in a single MATLAB workspace so no callback or listener can have access to the object that triggered the event. The callback could have access to a copy of the object. However, accessing a copy is not useful because the callback cannot access the current state of the object that triggered the event or effect any changes in that object.

"Comparison of Handle and Value Classes" on page 7-2 provides general information on handle classes.

"Events and Listeners Syntax" on page 11-18 shows the syntax for defining a handle class and events.

Property-Set and Query Events

There are four predefined events related to properties:

- PreSet Triggered just before the property value is set, before calling its set access method
- PostSet Triggered just after the property value is set
- PreGet Triggered just before a property value guery is serviced, before calling its get access method
- PostGet Triggered just after returning the property value to the query

These events are predefined and do not need to be listed in the class events block.

When a property event occurs, the callback is passed an event. PropertyEvent object. This object has three properties:

- EventName The name of the event described by this data object
- Source The source object whose class defines the event described by the data object
- AffectedObject The object whose property is the source for this event (that is, AffectedObject contains the object whose property was either accessed or modified).

You can define your own property-change event data by subclassing the event. EventData class. The event.PropertyEvent class is a sealed subclass of event.EventData.

See "Listen for Changes to Property Values" on page 11-32 for a description of the process for creating property listeners.

See "The PostSet Event Listener" on page 11-48 for an example.

See "Property Get and Set Methods" on page 8-39 for information on methods that control access to property values.

Listeners

Listeners encapsulate the response to an event. Listener objects belong to the event.listener class, which is a handle class that defines the following properties:

- Source Handle or array of handles of the object that generated the event
- EventName Name of the event
- Callback Function to execute when an enabled listener receives event notification
- Enabled Callback function executes only when Enabled is true. See "Enable and Disable Listeners" on page 11-50 for an example.
- Recursive Allow listener to trigger the same event that caused execution of the callback.

Recursive is false by default. If the callback triggers the event for which it is defined as the callback, the listener cannot execute recursively. Therefore, set Recursive to true if the callback must trigger its own event. Setting the Recursive property to true can create a situation where infinite recursion reaches the recursion limit and triggers an error.

"Control Listener Lifecycle" on page 11-23 provides more specific information.

Event Attributes

Specify Event Attributes

The following table lists the attributes you can set for events. To specify a value for an attribute, assign the attribute value on the same line as the event keyword. For example, all the events defined in the following events block have protected ListenAccess and private NotifyAccess.

```
events (ListenAccess = protected, NotifyAccess = private)
   EventName1
   EventName2
end
```

To define other events in the same class definition that have different attribute settings, create another events block.

Event Attributes

Attribute Name	Class	Description
Hidden	logical Default = false	If true, event does not appear in list of events returned by events function (or other event listing functions or viewers).
ListenAccess	 enumeration, default = public matlab.metadata.C lass object cell array of matlab.metadata.C lass objects 	 protected — Access from methods in class or subclasses private — Access by class methods only (not from
NotifyAccess	 enumeration, default = public matlab.metadata.C lass object cell array of matlab.metadata.C lass objects 	protected — Can trigger event from methods in class or derived classes
Framework attributes	Classes that use certain framework base classes have framework-specific attributes. See the documentation for the specific base class you are using for information on these attributes.	

See Also

Related Examples

• "Events and Listeners Syntax" on page 11-18

Events and Listeners Syntax

```
In this section...
"Components to Implement" on page 11-18
"Name Events" on page 11-18
"Trigger Events" on page 11-18
"Listen to Events" on page 11-19
"Define Event-Specific Data" on page 11-21
```

Components to Implement

Implementation of events and listeners involves these components:

- Specification of the name of an event in a handle class "Name Events" on page 11-18.
- A function or method to trigger the event when the action occurs "Trigger Events" on page 11-
- Listener objects to execute callback functions in response to the triggered event "Listen to Events" on page 11-19.
- Default or custom event data that the event passes to the callback functions "Define Event-Specific Data" on page 11-21.

Name Events

Define an event by declaring an event name inside an events block. For example, this class creates an event called ToggleState:

```
classdef ToggleButton < handle</pre>
   properties
      State = false
   events
      ToggleState
   end
end
```

Events cannot have the same name as the class that defines them.

Trigger Events

The OnStateChange method calls notify to trigger the ToggleState event. Pass the handle of the object that is the source of the event and the name of the event to notify.

```
classdef ToggleButton < handle</pre>
   properties
      State = false
   events
      ToggleState
   methods
```

```
function OnStateChange(obj,newState)
    if newState ~= obj.State
        obj.State = newState;
        notify(obj,'ToggleState');
    end
    end
end
end
```

Listen to Events

After the call to notify triggers an event, MATLAB broadcasts a message to all listeners that are defined for that event and source object. There are two ways to create listeners: using the handle class addlistener or listener method.

Use addlistener for Persistent Listeners

If you want the listener to persist beyond the normal variable scope, use addlistener to create it. The event source object holds a reference to the listener object. When the event source object is destroyed, MATLAB destroys the listener.

This code defines a listener for the ToggleState event:

```
lh = addlistener(obj,'ToggleState',@RespondToToggle.handleEvnt);
```

addlistener has these arguments:

- obj The object that is the source of the event
- ToggleState The event name passed as a char vector
- @RespondToToggle.handleEvnt A function handle to the callback function (see the following definition "Define Listener" on page 11-20).

Use handle.listener to Decouple Listener and Source

Use the listener method to create listeners when you want to manage the lifecycle of the listener and do not want a coupling between the event source and listener object. MATLAB does not destroy listeners created with listener when the event source is destroyed. However, your code must keep the listener object handle in scope when creating listeners using listener.

The listener method requires the same arguments as addlistener: the event-naming object, the event name, and a function handle to the callback. listener returns the handle to the listener object.

```
lh = listener(obj, 'EventName',@callbackFunction)
```

For example, this code uses the ToggleState event discussed previously:

```
lh = listener(obj, 'ToggleState',@RespondToToggle.handleEvnt)
```

Callback Function

The listener callback function must accept a minimum of two arguments, which MATLAB automatically passes to the callback. Here are the required arguments:

• The source of the event — that is, obj in the call to addlistener or event.listener.

• An event.EventData object or a subclass of event.EventData, such as the ToggleEventData object described in, "Define Event-Specific Data" on page 11-21.

Define the callback function to accept the source object and event data arguments.

```
function callbackFunction(src,evtdata)
end
```

For more information on callback syntax, see "Listener Callback Syntax" on page 11-24.

Define Listener

The RespondToToggle class defines objects that listen for the ToggleState event defined in the ToggleButton class.

```
classdef RespondToToggle < handle</pre>
  methods
      function obj = RespondToToggle(toggle_button_obj)
         addlistener(toggle_button_obj,'ToggleState',@RespondToToggle.handleEvnt);
   end
  methods (Static)
      function handleEvnt(src,~)
         if src.State
            disp('ToggleState is true')
         else
            disp('ToggleState is false')
         end
     end
   end
end
```

The class RespondToToggle adds the listener in its constructor. In this case, the class defines the callback (handleEvnt) as a static method that accepts the two required arguments:

- src The handle of the object triggering the event (that is, a ToggleButton object)
- evtdata An event. EventData object

For example, this code creates objects of both classes:

```
tb = ToggleButton;
rtt = RespondToToggle(tb);
```

Whenever you call the OnStateChange method of the ToggleButton object, notify triggers the event. For this example, the callback displays the value of the State property:

```
tb.OnStateChange(true)
ToggleState is true
tb.OnStateChange(false)
ToggleState is false
```

Remove Listeners

Remove a listener object by calling delete on its handle. For example, if the class RespondToToggle saved the listener handle as a property, you could delete the listener.

```
classdef RespondToToggle < handle</pre>
   properties
```

```
ListenerHandle % Property for listener handle
   end
   methods
       function obj = RespondToToggle(toggle button obj)
          hl = addlistener(toggle_button_obj,'ToggleState',@RespondToToggle.handleEvnt);
obj.ListenerHandle = hl; % Save listener handle
       end
   end
   methods (Static)
       function handleEvnt(src,~)
          if src.State
             disp('ToggleState is true')
          else
             disp('ToggleState is false')
          end
       end
   end
end
```

With this code change, you can remove the listener from an instance of the RespondToToggle class. For example:

```
tb = ToggleButton;
rtt = RespondToToggle(tb);
```

The object rtt is listening for the ToggleState event triggered by object tb. To remove the listener, call delete on the property containing the listener handle.

```
delete(rtt.ListenerHandle)
```

To deactivate a listener temporarily, see "Temporarily Deactivate Listeners" on page 11-23.

Define Event-Specific Data

Suppose that you want to pass the state of the toggle button as a result of the event to the listener callback. You can add more data to the default event data by subclassing the event. EventData class and adding a property to contain this information. Then you can pass this object to the notify method.

Note To save and load objects that are subclasses of event. EventData, such as ToggleEventData, enable the ConstructOnLoad class attribute for the subclass.

```
classdef (ConstructOnLoad) ToggleEventData < event.EventData
    properties
        NewState
    end

methods
    function data = ToggleEventData(newState)
        data.NewState = newState;
    end
end
end</pre>
```

The call to notify can use the ToggleEventData constructor to create the necessary argument.

```
evtdata = ToggleEventData(newState);
notify(obj,'ToggleState',evtdata);
```

See Also

Related Examples

- "Listener Callback Syntax" on page 11-24
- "Listen for Changes to Property Values" on page 11-32
- "Techniques for Using Events and Listeners" on page 11-40

Listener Lifecycle

In this section...

"Control Listener Lifecycle" on page 11-23

"Temporarily Deactivate Listeners" on page 11-23

"Permanently Delete Listeners" on page 11-23

Control Listener Lifecycle

There are two ways to create listeners:

- addlistener creates a coupling between the listener and event source object. The listener object persists until you delete it or until the event object is destroyed. When the event source object is destroyed, MATLAB automatically destroys the listener object.
- listener constructs listener objects that are not coupled to the lifecycle of the event source
 object. The listener is active as long as the listener object remains in scope and is not explicitly
 deleted. Therefore, your application must maintain a reference to the listener object by storing the
 listener handle. The advantage of uncoupling the listener and event objects is that you can define
 and destroy each independently.

For more information, see "Events and Listeners Syntax" on page 11-18.

Temporarily Deactivate Listeners

The addlistener method returns the listener object so that you can set its properties. For example, you can temporarily disable a listener by setting its Enabled property to false:

ListenerHandle.Enabled = false;

To reenable the listener, set Enabled to true.

ListenerHandle.Enabled = true;

Permanently Delete Listeners

Calling delete on a listener object destroys it and permanently removes the listener:

delete(ListenerHandle)

See Also

Related Examples

• "Enable and Disable Listeners" on page 11-50

Listener Callback Syntax

In this section...

"Specifying Listener Callbacks" on page 11-24

"Input Arguments for Callback Function" on page 11-24

"Additional Arguments for Callback Function" on page 11-25

Specifying Listener Callbacks

Callbacks are functions that execute when the listener receives notification of the event. Pass a function handle referencing the callback function to addlistener or listener when creating the listener.

All callback functions must accept at least two arguments:

- The handle of the object that is the source of the event
- An event.EventData object or an object that is derived from the event.EventData class.

Syntax to Reference Callback

```
For a function: functionName
lh = addlistener(eventSourceObj, 'EventName',@functionName)
For an ordinary method called with an object of the class: obj.methodName
lh = addlistener(eventSourceObj,'EventName',@obj.methodName)
For a static method:ClassName.methodName
lh = addlistener(eventSourceObj,'EventName',@ClassName.methodName)
For a function in a namespace:nspname.functionName
lh = addlistener(eventSourceObj,'EventName',@nspname.functionName)
```

Input Arguments for Callback Function

Define the callback function to accept the required arguments:

```
function callbackFunction(src,evnt)
end
```

If you do not use the event source and event data arguments, you can define the function to ignore these inputs:

```
function callbackFunction(~,~)
end
For a method:
function callbackMethod(obj,src,evnt)
end
```

Additional Arguments for Callback Function

To pass arguments to your callback in addition to the source and event data arguments passed by MATLAB, use an anonymous function. Anonymous functions can use any variables that are available in the current workspace.

Syntax Using Anonymous Function

Here is the syntax for an ordinary method. The input arguments (argl,...argn) must be defined in the context in which you call addlistener.

```
lh = addlistener(src,'EventName',@(src,evnt)obj.callbackMethod(src,evnt,arg1,...argn)
Use varargin to define the callback function.
function callbackMethod(src,evnt,varargin)
   arg1 = varargin{1};
   argn = varargin{n};
end
```

For general information on anonymous function, see "Anonymous Functions".

Using Methods for Callbacks

The TestAnonyFcn class shows the use of an anonymous function with an additional argument. The listener callback displays the inputs arguments to show how MATLAB calls the callback method.

```
classdef TestAnonyFcn < handle</pre>
   events
      Update
   end
   methods
      function obj = TestAnonyFcn
         t = datestr(now);
         addlistener(obj, 'Update',@(src,evnt)obj.evntCb(src,evnt,t));
      end
      function triggerEvnt(obj)
         notify(obj,'Update')
      end
   end
   methods (Access = private)
      function evntCb(~,~,evnt,varargin)
         disp(['Number of inputs: ',num2str(nargin)])
         disp(evnt.EventName)
         disp(varargin{:})
      end
   end
end
```

Create an object and trigger the event by calling the triggerEvt method:

```
obi = TestAnonyFcn;
obj.triggerEvnt;
Number of inputs: 4
Update
01-Jul-2008 17:19:36
```

See Also

Related Examples

- "Callback Execution" on page 11-27
- "Create Function Handle"

Callback Execution

In this section...

"When Callbacks Execute" on page 11-27

"Listener Order of Execution" on page 11-27

"Callbacks That Call notify" on page 11-27

"Manage Callback Errors" on page 11-27

"Invoke Functions from Function Handles" on page 11-27

When Callbacks Execute

Listeners execute their callback function when notified that the event has occurred. Listeners are passive observers in the sense that errors in the execution of a listener callback do not prevent the execution of other listeners responding to the same event, or execution of the function that triggered the event.

Callback function execution continues until the function completes. If an error occurs in a callback function, execution stops and control returns to the calling function. Then any remaining listener callback functions execute.

Listener Order of Execution

The order in which listeners callback functions execute after the firing of an event is undefined. However, all listener callbacks execute synchronously with the event firing.

The handle class notify method calls all listeners before returning execution to the function that called notify.

Callbacks That Call notify

Do not modify and reuse or copy and reuse the event data object that you pass to notify, which is then passed to the listener callback.

Listener callbacks can call notify to trigger events, including the same event that invoked the callback. When a function calls notify, MATLAB sets the property values of the event data object that is passed to callback functions. To ensure that these properties have appropriate values for subsequently called callbacks, always create a new event data object if you call notify with custom event data.

Manage Callback Errors

If you want to control how your program responds to errors, use a try/catch statement in your listener callback function to handle errors.

Invoke Functions from Function Handles

When you create a function handle inside a class method, the context of the method determines the context in which the function executes. This context gives the function access to private and protected methods that are accessible to that class.

For example, the UpdateEvt class defines an event named Update and a listener for that event. The listener callback is the private method evtCb.

```
classdef UpdateEvt < handle</pre>
   events
      Update
   end
   methods
      function obj = UpdateEvt
         addlistener(obj,'Update',@evtCb);
      end
   end
   methods (Access = private)
      function obj = evtCb(obj,varargin)
         disp('Updated Event Triggered')
      end
   end
end
```

Private methods are normally accessible only by class methods. However, because the function handle is created in a class method, notify can execute the callback from outside of the class:

```
a = UpdateEvt;
a.notify('Update')
Updated Event Triggered
```

See Also

Related Examples

"Listener Callback Syntax" on page 11-24

Determine If Event Has Listeners

```
In this section...

"Do Listeners Exist for This Event?" on page 11-29

"Why Test for Listeners" on page 11-29

"Coding Patterns" on page 11-29

"Listeners in Heterogeneous Arrays" on page 11-29
```

Do Listeners Exist for This Event?

Use the event.hasListener function to determine if a specific event has listeners. event.hasListener accepts an array of event source objects and an event name as input arguments. It returns an array of logical values indicating if listeners exist for the specified event on each object in the array.

Note When called, event.hasListener must have NotifyAccess for the event. That is, call event.hasListener in a context in which you can call notify for the event in question.

Why Test for Listeners

Use event.hasListener to avoid sending event notifications when there are no listeners for the event. For example, if creating custom event data consumes significant resources, or if events are triggered repeatedly, use event.hasListener to test for listeners before performing these steps.

Coding Patterns

• Conditionalize the creation of event data and the call to notify using event.hasListener. For an object array a, determine if there are listeners before creating event data and triggering the event:

```
if any(event.hasListener(a,'NameOfEvent'))
    evt = MyCustomEventData(...);
    notify(a,'NameOfEvent',evt)
end
```


• Trigger events selectively using logical indexing with the values returned by event.hasListener. Send event notifications only for array elements that have listeners:

```
ind = event.hasListeners(a,'NameOfEvent');
notify(a(ind),'NameOfEvent',evt)
```

Listeners in Heterogeneous Arrays

If the input object array is heterogeneous, the class of the array must define the specified event. You can query the listeners only for events that all objects in the array define.

For example, in the following diagram, the class of a heterogeneous array formed with objects of classes SpecificA, SpecificB, and SpecificC is RootSuperclass. Therefore, event.hasListener can find listeners only for the RootEvent event, because it is the only event common to all array elements.



Create a heterogeneous array with the three most specific classes:

```
het = [SpecificA, SpecificB, SpecificC];
class(het)
ans
RootSuperclass
events(het)
Events for class RootSuperclass
```

RootEvent

event.hasListener cannot determine if there are listeners for events that are defined by some but not all objects in the array:

```
event.hasListener(het,'ClassAEvent')
Error using event.hasListener
Event 'ClassAEvent' is not defined for class 'RootSuperclass'.
```

Determine if individual objects in the heterogeneous array have listeners defined for their specific events, by indexing into the array:

```
event.hasListener(het(1), 'ClassAEvent')
```

For more information about determining the class of heterogeneous arrays, see "Designing Heterogeneous Class Hierarchies" on page 10-19.

See Also

Related Examples

• "Listener Lifecycle" on page 11-23

Listen for Changes to Property Values

```
In this section...
"Create Property Listeners" on page 11-32
"Property Event and Listener Classes" on page 11-33
```

Create Property Listeners

For handle classes, you can define listeners for the predeclared property events (named: PreSet, PostSet, PreGet, and PostGet). To create listeners for those named events:

- Specify the SetObservable and/or GetObservable property attributes.
- Define callback functions
- Create the property listener by including the name of the property and the event in the call to addlistener or event.proplistener.
- If necessary, subclass event. EventData to create a specialized event data object to pass to the callback function.
- Prevent execution of the callback if the new value is the same as the current value (see "Assignment When Property Value Is Unchanged" on page 11-35).

Set Property Attributes to Enable Property Events

In the properties block, enable the SetObservable attribute. You can define PreSet and PostSet listeners for the properties defined in this block:

```
properties (SetObservable)
   Prop0ne
   PropTwo
end
```

Define Callback Function for Property Event

The listener executes the callback function when MATLAB triggers the property event. Define the callback function to have two specific arguments, which are passed to the function automatically when called by the listener:

- Event source a matlab.metadata.Property object describing the object that is the source of the property event
- Event data a event.PropertyEvent object containing information about the event

You can pass additional arguments if necessary. It is often simple to define this method as Static because these two arguments contain most necessary information in their properties.

For example, suppose the handlePropEvents function is a static method of the class creating listeners for two properties of an object of another class:

```
methods (Static)
   function handlePropEvents(src,evnt)
      switch src.Name
         case 'Prop0ne
           % PropOne has triggered an event
         case 'PropTwo'
```

```
$\% PropTwo has triggered an event {\color{red} end} \\ {\color{red} end} \\ {\color{red} end} \\ {\color{red} end}
```

Another possibility is to use the event.PropertyEvent object's EventName property in the switch statement to key off the event name (PreSet or PostSet in this case).

"Class Metadata" on page 16-2 provides more information about the matlab.metadata.Property class.

Add Listener to Property

The addlistener handle class method enables you to attach a listener to a property without storing the listener object as a persistent variable. For a property event, use the four-argument version of addlistener.

Here is a call to addlistener:

```
addlistener(EventObject, 'PropOne', 'PostSet',@ClassName.handlePropertyEvents);
```

The arguments are:

- EventObject handle of the object generating the event
- Prop0ne name of the property to which you want to listen
- PostSet name of the event for which you want to listen
- @ClassName.handlePropertyEvents function handle referencing a static method, which requires the use of the class name

If your listener callback is an ordinary method and not a static method, the syntax is:

```
addlistener(EventObject, 'PropOne', 'PostSet',@obj.handlePropertyEvents);
```

where obj is the handle of the object defining the callback method.

If the listener callback is a function that is not a class method, you pass a function handle to that function. Suppose that the callback function is a namespace function:

```
addlistener(EventObject, 'PropOne', 'PostSet',@namespace.handlePropertyEvents);
```

For more information on passing functions as arguments, see "Create Function Handle".

Property Event and Listener Classes

The following two classes show how to create PostSet property listeners for two properties — PropOne and PropTwo.

Class Generating the Event

The PropEvent class enables property PreSet and PostSet event triggering by specifying the SetObservable property attribute. These properties also enable the AbortSet attribute, which prevents the triggering of the property events if the properties are set to a value that is the same as their current value (see "Assignment When Property Value Is Unchanged" on page 11-35).

```
classdef PropEvent < handle
  properties (SetObservable, AbortSet)
     PropOne</pre>
```

```
PropTwo
   end
   methods
      function obj = PropEvent(p1,p2)
         if nargin > 0
            obj.PropOne = p1;
            obj.PropTwo = p2;
         end
      end
   end
end
```

Class Defining the Listeners

The PropListener class defines two listeners:

- Property Prop0ne PostSet event
- Property PropTwo PostSet event

You can define listeners for other events or other properties using a similar approach. It is not necessary to use the same callback function for each listener. See the matlab.metadata.Property and event. PropertyEvent reference pages for more on the information contained in the arguments passed to the listener callback function.

```
classdef PropListener < handle</pre>
   % Define property listeners
   methods
      function obj = PropListener(evtobj)
         if nargin > 0
            addlistener(evtobj,'PropOne','PostSet',@PropListener.handlePropEvents);
            addlistener(evtobj, 'PropTwo', 'PostSet',@PropListener.handlePropEvents);
         end
      end
   end
   methods (Static)
      function handlePropEvents(src,evnt)
         switch src.Name
            case 'Prop0ne'
               sprintf('PropOne is %s\n',num2str(evnt.AffectedObject.PropOne))
               sprintf('PropTwo is %s\n',num2str(evnt.AffectedObject.PropTwo))
         end
      end
   end
end
```

See Also

Related Examples

"Assignment When Property Value Is Unchanged" on page 11-35

Assignment When Property Value Is Unchanged

In this section...

"AbortSet When Value Does Not Change" on page 11-35

"How MATLAB Compares Values" on page 11-35

"When to Use AbortSet" on page 11-35

"Implement AbortSet" on page 11-36

"Using AbortSet with Property Validation" on page 11-37

AbortSet When Value Does Not Change

When you set a property value, MATLAB triggers the property PreSet and PostSet events, invokes the property set method (if one is defined), and sets the property value. These actions occur even when the current value of the property is the same as the new value.

You can prevent these actions by setting the property's AbortSet attribute to true. When AbortSet is enabled, MATLAB compares the current property value to the new value being assigned to the property. If the new value is the same as the current value, MATLAB does not:

- Set the property value.
- Trigger the PreSet and PostSet events.
- Call the property set method, if one exists.

To compare values, MATLAB must get the current value of the property. Getting the current value causes the property get method (get. *Property*) to execute, if one exists. Any errors that occur when calling the property get method are visible to the user, even if MATLAB does not change the current value.

Note The AbortSet attribute only works with properties defined in handle classes. It cannot be used with value classes.

How MATLAB Compares Values

MATLAB uses the isequal function to determine if the current value of the property is the same as the new value. To determine if specific values evaluate as equal when using the AbortSet attribute, see the isequal function documentation or any isequal method overloaded for the class of the property value.

When to Use AbortSet

Use of the AbortSet attribute does incur some overhead in the comparison of the current and new property values. Using the AbortSet attribute can slow all property assignments because the current and assigned value are always compared before the assignment is made. The AbortSet attribute is most useful when:

• You want to prevent notification of the PreSet and PostSet events and execution of the listener callbacks when the property value does not change.

The cost of setting a property value is greater than the cost of comparing the current property value with the value being assigned, and you are willing to incur the comparison cost with all assignments to the property.

Implement AbortSet

The following example shows how the AbortSet attribute works. The AbortTheSet class defines a property, PropOne, that has listeners for the PreGet, PreSet, PostGet, and PostSet events and enables the AbortSet attribute.

Note To use this class, save the AbortTheSet class in a file with the same name in a folder on your MATLAB path.

```
classdef AbortTheSet < handle</pre>
    properties (SetObservable, GetObservable, AbortSet)
        Prop0ne = 7
    end
    methods
        function obj = AbortTheSet
            addlistener(obj,'PropOne','PreGet',@obj.getPrePropEvt);
            addlistener(obj, 'PropOne', 'PreSet',@obj.setPrePropEvt);
            addlistener(obj,'PropOne','PostGet',@obj.getPostPropEvt);
            addlistener(obj, 'PropOne', 'PostSet', @obj.setPostPropEvt);
        end
        function propval = get.Prop0ne(obj)
            disp('get.Prop0ne called')
            propval = obj.Prop0ne;
        end
        function set.PropOne(obj,val)
            disp('set.Prop0ne called')
            obj.PropOne = val;
        end
        function getPrePropEvt(obj,src,evnt)
            disp ('Pre-get event triggered')
        end
        function setPrePropEvt(obj,src,evnt)
            disp ('Pre-set event triggered')
        end
        function getPostPropEvt(obj,src,evnt)
            disp ('Post-get event triggered')
            % ...
        function setPostPropEvt(obj,src,evnt)
            disp ('Post-set event triggered')
            % ...
        end
        function disp(obj)
            % Overload disp to avoid accessing property
            disp (class(obj))
        end
    end
end
```

The class specifies an initial value of 7 for the PropOne property. Therefore, if you create an object and assign the property value of 7, there is no need to trigger the PreSet event. However, the getPropOne method is called to get the current value of the property to compare to the assigned vale.

```
obj = AbortTheSet;
obj.PropOne = 7;
get.PropOne called
```

If you specify a value other than 7, then MATLAB performs these steps:

- Gets the current property value
- Triggers the PreSet event
- Sets the property to the assigned value
- Triggers the PostSet event

```
obj = AbortTheSet;
obj.PropOne = 9;
get.PropOne called
Pre-set event triggered
set.PropOne called
Post-set event triggered
```

If you query the property value, the PreGet and PostGet events are triggered.

obj.PropOne

```
Pre-get event triggered
get.PropOne called
Post-get event triggered
ans =
```

Using AbortSet with Property Validation

When classes use property validation and AbortSet in a property definition, MATLAB evaluates the property validation before comparing the current value to the value being assigned. For example, revise the AbortTheSet class to add a size restriction of 1-by-3 to the PropOne property.

```
classdef AbortTheSet < handle
  properties (SetObservable, GetObservable, AbortSet)
    % Restrict size to 1-by-3
    % *****************
    PropOne (1,3) = [7 7 7]
    % *****************

end
methods
    function obj = AbortTheSet
        addlistener(obj,'PropOne','PreGet',@obj.getPrePropEvt);
        addlistener(obj,'PropOne','PreSet',@obj.setPrePropEvt);
        addlistener(obj,'PropOne','PostGet',@obj.getPostPropEvt);
        addlistener(obj,'PropOne','PostGet',@obj.setPropEvt);
        addlistener(obj,'PropOne','PostSet',@obj.setPostPropEvt);
        addlistener(obj,'PropOne','PropOne','PropOne','PropOne','PropOne','PropOne','PropOne','PropOne','PropOne','PropOne','PropOne','PropOne','PropOne','PropOne','
```

```
end
        function propval = get.Prop0ne(obj)
            disp('get.Prop0ne called')
            propval = obj.Prop0ne;
        end
        function set.PropOne(obj,val)
            disp('set.Prop0ne called')
            obj.PropOne = val;
        function getPrePropEvt(obj,src,evnt)
            disp ('Pre-get event triggered')
            % ...
        end
        function setPrePropEvt(obj,src,evnt)
            disp ('Pre-set event triggered')
            % ...
        end
        function getPostPropEvt(obj,src,evnt)
            disp ('Post-get event triggered')
        function setPostPropEvt(obj,src,evnt)
            disp ('Post-set event triggered')
        end
        function disp(obj)
            % Overload disp to avoid accessing property
            disp (class(obj))
        end
    end
end
```

Because MATLAB applies scalar expansion to satisfy the size restriction, the following assignment does not trigger the PreSet or PostSet events.

```
obj = AbortTheSet;
obj.Prop0ne = 7;
get.PropOne called
obj.Prop0ne
Pre-get event triggered
get.PropOne called
Post-get event triggered
ans =
     7
           7
                 7
```

For information on property validation, see "Validate Property Values" on page 8-19.

See Also

Related Examples

"Property Get and Set Methods" on page 8-39

• "Determine If Event Has Listeners" on page 11-29

Techniques for Using Events and Listeners

In this section...

"Example Overview" on page 11-40

"Techniques Demonstrated in This Example" on page 11-41

"Summary of fcneval Class" on page 11-41

"Summary of fcnview Class" on page 11-42

"Methods Inherited from Handle Class" on page 11-43

"Using the fcneval and fcnview Classes" on page 11-43

"Implement UpdateGraph Event and Listener" on page 11-45

"The PostSet Event Listener" on page 11-48

"Enable and Disable Listeners" on page 11-50

"@fcneval/fcneval.m Class Code" on page 11-51

"@fcnview/fcnview.m Class Code" on page 11-52

Example Overview


This example defines two classes:

- fcneval The function evaluator class contains a MATLAB expression and evaluates this expression over a specified range
- fcnview The function viewer class contains a fcneval object and displays surface graphs of the evaluated expression using the data contained in fcneval.

This class defines two events:

- A class-defined event that occurs when a new value is specified for the MATLAB function
- A property event that occurs when the property containing the limits is changed

The following diagram shows the relationship between the two objects. The fcnview object contains a fcneval object and creates graphs from the data it contains. fcnview creates listeners to change the graphs if any of the data in the fcneval object change.



Techniques Demonstrated in This Example

- · Naming an event in the class definition
- Triggering an event by calling notify
- Enabling a property event via the SetObservable attribute
- Creating listeners for class-defined events and property PostSet events
- Defining listener callback functions that accept additional arguments
- · Enabling and disabling listeners

Summary of fcneval Class

The fcneval class evaluates a MATLAB expression over a specified range of two variables. The fcneval is the source of the data that objects of the fcnview class graph as a surface. fcneval is the source of the events used in this example. For a listing of the class definition, see "@fcneval/fcneval.m Class Code" on page 11-51

Property	Value	Purpose
FofXY	function handle	MATLAB expression (function of two variables).
Lm	two-element vector	Limits over which function is evaluated in both variables. SetObservable attribute set to true to enable property event listeners.
Data	structure with x, y, and z matrices	Data resulting from evaluating the function. Used for surface graph. Dependent attribute set to true, which means the get.Data method is called to determine property value when queried and no data is stored.

Event	When Triggered	
· ·	FofXY property set function (set.FofXY) calls the notify method when a new value is specified for the MATLAB expression on an object of this class.	

Method	Purpose
fcneval	Class constructor. Inputs are function handle and two-element vector specifying the limits over which to evaluate the function.
set.FofXY	FofXY property set function. Called whenever property value is set, including during object construction.
set.Lm	Lm property set function. Used to test for valid limits.
get.Data	Data property get function. This method calculates the values for the Data property whenever that data is queried (by class members or externally).
grid	A static method (Static attribute set to true) used in the calculation of the data.

Summary of fcnview Class

Objects of the fcnview class contain fcneval objects as the source of data for the four surface graphs created in a function view. fcnview creates the listeners and callback functions that respond to changes in the data contained in fcneval objects. For a listing of the class definition, see "@fcnview/fcnview.m Class Code" on page 11-52

Property	Value	Purpose
FcnObject	fcneval object	This object contains the data that is used to create the function graphs.
HAxes	axes handle	Each instance of a fcnview object stores the handle of the axes containing its subplot.
HLUpdateGraph	event.listener object for UpdateGraph event	Setting the event.listener object's Enabled property to true enables the listener; false disables listener.
HLLm	event.listener object for Lm property event	Setting the event.listener object's Enabled property to true enables the listener, false disables listener.
HEnableCm	uimenu handle	Item on context menu used to enable listeners (used to handle checked behavior)
HDisableCm	uimenu handle	Item on context menu used to disable listeners (used to manage checked behavior)
HSurface	surface handle	Used by event callbacks to update surface data.

Method	Purpose
fcnview	Class constructor. Input is fcneval object.
	Calls addlistener to create listeners for UpdateGraph and Lm property PostSet listeners.

Method	Purpose
lims	Sets axes limits to current value of fcneval object's Lm property. Used by event handlers.
updateSurfaceData	Updates the surface data without creating a new object. Used by event handlers.
listenUpdateGraph	Callback for UpdateGraph event.
listenLm	Callback for Lm property PostSet event
delete	Delete method for fcnview class.
createViews	Static method that creates an instance of the fcnview class for each subplot, defines the context menus that enable/disable listeners, and creates the subplots

Methods Inherited from Handle Class

Both the fcneval and fcnview classes inherit methods from the handle class. The following table lists only those inherited methods used in this example.

"Handle Class Methods" on page 7-11 provides a complete list of methods that are inherited when you subclass the handle class.

Methods Inherited from Handle Class	Purpose
	Register a listener for a specific event and attach listener to event-defining object.
notify	Trigger an event and notify all registered listeners.

Using the fcneval and fcnview Classes

This section explains how to use the classes.

- Create an instance of the fcneval class to contain the MATLAB expression of a function of two variables and the range over which you want to evaluate this function
- Use the fcnview class static function createViews to visualize the function
- Change the MATLAB expression or the limits contained by the fcneval object and all the fcnview objects respond to the events generated.


You create a fcneval object by calling its constructor with two arguments—an anonymous function and a two-element, monotonically increasing vector. For example:

```
feobject = fcneval(@(x,y) x.*exp(-x.^2-y.^2),[-2 2]);
```


Use the createViews static method to create the graphs of the function. Use the class name to call a static function:


```
fcnview.createViews(feobject);
```

The createView method generates four views of the function contained in the fcneval object.




Each subplot defines a context menu that can enable and disable the listeners associated with that graph. For example, if you disable the listeners on subplot 221 (upper left) and change the MATLAB expression contained by the fcneval object, only the remaining three subplots update when the UpdateGraph event is triggered:





Similarly, if you change the limits by assigning a value to the feobject. Lm property, the feobject triggers a PostSet property event and the listener callbacks update the graph.

feobject.Lm = $[-8 \ 3];$




In this figure, the listeners are reenabled via the context menu for subplot 221. Because the listener callback for the property PostSet event also updates the surface data, all views are now synchronized

Implement UpdateGraph Event and Listener

The UpdateGraph event occurs when the MATLAB representation of the mathematical function contained in the fcneval object is changed. The fcnview objects that contain the surface graphs are listening for this event, so they can update the graphs to represent the new function.

Define and Trigger UpdateGraph Event

The UpdateGraph event is a class-defined event. The fcneval class names the event and calls notify when the event occurs.



The fcnview class defines a listener for this event. When fcneval triggers the event, the fcnview listener executes a callback function that performs the follow actions:

- Determines if the handle of the surface object stored by the fcnview object is still valid (that is, does the object still exist)
- Updates the surface XData, YData, and ZData by querying the fcneval object's Data property.

The fcneval class defines an event name in an event block:

events

UpdateGraph end

Determine When to Trigger Event

The fcneval class defines a property set method for the FofXY property. FofXY is the property that stores the MATLAB expression for the mathematical function. This expression must be a valid MATLAB expression for a function of two variables.

The set. FofXY method:

- Determines the suitability of the expression
- If the expression is suitable:
 - Assigns the expression to the FofXY property
 - Triggers the UpdateGraph event

If fcneval.isSuitable does not return an MException object, the set.FofXY method assigns the value to the property and triggers the UpdateGraph event.

```
function set.FofXY(obj,func)
% Determine if function is suitable to create a surface
    me = fcneval.isSuitable(func);
    if ~isempty(me)
        throw(me)
    end
% Assign property value
    obj.FofXY = func;
% Trigger UpdateGraph event
    notify(obj,'UpdateGraph');
end
```

Determine Suitability of Expression

The set.FofXY method calls a static method (fcneval.isSuitable) to determine the suitability of the specified expression. fcneval.isSuitable returns an MException object if it determines that the expression is unsuitable. fcneval.isSuitable calls the MException constructor directly to create more useful error messages for the user.

set.FofXY issues the exception using the throw method. Issuing the exception terminates execution of set.FofXY and prevents the method from making an assignment to the property or triggering the UpdateGraph event.

Here is the fcneval.isSuitable method:

```
function is0k = isSuitable(funcH)
   v = [1 1; 1 1];
   % Can the expression except 2 numeric inputs
   try
       funcH(v,v);
      me = MException('DocExample:fcneval',...
['The function ',func2str(funcH),' Is not a suitable F(x,y)']);
       is0k = me;
       return
   % Does the expression return non-scalar data
   if isscalar(funcH(v,v));
       me = MException('DocExample:fcneval',...
['The function ',func2str(funcH),'' Returns a scalar when evaluated']);
       is0k = me:
       return
   end
   is0k = []:
end
```

The fcneval.isSuitable method could provide additional test to ensure that the expression assigned to the FofXY property meets the criteria required by the class design.

Other Approaches

The class could have implemented a property set event for the FofXY property and would, therefore, not need to call notify (see "Listen for Changes to Property Values" on page 11-32). Defining a class event provides more flexibility in this case because you can better control event triggering.

For example, suppose that you wanted to update the graph only if the new data is different. If the new expression produced the same data within some tolerance, the set. FofXY method could not trigger the event and avoid updating the graph. However, the method could still set the property to the new value.

Listener and Callback for UpdateGraph Event

The fcnview class creates a listener for the UpdateGraph event using the addlistener method:

```
obj.HLUpdateGraph = addlistener(obj.Fcn0bject,'UpdateGraph',...
            @(src,evnt)listenUpdateGraph(obj,src,evnt)); % Add obj to argument list
```

The fcnview object stores a handle to the event.listener object in its HLUpdateGraph property, which is used to enable/disable the listener by a context menu (see "Enable and Disable Listeners" on page 11-50).

The fcnview object (obj) is added to the two default arguments (src, evnt) passed to the listener callback. Keep in mind, the source of the event (src) is the fcneval object, but the fcnview object contains the handle of the surface object that the callback updates.

The listenUpdateGraph function is defined as follows:


```
function listenUpdateGraph(obj,src,evnt)
  if ishandle(obj.HSurface) % If surface exists
      obj.updateSurfaceData % Update surface data
  end
end
```

The updateSurfaceData function is a class method that updates the surface data when a different mathematical function is assigned to the fcneval object. Updating a graphics object data is more efficient than creating a new object using the new data:

```
function updateSurfaceData(obj)
% Get data from fcneval object and set surface data
   set(obj.HSurface,...
      'XData',obj.FcnObject.Data.X,...
      'YData',obj.FcnObject.Data.Y,...
      'ZData',obj.FcnObject.Data.Matrix);
end
```

The PostSet Event Listener

All properties support the predefined PostSet event (See "Property-Set and Query Events" on page 11-14 for more information on property events). This example uses the PostSet event for the fcneval Lm property. This property contains a two-element vector specifying the range over which the mathematical function is evaluated. Just after this property is changed (by a statement like obj.Lm = [-3 5];), the fcnview objects listening for this event update the graph to reflect the new data.



Sequence During the Lm Property Assignment

The fcneval class defines a set function for the Lm property. When a value is assigned to this property during object construction or property reassignment, the following sequence occurs:

- **1** An attempt is made to assign argument value to Lm property.
- 2 The set.Lm method executes to check whether the value is in appropriate range if yes, it makes assignment, if no, it generates an error.
- 3 If the value of Lm is set successfully, MATLAB triggers a PostSet event.
- **4** All listeners execute their callbacks, but the order is nondeterministic.

The PostSet event does not occur until an actual assignment of the property occurs. The property set function provides an opportunity to deal with potential assignment errors before the PostSet event occurs.

Enable PostSet Property Event

To create a listener for the PostSet event, you must set the property's SetObservable attribute to true:

```
properties (SetObservable = true)
   Lm = [-2*pi 2*pi]; % specifies default value
end
end
```

MATLAB automatically triggers the event so it is not necessary to call notify.

"Property Attributes" on page 8-8 provides a list of all property attributes.

Listener and Callback for PostSet Event

The fcnview class creates a listener for the PostSet event using the addlistener method:

```
obj.HLLm = addlistener(obj.FcnObject,'Lm','PostSet',...
    @(src,evnt)listenLm(obj,src,evnt)); % Add obj to argument list
```

The fcnview object stores a handle to the event.listener object in its HLLm property, which is used to enable/disable the listener by a context menu (see "Enable and Disable Listeners" on page 11-50).

The fcnview object (obj) is added to the two default arguments (src, evnt) passed to the listener callback. Keep in mind, the source of the event (src) is the fcneval object, but the fcnview object contains the handle of the surface object that the callback updates.

The callback sets the axes limits and updates the surface data because changing the limits causes the mathematical function to be evaluated over a different range:

```
function listenLm(obj,src,evnt)
  if ishandle(obj.HAxes) % If there is an axes
      lims(obj); % Update its limits
      if ishandle(obj.HSurface) % If there is a surface
         obj.updateSurfaceData % Update its data
      end
  end
end
```

Enable and Disable Listeners

Each fcnview object stores the handle of the listener objects it creates so that the listeners can be enabled or disabled via a context menu after the graphs are created. All listeners are instances of the event.listener class, which defines a property called Enabled. By default, this property has a value of true, which enables the listener. If you set this property to false, the listener still exists, but is disabled. This example creates a context menu active on the axes of each graph that provides a way to change the value of the Enabled property.

Context Menu Callback

There are two callbacks used by the context menu corresponding to the two items on the menu:

- Listen Sets the Enabled property for both the UpdateGraph and PostSet listeners to true and adds a check mark next to the **Listen** menu item.
- **Don't Listen** Sets the Enabled property for both the UpdateGraph and PostSet listeners to false and adds a check mark next to the **Don't Listen** menu item.

Both callbacks include the fcnview object as an argument (in addition to the required source and event data arguments) to provide access to the handle of the listener objects.

The enableLish function is called when the user selects **Listen** from the context menu.

```
function enableLisn(obj,src,evnt)
   obj.HLUpdateGraph.Enabled = true; % Enable listener
   obj.HLLm.Enabled = true; % Enable listener
   set(obj.HEnableCm,'Checked','on') % Check Listen
```

```
\operatorname{set}(\operatorname{obj.HDisableCm}, \operatorname{'Checked'}, \operatorname{'off'}) \ % \ \operatorname{Uncheck} \ \operatorname{Don't} \ \operatorname{Listen} \ \operatorname{end}
```

The disableLisn function is called when the user selects **Don't Listen** from the context menu.

```
function disableLisn(obj,src,evnt)
  obj.HLUpdateGraph.Enabled = false; % Disable listener
  obj.HLLm.Enabled = false; % Disable listener
  set(obj.HEnableCm,'Checked','off') % Uncheck Listen
  set(obj.HDisableCm,'Checked','on') % Check Don't Listen
end
```

@fcneval/fcneval.m Class Code

```
classdef fcneval < handle</pre>
  properties
     FofXY
   end
  properties (SetObservable = true)
     Lm = [-2*pi \ 2*pi]
  end % properties SetObservable = true
   properties (Dependent = true)
     Data
  end
  events
     UpdateGraph
  end
  methods
      function obj = fcneval(fcn_handle,limits)
         if nargin > 0
            obj.FofXY = fcn_handle;
            obj.Lm = limits;
         end
      end
      function set.FofXY(obj,func)
         me = fcneval.isSuitable(func);
         if ~isempty(me)
            throw(me)
         end
         obj.FofXY = func;
         notify(obj,'UpdateGraph');
      function set.Lm(obj,lim)
         if \sim (\lim(1) < \lim(2))
            error('Limits must be monotonically increasing')
         else
            obj.Lm = lim;
         end
      end
      function data = get.Data(obj)
         [x,y] = fcneval.grid(obj.Lm);
         matrix = obj.FofXY(x,y);
         data.X = x;
         data.Y = v;
         data.Matrix = real(matrix);
      end
   end % methods
```

```
methods (Static = true)
       function [x,y] = grid(lim)
           inc = (lim(2) - lim(1))/20;
           [x,y] = meshgrid(lim(1):inc:lim(2));
       end % grid
       function is0k = isSuitable(funcH)
           v = [1 \ 1; 1 \ 1];
           try
              funcH(v,v);
           catch %#ok<CTCH>
              me = MException('DocExample:fcneval',...
['The function ',func2str(funcH),' Is not a suitable F(x,y)']);
              is0k = me;
              return
           end
           if isscalar(funcH(v,v));
              me = MException('DocExample:fcneval',...
['The function ',func2str(funcH),' Returns a scalar when evaluated']);
              return
           end
           is0k = [];
       end
   end
end
```

@fcnview/fcnview.m Class Code

```
classdef fcnview < handle</pre>
   properties
      Fcn0bject
                    % fcneval object
      HAxes
                    % subplot axes handle
      HLUpdateGraph % UpdateGraph listener handle
      HLLm
                    % Lm property PostSet listener handle
      HEnableCm
                    % "Listen" context menu handle
      HDisableCm
                   % "Don't Listen" context menu handle
      HSurface
                    % Surface object handle
  end
   methods
      function obj = fcnview(fcnobj)
         if nargin > 0
            obj.FcnObject = fcnobj;
            obj.createLisn;
         end
      end
      function createLisn(obj)
         obj.HLUpdateGraph = addlistener(obj.FcnObject, 'UpdateGraph',...
            @(src,evnt)listenUpdateGraph(obj,src,evnt));
         obj.HLLm = addlistener(obj.FcnObject, 'Lm', 'PostSet',...
            @(src,evnt)listenLm(obj,src,evnt));
      end
      function lims(obj)
         lmts = obj.FcnObject.Lm;
         set(obj.HAxes,'XLim',lmts);
         set(obj.HAxes,'Ylim',lmts);
      end
```

```
function updateSurfaceData(obj)
         data = obj.FcnObject.Data;
         set(obj.HSurface,...
             'XData',data.X,...
             'YData',data.Y,...
'ZData',data.Matrix);
      end
      function listenUpdateGraph(obj,~,~)
         if ishandle(obj.HSurface)
             obj.updateSurfaceData
         end
      end
      function listenLm(obj,~,~)
         if ishandle(obj.HAxes)
             lims(obj);
             if ishandle(obj.HSurface)
                obj.updateSurfaceData
             end
         end
      end
      function delete(obj)
         if ishandle(obj.HAxes)
            delete(obj.HAxes);
         else
             return
         end
      end
   methods (Static)
      createViews(a)
   end
end
@fcnview/createViews
function createViews(fcnevalobj)
   p = pi; deg = 180/p;
   hfig = figure('Visible','off',...
       'Toolbar', 'none');
   for k=4:-1:1
      fcnviewobj(k) = fcnview(fcnevalobj);
      axh = subplot(2,2,k);
      fcnviewobj(k).HAxes = axh;
      hcm(k) = uicontextmenu;
      set(axh,'Parent',hfig,...
          'FontSize',8,...
          'UIContextMenu', hcm(k))
      fcnviewobj(k).HEnableCm = uimenu(hcm(k),...
         'Label','Listen',...
'Checked','on',...
'Callback',@(src,evnt)enableLisn(fcnviewobj(k),src,evnt));
      fcnviewobj(k).HDisableCm = uimenu(hcm(k),...
          'Label','Don''t Listen',...
```

```
'Checked', 'off',...
         'Callback',@(src,evnt)disableLisn(fcnviewobj(k),src,evnt));
      az = p/k*deg;
      view(axh,az,30)
      title(axh,['View: ',num2str(az),' 30'])
      fcnviewobj(k).lims;
      surfLight(fcnviewobj(k),axh)
   end
   set(hfig,'Visible','on')
function surfLight(obj,axh)
   obj.HSurface = surface(obj.FcnObject.Data.X,...
      obj.FcnObject.Data.Y,...
      obj.FcnObject.Data.Matrix,...
      'FaceColor',[.8 .8 0], 'EdgeColor',[.3 .3 .2],...
      'FaceLighting','phong',...
      'FaceAlpha',.3,...
      'HitTest','off',...
      'Parent', axh);
   lims(obj)
   camlight left; material shiny; grid off
   colormap copper
end
function enableLisn(obj,~,~)
   obj.HLUpdateGraph.Enabled = true;
   obj.HLLm.Enabled = true;
   set(obj.HEnableCm, 'Checked', 'on')
   set(obj.HDisableCm,'Checked','off')
function disableLisn(obj,~,~)
   obj.HLUpdateGraph.Enabled = false;
   obj.HLLm.Enabled = false;
   set(obj.HEnableCm, 'Checked', 'off')
   set(obj.HDisableCm, 'Checked', 'on')
end
```

How to Build on Other Classes

- "Hierarchies of Classes Concepts" on page 12-2
- "Subclass Syntax" on page 12-5
- "Design Subclass Constructors" on page 12-7
- "Control Sequence of Constructor Calls" on page 12-11
- "Modify Inherited Methods" on page 12-13
- "Modify Inherited Properties" on page 12-17
- "Subclassing Multiple Classes" on page 12-19
- "Specify Allowed Subclasses" on page 12-21
- "Class Members Access" on page 12-23
- "Method Access List" on page 12-29
- "Event Access List" on page 12-30
- "Handle Compatible Classes" on page 12-31
- "How to Define Handle-Compatible Classes" on page 12-33
- "Methods for Handle-Compatible Classes" on page 12-37
- "Handle-Compatible Classes and Heterogeneous Arrays" on page 12-38
- "Subclasses of MATLAB Built-In Types" on page 12-40
- "Behavior of Inherited Built-In Methods" on page 12-43
- "Subclasses of Built-In Types Without Properties" on page 12-47
- "Subclasses of Built-In Types with Properties" on page 12-53
- "Use of size and numel with Classes" on page 12-60
- "Determine Array Class" on page 12-65
- "Abstract Classes and Class Members" on page 12-68
- "Define an Interface Superclass" on page 12-72

Hierarchies of Classes — Concepts

In this section...

"Classification" on page 12-2

"Develop the Abstraction" on page 12-3


"Design of Class Hierarchies" on page 12-3

"Super and Subclass Behavior" on page 12-3

"Implementation and Interface Inheritance" on page 12-4

Classification

Organizing classes into hierarchies facilitates the reuse of code and the reuse of solutions to design problems that have already been solved. You can think of class hierarchies as sets — supersets (referred to as superclasses or base classes), and subsets (referred to as subclasses or derived classes). For example, the following picture shows how you could represent an employee database with classes.



The root of the hierarchy is the Employees class. It contains data and operations that apply to the set of all employees. Contained in the set of employees are subsets whose members, while still employees, are also members of sets that more specifically define the type of employee. Subclasses like TestEngineer are examples of these subsets.

Develop the Abstraction

Classes are representations of real world concepts or things. When designing a class, form an abstraction of what the class represents. Consider an abstraction of an employee and what are the essential aspects of employees for the intended use of the class. Name, address, and department can be what all employees have in common.

When designing classes, your abstraction contains only those elements that are necessary. For example, the employee hair color and shoe size certainly characterize the employee, but are probably not relevant to the design of this employee class. Their sales region is relevant only to some employee so this characteristic belongs in a subclass.

Design of Class Hierarchies

As you design a system of classes, put common data and functionality in a superclass, which you then use to derive subclasses. The subclasses inherit the data and functionality of the superclass and define only aspects that are unique to their particular purposes. This approach provides advantages:

- · Avoid duplicating code that is common to all classes.
- Add or change subclasses at any time without modifying the superclass or affecting other subclasses.
- If the superclass changes (for example, all employees are assigned a number), then the subclass automatically get these changes.

Super and Subclass Behavior

Subclass objects behave like objects of the superclass because they are specializations of the superclass. This fact facilitates the development of related classes that behave similarly, but are implemented differently.

A Subclass Object "Is A" Superclass Object

You can usually describe the relationship between an object of a subclass and an object of its superclass with a statement like:

The subclass is a superclass. For example: An Engineer is an Employee.

This relationship implies that objects belonging to a subclass have the same properties, methods, and events as the superclass. Subclass objects also have any new features defined by the subclass. Test this relationship with the isa function.

Treat Subclass Objects like Superclass Objects

You can pass a subclass object to a superclass method, but you can access only those properties that the superclass defines. This behavior enables you to modify the subclasses without affecting the superclass.

Two points about super and subclass behavior to keep in mind are:

- Methods defined in the superclass can operate on subclass objects.
- Methods defined in the subclass cannot operate on superclass objects.

Therefore, you can treat an Engineer object like any other Employees object, but an Employee object cannot pass for an Engineer object.

Limitations to Object Substitution

MATLAB determines the class of an object based on its most specific class. Therefore, an Engineer object is of class Engineer, while it is also an Employees object, as using the isa function reveals.

Generally, MATLAB does not allow you to create arrays containing a mix of superclass and subclass objects because an array can be of only one class. If you attempt to concatenate objects of different classes, MATLAB looks for a converter method defined by the less dominant class

See "Concatenating Objects of Different Classes" on page 10-14 for more information.

See matlab.mixin.Heterogeneous for information on defining heterogeneous class hierarchies.

See "Object Converters" on page 17-5 for information on defining converter methods.

Implementation and Interface Inheritance

MATLAB classes support both the inheritance of implemented methods from a superclass and the inheritance of interfaces defined by abstract methods in the superclass.

Implementation inheritance enables code reuse by subclasses. For example, an employee class can have a submitStatus method that all employee subclasses can use. Subclasses can extend an inherited method to provide specialized functionality, while reusing the common aspects. See "Modify Inherited Methods" on page 12-13 for more information on this process.

Interface inheritance is useful in these cases:

- You want a group of classes to provide a common interface.
- Subclasses create specialized implementations of methods and properties.

Create an interface using an abstract class as the superclass. This class defines the methods and properties that you must implement in the subclasses, but does not provide an implementation.

The subclasses must provide their own implementation of the abstract members of the superclass. To create an interface, define methods and properties as abstract using their Abstract attribute. See "Abstract Classes and Class Members" on page 12-68 for more information and an example.

See Also

Related Examples

"Design Subclass Constructors" on page 12-7

Subclass Syntax

```
In this section...

"Subclass Definition Syntax" on page 12-5

"Subclass double" on page 12-5
```

Subclass Definition Syntax

To define a class that is a subclass of another class, add the superclass to the classdef line after a < character:

```
classdef ClassName < SuperClass</pre>
```

When inheriting from multiple classes, use the & character to indicate the combination of the superclasses:

```
classdef ClassName < SuperClass1 & SuperClass2</pre>
```

See "Class Member Compatibility" on page 12-19 for more information on deriving from multiple superclasses.

Class Attributes

Subclasses do not inherit superclass attributes.

Subclass double

Suppose you want to define a class that derives from double and restricts values to be positive numbers. The PositiveDouble class:

- Supports a default constructor (no input arguments). See "No Input Argument Constructor Requirement" on page 9-19
- Restricts the inputs to positive values using mustBePositive
- Calls the superclass constructor with the input value to create the double numeric value

```
classdef PositiveDouble < double
  methods
    function obj = PositiveDouble(data)
    if nargin == 0
        data = 1;
    else
        mustBePositive(data)
    end
    obj = obj@double(data);
  end
end
end</pre>
```

Create an object of the PositiveDouble class using a 1-by-5 array of numbers:

```
a = PositiveDouble(1:5);
```

You can perform operations on objects of this class like any double.

```
sum(a)
ans =
    15
Objects of the PositiveDouble class must be positive values.
a = PositiveDouble(0:5);
Error using mustBePositive (line 19)
Value must be positive.
Error in PositiveDouble (line 7)
            mustBePositive(data)
```

See Also

Related Examples

- "Design Subclass Constructors" on page 12-7
- "Subclasses of MATLAB Built-In Types" on page 12-40

Design Subclass Constructors

```
In this section...

"Call Superclass Constructor Explicitly" on page 12-7

"Call Superclass Constructor from Subclass" on page 12-7

"Subclass Constructor Implementation" on page 12-8

"Call Only Direct Superclass from Constructor" on page 12-9
```

Call Superclass Constructor Explicitly

Explicitly calling each superclass constructor from a subclass constructor enables you to:

- Pass arguments to superclass constructors
- Control the order in which MATLAB calls the superclass constructors

If you do not explicitly call the superclass constructors from the subclass constructor, MATLAB implicitly calls these constructors with no arguments. The superclass constructors must support the no argument syntax to support implicit calls, and the constructors are called in the order they appear at the top of the class block, from left to right. To change the order in which MATLAB calls the constructors or to call constructors with arguments, call the superclass constructors explicitly from the subclass constructor.

If you do not define a subclass constructor, you can call the default constructor with superclass arguments. For more information, see "Default Constructor" on page 9-17 and "Implicit Call to Inherited Constructor" on page 9-21.

Call Superclass Constructor from Subclass

To call the constructor for each superclass within the subclass constructor, use the following syntax:

```
obj@SuperClass1(args,...);
...
obj@SuperclassN(args,...);
```

Where obj is the output of the subclass constructor, SuperClass... is the name of a superclass, and args are any arguments required by the respective superclass constructor.

For example, the following segment of a class definition shows that a class called Stocks that is a subclass of a class called Assets.

```
classdef Stocks < Assets
  methods
  function s = Stocks(asset_args,...)
  if nargin == 0
    % Assign values to asset_args
  end
  % Call asset constructor
  s@Assets(asset_args);
  ...</pre>
```

```
end
end
end
```

"Subclass Constructors" on page 9-19 provides more information on creating subclass constructor methods.

Reference Superclasses Contained in Namespaces

If a superclass is contained in a namespace, include the namespace name. For example, the Assests class is in the finance namespace:

```
classdef Stocks < finance.Assets
  methods
    function s = Stocks(asset_args,...)
    if nargin == 0
        ...
    end
    % Call asset constructor
    s@finance.Assets(asset_args);
    ...
  end
end
end</pre>
```

Initialize Objects Using Multiple Superclasses

To derive a class from multiple superclasses, initialize the subclass object with calls to each superclass constructor:

```
classdef Stocks < finance.Assets & Taxable
  methods
    function s = Stocks(asset_args,tax_args,...)
        if nargin == 0
        ...
    end
        % Call asset and member class constructors
        s@finance.Assets(asset_args)
        s@Taxable(tax_args)
    ...
    end
    end
end</pre>
```

Subclass Constructor Implementation

To ensure that your class constructor supports the zero arguments syntax, assign default values to input argument variables before calling the superclass constructor. You cannot conditionalize a subclass call to the superclass constructor. Locate calls to superclass constructors outside any conditional code blocks.

For example, the Stocks class constructor supports the no argument case with the if statement, but calls the superclass constructor outside of the if code block.

```
classdef Stocks < finance.Assets
   properties
   NumShares</pre>
```

```
Symbol
end
methods
  function s = Stocks(description, numshares, symbol)
  if nargin == 0
     description = '';
     numshares = 0;
     symbol = '';
  end
  s@finance.Assets(description);
  s.NumShares = numshares;
  s.Symbol = symbol;
end
end
end
```

Call Only Direct Superclass from Constructor

Call only direct superclass constructors from a subclass constructor. For example, suppose class B derives from class A and class C derives from class B. The constructor for class C cannot call the constructor for class A to initialize properties. Class B must initialize class A properties.

The following implementations of classes A, B, and C show how to design this relationship in each class.

Class A defines properties x and y, but assigns a value only to x:

Class B inherits properties x and y from class A. The class B constructor calls the class A constructor to initialize x and then assigns a value to y.

```
classdef B < A
  methods
    function obj = B(x,y)
    ...
    obj@A(x);
    obj.y = y;
  end
  end
end</pre>
```

Class C accepts values for the properties x and y, and passes these values to the class B constructor, which in turn calls the class A constructor:

```
classdef C < B
  methods</pre>
```

```
function obj = C(x,y)
         obj@B(x,y);
      end
   end
end
```

See Also

Related Examples


"No Input Argument Constructor Requirement" on page 9-19

Control Sequence of Constructor Calls


MATLAB does not guarantee the sequence in which superclass constructors are called when constructing a subclass object. However, you can control this order by calling superclass constructors explicitly from the subclass constructor.

If you explicitly call a superclass constructor from the most specific subclass constructor (ClassC in the following diagram), then MATLAB calls the most specific subclass constructor first. If you do not make an explicit call to a superclass constructor from the subclass constructor, MATLAB makes the implicit call when accessing the object.

Suppose that you have a hierarchy of classes in which ClassC derives from ClassB, which derives from ClassA. The constructor for a subclass can call only direct superclasses. Therefore, each class constructor can call the direct superclass constructor:



In cases of multiple inheritance, the subclass constructor can call each superclass constructor. To ensure that a specific superclass constructor calling sequence is followed, call all direct superclass constructors explicitly from the most specific subclass constructor:



See Also

Related Examples

- "Call Only Direct Superclass from Constructor" on page 12-9 $\,$
- "Class Constructor Methods" on page 9-15

Modify Inherited Methods

In this section...

"When to Modify Superclass Methods" on page 12-13

"Extend Superclass Methods" on page 12-13

"Reimplement Superclass Process in Subclass" on page 12-14

"Redefine Superclass Methods" on page 12-15

"Implement Abstract Method in Subclass" on page 12-15

When to Modify Superclass Methods

Class designs enable you to pass subclass objects to superclass methods. The superclass method executes properly because the subclass object is a superclass object. However, subclasses can implement their own versions of superclass methods, which MATLAB calls when passed subclass objects.

Subclasses override inherited methods (that is, implement a method of the same name) when there is a need to provide specialized behavior in the subclass. Here are some patterns that override superclass methods.

- Extend the superclass method by calling it from within the subclass method. The subclass method can perform subclass-specific processing in addition to calling the superclass method.
- In a superclass method, implement a series of steps in a procedure using protected methods. Then reimplement these steps in a subclass method by redefining the protected methods that are called from within a public superclass method.
- Redefine the same-named method in the subclass, but use different implementations to perform the same operation differently on subclass objects.
- Implement abstract superclass methods in the subclass. Abstract superclasses can define methods with no implementation and rely on subclasses to provide the implementation. For more information, see "Define an Interface Superclass" on page 12-72.

Subclass methods that override superclass methods must define the same value for the Access attribute as is defined by the superclass method.

Extend Superclass Methods

Calling the same-named superclass method from a subclass method enables you to extend the superclass method for subclass objects without affecting the superclass method.

For example, suppose that both superclass and subclass define a method called foo. The subclass method calls the superclass method and performs other steps in addition to the call to the superclass method. The subclass method can operate on the specialized parts to the subclass that are not part of the superclass.

For example, this subclass defines a foo method that calls the superclass foo method

```
classdef Sub < Super
  methods
     function foo(obj)</pre>
```

```
% preprocessing steps
...
foo@Super(obj);
% postprocessing steps
...
end
end
end
end
end
```

Reimplement Superclass Process in Subclass

A superclass method can define a process that executes in a series of steps using a method for each step (typically Access attribute is set to protected for the step methods). This pattern (referred to as a template method) enables subclasses to create their own versions of the protected methods that implement the individual steps in the process. The process is specialized for the subclass.

Implement this technique as shown here:

```
classdef Super
   methods (Sealed)
      function foo(obj)
         step1(obj) % Call step1
         step2(obj) % Call step2
         step3(obj) % Call step3
      end
   end
   methods (Access = protected)
      function step1(obj)
         % Superclass version
      end
      function step2(obj)
         % Superclass version
      function step3(obi)
         % Superclass version
      end
   end
end
```

The subclass does not override the foo method. Instead it overrides only the protected methods that perform the series of steps (step1(obj), step2(obj), step3(obj)). This technique enables the subclass to specialize the actions taken by each step, but not control the order of the steps in the process. When you pass a subclass object to the superclass foo method, MATLAB calls the subclass step methods because of the dispatching rules. For more information on method dispatching, see "Method Invocation" on page 9-11.

```
classdef Sub < Super
...
methods (Access = protected)
function step1(obj)
% Subclass version
end
function step2(obj)
% Subclass version
end
function step3(obj)</pre>
```

```
% Subclass version
end
...
end
end
```

Redefine Superclass Methods

You can completely redefine a superclass method in a subclass. In this case, both the superclass and the subclass would define a method with the same name. However, the implementation would be different and the subclass method would not call the superclass method. Creating independent versions of the same-named method can be necessary when the same operation requires different implementation on the superclass and subclass.

```
classdef Super
  methods
    function foo(obj)
    % Superclass implementation
  end
end
end

classdef Sub < Super
  methods
    function foo(obj)
    % Subclass implementation
  end
end
end
end</pre>
```

Implement Abstract Method in Subclass

Abstract methods have no implementation. Subclasses that inherit abstract methods must provide a subclass-specific implementation for the subclass to be a concrete class. For more information, see "Abstract Classes and Class Members" on page 12-68.

```
classdef Super
  methods (Abstract)
     foo(obj)
     % Abstract method without implementation
  end
end

classdef Sub < Super
  methods
     function foo(obj)
     % Subclass implementation of concrete method
  end
  end
end</pre>
```

See Also

Related Examples

- "Call Superclass Methods on Subclass Objects" on page 5-11
- "Abstract Classes and Class Members" on page 12-68
- "Modify Inherited Properties" on page 12-17

Modify Inherited Properties

```
In this section...

"Superclass Property Modification" on page 12-17

"Private Local Property Takes Precedence in Method" on page 12-17
```

Superclass Property Modification

There are two separate conditions under which you can redefine superclass properties:

- The value of the superclass property Abstract attribute is true
- The values of the superclass property SetAccess and GetAccess attributes are private

If a superclass defines a property as abstract, the subclass must implement a concrete version of this property or the subclass is also abstract. Superclasses define abstract properties to create a consistent interface among subclasses.

If a superclass defines a property with private access, then only the superclass can access this property. The subclass can implement a different property with the same name.

Private Local Property Takes Precedence in Method

When superclass and subclass define a property with the same name, methods that refer to this property access the property of the class defining the method.

For example, if a subclass property has the same name as a superclass private property, and a method of the superclass references the property name, MATLAB accesses the property defined by the superclass.

Consider the following classes, Super and Sub:

```
classdef Super
  properties (Access = private)
     Prop = 2
  end
  methods
     function p = superMethod(obj)
        p = obj.Prop;
  end
  end
end

classdef Sub < Super
  properties
     Prop = 1
  end
end</pre>
```

If you create an instance of the Sub class and use it to call the superclass method, MATLAB accesses the private property of the superclass:

```
sub0bj = Sub
```

```
subObj =
 Sub with properties:
   Prop: 1
subObj.superMethod
ans =
     2
```

See Also

More About

"Property Attributes" on page 8-8

Subclassing Multiple Classes

In this section...

"Specify Multiple Superclasses" on page 12-19

"Class Member Compatibility" on page 12-19

"Multiple Inheritance" on page 12-20

Specify Multiple Superclasses

When inheriting from multiple classes, use the & character to indicate the combination of the superclasses:

classdef ClassName < SuperClass1 & SuperClass2</pre>

For more information on class syntax, see "Subclass Syntax" on page 12-5.

Class Member Compatibility

When you create a subclass derived from multiple superclasses, the subclass inherits the properties, methods, and events defined by all specified superclasses. If more than one superclass defines a property, method, or event having the same name, there must be an unambiguous resolution to the multiple definitions. You cannot derive a subclass from any two or more classes that define incompatible class members.

Here are various situations where you can resolve name and definition conflicts.

Property Conflicts

If two or more superclasses define a property with the same name, then at least one of the following must be true:

- All, or all but one of the properties must have their SetAccess and GetAccess attributes set to private
- The properties have the same definition in all superclasses (for example, when all superclasses inherited the property from a common base class)

Method Conflicts

If two or more superclasses define methods with the same name, then at least one of the following must be true:

- The method Access attribute is private so only the defining superclass can access the method.
- The method has the same definition in all subclasses. This situation can occur when all superclasses inherit the method from a common base class and none of the superclasses override the inherited definition.
- The subclass redefines the method to disambiguate the multiple definitions across all superclasses. Therefore, the superclass methods must not have their Sealed attribute set to true.
- Only one superclass defines the method as Sealed, in which case, the subclass adopts the sealed method definition.

• The superclasses define the methods as Abstract and rely on the subclass to define the method.

Event Conflicts

If two or more superclasses define events with the same name, then at least one of the following must be true:

- The event ListenAccess and NotifyAccess attributes must be private.
- The event has the same definition in all superclasses (for example, when all superclasses inherited the event from a common base class)

Multiple Inheritance

Resolving the potential conflicts involved when defining a subclass from multiple classes often reduces the value of this approach. For example, problems can arise when you enhance superclasses in future versions and introduce new conflicts.

Reduce potential problems by implementing only one unrestricted superclass. In all other superclasses, all methods are

- Abstract
- · Defined by a subclass
- Inherited from the unrestricted superclass

When using multiple inheritance, ensure that all superclasses remain free of conflicts in definition.

See Also

Related Examples

- "Design Subclass Constructors" on page 12-7
- "Handle Compatible Classes" on page 12-31

Specify Allowed Subclasses

In this section...

"Why Control Allowed Subclasses" on page 12-21

"Specify Allowed Subclasses" on page 12-21

"Define Sealed Hierarchy of Classes" on page 12-22

Why Control Allowed Subclasses

A class definition can specify a list of classes that it allows as subclasses. Classes not in the list cannot be defined as subclass of the class. To specify the allowed subclasses, use the AllowedSubclasses class attribute.

The AllowedSubclasses attribute provides a design point between Sealed classes, which do not allow subclassing, and the default behavior, which does not restrict subclassing.

By controlling the allowed subclasses, you can create a sealed hierarchy of classes. That is, a system of classes that enables a specific set of classes to derive from specific base classes, but that does not allow unrestricted subclassing.

See "Define Sealed Hierarchy of Classes" on page 12-22 for more about this technique.

Specify Allowed Subclasses

Specify a list of one or more allowed subclasses in the classdef statement by assigning matlab.metadata.Class objects to the AllowedSubclasses attribute. Create the matlab.metadata.Class object referencing a specific class using the ? operator and the class name:

```
classdef (AllowedSubclasses = ?ClassName) MySuperClass
   ...
end
```

Use a cell array of matlab.metadata.Class objects to define more than one allowed subclass:

```
{\tt classdef (AllowedSubclasses = \{?ClassName1,?ClassName2,...?ClassNameN\}) \ MySuperClasson end} end
```

Always use the fully qualified class name when referencing the class name:

```
{\tt classdef~(AllowedSubclasses = ?namespace.inneramespace.ClassName1)~MySuperClass} \dots \\ {\tt end}
```

Assigning an empty cell array to the AllowedSubclasses attribute is effectively the same as defining a Sealed class.

```
classdef (AllowedSubclasses = {}) MySuperClass
   ...
end
```

Note Use only the ? operator and the class name to generate matlab.metadata.Class objects. Values assigned to the AllowedSubclasses attribute cannot contain any other MATLAB

expressions, including functions that return either matlab.metadata.Class objects or cell arrays of matlab.metadata.Class objects.

Result of Declaring Allowed Subclasses

Including a class in the list of AllowedSubclasses does not define that class as a subclass or require you to define the class as a subclass. It just allows the referenced class to be defined as a subclass. Declaring a class as an allowed subclass also does not affect whether this class can itself be subclassed.

A class definition can contain assignments to the AllowedSubclasses attribute that reference classes that are not currently defined or available on the MATLAB path. Any referenced subclass that MATLAB cannot find when loading the class is effectively removed from the list without causing an error or warning. MATLAB remembers the referenced class in case it becomes available at a later point in time.

Note If MATLAB does not find any of the classes in the allowed subclasses list, the class is effectively Sealed. A sealed class is equivalent to AllowedSubclasses = {}.

Use the matlab.metadata.Class property RestrictsSubclassing to determine if a class is Sealed or specifies AllowedSubclasses.

Define Sealed Hierarchy of Classes

The AllowedSubclasses attribute enables you to define a sealed class hierarchy by sealing the allowed subclasses:

```
classdef (AllowedSubclasses = {?SubClass1,?SubClass2}) SuperClass
end
```

Define the allowed subclasses as Sealed:

```
classdef (Sealed) SubClass1
end
classdef (Sealed) SubClass2
end
```

Sealed class hierarchies enable you to use the level of abstraction that your design requires while maintaining a closed system of classes.

See Also

Related Examples

"Handle Compatible Classes" on page 12-31

Class Members Access

In this section...

"Basic Knowledge" on page 12-23

"Applications for Access Control Lists" on page 12-24

"Specify Access to Class Members" on page 12-24

"Properties with Access Lists" on page 12-25

"Methods with Access Lists" on page 12-25

"Abstract Methods with Access Lists" on page 12-28

Basic Knowledge

The material presented in this section builds on an understanding of these concepts:

Terminology and Concepts

- Class members Properties, methods, and events defined by a class
- Defining class The class defining the class member for which access is being specified
- Get access Permission to read the value of a property, controlled by the property GetAccess attribute
- Set access Permission to assign a value to a property; controlled by the property SetAccess attribute
- Method access Determines what other methods and functions can call the class method; controlled by the method Access attribute
- Listen access Permission to define listeners; controlled by the event ListenAccess attribute
- Notify access Permission to trigger events, controlled by the event NotifyAccess attribute

Possible Values for Access to Class Members

The following class member attributes can contain a list of classes:

- Properties Access, GetAccess, and SetAccess. For a list of all property attributes, see "Property Attributes" on page 8-8.
- Methods Access. For a list of all method attributes, see "Method Attributes" on page 9-4.
- Events ListenAccess and NotifyAccess. For a list of all event attributes, see "Event Attributes" on page 11-16.

These attributes accept these values:

- public Unrestricted access
- protected Access by defining class and its subclasses
- private Access by defining class only
- Access list A list of one or more classes. Only the defining class and the classes in the list have
 access to the class members to which the attribute applies. If you specify a list of classes, MATLAB
 does not allow access by any other class (that is, access is private, except for the listed classes).

Applications for Access Control Lists

Access control lists enable you to control access to specific class properties, methods, and events. Access control lists specify a list of classes to which you grant access to these class members.

This technique provides greater flexibility and control in the design of a system of classes. For example, use access control lists to define separate classes, but not allow access to class members from outside the class system.

Specify Access to Class Members

Specify the classes that are allowed to access a particular class member in the member access attribute statement. For example:

```
methods (Access = {?ClassName1,?ClassName2,...})
```

Use the class matlab.metadata.Class object to refer to classes in the access list. To specify more than one class, use a cell array of matlab.metadata.Class objects. Use the namespace name when referring to classes that are in namespaces.

Note Specify the matlab.metadata.Class objects explicitly (created with the? operator), not as values returned by functions or other MATLAB expressions.

How MATLAB Interprets Attribute Values

- Granting access to a list of classes restricts access to only:
 - The defining class
 - The classes in the list
 - Subclasses of the classes in the list
- Including the defining class in the access list gives all subclasses of the defining class access.
- MATLAB resolves references to classes in the access list only when the class is loaded. If MATLAB cannot find a class that is included in the access list, that class is effectively removed from access.
- MATLAB replaces unresolved matlab.metadata.Class entries in the list with empty matlab.metadata.Class objects.
- An empty access list (that is, an empty cell array) is equivalent to private access.

Specify Metaclass Objects

Generate the matlab.metadata.Class objects using only the? operator and the class name. Values assigned to the attributes cannot contain any other MATLAB expressions, including functions that return allowed attribute values:

- matlab.metadata.Class objects
- Cell arrays of matlab.metadata.Class objects
- The values public, protected, or private

Specify these values explicitly, as shown in the example code in this section.

Properties with Access Lists

These sample classes show the behavior of a property that grants read access (GetAccess) to a class. The GrantAccess class gives GetAccess to the NeedAccess class for the Prop1 property:

```
classdef GrantAccess
  properties (GetAccess = ?NeedAccess)
     Prop1 = 7
  end
end
```

The NeedAccess class defines a method that uses the value of the GrantAccess Prop1 value. The dispObj method is defined as a Static method, however, it could be an ordinary method.

```
classdef NeedAccess
  methods (Static)
    function dispObj(GrantAccessObj)
        disp(['Prop1 is: ',num2str(GrantAccessObj.Prop1)])
    end
  end
end
```

Get access to Prop1 is private so MATLAB returns an error if you attempt to access the property from outside the class definition. For example, from the command line:

```
a = GrantAccess;
a.Prop1
Getting the 'Prop1' property of the 'GrantAccess' class is not allowed.
```

However, MATLAB allows access to Prop1 by the NeedAccess class:

```
NeedAccess.dispObj(a)
Prop1 is: 7
```

Methods with Access Lists

Classes granted access to a method can:

- Call the method using an instance of the defining class.
- Define their own method with the same name (if not a subclass).
- Override the method in a subclass only if the superclass defining the method includes itself or the subclass in the access list.

These sample classes show the behavior of methods called from methods of other classes that are in the access list. The class AcListSuper gives the AcListNonSub class access to its m1 method:

```
classdef AcListSuper
  methods (Access = {?AcListNonSub})
    function obj = m1(obj)
        disp ('Method m1 called')
    end
  end
end
```

Because AcListNonSub is in the access list of m1, its methods can call m1 using an instance of AcListSuper:

```
classdef AcListNonSub
   methods
      function obj = nonSub1(obj,AcListSuper Obj)
         % Call m1 on AcListSuper class
         AcListSuper Obj.m1;
      function obj = m1(obj)
         % Define a method named m1
         disp(['Method m1 defined by ',class(obj)])
      end
   end
end
Create objects of both classes:
a = AcListSuper;
b = AcListNonSub;
Call the AcListSuper m1 method using an AcListNonSub method:
b.nonSub1(a);
Method m1 called
Call the AcListNonSub m1 method:
b.m1:
Method ml defined by AcListNonSub
```

Subclasses Without Access

Including the defining class in the access list for a method grants access to all subclasses derived from that class. When you derive from a class that has a method with an access list and that list does *not* include the defining class:

- Subclass methods cannot call the superclass method.
- Subclass methods can call the superclass method indirectly using an instance of a class that is in the access list.
- Subclasses cannot override the superclass method.
- Methods of classes that are in the superclass method access list, but that are not subclasses, can call the superclass method.

For example, AcListSub is a subclass of AcListSuper. The AcListSuper class defines an access list for method m1. However, this list does not include AcListSuper, so subclasses of AcListSuper do not have access to method m1:

```
classdef AcListSub < AcListSuper
  methods
    function obj = subl(obj,AcListSuper_Obj)
        % Access ml via superclass object (***NOT ALLOWED***)
        AcListSuper_Obj.ml;
end
function obj = sub2(obj,AcListNonSub_Obj,AcListSuper_obj)
        % Access ml via object that is in access list (is allowed)
        AcListNonSub_Obj.nonSub1(AcListSuper_Obj);</pre>
```

```
end
end
end
```

No Direct Call to Superclass Method

Attempting to call the superclass m1 method from the sub1 method results in an error because subclasses are not in the access list for m1:

Indirect Call to Superclass Method

You can call a superclass method from a subclass that does not have access to that method using an object of a class that is in the superclass method access list.

The AcListSub sub2 method calls a method of a class (AcListNonSub) that is on the access list for m1. This method, nonSub1, does have access to the superclass m1 method:

```
a = AcListSuper;
b = AcListNonSub;
c = AcListSub;
c.sub2(b,a);
```

No Redefining Superclass Method

When subclasses are not included in the access list for a method, those subclasses cannot define a method with the same name. This behavior is not the same as cases in which the method Access is explicitly declared as private.

For example, adding the following method to the AcListSub class definition produces an error when you attempt to instantiate the class.

```
methods (Access = {?AcListNonSub})
  function obj = m1(obj)
    disp('AcListSub m1 method')
  end
end

c = AcListSub;
Class 'AcListSub' is not allowed to override the method 'm1' because neither it nor its superclasses have been granted access to the method by class 'AcListSuper'.
```

Call Superclass from Listed Class Via Subclass

The AcListNonSub class is in the m1 method access list. This class can define a method that calls the m1 method using an object of the AcListSub class. While AcListSub is not in the access list for method m1, it is a subclass of AcListSuper.

For example, add the following method to the AcListNonSub class:

```
methods
   function obj = nonSub2(obj,AcListSub_Obj)
      disp('Call m1 via subclass object:')
      AcListSub_Obj.m1;
  end
end
```

Calling the nonSub2 method results in execution of the superclass m1 method:

```
b = AcListNonSub;
c = AcListSub;
b.nonSub2(c);
Call m1 via subclass object:
Method m1 called
```

This behavior is consistent with the behavior of any subclass object, which can substitute for an object of its superclass.

Abstract Methods with Access Lists

A class containing a method declared as Abstract is an abstract class. It is the responsibility of subclasses to implement the abstract method using the function signature declared in the class definition.

When an abstract method has an access list, only the classes in the access list can implement the method. A subclass that is not in the access list cannot implement the abstract method so that subclass is itself abstract.

See Also

Related Examples

- "Property Attributes" on page 8-8
- "Method Access List" on page 12-29
- "Event Access List" on page 12-30

Method Access List

This class declares an access list for the method Access attribute:

```
classdef MethodAccess
  methods (Access = {?ClassA, ?ClassB, ?MethodAccess})
    function listMethod(obj)
    ...
    end
end
end
```

The MethodAccess class specifies the following method access:

- Access to listMethod from an instance of MethodAccess by methods of the classes ClassA and ClassB.
- Access to listMethod from an instance of MethodAccess by methods of subclasses of MethodAccess, because of the inclusion of MethodAccess in the access list.
- Subclasses of ClassA and ClassB are allowed to define a method named listMethod, and MethodAccess is allowed to redefine listMethod. However, if MethodAccess was not in the access list, its subclasses could not redefine listMethod.

See Also

Related Examples

"Methods with Access Lists" on page 12-25

Event Access List

This class declares an access list for the event ListenAccess attribute:

```
classdef EventAccess
   events (NotifyAccess = private, ListenAccess = {?ClassA, ?ClassB})
      Event1
      Event2
   end
end
```

The class EventAccess specifies the following event access:

- Limits notify access for Event1 and Event2 to EventAccess; only methods of the EventAccess can trigger these events.
- Gives listen access for Event1 and Event2 to methods of ClassA and ClassB. Methods of EventAccess, ClassA, and ClassB can define listeners for these events. Subclasses of MyClass cannot define listeners for these events.

See Also

Related Examples

"Events and Listeners Syntax" on page 11-18

Handle Compatible Classes

In this section...

"Basic Knowledge" on page 12-31

"When to Use Handle-Compatible Classes" on page 12-31

"Handle Compatibility Rules" on page 12-31

"Identify Handle Objects" on page 12-32

Basic Knowledge

The material presented in this section builds on knowledge of the following information.

- "Design Subclass Constructors" on page 12-7
- "Subclassing Multiple Classes" on page 12-19
- "Comparison of Handle and Value Classes" on page 7-2

Key Concepts

Handle-compatible class — a class that you can include with handle classes in a class hierarchy, even if the class is not a handle class.

- All handle classes are handle-compatible.
- All superclasses of handle-compatible classes must also be handle compatible.

HandleCompatible — the class attribute that defines nonhandle classes as handle compatible.

When to Use Handle-Compatible Classes

Typically, when deriving a MATLAB class from other classes, all the superclasses are handle classes, or none of them are handle classes. However, there are situations in which a class provides some utility that is used by both handle and nonhandle subclasses. Because it is not legal to combine handle and nonhandle classes, the author of the utility class must implement two distinct versions of the utility.

The solution is to use handle-compatible classes. You can use handle-compatible classes with handle classes when forming sets of superclasses. Designate a class as handle compatible by using the HandleCompatible class attribute.

```
classdef (HandleCompatible) MyClass
   ...
end
```

Handle Compatibility Rules

Handle-compatible classes (that is, classes whose HandleCompatible attribute is set to true) follow these rules:

- All superclasses of a handle-compatible class must also be handle compatible
- If a class explicitly sets its <code>HandleCompatibility</code> attribute to <code>false</code>, then none of the class superclasses can be handle classes.

- If a class does not explicitly set its HandleCompatible attribute and, if any superclass is a handle, then all superclasses must be handle compatible.
- The HandleCompatible attribute is not inherited.

A class that does not explicitly set its HandleCompatible attribute to true is:

- A handle class if any of its superclasses are handle classes
- A value class if none of the superclasses are handle classes

Identify Handle Objects

To determine if an object is a handle object, use the isa function:

```
isa(obj,'handle')
```

See Also

Related Examples

"How to Define Handle-Compatible Classes" on page 12-33

How to Define Handle-Compatible Classes

```
In this section...

"What Is Handle Compatibility?" on page 12-33

"Subclassing Handle-Compatible Classes" on page 12-35
```

What Is Handle Compatibility?

A class is handle compatible if:

- · It is a handle class
- Its HandleCompatible attribute is set to true

The HandleCompatible class attribute identifies classes that you can combine with handle classes when specifying a set of superclasses.

Handle compatibility provides greater flexibility when defining abstract superclasses. For example, when using superclasses that support both handle and value subclasses, handle compatibility removes the need to define both a handle version and a nonhandle version of a class.

A Handle Compatible Class

In this example, the Utility class defines a method to reset property values to the default values defined in the respective class definition. This functionality is useful to both handle and value subclasses.

```
classdef (HandleCompatible) Utility
  methods
    function obj = resetDefaults(obj)
    mc = metaclass(obj);
    mp = mc.PropertyList;
    for k=1:length(mp)
        if mp(k).HasDefault && ~strcmp(mp(k).SetAccess,'private')
            obj.(mp(k).Name) = mp(k).DefaultValue;
        end
    end
    end
end
end
```

The Utility class is handle compatible. Therefore, you can use it in the derivation of classes that are either handle classes or value classes. See "Class Introspection and Metadata" for information on using meta-data classes.

Return Modified Objects

The resetDefaults method defined by the Utility class returns the object it modifies. When you call resetDefaults with a value object, the method must return the modified object. It is important to implement methods that work with both handle and value objects in a handle compatible superclass. See "Object Modification" on page 5-35 for more information on modifying handle and value objects.

Consider the behavior of a value class that subclasses the Utility class. The PropertyDefaults class defines three properties, all of which have default values:

```
classdef PropertyDefaults < Utility
  properties
    p1 = datestr(rem(now,1)) % Current time
    p2 = 'red' % Character vector
    p3 = pi/2 % Result of division operation
  end
end</pre>
```

Create a PropertyDefaults object. MATLAB evaluates the expressions assigned as default property values when the class is first loaded. MATLAB uses these same default values whenever you create an instance of this class in the current MATLAB session.

```
pd = PropertyDefaults

pd =

PropertyDefaults with properties:

   p1: ' 4:42 PM'
   p2: 'red'
   p3: 1.5708
```

Assign new values that are different from the default values:

```
pd.p1 = datestr(rem(now,1));
pd.p2 = 'green';
pd.p3 = pi/4;
```

All pd object property values now contain values that are different from the default values originally defined by the class:

```
pd

pd =

PropertyDefaults with properties:

p1: ' 4:45 PM'
p2: 'green'
p3: 0.7854
```

Call the resetDefaults method, which is inherited from the Utility class. Because the PropertyDefaults class is not a handle class, return the modified object.

```
pd = pd.resetDefaults

pd =

PropertyDefaults with properties:
   p1: ' 4:54 PM'
   p2: 'red'
   p3: 1.5708
```

If the PropertyDefaults class was a handle class, then you would not need to save the object returned by the resetDefaults method. To design a handle compatible class like Utility, ensure that all methods work with both kinds of classes.

Subclassing Handle-Compatible Classes

According to the rules described in "Handle Compatibility Rules" on page 12-31, when you combine a handle superclass with a handle-compatible superclass, the result is a handle subclass, which is handle compatible.

However, subclassing a handle-compatible class does not necessarily result in the subclass being handle compatible. Consider the following two cases, which demonstrate two possible results.

Combine Nonhandle Utility Class with Handle Classes

Define a class that subclasses a handle class and the handle-compatible Utility class discussed in "A Handle Compatible Class" on page 12-33. The HPropertyDefaults class has these characteristics:

- It is a handle class because it derives from handle.
- All its superclasses are handle compatible because handle classes are handle compatible by definition.

```
classdef HPropertyDefaults < handle & Utility
  properties
    GraphPrim = line
    Width = 1.5
    Color = 'black'
  end
end</pre>
```

The HPropertyDefaults class is handle compatible.

```
hpd = HPropertyDefaults;
mc = metaclass(hpd);
mc.HandleCompatible
ans =
```

Nonhandle Subclasses of a Handle-Compatible Class

If you subclass both a value class that is not handle compatible and a handle compatible class, the subclass is a nonhandle compatible value class. The ValueSub class:

- Is a value class (it does not derive from handle.)
- One of its superclasses is handle compatible (the Utility class).

```
classdef ValueSub < MException & Utility
  methods
    function obj = ValueSub(str1,str2)
        obj = obj@MException(str1,str2);
    end
end
end</pre>
```

The ValueSub class is a nonhandle-compatible value class because the MException class does not define the HandleCompatible attribute as true:

```
hv = ValueSub('MATLAB:narginchk:notEnoughInputs',...
      'Not enough input arguments.');
mc = metaclass(hv);
mc.HandleCompatible
ans =
     0
```

See Also

Related Examples

"Methods for Handle-Compatible Classes" on page 12-37

Methods for Handle-Compatible Classes

In this section... "Methods for Handle and Value Objects" on page 12-37 "Modify Value Objects in Methods" on page 12-37

Methods for Handle and Value Objects

Objects passed to methods of handle-compatible classes can be either handle or value objects. There are two different behaviors to consider when implementing methods for a class that operate on both handles and values:

- If an input object is a handle object and the method alters the handle object, these changes are visible to all workspaces that contain the same handle.
- If an input object is a value object, then changes to the object made inside the method affect only the value inside the method workspace.

Handle compatible methods generally do not alter input objects because the effects of such changes are not the same for handle and nonhandle objects.

See "Object Modification" on page 5-35 for information about modifying handle and value objects.

Modify Value Objects in Methods

If a method operates on both handle and value objects, the method must return the modified object. For example, the setTime method returns the object it modifies:

```
classdef (HandleCompatible) Util
  % Utility class that adds a time stamp
  properties
     TimeStamp
  end
  methods
     function obj = setTime(obj)
        obj.TimeStamp = now;
  end
  end
end
```

See Also

Related Examples

"Handle-Compatible Classes and Heterogeneous Arrays" on page 12-38

Handle-Compatible Classes and Heterogeneous Arrays

```
In this section...
"Heterogeneous Arrays" on page 12-38
"Methods Must Be Sealed" on page 12-38
"Template Technique" on page 12-38
```

Heterogeneous Arrays

A heterogeneous array contains objects of different classes. Members of a heterogeneous array have a common superclass, but can belong to different subclasses. See the matlab.mixin.Heterogeneous class for more information on heterogeneous arrays. The matlab.mixin.Heterogeneous class is a handle-compatible class.

Methods Must Be Sealed

You can invoke only those methods that are sealed by the common superclass on heterogeneous arrays (Sealed attribute set to true). Sealed methods prevent subclasses from overriding those methods and guarantee that methods called on heterogeneous arrays have the same definition for the entire array.

Subclasses cannot override sealed methods. In situations requiring subclasses to specialize methods defined by a utility class, you can employ the design pattern referred to as the template method.

Template Technique

Suppose that you implement a handle-compatible class that works with heterogeneous arrays. This approach enables you to seal public methods, while providing a way for each subclass to specialize how the method works on each subclass instance. In the handle-compatible class:

- Define a sealed method that accepts a heterogeneous array as input.
- Define a protected, abstract method that each subclass must implement.
- Within the sealed method, call the overridden method for each array element.

Each subclass in the heterogeneous hierarchy implements a concrete version of the abstract method. The concrete method provides specialized behavior required by the particular subclass.

The Printable class shows how to implement a template method approach:

```
classdef (HandleCompatible) Printable
   methods(Sealed)
      function print(aryIn)
         n = numel(aryIn);
         for k=1:n
            printElement(aryIn(k));
         end
      end
   end
   methods(Access=protected, Abstract)
```

```
printElement(objIn)
end
end
```

See Also

Related Examples

• "Handle Compatible Classes" on page 12-31

Subclasses of MATLAB Built-In Types

In this section...

"MATLAB Built-In Types" on page 12-40

"Built-In Types You Can Subclass" on page 12-40

"Why Subclass Built-In Types" on page 12-40

"Which Functions Work with Subclasses of Built-In Types" on page 12-41

"Behavior of Built-In Functions with Subclass Objects" on page 12-41

"Built-In Subclasses That Define Properties" on page 12-42

MATLAB Built-In Types

Built-in types represent fundamental kinds of data such as numeric arrays, logical arrays, and character arrays. Other built-in types like cell arrays and structures contain data belonging to any class.

Built-in types define methods that perform operations on objects of these classes. For example, you can perform operations on numeric arrays such as, sorting, arithmetic, and logical operations.

See "Fundamental MATLAB Classes" for more information on MATLAB built-in classes.

Note Defining a class with the same name as a built-in class is not supported.

Built-In Types You Can Subclass

You can subclass MATLAB numeric classes and the logical class. For a list of numeric types, see "Numeric Types".

You cannot subclass any class that has its Sealed attribute set to true. To determine if the class is Sealed, query the class metadata:

```
mc = ?ClassName;
mc.Sealed
```

A value of 0 indicates that the class is not Sealed and can be subclasses.

Why Subclass Built-In Types

Subclass a built-in class to extend the operations that you can perform on a particular class of data. For example, when you want to:

- Perform unique operations on class data
- Use methods of the built-in class and other built-in functions directly with objects of the subclass. For example, you do not need to reimplement all the mathematical operators if you derived from a class such as **double** that defines these operators.

Which Functions Work with Subclasses of Built-In Types

Consider a class that defines enumerations. It can derive from an integer class and inherit methods that enable you to compare and sort values. For example, integer classes like int32 support all the relational methods (eq. qe, qt, le, lt, ne).

To see a list of functions that the subclass has inherited as methods, use the methods function:

methods('SubclassName')

Generally, you can use an object of the subclass with any:

- · Inherited methods
- Functions that normally accept input arguments of the same class as the superclass.

Behavior of Built-In Functions with Subclass Objects

When you define a subclass of a built-in class, the subclass inherits all the methods defined by that built-in class. MATLAB also provides additional methods to subclasses of built-in classes that override several built-in functions.

Built-in functions and methods that work on built-in classes can behave differently when called with subclasses of built-in classes. Their behavior depends on which function you are using and whether your subclass defines properties.

Behavior Categories

When you call an inherited method on a subclass of a built-in class, the result depends on the nature of the operation performed by the method. The behaviors of these methods fit into several categories.

- Operations on data values return objects of the superclass. For example, if you subclass double
 and perform addition on two subclass objects, MATLAB adds the numeric values and returns a
 value of class double.
- Operations on the orientation or structure of the data return objects of the subclass. Methods that perform these kinds of operations include, reshape, permute, transpose, and so on.
- Converting a subclass object to a built-in class returns an object of the specified class. Functions such as uint32, double, char work with subclass objects the same as they work with built-in objects.
- Comparing objects or testing for inclusion in a specific set returns logical or built-in objects, depending on the function. Functions such as isequal, ischar, isobject work with subclass objects the same as they work with superclass objects.
- Indexing expressions return objects of the subclass. If the subclass defines properties, then default indexing no longer works. The subclass must define its own indexing methods.
- Concatenation returns an object of the subclass. If the subclass defines properties, then default concatenation no longer works and the subclass must define its own concatenation methods.

To list the built-in functions that work with a subclass of a built-in class, use the methods function.

Built-In Subclasses That Define Properties

When a subclass of a built-in class defines properties, MATLAB no longer supports indexing and concatenation operations. MATLAB cannot use the built-in functions normally called for these operations because subclass properties can contain any data.

The subclass must define what indexing and concatenation mean for a class with properties. If your subclass needs indexing and concatenation functionality, then the subclass must implement the appropriate methods.

Methods for Indexing

To support indexing operations, the subclass must implement these methods:

- subsasgn Implement dot notation and indexed assignments
- subsref Implement dot notation and indexed references
- subsindex Implement object as index value

Note Modular indexing mixin classes were introduced in R2021b, but these mixins are not compatible with subclasses of built-in classes. See "Code Patterns for subsref and subsasgn Methods" on page 17-9 for more information on how to implement subsref, subsasgn, and subsindex.

Methods for Concatenation

To support concatenation, the subclass must implement the following methods:

- horzcat Implement horizontal concatenation of objects
- vertcat Implement vertical concatenation of objects
- cat Implement concatenation of object arrays along specified dimension

See Also

Related Examples

- "Subclasses of Built-In Types with Properties" on page 12-53
- "Subclasses of Built-In Types Without Properties" on page 12-47

Behavior of Inherited Built-In Methods

```
In this section...

"Subclass double" on page 12-43

"Built-In Data Value Methods" on page 12-44

"Built-In Data Organization Methods" on page 12-44

"Built-In Indexing Methods" on page 12-45

"Built-In Concatenation Methods" on page 12-45
```

Subclass double

Most built-in functions used with built-in classes are actually methods of the built-in class. For example, the double and single classes define several methods to perform arithmetic operations, indexing, matrix operation, and so on. All these built-in class methods work with subclasses of the built-in class.

Subclassing double enables your class to use features without implementing the methods that a MATLAB built-in class defines.

The DocSimpleDouble class subclasses the built-in double class.

```
classdef DocSimpleDouble < double
  methods
    function obj = DocSimpleDouble(data)
    if nargin == 0
        data = 0;
    end
    obj = obj@double(data);
  end
end
end</pre>
```

Create an instance of the class DocSimpleDouble.

Call a method inherited from class double that operates on the data, such as sum. sum returns a double and, therefore, uses the display method of class double:

```
sum(sc)
ans =
```

Index sc like an array of doubles. The returned value is the class of the subclass:

```
a = sc(2:4)
a =
  1x3 DocSimpleDouble:
```

```
double data:
   2
        3
               4
```

Indexed assignment works the same as the built-in class. The returned value is the class of the subclass:

```
sc(1:5) = 5:-1:1
  1x10 DocSimpleDouble:
 double data:
                                       7
         4
                            1
                                 6
                                             8
                                                        10
```

Calling a method that modifies the order of the data elements operates on the data, but returns an object of the subclass:

```
sc = DocSimpleDouble(1:10);
sc(1:5) = 5:-1:1;
a = sort(sc)
  1x10 DocSimpleDouble:
 double data:
                                     7 8
    1
         2
               3
                     4
                          5
                               6
                                               9
                                                     10
```

Built-In Data Value Methods

When you call a built-in data value method on a subclass object, MATLAB uses the superclass part of the subclass object as inputs to the method. The value returned is same class as the built-in class. For example:

```
sc = DocSimpleDouble(1:10);
a = sin(sc);
class(a)
ans =
double
```

Built-In Data Organization Methods

This group of built-in methods reorders or reshapes the input argument array. These methods operate on the superclass part of the subclass object, but return an object of the same type as the subclass.

```
sc = DocSimpleDouble(randi(9,1,10))
sc = DocSimpleDouble(randi(9,1,10))
sc =
 1x10 DocSimpleDouble:
 double data:
                8
                      9
                           7
                                 7
                                       7
         1
                                              4
                                                   6
b = sort(sc)
```

Methods in this group include:

- reshape
- permute
- sort
- transpose
- ctranspose

Built-In Indexing Methods

When you use indexing to reference into an object that inherits from a built-in class, only the built-in data is referenced, not the properties defined by your subclass. You cannot make indexed references if your subclass defines properties, unless your subclass overrides the default subsref method.

For example, indexing element 2 in the DocSimpleDouble subclass object returns the second element in the vector.

```
sc = DocSimpleDouble(1:10);
a = sc(2)
a =
   DocSimpleDouble
   double data:
    2
```

The value returned from an indexing operation is an object of the subclass.

Assigning a new value to the second element in the DocSimpleDouble object operates only on the superclass data.

The subsref method also implements dot notation for methods.

Built-In Concatenation Methods

Built-in classes use the functions horzcat, vertcat, and cat to implement concatenation. When you use these functions with subclass objects of the same type, MATLAB concatenates the superclass data to form a new object. For example, you can concatenate objects of the DocSimpleDouble class:

```
sc1 = DocSimpleDouble(1:10);
sc2 = DocSimpleDouble(11:20);
[sc1,sc2]
```

```
ans =
 1x20 DocSimpleDouble:
 double data:
 Columns 1 through 13
                                                        10
                                                               11
                                                                     12
                                                                           13
 Columns 14 through 20
                           18
                                 19
   14 15
               16
                                       20
[sc1;sc2]
ans =
 2x10 DocSimpleDouble:
 double data:
                      4
                            5
                                                    9
                3
                                  6
                                              8
                                                         10
         12
                           15
                                       17
                                             18
   11
               13
                     14
                                 16
                                                   19
                                                         20
```

Concatenate two objects along a third dimension:

```
c = cat(3,sc1,sc2)
C =
 1x10x2 DocSimpleDouble:
 double data:
(:,:,1) =
     1
           2
                  3
                        4
                               5
                                     6
                                            7
                                                  8
                                                         9
                                                              10
(:,:,2) =
    11
          12
                 13
                              15
                                           17
                                                        19
                                                              20
                       14
                                    16
                                                 18
```

If the subclass of a built-in class defines properties, you cannot concatenate objects of the subclass. There is no way to determine how to combine properties of different objects. However, your subclass can define custom horzcat and vertcat methods to support concatenation in whatever way makes sense for your subclass.

See Also

Related Examples

- "Subclasses of Built-In Types Without Properties" on page 12-47
- "Subclasses of Built-In Types with Properties" on page 12-53

Subclasses of Built-In Types Without Properties

```
In this section...

"Specialized Numeric Types" on page 12-47

"A Class to Manage uint8 Data" on page 12-47

"Using the DocUint8 Class" on page 12-48
```

Specialized Numeric Types

Subclass built-in numeric types to create customized data types that inherit the functionality of the built-in type. Add functionality to that provided by the superclass by implementing class methods. Subclasses without properties store numeric data as the superclass type. If your subclass design does not require properties to store other data, the implementation is simpler because you do not need to define indexing and concatenation methods.

For more information, see "Subclasses of MATLAB Built-In Types" on page 12-40.

A Class to Manage uint8 Data

This example shows a class derived from the built-in uint8 class. This class simplifies the process of maintaining a collection of intensity image data defined by uint8 values. The basic operations of the class include:

- Capability to convert various classes of image data to uint8 to reduce object data storage.
- A method to display the intensity images contained in the subclass objects.
- Ability to use all the methods supported by uint8 data (for example, size, indexing, reshape, bitshift, cat, fft, arithmetic operators, and so on).

The class data are matrices of intensity image data stored in the superclass part of the subclass object. This approach requires no properties.

The DocUint8 class stores the image data, which converts the data, if necessary:


```
classdef DocUint8 < uint8</pre>
   methods
      function obj = DocUint8(data)
         if nargin == 0
            data = uint8(0);
         obj = obj@uint8(data); % Store data on superclass
      end
      function h = showImage(obj)
         data = uint8(obj);
         figure; colormap(gray(256))
         h = imagesc(data, [0 255]);
         axis image
         brighten(.2)
      end
  end
end
```

Using the DocUint8 Class

Create DocUint8 Objects

The DocUint8 class provides a method to display all images stored as DocUint8 objects in a consistent way. For example:

```
cir = imread('circuit.tif');
img1 = DocUint8(cir);
img1.showImage;
```



Because DocUint8 subclasses uint8, you can use any uint8 methods. For example,

```
size(img1)
ans =
         272
   280
```

returns the size of the image data.


Indexing Operations

Inherited methods perform indexing operations, but return objects of the same class as the subclass.

Therefore, you can index into the image data and call a subclass method:

```
showImage(img1(100:200,1:160));
```


Subscripted reference operations (controlled by the inherited subsref method) return a DocUint8 object.



You can assign values to indexed elements:

img1(100:120,140:160) = 255;img1.showImage;


Subscripted assignment operations (controlled by the inherited subsasgn method) return a DocUint8 object.



Concatenation Operations

Concatenation operations work on DocUint8 objects because this class inherits the uint8 horzcat and vertcat methods, which return a DocUint8 object:

showImage([img1 img1]);



Data Operations

Methods that operate on data values, such as arithmetic operators, always return an object of the built-in type (not of the subclass type). For example, multiplying DocUint8 objects returns a uint8 object, so calling showImage throws an error:

```
a = img1.*1.8;
showImage(a);
```

Check for missing argument or incorrect argument data type in call to function 'showImage'.

To perform operations of this type, implement a subclass method to override the inherited method. The times method implements array (element-by-element) multiplication.

Add this method to the DocUint8 class:


```
function o = times(obj,val)
  u8 = uint8(obj).*val;
  o = DocUint8(u8);
end
```

When you override a uint8 method, MATLAB calls the subclass method, not the base class method. The subclass method must:

- Call the uint8 times method on the DocUint8 object data.
- Construct a new DocUint8 object using the uint8 data.

After adding the times method to the DocUint8 class, the output of multiplication expressions is an object of the DocUint8 class:

showImage(img1.*1.8);



See Also

Related Examples

- "Operator Overloading" on page 17-19
- "Subclasses of Built-In Types with Properties" on page 12-53

Subclasses of Built-In Types with Properties

In this section...

"Specialized Numeric Types with Additional Data Storage" on page 12-53

"Subclasses with Properties" on page 12-53

"Property Added" on page 12-53

"Methods Implemented" on page 12-53

"Class Definition Code" on page 12-54

"Using ExtendDouble" on page 12-55

"Concatenation of ExtendDouble Objects" on page 12-58

Specialized Numeric Types with Additional Data Storage

Subclass built-in numeric types to create customized data types that inherit the functionality of the built-in type. Add or modify functionality to that provided by the superclass by implementing class methods.

Providing additional data storage in the subclass by defining properties can be a useful extension to the built-in data class. However, the addition of properties to the subclass requires the subclass to define methods to implement standard array behaviors.

For more information, see "Subclasses of MATLAB Built-In Types" on page 12-40.

Subclasses with Properties

When a subclass of a built-in class defines properties, default indexing and concatenation do not work. The default subsref, subsasgn, horzcat, and vertcat functions cannot work with unknown property types and values. Therefore, the subclass must define these behaviors by implementing these methods.

This sample implementation of the ExtendDouble class derives from the double class and defines a single property. The ExtendDouble class definition demonstrates how to implement indexing and concatenation for subclasses of built-in classes

Property Added

The ExtendDouble class defines the DataString property to contain text that describes the data. The superclass part of the class contains the numeric data.

Methods Implemented

The following methods modify the behavior of the ExtendDouble class:

- ExtendDouble The constructor supports a no argument syntax that initializes properties to empty values.
- subsref Enables subscripted reference to the superclass part of the subclass, dot notation reference to the DataString property, and dot notation reference the built-in data via the name Data.

- subsasgn Enables subscripted assignment to the superclass part of the subclass, dot notation reference to the DataString property, and dot notation reference the built-in data via the name Data.
- horzcat Defines horizontal concatenation of ExtendDouble objects. concatenates the superclass part using the double class horzcat method and forms a cell array of the DataString properties.
- vertcat The vertical concatenation equivalent of horzcat (both are required).
- char A ExtendDouble to char converter used by horzcat and vertcat.
- disp ExtendDouble implements a disp method to provide a custom display for the object.

Class Definition Code

The ExtendDouble class extends double and implements methods to support subscripted indexing and concatenation.

```
classdef ExtendDouble < double</pre>
   properties
      DataString
   end
   methods
      function obj = ExtendDouble(data,str)
         if nargin == 0
            data = 0;
            str = ''
         elseif nargin == 1
            str = '
         obj = obj@double(data);
         obj.DataString = str;
      end
      function sref = subsref(obj,s)
         switch s(1).type
            case '.
               switch s(1).subs
                  case 'DataString'
                      sref = obj.DataString;
                   case 'Data
                      d = double(obj);
                      if length(s)<2</pre>
                         sref = d;
                      elseif length(s)>1 && strcmp(s(2).type,'()')
                         sref = subsref(d,s(2:end));
                      end
                   otherwise
                      error('Not a supported indexing expression')
            case '()'
               d = double(obi);
               newd = subsref(d,s(1:end));
               sref = ExtendDouble(newd,obj.DataString);
            case '{}'
               error('Not a supported indexing expression')
```

```
end
      end
      function obj = subsasgn(obj,s,b)
         switch s(1).type
            case '.
               switch s(1).subs
                  case 'DataString'
                     obj.DataString = b;
                  case 'Data'
                     if length(s)<2</pre>
                         obj = ExtendDouble(b,obj.DataString);
                     elseif length(s)>1 && strcmp(s(2).type,'()')
                         d = double(obj);
                         newd = subsasgn(d,s(2:end),b);
                         obj = ExtendDouble(newd,obj.DataString);
                     end
                  otherwise
                     error('Not a supported indexing expression')
               end
            case '()'
               d = double(obj);
               newd = subsasgn(d,s(1),b);
               obj = ExtendDouble(newd,obj.DataString);
               error('Not a supported indexing expression')
         end
      end
      function newobj = horzcat(varargin)
         d1 = cellfun(@double, varargin, 'UniformOutput', false );
         data = horzcat(d1{:});
         str = horzcat(cellfun(@char,varargin,'UniformOutput',false));
         newobj = ExtendDouble(data,str);
      end
      function newobj = vertcat(varargin)
         d1 = cellfun(@double, varargin, 'UniformOutput', false );
         data = vertcat(d1{:});
         str = vertcat(cellfun(@char,vararqin,'UniformOutput',false));
         newobj = ExtendDouble(data,str);
      end
      function str = char(obj)
         str = obj.DataString;
      end
      function disp(obj)
         disp(obj.DataString)
         disp(double(obj))
      end
   end
end
```

Using ExtendDouble

Create an instance of ExtendDouble and notice that the display is different from the default:

```
ed = ExtendDouble(1:10, 'One to ten')
ed =
One to ten
            2
                  3
                                5
                                      6
                                             7
                                                                10
     1
                         4
                                                   8
```

Inherited Methods

The ExtendDouble class inherits methods from the class double. To see a list of all public methods defined by the double class, use the methods function:

```
methods(double.empty)
```

The sum function continues to operate on the superclass part of the object:

```
sum(ed)
ans =
    55
```

The sort function works on the superclass part of the object:

```
sort(ed(10:-1:1))
ans =
     1
            2
                   3
                          4
                                 5
                                        6
                                              7
                                                     8
                                                                  10
```

Arithmetic operators work on the superclass part of the object:

```
ed.^2
ans =
                   9
                                25
     1
            4
                         16
                                       36
                                             49
                                                    64
                                                           81
                                                                 100
```

Subscripted Indexing

Because the ExtendDouble class defines a property, the class must implement its own subsref and subsasgn methods.

This class implements the following subscripted indexing expressions for reference and assignment.

- obj.DataString access the DataString property.
- obj.Data, obj.Data(ind) access the data using a property-style reference. Reference returns values of type double.
- obj(ind) access the numeric data (same as obj.Data(ind)). Reference returns values of type ExtendDouble.

The class subsref method enables you to use ExtendDouble objects like numeric arrays to reference the numeric data:

```
ed = ExtendDouble(1:10, 'One to ten');
ed(10:-1:1)
ans =
```

```
One to ten

10 9 8 7 6 5 4 3 2 1
```

Access the numeric data of the ExtendDouble using property-style indexing with the arbitrarily chosen name Data:

```
ed.Data(10:-1:1)
ans =

One to ten
    10     9     8      7     6     5     4     3     2     1
```

Access the DataString property:

```
ed.DataString
```

```
ans =
One to ten
```

Subscripted assignment implements similar syntax in the class subsasgn method.

The ExtendDouble inherits converter methods from the double class. For example, MATLAB calls the char method to perform this assignment statement.

```
ed(11:13) = ['a','b','c']
ed =
one to thirteen
    1    2    3    4    5    6    7    8    9    10    97    98    99
```

Class of Value Returned by Indexing Expression

The ExtendDouble implements two forms of indexed reference in the subsref method:

- obj.Data and obj.Data(ind) Return values of class double
- obj(ind) Return values of class ExtendDouble

For example, compare the values returned by these expressions.

```
ed = ExtendDouble(1:10,'One to ten');
a = ed(1)
a =
One to ten
    1
b = ed.Data(1)
```

```
b =
    1
whos
                           Bytes Class
 Name
           Size
                                                  Attributes
           1x1
                             132 ExtendDouble
 b
           1×1
                               8 double
            1x10
                             204 ExtendDouble
```

The increased flexibility of the implementation of indexed reference in the ExtendDouble class.

Concatenation of ExtendDouble Objects

Create these two objects:

ed2

hcat

```
ed1 = ExtendDouble([1:10], 'One to ten');
ed2 = ExtendDouble([10:-1:1], 'Ten to one');
```

Concatenate these objects along the horizontal dimension:

```
hcat = [ed1, ed2]
hcat =
   'One to ten' 'Ten to one'
 Columns 1 through 13
 Columns 14 through 20
                         3
whos
  Name
             Size
                              Bytes Class
                                                      Attributes
  ed1
             1x10
                                 204 ExtendDouble
```

Vertical concatenation works in a similar way:

1x10

1x20

```
vcat = [ed1;ed2]
vcat =
    'One to ten' 'Ten to one'
           2
                 3
                       4
                             5
                                   6
                                                           10
                 8
                       7
                             6
                                   5
                                               3
                                                            1
```

Both horzcat and vertcat return a new object of the same class as the subclass.

204 ExtendDouble

528 ExtendDouble

See Also

Related Examples

• "Subclasses of Built-In Types Without Properties" on page 12-47

Use of size and numel with Classes

```
In this section...
"size and numel" on page 12-60
"Built-In Class Behavior" on page 12-60
"Subclasses Inherit Behavior" on page 12-61
"Classes Not Derived from Built-In Classes" on page 12-62
"Change the Behavior of size or numel" on page 12-63
"Overload numArgumentsFromSubscript Instead of numel" on page 12-64
```

size and numel

The size function returns the dimensions of an array. The numel function returns the number of elements in an array, which is equivalent to prod(size(objArray)). That is, the product of the array dimensions.

The size and numel functions work consistently with arrays of user-defined objects. There is generally no need to overload size or numel in user-defined classes.

Several MATLAB functions use size and numel to perform their operations. Therefore, if you do overload either of these functions in your class, be sure that objects of your class work as designed with other MATLAB functions.

If your class modifies array indexing, see "Overload numArgumentsFromSubscript Instead of numel" on page 12-64

Built-In Class Behavior

When you use the size and numel functions in classes derived from built-in classes, these functions behave the same as they behave in the superclass.

Consider the built-in class double:

```
d = 1:10;
size(d)
ans =
     1
          10
numel(d)
ans =
    10
dsub = d(7:end);
size(dsub)
ans =
     1
            4
```

The double class defines these behaviors, including parentheses indexing.

Subclasses Inherit Behavior

size(sdsub)

Unless the subclass explicitly overrides superclass behavior, subclasses behave like their superclasses. For example, SimpleDouble subclasses double and defines no properties:

```
classdef SimpleDouble < double</pre>
   methods
      function obj = SimpleDouble(data)
          if nargin == 0
             data = 0;
          obj = obj@double(data);
      end
   end
end
Create an object and assign the values 1:10:
sd = SimpleDouble(1:10);
The size function returns the size of the superclass part:
size(sd)
ans =
     1
           10
The numel function returns the number of elements in the superclass part:
numel(sd)
ans =
     10
Object arrays return the size of the superclass arrays:
size([sd;sd])
ans =
     2
           10
numel([sd;sd])
ans =
     20
The SimpleDouble class inherits the indexing behavior of the double class:
sdsub = sd(7:end);
```

```
ans =
     1
           4
```

Classes Not Derived from Built-In Classes

Consider a simple value class. This class does not inherit the array-like behaviors of the double class. For example:

```
classdef VerySimpleClass
   properties
      Value
   end
end
Create an object and assign a 10-element array to the Value property:
vs = VerySimpleClass;
vs.Value = 1:10;
size(vs)
ans =
    1 1
numel(vs)
ans =
     1
size([vs;vs])
ans =
     2
           1
numel([vs;vs])
ans =
     2
vs is a scalar object. The Value property is an array of doubles:
size(vs.Value)
ans =
     1 10
Apply indexing expressions to the object property:
vssub = vs.Value(7:end);
size(vssub)
ans =
     1 4
```

The vs. Value property is an array of class double:

MATLAB does not apply scalar expansion to object array property value assignment. Use the deal function for this purpose:

```
[vsArray.Value] = deal(1:10);
isempty([vsArray.Value])
ans =
0
```

The deal function assigns values to each Value property in the vsArray object array.

Indexing rules for object arrays are equivalent to the rules for arrays of struct:

Change the Behavior of size or numel

Subclasses of built-in numeric classes inherit a size method, which operates on the superclass part of the subclass object (these methods are hidden). If you want size or numel to behave differently, override them by defining a size or numel method in your subclass.

Other MATLAB functions use the values returned by these functions. If you change the way that size and numel behave, ensure that the values returned make sense for the intended use of your class.

Overload numArgumentsFromSubscript Instead of numel

If classes implement a numArgumentsFromSubscript method, MATLAB calls it instead of numel to determine the number of elements returned by indexed expressions that return comma-separated lists. For example, expressions such as:

A(1:2).Prop

Both subsref and subsasgn use numArgumentsFromSubscript:

- subsref numArgumentsFromSubscript computes the number of expected outputs (nargout) returned subsref.
- subsasgn numArgumentsFromSubscript computes the number of expected inputs (nargin) that MATLAB assigns as a result of a call to subsasgn.

Subclasses of built-in classes always return scalar objects as a result of subscripted reference and always use scalar objects for subscripted assignment.

If you define a class in which nargout for subsref or nargin for subsasgn must be a specific value, then overload numArgumentsFromSubscript to return that value.

See Also

numArgumentsFromSubscript

Determine Array Class

```
In this section...

"Query the Class Name" on page 12-65

"Test for Array Class" on page 12-65

"Test for Specific Types" on page 12-66

"Test for Subclasses of Built-in Types" on page 12-67
```

Query the Class Name

To determine the class of an array, use the class function:

```
a = [2,5,7,11];
class(a)
ans =
double
str = 'Character array';
class(str)
ans =
char
```

Test for Array Class

The isa function enables you to test for a specific class or a category of numeric class (numeric, float, integer):

```
a = [2,5,7,11];
isa(a,'double')
ans =
1
```

Floating-point values (single and double precision values):

```
isa(a,'float')
ans =
    1
```

Numeric values (floating-point and integer values):

```
isa(a,'numeric')
ans =
    1
```

isa Returns True for Subclasses

isa returns true for classes derived from the specified class. For example, the SubInt class derives
from the built-in type int16:

```
classdef SubInt < int16</pre>
   methods
      function obj = SubInt(data)
         if nargin == 0
             data = 0;
         end
         obj = obj@int16(data);
      end
   end
end
```

By definition, an instance of the SubInt class is also an instance of the int16 class:

```
aInt = SubInt;
isa(aInt,'int16')
ans =
     1
```

Using the integer category also returns true:

```
isa(aInt,'integer')
ans =
     1
```

For information on how to distinguish between built-in types and their subclasses, see "Test for Subclasses of Built-in Types" on page 12-67.

Test for Specific Types

The class function returns the name of the *most derived* class of an object:

```
class(aInt)
ans =
SubInt
```

Use the strcmp function with the class function to check for a specific class of an object:

```
a = int16(7);
strcmp(class(a),'int16')
ans =
    1
```

Because the class function returns the class name as a char vector, the inheritance does not affect the result of the comparison performed by strcmp:

```
aInt = SubInt;
strcmp(class(aInt),'int16')
ans =
     0
```

Test for Subclasses of Built-in Types

The isa function returns true for subclasses of the specified class. To define functions that require inputs that are MATLAB built-in types but exclude subclasses, use one of these techniques.

Test for Specific Types

Use strcmp and class to test for a specific built-in type. This conditional statement checks to see if inputArg is single, and if not, it attempts to convert inputArg to single.

```
if strcmp(class(inputArg),'single')
  % Call function
else
  inputArg = single(inputArg);
end
```

Test for a Category of Types

Suppose that you create a MEX-function, myMexFcn, that requires two numeric inputs that must be of type double or single.

```
outArray = myMexFcn(a,b)
```

Define a cell array that contains the character arrays double and single:

```
floatTypes = {'double','single'};
```

Use strcmp and class to test the inputs against the types specified in the cell array.

```
if any(strcmp(class(a),floatTypes)) && ...
    any(strcmp(class(b),floatTypes))
    outArray = myMexFcn(a,b);
else
    % Try to convert inputs to avoid error
    ...
end
```

Use isobject

Use isobject to separate built-in types from subclasses of built-in types. The isobject function returns false for instances of built-in types.

```
% Create a int16 array
a = int16([2,5,7,11]);
isobject(a)
ans =
0
```

This conditional tests if arr is an array is one of the built-in integer types.

```
if isa(arr,'integer') && ~isobject(arr)
  % if previous statement is true, arr is a built-in integer type
   ...
end
```

Abstract Classes and Class Members

In this section...

"Abstract Classes" on page 12-68

"Declare Classes as Abstract" on page 12-68

"Determine If a Class Is Abstract" on page 12-70

"Find Inherited Abstract Properties and Methods" on page 12-70

Abstract Classes

Abstract classes are useful for describing functionality that is common to a group of classes, but requires unique implementations within each class.

Abstract Class Terminology

abstract class — A class that cannot be instantiated, but that defines class components used by subclasses.

abstract members — Properties or methods declared in an abstract class, but implemented in subclasses.

concrete class — A class that can be instantiated. Concrete classes contain no abstract members.

concrete members — Properties or methods that are fully implemented by a class.

interface — An abstract class describing functionality that is common to a group of classes, but that requires unique implementations within each class. The abstract class defines the interface of each subclass without specifying the actual implementation.

An abstract class serves as a basis (that is, a superclass) for a group of related subclasses. An abstract class can define abstract properties and methods that subclasses implement. Each subclass can implement the concrete properties and methods in a way that supports their specific requirements.

Implementing a Concrete Subclass

A subclass must implement all inherited abstract properties and methods to become a concrete class. Otherwise, the subclass is itself an abstract class.

MATLAB does not force subclasses to implement concrete methods with the same signature or attributes.

Abstract classes:

- Can define properties and methods that are not abstract
- Pass on their concrete members through inheritance
- · Do not need to define any abstract members

Declare Classes as Abstract

A class is abstract when it declares:

- The Abstract class attribute
- · An abstract method
- An abstract property

If a subclass of an abstract class does not define concrete implementations for all inherited abstract methods or properties, it is also abstract.

Abstract Class

Declare a class as abstract in the classdef statement:

```
classdef (Abstract) AbsClass
    ...
end
```

For classes that declare the Abstract class attribute:

- Concrete subclasses must redefine any properties or methods that are declared as abstract.
- The abstract class does not need to define any abstract methods or properties.

When you define any abstract methods or properties, MATLAB automatically sets the class Abstract attribute to true.

Abstract Methods

Define an abstract method:

```
methods (Abstract)
  abstMethod(obj)
end
```

For methods that declare the Abstract method attribute:

- Do not use a function...end block to define an abstract method, use only the method signature.
- Abstract methods have no implementation in the abstract class.
- Concrete subclasses are not required to support the same number of input and output arguments and do not need to use the same argument names. However, subclasses generally use the same signature when implementing their version of the method.
- Abstract methods cannot define arguments blocks.

Abstract Properties

Define an abstract property:

```
properties (Abstract)
  AbsProp
end
```

For properties that declare the Abstract property attribute:

- Concrete subclasses must redefine abstract properties without the Abstract attribute.
- Concrete subclasses must use the same values for the SetAccess and GetAccess attributes as those attributes used in the abstract superclass.

 Abstract properties cannot define access methods and cannot specify initial values. The subclass that defines the concrete property can create access methods and specify initial values.

For more information on access methods, see "Property Get and Set Methods" on page 8-39.

Determine If a Class Is Abstract

Determine if a class is abstract by querying the Abstract property of its matlab.metadata.Class object. For example, the AbsClass defines two abstract methods:

```
classdef AbsClass
   methods(Abstract)
      result = absMethodOne(obj)
      output = absMethodTwo(obj)
   end
end
```

Use the logical value of the matlab.metadata.Class Abstract property to determine if the class is abstract:

```
mc = ?AbsClass:
if ~mc.Abstract
   % not an abstract class
end
```

Display Abstract Member Names

Use the matlab.metadata.abstractDetails function to display the names of abstract properties or methods and the names of the defining classes:

```
matlab.metadata.abstractDetails('AbsClass');
Abstract methods for class AbsClass:
  absMethodTwo % defined in AbsClass
  absMethodOne % defined in AbsClass
```

Find Inherited Abstract Properties and Methods

The matlab.metadata.abstractDetails function returns the names and defining class of any inherited abstract properties or methods that you have not implemented in your subclass. Use this function if you want the subclass to be concrete and must determine what abstract members the subclass inherits.

For example, suppose that you create a subclass of the AbsClass class that is defined in the previous section. In this case, the subclass implements only one of the abstract methods defined by AbsClass.

```
classdef SubAbsClass < AbsClass</pre>
% Does not implement absMethodOne
% defined as abstract in AbsClass
   methods
      function out = absMethodTwo(obj)
      end
   end
end
```

Determine if you implemented all inherited class members using matlab.metadata.abstractDetails:

```
matlab.metadata.abstractDetails(?SubAbsClass)
```

```
Abstract methods for class SubAbsClass:
absMethodOne % defined in AbsClass
```

The SubAbsClass class is abstract because it has not implemented the absMethodOne method defined in AbsClass.

```
msub = ?SubAbsClass;
msub.Abstract
ans =
1
```

If you implement both methods defined in AbsClass, the subclass becomes concrete.

See Also

Related Examples

"Define an Interface Superclass" on page 12-72

Define an Interface Superclass

In this section...

"Interfaces" on page 12-72

"Interface Class Implementing Graphs" on page 12-72

Interfaces

The properties and methods defined by a class form the interface that determines how class users interact with objects of the class. When creating a group of related classes, interfaces define a common interface to all these classes. The actual implementations of the interface can differ from one class to another.

Consider a set of classes designed to represent various types of graphs. All classes must implement a Data property to contain the data used to generate the graph. However, the form of the data can differ considerably from one type of graph to another. Each class can implement the Data property differently.

The same differences apply to methods. All classes can have a draw method that creates the graph, but the implementation of this method changes with the type of graph.

The basic idea of an interface class is to specify the properties and methods that each subclass must implement without defining the actual implementation. This approach enables you to enforce a consistent interface to a group of related objects. As you add more classes in the future, the interface remains the same.

Interface Class Implementing Graphs

This example creates an interface for classes used to represent specialized graphs. The interface is an abstract class that defines properties and methods that the subclasses must implement, but does not specify how to implement these components.

This approach enforces the use of a consistent interface while providing the necessary flexibility to implement the internal workings of each specialized subclass differently.

In this example, a namespace folder contains the interface, derived subclasses, and a utility function:

```
+graphics/GraphInterface.m % abstract interface class
+graphics/LineGraph.m
                            % concrete subclass
```

Interface Properties and Methods

The GraphInterface class specifies the following properties, which the subclasses must define:

- Primitive Handle of the graphics object used to implement the specialized graph. The class user has no need to access these objects directly so this property has protected SetAccess and
- AxesHandle Handle of the axes used for the graph. The specialized graph objects can set axes object properties. This property has protected SetAccess and GetAccess.
- Data All subclasses of the GraphInterface class must store data. The type of data varies and each subclass defines the storage mechanism. Subclass users can change the data values so this property has public access rights.

The GraphInterface class names three abstract methods that subclasses must implement. The GraphInterface class also suggests in comments that each subclass constructor must accept the plot data and property name/property value pairs for all class properties.

- Subclass constructor Accept data and P/V pairs and return an object.
- draw Used to create a drawing primitive and render a graph of the data according to the type of graph implemented by the subclass.
- zoom Implementation of a zoom method by changing the axes CameraViewAngle property. The interface suggests the use of the camzoom function for consistency among subclasses. The zoom buttons created by the addButtons static method use this method as a callback.
- updateGraph Method called by the set.Data method to update the plotted data whenever the Data property changes.

Interface Guides Class Design

The namespace of classes that derive from the GraphInterface abstract class implement the following behaviors:

- Creating an instance of a specialized GraphInterface object (subclass object) without rendering the plot
- Specifying any or none of the object properties when you create a specialized GraphInterface object
- Changing any object property automatically updates the currently displayed plot
- Allowing each specialized GraphInterface object to implement whatever additional properties it requires to give class users control over those characteristics.

Define the Interface

The GraphInterface class is an abstract class that defines the methods and properties used by the subclasses. Comments in the abstract class describe the intended implementation:

```
classdef GraphInterface < handle</pre>
   % Abstract class for creating data graphs
   % Subclass constructor should accept
   % the data that is to be plotted and
   % property name/property value pairs
   properties (SetAccess = protected, GetAccess = protected)
      Primitive
      AxesHandle
   end
   properties
      Data
   end
   methods (Abstract)
      draw(obj)
      % Use a line, surface,
      % or patch graphics primitive
      zoom(obj,factor)
      % Change the CameraViewAngle
      % for 2D and 3D views
      % use camzoom for consistency
      updateGraph(obi)
      % Update the Data property and
      % update the drawing primitive
```

```
end
   methods
      function set.Data(obj,newdata)
         obj.Data = newdata;
         updateGraph(obj)
      function addButtons(gobj)
         hfig = get(gobj.AxesHandle,'Parent');
         uicontrol(hfig, 'Style', 'pushbutton', 'String', 'Zoom Out',...
             Callback',@(src,evnt)zoom(gobj,.5));
         uicontrol(hfig, 'Style', 'pushbutton', 'String', 'Zoom In',...
             'Callback',@(src,evnt)zoom(gobj,2),...
            'Position',[100 20 60 20]);
      end
   end
end
```

The GraphInterface class implements the property set method (set.Data) to monitor changes to the Data property. An alternative is to define the Data property as Abstract and enable the subclasses to determine whether to implement a set access method for this property. The GraphInterface class defines a set access method that calls an abstract method (updateGraph, which each subclass must implement). The GraphInterface interface imposes a specific design on the whole namespace of classes, without limiting flexibility.

Method to Work with All Subclasses

The addButtons method adds push buttons for the zoom methods, which each subclass must implement. Using a method instead of an ordinary function enables addButtons to access the protected class data (the axes handle). Use the object zoom method as the push-button callback.

```
function addButtons(gobj)
   hfig = get(gobj.AxesHandle, 'Parent');
   uicontrol(hfig,'Style','pushbutton',...
      'String','Zoom Out',...
      'Callback',@(src,evnt)zoom(gobj,.5));
   uicontrol(hfig, 'Style', 'pushbutton',...
      'String','Zoom In',...
      'Callback',@(src,evnt)zoom(gobj,2),...
      'Position',[100 20 60 20]);
end
```

Derive a Concrete Class — LineGraph

This example defines only a single subclass used to represent a simple line graph. It derives from GraphInterface, but provides implementations for the abstract methods draw, zoom, updateGraph, and its own constructor. The base class GraphInterface and subclass are all contained in a namespace (graphics), which you must use to reference the class name:

```
classdef LineGraph < graphics.GraphInterface</pre>
```

Add Properties

The LineGraph class implements the interface defined in the GraphInterface class and adds two additional properties—LineColor and LineType. This class defines initial values for each property, so specifying property values in the constructor is optional. You can create a LineGraph object with no data, but you cannot produce a graph from that object.

```
properties
  LineColor = [0 0 0];
  LineType = '-';
end
```

The LineGraph Constructor

The constructor accepts a struct with x and y coordinate data, and property name/property value pairs:

```
function gobj = LineGraph(data,varargin)
  if nargin > 0
    gobj.Data = data;
  if nargin > 2
    for k=1:2:length(varargin)
        gobj.(varargin{k}) = varargin{k+1};
    end
  end
end
end
```

Implement the draw Method

The LineGraph draw method uses property values to create a line object. The LineGraph class stores the line handle as protected class data. To support the use of no input arguments for the class constructor, draw checks the Data property to determine if it is empty before proceeding:

```
function gobj = draw(gobj)
  if isempty(gobj.Data)
    error('The LineGraph object contains no data')
  end
  h = line(gobj.Data.x,gobj.Data.y,...
    'Color',gobj.LineColor,...
    'LineStyle',gobj.LineType);
  gobj.Primitive = h;
  gobj.AxesHandle = get(h,'Parent');
end
```

Implement the zoom Method

The LineGraph zoom method follows the comments in the GraphInterface class which suggest using the camzoom function. camzoom provides a convenient interface to zooming and operates correctly with the push buttons created by the addButtons method.

Define the Property Set Methods

Property set methods provide a convenient way to execute code automatically when the value of a property changes for the first time in a constructor. (See "Property Get and Set Methods" on page 8-39.) The linegraph class uses set methods to update the line primitive data (which causes a redraw of the plot) whenever a property value changes. The use of property set methods provides a way to update the data plot quickly without requiring a call to the draw method. The draw method updates the plot by resetting all values to match the current property values.

Three properties use set methods: LineColor, LineType, and Data. LineColor and LineType are properties added by the LineGraph class and are specific to the line primitive used by this class. Other subclasses can define different properties unique to their specialization (for example, FaceColor).

The GraphInterface class implements the Data property set method. However, the GraphInterface class requires each subclass to define a method called updateGraph, which handles the update of plot data for the specific drawing primitive used.

The LineGraph Class

Here is the LineGraph class definition.


```
classdef LineGraph < graphics.GraphInterface</pre>
   properties
      LineColor = [0 \ 0 \ 0]
      LineType = '-'
   end
   methods
      function gobj = LineGraph(data, varargin)
         if nargin > 0
            gobj.Data = data;
            if nargin > 1
                for k=1:2:length(varargin)
                   gobj.(varargin{k}) = varargin{k+1};
                end
            end
         end
      end
      function gobj = draw(gobj)
         if isempty(gobj.Data)
            error('The LineGraph object contains no data')
         h = line(gobj.Data.x,gobj.Data.y,...
            'Color',gobj.LineColor,...
            'LineStyle',gobj.LineType);
         gobj.Primitive = h;
         gobj.AxesHandle = h.Parent;
      end
      function zoom(gobj,factor)
         camzoom(gobj.AxesHandle,factor)
      end
      function updateGraph(gobj)
         set(gobj.Primitive,...
             'XData',gobj.Data.x,...
            'YData',gobj.Data.y)
      end
      function set.LineColor(gobj,color)
         gobj.LineColor = color;
         set(gobj.Primitive,'Color',color)
      end
      function set.LineType(gobj,ls)
         gobj.LineType = ls;
         set(gobj.Primitive,'LineStyle',ls)
      end
   end
end
```

Use the LineGraph Class

The LineGraph class defines the simple API specified by the graph base class and implements its specialized type of graph:

```
d.x = 1:10;
d.y = rand(10,1);
lg = graphics.LineGraph(d,'LineColor','b','LineType',':');
lg.draw;
lg.addButtons;
```


Clicking the **Zoom In** button shows the **zoom** method providing the callback for the button.



Changing properties updates the graph:

```
d.y = rand(10,1);
lg.Data = d;
lg.LineColor = [0.9,0.1,0.6];
```

Now click **Zoom Out** and see the new results:



See Also

Related Examples

"Abstract Classes and Class Members" on page 12-68

Saving and Loading Objects

- "Default Save and Load Process for Objects" on page 13-2
- "Avoid Property Initialization Order Dependency" on page 13-4
- "When to Customize the Serialization Process" on page 13-7
- "Maintain Backward and Forward Compatibility Between Class Definitions" on page 13-9
- "Serialization with Class Hierarchies" on page 13-13
- "Transitioning Serialization and Deserialization Processes to matlab.mixin.CustomElementSerialization" on page 13-17
- "Code Patterns for saveobj and loadobj" on page 13-24

Default Save and Load Process for Objects

In this section...

"Save and Load Functions" on page 13-2

"What Information Is Saved?" on page 13-2

"How Is the Property Data Loaded?" on page 13-2

MATLAB follows a default set of steps when serializing (saving) and deserializing (loading) objects. This topic describes the default steps MATLAB uses for classes that have not implemented customized serialization. For more information on customizing serialization, see "When to Customize the Serialization Process" on page 13-7.

Save and Load Functions

Use save and load to serialize and describlize objects. These are the basic syntaxes.

```
save("filename","variablename")
load("filename","variablename")
```

What Information Is Saved?

Serializing objects in MAT-files stores:

- The full name of the object class, including any namespace qualifiers.
- · Values of dynamic properties.
- All property default values defined by the class at the time the first object of the class is saved to the MAT-file.
- The names and values of all properties, with these exceptions:
 - Properties are not saved if their current values are the same as the default values specified in the class definition.
 - Properties are not saved if they are defined as transient, constant, or dependent. For a description of these property attributes, see "Property Attributes" on page 8-8.

How Is the Property Data Loaded?

When deserializing objects from MAT-files, the load function restores the object using these steps:

- load creates a new object.
- If the class ConstructOnLoad attribute is set to true, load calls the class constructor with no arguments. Otherwise, load does not call the class constructor.
- load assigns the saved property values to the object (except in the case of dependent, constant, or transient properties, which are not saved by default). If the class defines set methods for any of the properties, MATLAB calls them. The property values must satisfy any property validation defined by the current definition of the class. For information, see "Property Get and Set Methods" on page 8-39 and "Validate Property Values" on page 8-19.
- load assigns the default values saved in the MAT file to properties whose values were not saved because the properties were set to their default values. These assignments result in calls to property set methods defined by the class.

- If a property of an object being loaded contains an object, then load creates a new object of the same class and assigns it to the property.
- If one or more properties of the object were renamed or removed from the class definition since the object was serialized, the load function reconstitutes the object without those changed properties.
- If the validation is changed for one or more properties and the saved values are no longer valid, MATLAB substitutes the currently defined default value for that property.

See Also

save | load

Related Examples

• "Property Attributes" on page 8-8

Avoid Property Initialization Order Dependency

```
In this section...

"Control Property Loading" on page 13-4

"Dependent Property with Private Storage" on page 13-4

"Property Value Computed from Other Properties" on page 13-6
```

Control Property Loading

Problems can occur if property values depend on the order in which load sets the property values.

Suppose that your class design is such that both of the following are true:

- A property set method changes another property value.
- A property value is computed from other property values.

Then the final state of an object after changing a series of property values can depend on the order in which you set the properties. This order dependency can affect the result of loading an object.

The load function sets property values in a particular order. This order can be different from the order in which you set the properties in the saved object. As a result, the loaded object can have different property values than the object had when it was saved.

Restore Nondependent Properties

If a property set function changes the values of other properties, then define the Dependent attribute of that property as true. MATLAB does not save or restore dependent property values.

Use nondependent properties for storing the values set by the dependent property. Then the load function restores the nondependent properties with the same values that were saved. The load function does not call the dependent property set method because there is no value in the saved file for that property.

Dependent Property with Private Storage

The **Odometer** class avoids order dependences when loading objects by controlling which properties are restored when loading:

- The Units property is dependent. Its property set method sets the TotalDistance property. Therefore load does not call the Units property set method.
- The load function restores TotalDistance to whatever value it had when you saved the object.

```
classdef Odometer
  properties(Constant)
     ConversionFactor = 1.6
  end
  properties
     TotalDistance = 0
  end
```

```
properties(Dependent)
      Units
   end
   properties(Access=private)
      PrivateUnits = 'mi'
   end
   methods
      function unit = get.Units(obj)
         unit = obj.PrivateUnits;
      function obj = set.Units(obj,newUnits)
         % validate newUnits to be a char vector
         switch(newUnits)
            case 'mi'
               if strcmp(obj.PrivateUnits,'km')
                  obj.TotalDistance = obj.TotalDistance / ...
                     obj.ConversionFactor;
                  obj.PrivateUnits = newUnits;
               end
            case 'km'
               if strcmp(obj.PrivateUnits,'mi')
                  obj.TotalDistance = obj.TotalDistance * ...
                     obj.ConversionFactor;
                  obj.PrivateUnits = newUnits;
               end
            otherwise
               error('Odometer:InvalidUnits', ...
                  'Units ''%s'' is not supported.', newUnits);
         end
      end
   end
end
```

Suppose that you create an instance of Odometer and set the following property values:

```
od0bj = Odometer;
od0bj.Units = 'km';
od0bj.TotalDistance = 16;
```

When you save the object:

- ConversionFactor is not saved because it is a Constant property.
- TotalDistance is saved.
- Units is not saved because it is a Dependent property.
- PrivateUnits is saved and provides the storage for the current value of Units.

When you load the object:

- ConversionFactor is obtained from the class definition.
- TotalDistance is loaded.
- Units is not loaded, so its set method is not called.
- PrivateUnits is loaded from the saved object.

If the Units property was not Dependent, loading it calls its set method and causes the TotalDistance property to be set again.

Property Value Computed from Other Properties

The Odometer2 class TripDistance property depends only on the values of two other properties, TotalDistance and TripMarker.

The class avoids order dependence when initializing property values during the load process by making the TripDistance property dependent. MATLAB does not save or load a value for the TripDistance property, but does save and load values for the two properties used to calculate TripDistance in its property get method.

```
classdef Odometer2
  properties
    TotalDistance = 0
    TripMarker = 0
  end
  properties(Dependent)
    TripDistance
  end
  methods
    function distance = get.TripDistance(obj)
       distance = obj.TotalDistance - obj.TripMarker;
  end
  end
end
```

See Also

Related Examples

- "When to Customize the Serialization Process" on page 13-7
- "Object Save and Load"

When to Customize the Serialization Process

Supporting backward and forward compatibility of classes is the primary reason to customize the serialization (saving) and deserialization (loading) process for objects. Customize the serialization process when you change a class definition, including but not limited to:

- · Renaming properties
- Adding or removing properties
- Changing validation for properties

How to Modify the Serialization Process

MATLAB includes two ways to customize the serialization process:

- Inherit from matlab.mixin.CustomElementSerialization.
- Implement loadobj and saveobj methods.

The recommended process for customizing serialization is to inherit from matlab.mixin.CustomElementSerialization. This mixin, combined with the functionality of matlab.serialization.ElementSerializationContent and matlab.serialization.SerializationContext, enables you to control what information is serialized and deserialized. This control supports robust backward and forward compatibility between different versions of the same class. matlab.serialization.SerializationContext can be useful when serializing to destinations other than MAT files. matlab.mixin.CustomElementSerialization also supports the addition of dynamic properties during serialization, which loadobj and saveobj do not.

Use loadobj and saveobj when:

- You have an existing implementation of saveobj that serializes data in a type other than an object or a struct, and your loadobj implementation can only deserialize data from that particular type.
- You have an existing implementation of loadobj that can only handle structure inputs. Revising your class to use matlab.mixin.CustomElementSerialization can break forward compatibility when the revised class saves data as an object because loadobj in the older class definition might not be able to load all properties. See "Transitioning Serialization and Deserialization Processes to matlab.mixin.CustomElementSerialization" on page 13-17 for more information.
- You are using a MATLAB release older than R2024b.

See Also

```
matlab.mixin.CustomElementSerialization |
matlab.serialization.ElementSerializationContent |
matlab.serialization.SerializationContext | loadobj | saveobj
```

Related Examples

"Object Save and Load"

"Transitioning Serialization and Deserialization Processes to matlab.mixin.CustomElementSerialization" on page 13-17

Maintain Backward and Forward Compatibility Between Class Definitions

Revising a class definition can lead to errors when trying to deserialize instances of a different version of that class using the default load process. When changing a class definition, you can inherit from matlab.mixin.CustomElementSerialization and use it to control how the new class definition serializes and deserializes instances to preserve compatibility. The general process is:

- When you revise your class definition in a way that breaks compatibility with the older version, add matlab.mixin.CustomElementSerialization as a superclass.
- If you need to change how objects of the revised class are serialized, implement the modifyOutgoingSerializationContent method of matlab.mixin.CustomElementSerialization. The method takes an instance of matlab.serialization.ElementSerializationContent as input. That object represents what will be serialized, and the methods of matlab.serialization.ElementSerializationContent enable you to change how properties are serialized.
- If you need to change how objects of the revised class are deserialized, implement the modifyIncomingSerializationContent method of matlab.mixin.CustomElementSerialization. The method takes an instance of the matlab.serialization.ElementSerializationContent class as input. That object represents what will be deserialized, and the methods of matlab.serialization.ElementSerializationContent enable you to change how properties are deserialized.
- If you need to perform any final operations on the descrialized object, such as adding an event listener, implement the finalizeIncomingObject method of matlab.mixin.CustomElementSerialization. The method takes the descrialized object as input.

Backward Compatibility

Define a class Employee that stores basic information. The EmployeeID property is stored as a string with "ID-" at the beginning, as shown by the default value.

```
classdef Employee
    properties
    Name
    Department
    EmployeeID = "ID-0000"
    Email
    end
end
```

Create an instance of Employee, assign values to all the properties, and save it. Replace yourfilepath with your local path.

```
e0ld = Employee;
e0ld.Name = "Alex Cruz";
e0ld.Department = "Sales";
e0ld.EmployeeID = "ID-1301"
e0ld.Email = "acruz@notacompany.com"
save("yourfilepath/oldEmployee.mat","e0ld");
```

Update the class definition with new and redefined properties:

- Split Name into FirstName and LastName.
- Change Department to Division.
- Remove the "ID-" prefix from the EmployeeID property.

Trying to describilize an object that was serialized under the old definition would leave some properties without proper values. To keep the old objects as accessible as possible, add matlab.mixin.CustomElementSerialization as a superclass and implement the static method modifyIncomingSerialization to convert the old property data into the new format as needed.

```
classdef Employee < matlab.mixin.CustomElementSerialization</pre>
    properties
        LastName
        FirstName
        EmployeeID
        Division
        Email
    end
   methods (Static)
        function modifvIncomingSerializationContent(s0bi)
            if s0bj.hasNameValue("Name")
                nameArray = split(s0bj.Name);
                s0bj.addNameValue("FirstName", nameArray(1));
                s0bj.addNameValue("LastName", nameArray(2));
                s0bj.remove("Name");
                s0bj.rename("Department", "Division");
                id = split(sObj.EmployeeID,"-");
                s0bj.updateValue("EmployeeID",id(2));
            end
        end
   end
end
```

MATLAB calls modifyIncomingSerializationContent when you load an object of Employee. The method takes as input an instance of

matlab.serialization.ElementSerializationContent. The hasNameValue method of matlab.serialization.ElementSerializationContent checks to see if the saved object has a property called Name. If there is a Name property, the object being deserialized was serialized under the old class definition. In that case, the methods of

matlab.serialization.ElementSerializationContent convert and assign the old property
data into the revised properties:

- The value of the Name property is split into an array of two strings, and the addNameValue method adds the FirstName and LastName properties. remove discards the old property Name.
- The rename method changes Department to Division.
- The updateValue method changes the value of the EmployeeID property to include only the numeric portion.

Clear e0ld from memory.

```
clear("e0ld")
```

Remove the old definition of Employee from your path. Add the revised definition of Employee to the path, and load the e0ld object. Display the object to confirm that the variable has been deserialized as an object of the revised definition of Employee.

```
load("yourfilepath/oldEmployee.mat","e0ld")
e0ld
e0ld =
   Employee with properties:
        LastName: "Cruz"
        FirstName: "Alex"
        EmployeeID: "1301"
        Division: "Sales"
        Email: "acruz@notacompany.com"
```

matlab.mixin.CustomElementSerialization also provides a static finalizeIncomingObject method. If the method is implemented, MATLAB calls it after modifyIncomingSerializationContent. Use the method to perform any necessary cleanup on the deserialized object, like restoring property listeners, for example. In the case of Employee, finalizeIncomingObject could be used to fill in the unknown value for EmployeeID if the method has access to that data from other sources.

The modifyOutgoingSerializationContent method also has an optional input argument, an instance of matlab.serialization.SerializationContext. An instance of this class can be used to determine the context in which the object is being serialized. For example, MATLAB sets the CustomizeForReadability property of the instance to true if the serialized object is readable by external users.

For an additional example on preserving backward compatibility, see "Load Serialized Objects After Changing Class Definition".

Forward Compatibility

The latest version of Employee can now successfully deserialize objects saved under the older version of the class, but the class does not have forward compatibility. In other words, someone who only has access to the older version of the class cannot successfully deserialize an object serialized under the latest version of the class.

To support forward compatibility, implement the modifyOutgoingSerializationContent method of matlab.mixin.CustomElementSerialization in the new class definition. This method controls what information is serialized, so the goal is to save the information in a way that both the old and new versions of the class can access.

MATLAB calls modifyOutgoingSerializationContent when you save an object of Employee. The method takes as inputs an object of

matlab.serialization.ElementSerializationContent as well as the object itself. The process from there is the inverse of how modifyIncomingSerializationContent works. The properties are reverted to the format of the older version so that the data can be deserialized by either version of the class.

```
classdef Employee < matlab.mixin.CustomElementSerialization
    properties
    LastName</pre>
```

```
FirstName
        EmployeeID = "0000"
        Division
        Email
    end
    methods (Static)
        function modifyIncomingSerializationContent(s0bj)
             if s0bj.hasNameValue("Name")
                 nameArray = split(s0bj.Name);
                 s0bj.addNameValue("FirstName", nameArray(1));
s0bj.addNameValue("LastName", nameArray(2));
                 s0bj.remove("Name");
                 s0bj.rename("Department", "Division");
                 id = split(s0bj.EmployeeID,"-");
                 s0bj.updateValue("EmployeeID",id(2));
            end
        end
        function modifyOutgoingSerializationContent(sObj,obj)
             nameStr = append(obj.FirstName," ",obj.LastName);
             s0bj.addNameValue("Name", nameStr);
             s0bj.remove("FirstName");
             s0bj.remove("LastName");
             s0bj.rename("Division","Department");
             fullID = append("ID-",obj.EmployeeID);
             s0bj.updateValue("EmployeeID", fullID);
        end
     end
end
```

Resave eold under the newer definition of Employee and then load it under the older class definition. The describilized version under the older definition is in the correct format.

```
eOld =
   Employee with properties:
        Name: "Alex Cruz"
   Department: "Sales"
   EmployeeID: "ID-1301"
        Email: "acruz@notacompany.com"
```

For another example of a revised class definition that supports both forward and backward compatibility, see "Maintain Backward and Forward Compatibility During Serialization".

See Also

```
matlab.mixin.CustomElementSerialization |
matlab.serialization.ElementSerializationContent |
matlab.serialization.SerializationContext
```

Related Examples

- "Object Save and Load"
- "Maintain Backward and Forward Compatibility During Serialization"

Serialization with Class Hierarchies

In this section...

"Call Superclass Methods of matlab.mixin.CustomElementSerialization" on page 13-13
"Customize Serialization in Both Superclasses and Subclasses" on page 13-15

When you revise classes in a hierarchy, your hierarchy can inherit from matlab.mixin.CustomElementSerialization and define modifyIncomingSerializationContent and modifyOutgoingSerialization methods to manage the changes.

Call Superclass Methods of matlab.mixin.CustomElementSerialization

In this example, the abstract SensorData superclass is the parent of several subclasses representing different sensors and measurements. In the first version, the superclass defines properties for the data, the first time the data is collected, the interval between data points, and the location of the sensor.

```
classdef (Abstract) SensorData
    properties
        Data {mustBeVector} = 0
        StartTime = datetime("today",Format="MMMM d, yyyy HH:mm:ss")
        Interval = duration(0,1,0)
        Location {mustBeTextScalar} = ""
    end
end
```

One of the subclasses, TempData, is designed specifically for temperature data and includes a Units property with validation.

```
classdef TempData < SensorData
    properties
        Units {mustBeMember(Units,["F","C"])} = "C"
    end
end

Create an instance of TempData.

t1 = TempData;
t1 Data = [15, 17, 17, 16];</pre>
```

```
t1.Data = [15 17 17 16];
t1.Interval = hours(1);
t1.Location = "NW Building 1"

t1 =

TempData with properties:

    Units: "C"
        Data: [15 17 17 16]
    StartTime: June 18, 2024 00:00:00
    Interval: 1 hr
    Location: "NW Building 1"
```

Save t1 and then clear the instance.

```
save("yourfilepath/SensorTest.mat","t1")
clear t1
```

In the second version, the SensorData class includes a TimeStamps property. Instead of calculating the time of each data point on demand, this version of the class uses the TimeStamps property to store a vector of times that correspond to each element of the Data property. The class implements modifyIncomingSerializationContent to add the new property during deserialization, if necessary, and calculate the values based on the StartTime and Interval properties.

```
classdef (Abstract) SensorData < matlab.mixin.CustomElementSerialization</pre>
    properties
        Data {mustBeVector} = 0
        TimeStamps {mustBeVector} = datetime("today",Format="MMMM d, yyyy HH:mm:ss")
        StartTime = datetime("today",Format="MMMM d, yyyy HH:mm:ss")
        Interval = duration(0,1,0)
        Location {mustBeTextScalar} = ""
    end
    methods (Static)
        function modifyIncomingSerializationContent(s0bj)
            if ~sObj.hasNameValue("TimeStamps")
                 ts(1) = s0bj.StartTime;
                % Set the last value of ts to the StartTime to
                % preallocate space for the vector.
                ts(length(s0bj.Data)) = s0bj.StartTime;
                 for i = 2:length(s0bj.Data)
                     ts(i) = ts(i-1) + s0bj.Interval;
                 s0bj.addNameValue("TimeStamps",ts);
            end
        \quad \text{end} \quad
    end
end
```

To correctly describlize TempData instances serialized under the older definition of SensorData, the TempData class must implement its own version of modifyIncomingSerializationContent that explicitly calls the superclass modifyIncomingSerializationContent method. MATLAB does not automatically call matlab.mixin.CustomElementSerialization methods defined by superclasses. The method first checks if the TimeStamps property exists in the data being describlized. If not, the method calls the superclass modifyIncomingSerializationContent method to create it.

```
classdef TempData < SensorData
    properties
        Units {mustBeMember(Units,["F","C"])} = "C"
    end
    methods (Static)
        function modifyIncomingSerializationContent(sObj)
            if ~sObj.hasNameValue("TimeStamps")
                  modifyIncomingSerializationContent@SensorData(sObj);
        end
    end
end
end</pre>
```

Load the saved instance t1 under the new definitions of SensorData and TempData. The TimeStamps property is added.

This example shows how to implement backward compatibility, enabling instances of TempData serialized under the old definition to be describilized correctly under the new definition. Forward compatibility is not supported in this particular example. For an example of a class that supports both backward and forward compatibility, see matlab.mixin.CustomElementSerialization.

Customize Serialization in Both Superclasses and Subclasses

Some class revisions require changes to the serialization or deserialization process in both the superclass and a subclass, and the order of those changes can be important. In this example, change the datetime display format of the TimeStamps property from "MMMM d, yyyy HH:mm:ss" to "dd-MMM-uuuu HH:mm". To apply this format change to TempData but not the other subclasses of SensorData, make the change in TempData.

Create an instance of TempData using the first version of the class.

```
t2 = TempData;
t2.Data = [18 18 17 18];
t2.Interval = minutes(30);
t2.Location = "NW Building 1"

t2 =

TempData with properties:

    Units: "C"
    Data: [18 18 17 18]
    StartTime: June 19, 2024 00:00:00
    Interval: 30 min
    Location: "NW Building 1"

Save t2 and then clear the instance.

save("yourfilepath/SensorTest2.mat","t2") clear t2
```

Update the second version of the TempData class. The modifyIncomingSerializationContent method must first call the superclass method and then apply the format change to the newly created TimeStamps property.

```
classdef TempData < SensorData
    properties
        Units {mustBeMember(Units,["F","C"])} = "C"
    end</pre>
```

```
methods (Static)
    function modifyIncomingSerializationContent(s0bj)
    if ~s0bj.hasNameValue("TimeStamps")
        modifyIncomingSerializationContent@SensorData(s0bj);
    end
        s0bj.TimeStamps = datetime(s0bj.TimeStamps,Format="dd-MMM-uuuu HH:mm");
    end
end
end
```

Load the instance t2 under the latest definitions of SensorData and TempData. The superclass method adds the TimeStamps property, and the subclass method reformats the data in TimeStamps.

```
load("yourfilepath/SensorTest2.mat","t2")
t2

t2 =

TempData with properties:

Units: "C"
    Data: [18 18 17 18]

TimeStamps: [19-Jun-2024 00:00 19-Jun-2024 00:30 19-Jun-2024 01:00 19-Jun-2024 01:30 StartTime: June 19, 2024 00:00:00
    Interval: 30 min
    Location: "NW Building 1"
```

See Also

```
matlab.mixin.CustomElementSerialization |
matlab.serialization.ElementSerializationContent |
matlab.serialization.SerializationContext
```

Related Examples

- "Object Save and Load"
- "Maintain Backward and Forward Compatibility During Serialization"

Transitioning Serialization and Deserialization Processes to matlab.mixin.CustomElementSerialization

In this section...

"Preserve Version Compatibility Between loadobj and saveobj Implementations and matlab.mixin.CustomElementSerialization" on page 13-17

"Private Properties with the Same Name in Class Hierarchies" on page 13-20

"Maintaining Existing loadobj and saveobj Implementations" on page 13-22

The recommended process for customizing serialization and deserialization of objects is to use the matlab.mixin.CustomElementSerialization mixin. Transitioning to the mixin from an existing implementation of loadobj and saveobj can give you greater control of the serialization process in future revisions of the class. However, some existing implementations might make loadobj and saveobj the better option.

Preserve Version Compatibility Between loadobj and saveobj Implementations and matlab.mixin.CustomElementSerialization

The first version of the Rectangle class represents a rectangle using the coordinates of the lower-left and upper-right vertices. The saveobj and loadobj methods only handle the property data using structures. This implementation enables flexibility for any future class versions that use different properties to define the rectangle.

```
classdef Rectangle % Version 1
    properties
        x1
        y1
        x2
        y2
    end
    methods
        function obj = Rectangle(x1,y1,x2,y2)
            obj.x1 = x1;
            obj.y1 = y1;
            obi.x2 = x2;
            obj.y2 = y2;
        function s = saveobj(obj)
            s.x1 = obj.x1;
            s.y1 = obj.y1;
            s.x2 = obj.x2;
            s.y2 = obj.y2;
        end
    end
    methods(Static)
        function obj = loadobj(s)
            obj = Rectangle(s.x1,s.y1,s.x2,s.y2);
        end
    end
end
```

Version 2 of the class represents the rectangle using the coordinates of the lower-left vertex, the height, and the width. The revision maintains compatibility by implementing saveobj and loadobj methods to ensure that Version 2 of the class can load instances saved under Version 1, and Version 1 of the class can load instances saved under Version 2. The constructor accepts the same property values of Version 1, namely the coordinates of the lower-left and upper-right coordinates. The loadobj method calls the Rectangle constructor with those values. To preserve compatibility with Version 1, the saveobj method converts the new properties back to the old properties and saves them as a structure.

```
classdef Rectangle % Version 2
   properties
        x0
        y0
        width
        height
    end
   methods
        function obj = Rectangle(x1,y1,x2,y2)
            obi.x0 = x1;
            obj.y0 = y1;
            obj.width = x2 - x1;
            obj.height = y2 - y1;
        end
        function s = saveobj(obj)
            s.x1 = obj.x0;
            s.y1 = obj.y0;
            s.x2 = obj.x0 + obj.width;
            s.y2 = obj.y0 + obj.height;
        end
   end
   methods(Static)
        function obj = loadobj(s)
             obj = Rectangle(s.x1,s.y1,s.x2,s.y2);
        end
    end
end
```

Version 2a of the Rectangle class is a subclass of matlab.mixin.CustomElementSerialization, but its behavior is consistent with Version 2. The

matlab.mixin.CustomElementSerialization, but its behavior is consistent with version 2. The modifyOutgoingSerializationContent method stores the data in properties consistent with Version 1 of the class. With this method in place:

- Both Version 1 and Version 2 of the class can load instances saved under Version 2a because the property values are stored in the original format of Version 1.
- modifyOutgoingSerializationContent saves the rectangle information as x0, y0, width, and height by default, but it also saves the coordinates x1, x2, y1, and y2. Because Version 2a includes the properties and values in the same format as Versions 1 and 2, Version 2a can load an instance of any version.

```
end
    methods
        function obj = Rectangle(x1,y1,x2,y2)
            obj.x0 = x1;
            obj.y0 = y1;
            obj.width = x2 - x1;
            obj.height = y2 - y1;
        end
    end
    methods(Static)
        function modifyOutgoingSerializationContent(sObj,obj)
            s0bj.addNameValue("x1",obj.x0);
            s0bj.addNameValue("x2",obj.x0 + obj.width);
            s0bj.addNameValue("y1",obj.y0);
            s0bj.addNameValue("y2",obj.y0 + obj.height);
        end
    end
end
With this new version, you can now take advantage of all of the capabilities of
matlab.mixin.CustomElementSerialization. To check the compatibility, create an instance of
Rectangle under Version 2a.
test = Rectangle(1,1,4,6)
test =
  Rectangle with properties:
        x0: 1
        y0: 1
     width: 3
    height: 5
Save the instance. modifyOutgoingSerializationContent uses the width and height
properties to define the second vertex.
save("yourfilepath/RectV2a.mat","test")
Clear the instance, and then load it under Version 1.
clear test
load("yourfilepath/RectV2a.mat","test")
test
test =
  Rectangle with properties:
```

x1: 1 y1: 1 x2: 4 y2: 6

Private Properties with the Same Name in Class Hierarchies

Classes in a hierarchy that define private properties with the same name require special handling when serializing and deserializing with loadobj and saveobj. The Animal class and its subclass Pet both define a private property named ID. To handle both properties:

- The saveobj method of Animal saves its ID property in the outgoing structure under the name of AnimalID to avoid conflicting with the ID property of Pet.
- The loadobj methods of both classes pass the value of AnimalID to the constructor to recreate the ID property of Animal.

```
classdef Animal
    properties
        Species
   properties(Access = private)
        ΙD
   end
   methods
        function obj = Animal(Species,ID)
            obj.Species = Species;
            obj.ID = ID;
        end
        function s = saveobj(obj)
            s.Species = obj.Species;
            s.AnimalID = obj.ID;
        end
   end
   methods (Static)
        function obj = loadobj(s)
            if isstruct(s)
                obj = Animal(s.Species,s.AnimalID);
                obj = s;
            end
        end
    end
end
classdef Pet < Animal</pre>
   properties
        OwnerName
   properties(Access = private)
        ID
   end
   methods
        function obj = Pet(Species, AnimalID, OwnerName, ID)
            obj@Animal(Species, AnimalID);
            obj.OwnerName = OwnerName;
            obj.ID = ID;
        end
        function s = saveobj(obj)
            s = saveobj@Animal(obj);
            s.OwnerName = obj.OwnerName;
```

```
s.ID = obj.ID;
end
end

methods(Static)
   function obj = loadobj(s)
        if isstruct(s)
            obj = Pet(s.Species, s.AnimalID, s.OwnerName, s.ID);
        else
            obj = s;
        end
end
end
```

The matlab.mixin.CustomElementSerialization mixin enables you to reference private properties with the same name by preceding the property name with the name of the defining class and a dot. You can use this convention to transition classes with private property overlap to use the mixin instead of saveobj and loadobj.

For example, the following revised Animal class inherits from the mixin and implements a modifyIncomingSerializationContent method. The saveobj method of the original Animal stores its ID property as AnimalID. The modifyIncomingSerializationContent method checks for an AnimalID field in the incoming content. If AnimalID is part of the serialized content, the modifyIncomingSerializationContent method renames the property to Animal.ID. The rename method uses the className.propertyName syntax that is required for private properties. (For more information, see the description for rename in matlab.serialization.ElementSerializationContent.)

```
classdef Animal < matlab.mixin.CustomElementSerialization</pre>
    properties
        Species
    end
   properties (Access = private)
        TD
    end
   methods
        function obj = Animal(Species,ID)
            obj.Species = Species;
            obi.ID = ID;
        end
    end
   methods(Static)
        function modifyIncomingSerializationContent(s0bj)
            if s0bj.hasNameValue("AnimalID")
                 s0bj.rename("AnimalID", "Animal.ID");
            end
        end
    end
end
```

The revised Pet class implements a modifyIncomingSerializationContent method that calls the superclass method to process the superclass ID property. To enable the older version of the class to deserialize objects saved under the new definition, Pet implements modifyOutgoingSerializationContent to save the superclass ID property as AnimalID.

```
classdef Pet < Animal</pre>
    properties
        OwnerName
    properties(Access = private)
        ID
    end
    methods
        function obj = Pet(Species, AnimalID, OwnerName, ID)
            obi@Animal(Species.AnimalID):
            obi.OwnerName = OwnerName:
            obi.ID = ID;
        end
    end
    methods(Static)
        function modifyOutgoingSerializationContent(sObj,~)
            sObj.addNameValue("AnimalID", sObj.getValue("Animal.ID"));
            s0bj.remove("Animal.ID");
        end
        function modifyIncomingSerializationContent(s0bj)
            modifyIncomingSerializationContent@Animal(s0bj)
        end
    end
end
```

Maintaining Existing loadobj and saveobj Implementations

In some cases, existing designs using loadobj and saveobj cannot be easily transitioned to a matlab.mixin.CustomElementSerialization design without significant revision of existing classes. For example:

- The loadobj method of an existing class only accepts a structure as input. Deserializing an object under the old definition might cause warnings. To force loadobj to deserialize the content as a structure, you can use modifyOutgoingSerializationContent to add a property that is not part of the original class definition. The disadvantage to this method is that the added property is now stored, even though it has no meaning in either version of the class.
- The loadobj method can only deserialize data from a format other than an object or a structure. For example, a class could use saveobj to save property values in a table, and the corresponding loadobj can only accept a table as input. The methods of matlab.mixin.CustomElementSerialization only support object data, so data from the older version of the class would be inaccessible. In this case, the only workaround is to revise how the existing class definition serializes data.

In cases like these, maintaining your existing loadobj and saveoobj implementations might be preferable to what would be required to transition to matlab.mixin.CustomElementSerialization.

See Also

```
matlab.mixin.CustomElementSerialization |
matlab.serialization.ElementSerializationContent |
matlab.serialization.SerializationContext
```

Related Examples

- "Object Save and Load"
- "Maintain Backward and Forward Compatibility During Serialization"

Code Patterns for saveobj and loadobj

```
In this section...

"Using saveobj and loadobj" on page 13-24

"saveobj and loadobj with Subclass Objects" on page 13-26

"Additional Considerations for loadobj and saveobj" on page 13-28
```

The recommended process for customizing serialization and deserialization of objects is to use the matlab.mixin.CustomElementSerialization mixin and its associated classes to control how objects are serialized and deserialized. However, using the mixin does not work if:

- You have an existing implementation of saveobj that serializes data in a type other than an object
 or a struct, and your loadobj implementation can only deserialize data from that particular
 type.
- You are using a MATLAB release older than R2024b.

Using saveobj and loadobj

Depending on the requirements of your class, there are various ways you can use saveobj and loadobj methods. This pattern is a flexible way to solve problems that you cannot address by simpler means.

The basic process is:

- Use saveobj to save all essential data in a struct.
- Use loadobj to reconstruct the object from the saved data.

This approach is not useful in cases where you cannot save property values in a struct field, such as a file identifier.

If you implement a saveobj method without implementing a loadobj method, MATLAB loads a default object of the class using the current class definition. Add a loadobj method to the class to create an object using the data saved with the saveobj method.

Use saveobj to Store Class Data as a Structure

Define saveobj as an ordinary method that accepts an object of the class and returns a struct.

- Copy each property value to a structure field of the same name.
- You can save only the data that is necessary to rebuild the object. Avoid saving whole object hierarchies, such as those created by graphs.

methods

```
function s = saveobj(obj)
    s.Prop1 = obj.Prop1;
    s.Prop2 = obj.Prop2
    s.Data = obj.GraphHandle.YData;
end
end
end
end
```

Use loadobj to Load Class Data from a Structure

Define loadobj as a static method. Create an object by calling the class constructor. Then assign values to properties from the struct passed to loadobj. Use the data to regenerate properties that were not saved.

```
methods(Static)
  function obj = loadobj(s)
   if isstruct(s)
      newObj = ClassConstructor;
      newObj.Prop1 = s.Prop1;
      newObj.Prop2 = s.Prop2
      newObj.GraphHandle = plot(s.Data);
      obj = newObj;
  else
      obj = s;
  end
  end
end
```

If the load function encounters an error, load passes loadobj a struct instead of an object. Your loadobj method must always be able to handle a struct as the input argument. The input to loadobj is always a scalar.

Using loadobj Without a Corresponding saveobj

loadobj can handle a struct input even if you are not using a saveobj method. For example, the GraphExpression class creates a graph of a MATLAB expression over a specified range of data. GraphExpression uses its loadobj method to regenerate the graph, which is not saved with the object.

```
classdef GraphExpression
   properties
      FuncHandle
      Range
   end
   methods
      function obj = GraphExpression(fh,rg)
         obj.FuncHandle = fh;
         obj.Range = rg;
         makeGraph(obj)
      function makeGraph(obj)
         rg = obj.Range;
         x = min(rg):max(rg);
         data = obj.FuncHandle(x);
         plot(data)
      end
   end
   methods (Static)
      function obj = loadobj(s)
         if isstruct(s)
            fh = s.FuncHandle;
            rg = s.Range;
            obj = GraphExpression(fh,rg);
            makeGraph(s);
```

```
obj = s;
     end
     end
     end
end
end
```

Create a GraphExpression instance with an anonymous function and a range of data as inputs.

```
h = GraphExpression(@(x)x.^4,[1:25])
h =
   GraphExpression with properties:
    FuncHandle: @(x)x.^4
        Range: [1x25 double]
```

Save the GraphExpression object and close the graph.

```
save myFile h
close
```

When you load the object, MATLAB recreates the graph.

saveobj and loadobj with Subclass Objects

If the most specific class of an object does not define a loadobj or saveobj method, the class can inherit loadobj or saveobj methods from a superclass.

If any class in the hierarchy defines saveobj or loadobj methods:

- Define saveobj for all classes in the hierarchy.
- Call superclass saveobj methods from the subclass saveobj method because the save function calls only the most specific saveobj method.
- The subclass loadobj method can call the superclass loadobj, or other methods as required, to assign values to their properties.

Reconstruct the Subclass Object from a Saved struct

Suppose that you want to save a subclass object by first converting its property data to a struct in the subclass saveobj method. Then you reconstruct the object when loaded using its loadobj method. This action requires that:

- Superclasses implement saveobj methods to save their property data in the struct.
- The subclass saveobj method calls each superclass saveobj method and returns the completed struct to the save function. Then the save function writes the struct to the MAT-file.
- The subclass loadobj method creates a subclass object and calls superclass methods to assign their property values in the subclass object.
- The subclass loadobj method returns the reconstructed object to the load function, which loads the object into the workspace.

The following superclass (MySuper) and subclass (MySub) definitions show how to code these methods.

- The MySuper class defines a loadobj method to enable an object of this class to be loaded directly.
- The subclass loadobj method calls a method named reload after it constructs the subclass object.
- reload first calls the superclass reload method to assign superclass property values and then assigns the subclass property value.

```
classdef MySuper
   properties
      Χ
      Υ
   end
   methods
      function S = saveobj(obj)
         S.PointX = obi.X;
         S.PointY = obj.Y;
      end
      function obj = reload(obj,S)
         obj.X = S.PointX;
         obj.Y = S.PointY;
      end
   end
   methods (Static)
      function obj = loadobj(S)
         if isstruct(S)
            obj = MySuper;
            obj = reload(obj,S);
         end
      end
   end
end
```

Call the superclass saveobj and loadobj methods from the subclass saveobj and loadobj methods. (The loadobj method does this indirectly by calling the reload method, which in turn calls the superclass loadobj.)

```
classdef MySub < MySuper</pre>
   properties
      Ζ
   end
   methods
      function S = saveobj(obj)
         S = saveobi@MySuper(obi);
         S.PointZ = obj.Z;
      function obj = reload(obj,S)
         obj = reload@MySuper(obj,S);
         obj.Z = S.PointZ;
      end
   end
   methods (Static)
      function obj = loadobj(S)
         if isstruct(S)
            obj = MySub;
            obj = reload(obj,S);
         end
      end
```

end end

Additional Considerations for loadobj and saveobj

When you decide to modify the default save and load process with loadobj and saveobj, keep these points in mind:

- If loading any property value from the MAT file produces an error, load passes a struct to loadobj. The struct field names correspond to the property names extracted from the file.
- loadobj must always be able to accept a struct as input and return an object, even if saveobj is not defined or saveobj does not return a struct.
- If saveobj returns a struct, then load always passes that struct to loadobj.
- Subclass objects inherit superclass loadobj and saveobj methods. Therefore, if you do not implement a loadobj or saveobj method in the subclass, MATLAB calls the inherited methods.

If a superclass implements a loadobj or saveobj method, then a subclass can also implement a loadobj or saveobj method that calls the superclass methods. For more information, see "Call Superclass Methods on Subclass Objects" on page 5-11.

- The load function does not call the constructor by default. For more information, see "Default Save and Load Process for Objects" on page 13-2.
- Customizing loadobj and saveobj is not supported for enum classes.

See Also

Related Examples

- "When to Customize the Serialization Process" on page 13-7
- "Object Save and Load"

Enumerations

- "Named Values" on page 14-2
- "Define Enumeration Classes" on page 14-4
- "Refer to Enumerations" on page 14-9
- "Enumerations for Property Values" on page 14-14
- "Operations on Enumerations" on page 14-16
- "Hide Enumeration Members" on page 14-23
- "Enumeration Class Restrictions" on page 14-26
- "Enumerations Derived from Built-In Classes" on page 14-27
- "Mutable Handle vs. Immutable Value Enumeration Members" on page 14-32
- "Enumerations That Encapsulate Data" on page 14-37
- "Save and Load Enumerations" on page 14-40

Named Values

In this section...

"Kinds of Predefined Names" on page 14-2

"Techniques for Defining Enumerations" on page 14-2

Kinds of Predefined Names

MATLAB supports two kinds of predefined names:

- Constant properties
- Enumerations

Constant Properties

Use constant properties when you want a collection of related constant values that can belong to different types (numeric values, character strings, and so on). Define properties with constant values by setting the property Constant attribute. Reference constant properties by name whenever you need access to that particular value.

See "Define Class Properties with Constant Values" on page 15-2 for more information.

Enumerations

Use enumerations when you want to create a fixed set of names representing a single type of value. Use this new type in multiple places without redefining it for each class.

You can derive enumeration classes from other classes to inherit the operations of the superclass. For example, if you define an enumeration class that subclasses a MATLAB numeric class like double or int32, the enumeration class inherits all the mathematical and relational operations that MATLAB defines for those classes.

Using enumerations instead of character strings to represent a value, such as colors ('red'), can result in more readable code because:

- You can compare enumeration members with == instead of using strcmp
- Enumerations maintain type information, while char vectors do not. For example, passing a char vector 'red' to functions means that every function must interpret what 'red' means. If you define red as an enumeration, the actual value of 'red' can change (from [1 0 0] to [.93 .14 .14], for example) without updating every function that accepts colors, as you would if you defined the color as the char vector 'red'.

Define enumerations by creating an enumeration block in the class definition.

See "Define Enumeration Classes" on page 14-4 for more information.

Techniques for Defining Enumerations

Enumerations enable you to define names that represent entities useful to your application, without using numeric values or character strings. All enumerations support equality and inequality operations. Therefore, switch, if, and several comparison functions like isequal and ismember work with enumeration members.

You can define enumeration classes in ways that are most useful to your application, as described in the following sections.

Simple Enumerated Names

Simple enumeration classes have no superclasses and no properties. These classes define a set of related names that have no underlying values associated with them. Use this kind of enumeration when you want descriptive names, but your application does not require specific information associated with the name.

See the WeekDays class in the "Enumeration Class" on page 14-4 and the "Define Methods in Enumeration Classes" on page 14-5 sections.

Enumerations with Built-In Class Behaviors

Enumeration classes that subclass MATLAB built-in classes inherit most of the behaviors of those classes. For example, an enumeration class derived from the double class inherits the mathematical, relational, and set operations that work with variables of the class.

Enumerations do not support the colon (:) operator, even if the superclass does.

Enumerations with Properties for Member Data

Enumeration classes that do not subclass MATLAB built-in numeric and logical classes can define properties. These classes can define constructors that set each member's unique property values.

The constructor can save input arguments in property values. For example, a Color class can specify a Red enumeration member color with three (Red, Green, Blue) values:

```
enumeration
Red (1,0,0)
end
```

See Also

Related Examples

- "Enumeration Class Restrictions" on page 14-26
- "Enumerations Derived from Built-In Classes" on page 14-27
- "Enumerations That Encapsulate Data" on page 14-37

Define Enumeration Classes

```
"Enumeration Class" on page 14-4

"Construct an Enumeration Member" on page 14-4

"Convert to Superclass Value" on page 14-4

"Define Methods in Enumeration Classes" on page 14-5

"Define Properties in Enumeration Classes" on page 14-6

"Enumeration Class Constructor Calling Sequence" on page 14-7
```

Enumeration Class

Create an enumeration class by adding an enumeration block to a class definition. For example, the WeekDays class enumerates a set of days of the week.

```
classdef WeekDays
  enumeration
     Monday, Tuesday, Wednesday, Thursday, Friday
  end
end
```

To execute the MATLAB code in the following sections, place the WeekDays class definition in a .m file on your path.

Construct an Enumeration Member

Refer to an enumeration member using the class name and the member name:

```
ClassName.MemberName
```

For example, assign the enumeration member WeekDays. Tuesday to the variable today:

```
today = WeekDays.Tuesday;
```

today is a variable of class WeekDays:

whos

```
Name Size Bytes Class Attributes
today 1x1 104 WeekDays
today
today =
Tuesday
```

Convert to Superclass Value

If an enumeration class specifies a superclass, you can convert an enumeration object to the superclass by passing the object to the superclass constructor. However, the superclass constructor

must be able to accept its own class as input and return an instance of the superclass. MATLAB built-in numeric classes, such as uint32, allow this conversion.

For example, the Bearing class derives from the uint32 built-in class:

```
classdef Bearing < uint32</pre>
   enumeration
      North (0)
      East (90)
      South (180)
      West (270)
   end
end
Assign the Bearing. East member to the variable a:
a = Bearing.East;
Pass a to the superclass constructor and return a uint32 value:
b = uint32(a);
whos
                              Bytes Class
                                                  Attributes
  Name
             Size
  а
             1x1
                                   4
                                      Bearing
             1x1
                                   4 uint32
```

The uint32 constructor accepts an object of the subclass Bearing and returns an object of class uint32.

Define Methods in Enumeration Classes

Define methods in an enumeration class like any MATLAB class. For example, define a method called isMeetingDay for the WeekDays enumeration class. The use case is that the user has a recurring meeting on Tuesdays. The method checks if the input argument is an instance of the WeekDays member Tuesday.

```
classdef WeekDays
    enumeration
        Monday, Tuesday, Wednesday, Thursday, Friday
    end
    methods
        function tf = isMeetingDay(obj)
            tf = WeekDays.Tuesday == obj;
        end
    end
end

Call isMeetingDay with an instance of the WeekDays class:
today = WeekDays.Tuesday;
today.isMeetingDay
```

ans =

1

You can also use the enumeration member as a direct input to the method:

```
isMeetingDay(WeekDays.Wednesday)
ans =
0
```

Define Properties in Enumeration Classes

Add properties to an enumeration class when you must store data related to the enumeration members. Set the property values in the class constructor. For example, the SyntaxColors class defines three properties. The class constructor assigns the values of the input arguments to the corresponding properties when you reference a class member.

```
classdef SyntaxColors
   properties
      R
      G
      В
   end
   methods
      function c = SyntaxColors(r, g, b)
         c.R = r; c.G = q; c.B = b;
   end
   enumeration
      Error
              (1, 0, 0)
      Comment (0, 1, 0)
      Keyword (0, 0, 1)
      String (1, 0, 1)
   end
end
```

When you refer to an enumeration member, the constructor initializes the property values:

```
e = SyntaxColors.Error;
e.R
ans =
```

Because SyntaxColors is a value class (it does not derive from handle), only the class constructor can set property values:

```
e.R = 0
You cannot set the read-only property 'R' of SyntaxColors.
```

For more information on enumeration classes that define properties, see "Mutable Handle vs. Immutable Value Enumeration Members" on page 14-32.

Enumeration Class Constructor Calling Sequence

Each statement in an enumeration block is the name of an enumeration member, optionally followed by an argument list. If the enumeration class defines a constructor, MATLAB calls the constructor to create the enumerated instances.

MATLAB provides a default constructor for all enumeration classes that do not explicitly define a constructor. The default constructor creates an instance of the enumeration class:

- Using no input arguments, if the enumeration member defines no input arguments
- Using the input arguments defined in the enumeration class for that member

For example, the input arguments for the Bool class are 0 for Bool. No and 1 for Bool. Yes.

```
classdef Bool < logical
   enumeration
    No (0)
    Yes (1)
   end
end</pre>
```

The values of 0 and 1 are of class logical because the default constructor passes the argument to the first superclass. That is, this statement:

```
n = Bool.No;
```

Results in a call to logical that is equivalent to the following statement in a constructor:

```
function obj = Bool(val)
  obj@logical(val)
end
```

MATLAB passes the member argument only to the first superclass. For example, suppose Bool derived from another class:

```
classdef Bool < logical & MyBool
  enumeration
    No (0)
    Yes (1)
  end
end</pre>
```

The MyBool class can add some specialized behavior:

The default Bool constructor behaves as if defined like this function:

- Argument passed to first superclass constructor
- No arguments passed to subsequent constructors

```
function obj = Bool(val)
  obj@logical(val)
    obj@MyBool
end
```

See Also

Related Examples

- "Refer to Enumerations" on page 14-9
- "Operations on Enumerations" on page 14-16

Refer to Enumerations

```
In this section...

"Instances of Enumeration Classes" on page 14-9

"Conversion of Characters to Enumerations" on page 14-10

"Enumeration Arrays" on page 14-12
```

Instances of Enumeration Classes

Enumeration members are instances of the enumeration class. You can assign enumeration members to variables and form arrays of enumeration members. If an enumeration class derives from a superclass, you can substitute an enumeration member for an instance of the superclass.

The WeekDays class defines enumeration members for five days of the week.

```
classdef WeekDays
  enumeration
     Monday, Tuesday, Wednesday, Thursday, Friday
  end
end
```

Create objects of the WeekDays class representing specific days.

```
today = WeekDays.Monday;
tomorrow = WeekDays.Tuesday;
```

The variables today and tomorrow are objects of the WeekDays class.

The PPM class defines three enumeration members. Each member has an associated numeric value derived from the class superclass.

```
classdef PPM < double
  enumeration
    High (1000)
    Medium (100)
    Low (10)
  end
end</pre>
```

Assign an enumeration member to a variable.

```
level = PPM.High;
```

When you substitute enumeration members for instances of the superclass, MATLAB coerces the enumeration member to the superclass. For example, add a numeric value to an enumeration member of the PPM class.

The result is of class double.

whos

Name	Size	Bytes	Class	Attributes
level	1x1	108	PPM	
levelNew	1x1	8	double	

You can substitute superclass values for corresponding enumeration members. For example, pass one of the numeric values defined in the enumeration class to the PPMSwitch function.

```
function PPMSwitch(ppm)
    switch ppm
    case PPM.Low
        disp Low
    case PPM.Medium
        disp Medium
        case PPM.High
        disp High
    end
end

PPMSwitch(100)

Medium
```

You can also use an enumeration member directly:

```
PPMSwitch(PPM.Medium)
```

Medium

For information on operations you can perform on enumeration class instances, see "Operations on Enumerations" on page 14-16.

Conversion of Characters to Enumerations

Enumeration classes can convert char vectors to enumeration members when the char vector represents an enumeration member defined by the class. This conversion enables you to pass a valid char vector or a cell array of char vectors when enumerations are expected.

Use a char vector instead of a direct reference to an enumeration member when you want to use a simple character string to specify an enumeration member. However, specifying an enumeration member directly eliminates the conversion from char to enumeration.

Enumeration classes provide a converter function using the constructor syntax.

```
today = WeekDays('Tuesday');
```

Because the char vector 'Tuesday' matches the enumeration member WeekDays. Tuesday, the Weekdays char method can perform the conversion.

```
class(today)
ans =
WeekDays
```

Create an enumeration array using the WeekDay class constructor and a cell array of char vectors.

```
wd = WeekDays({'Monday','Wednesday','Friday'})
wd =
    Monday Wednesday Friday
class(wd)
ans =
WeekDays
```

All char vectors in the cell array must correspond to an enumeration member defined by the class.

Coercion of char to Enumerations

MATLAB coerces char vectors into enumeration members when the dominant argument is an enumeration. Because user-defined classes are dominant over the char class, MATLAB attempts to convert the char vector to a member of the enumeration class.

Create an enumeration array. Then insert a char vector that represents an enumeration member into the array.

Substitute Enumeration Members for char Vectors

You can use enumeration members in place of char vectors in cases where functions require char vectors. For example, this call to sprintf expects a char vector, designated by the %s format specifier.

```
sprintf('Today is %s',WeekDays.Friday)
ans =
Today is Friday
```

WeekDays

The automatic conversion of enumeration classes to char enable you to use enumeration members in this case.

Enumeration Arrays

Create enumeration arrays by:

- Concatenating enumeration members using []
- Assigning enumeration members to an array using indexed assignment

Create an enumeration array of class WeekDays by concatenating enumeration members:

```
wd = [WeekDays.Tuesday,WeekDays.Wednesday,WeekDays.Friday];
```

Create an enumeration array of class WeekDays by indexed assignment:

```
a(1) = WeekDays.Tuesday;
a(2) = WeekDays.Wednesday;
a(3) = WeekDays.Friday;
```

Mixed Enumeration Members and char Vectors

You can concatenate enumeration members and char vectors as long as the char vector represents an enumeration member.

```
clear a
a = [WeekDays.Wednesday, 'Friday'];
class(a)
ans =
WeekDays
```

You can also assign a char vector to an enumeration array:

```
a(1) = WeekDays.Wednesday;
a(2) = 'Friday';
class(a)
ans =
WeekDays
```

Default Enumeration Member

The default member of an enumeration class is the first enumeration member defined in the enumeration block. For the WeekDays class, the default enumeration member is WeekDays. Monday.

```
classdef WeekDays
   enumeration
      Monday, Tuesday, Wednesday, Thursday, Friday
   end
end
```

MATLAB allows assignment to any element of an array, even if the array variable does not previously exist. To fill in unassigned array elements, MATLAB uses the default enumeration member.

For example, assign a value to element 5 of an array, a:

```
clear a
a(5) = WeekDays.Tuesday;
```

MATLAB must initialize the values of array elements a(1:4) with the default enumeration member. The result of the assignment to the fifth element of the array a is:

```
a
a =
    Monday    Monday    Monday    Tuesday
```

See Also

Related Examples

"Operations on Enumerations" on page 14-16

Enumerations for Property Values

```
In this section...

"Syntax for Property/Enumeration Definition" on page 14-14

"Example of Restricted Property" on page 14-14
```

Syntax for Property/Enumeration Definition

You can restrict the values that are allowed for a property to members of an enumeration class. Define the property as restricted to a specific enumeration class in the class definition using this syntax:

```
properties
   PropName EnumerationClass
end
```

This syntax restricts values of *PropName* to members of the enumeration class *EnumerationClass*.

Example of Restricted Property

For example, the Days class defines a property named Today. The allowed values for the Today property are enumeration members of the WeekDays class.

The WeekDays class defines the enumerations:

```
classdef WeekDays
  enumeration
     Monday, Tuesday, Wednesday, Thursday, Friday
  end
end
```

Use the WeekDays enumerations to restrict the allowed values of the Today property:

```
classdef Days
    properties
        Today WeekDays
    end
end

Create an object of the Days class.
d = Days;
d.Today = WeekDays.Tuesday;
d =
    Days with properties:
    Today: Tuesday
```

Representing Enumeration Members with char Vectors

The automatic conversion feature enables users of the Days class to assign values to the Today property as either enumeration members, char vectors, or string scalars. The Today property is

restricted to members of the WeekDays enumeration class. Therefore, you can assign a char vector that represents a member of the WeekDays class.

```
d = Days;
d.Today = 'Tuesday';
Also, you can use a string scalar:
d = Days;
d.Today = "Tuesday";
```

For more information on restricting property values, see "Validate Property Values" on page 8-19 and "Property Class and Size Validation" on page 8-24.

Operations on Enumerations

```
In this section...

"Operations Supported by Enumerations" on page 14-16

"Example Enumeration Class" on page 14-16

"Default Methods" on page 14-16

"Convert Enumeration Members to Strings or char Vectors" on page 14-17

"Convert Enumeration Arrays to String Arrays or Cell Arrays of char Vectors" on page 14-17

"Relational Operations with Enumerations, Strings, and char Vectors" on page 14-18

"Enumerations in switch Statements" on page 14-19

"Enumeration Set Membership" on page 14-20

"Enumeration Text Comparison Methods" on page 14-21

"Get Information About Enumerations" on page 14-21

"Testing for an Enumeration" on page 14-22
```

Operations Supported by Enumerations

You can use logical, set membership, and string comparison operations on enumerations. These operations also support the use of enumerations in conditional statements, such as switch and if statements. The string and char functions enable you to convert enumeration members to strings and char vectors.

Example Enumeration Class

This topic uses the WeekDays class to illustrate how to perform operations on enumerations. The WeekDays class defines members that enumerate days of the week.

```
classdef WeekDays
   enumeration
       Monday, Tuesday, Wednesday, Thursday, Friday
   end
end
```

For information on defining enumerations, see "Define Enumeration Classes" on page 14-4.

Default Methods

Enumeration classes have the following default methods:

```
methods('WeekDays')

Methods for class WeekDays:

WeekDays char intersect ne setxor strcmpi strncmp union cellstr eq ismember setdiff strcmp string strncmpi
```

The WeekDays method converts text formats into enumerations. Supported formats include strings, char vectors, string arrays, and cell arrays of char vectors. For example:

```
f = WeekDays(["Monday" "Friday"])
```

```
f =
  1×2 WeekDays enumeration array
  Monday Friday
```

Convert Enumeration Members to Strings or char Vectors

Conversion of enumeration members to strings and char vectors is useful for creating text that contains enumeration member names. For example, use the string function to convert an enumeration member to a string and include it in a sentence:

```
string(WeekDays.Monday) + " is our meeting day."
ans =
    "Monday is our meeting day."
Use the char function in a similar way:
['Today is ' char(WeekDays.Friday) '.']
ans =
    'Today is Friday.'
```

Convert Enumeration Arrays to String Arrays or Cell Arrays of char Vectors

Use the string function to convert an enumeration array into a string array:

```
sa = [WeekDays.Tuesday WeekDays.Thursday];
string(sa)
ans =
    1×2 string array
    "Tuesday" "Thursday"

Use cellstr to convert an enumeration array to a cell array of char vectors.
ca = cellstr([WeekDays.Tuesday WeekDays.Thursday]);
class(ca)
ans =
    'cell'

Both cells in the cell array contain char vectors:
class([ca{1:2}])
ans =
    'char'
```

Relational Operations with Enumerations, Strings, and char Vectors

You can compare enumeration instances with char vectors and strings using the relational operators eq (==) and ne $(\sim=)$, as well as the isequal method.

Relational Operators eq and ne

Use eq and ne to compare enumeration members with text values. For example, you can compare an enumeration member with a string:

```
today = WeekDays.Friday;
today == "Friday"
ans =
  logical
```

Compare an enumeration array to one char vector. The return value is a logical array indicating which members of the enumeration array are equivalent to the char vector:

```
wd = [WeekDays.Monday WeekDays.Wednesday WeekDays.Friday];
wd == 'Friday'
ans =
   1×3 logical array
   0   0   1
```

This example uses the **ne** function to compare the corresponding elements of an enumeration array and a string array of equal length:

```
sa = ["Monday" "Wednesday" "Friday"];
md = [WeekDays.Tuesday WeekDays.Thursday WeekDays.Friday];
md ~= sa
ans =
    1×3 logical array
    1    1    0
```

The char vector Wednesday is equal to (==) the enumeration member WeekDays. Wednesday. You can use this equality in conditional statements:

```
today = 'Wednesday';
...
if today == WeekDays.Wednesday
    disp('Team meeting at 2:00')
end
```

isegual Method

The isequal method also enables comparisons between enumeration instances and strings, character vectors, string arrays, and cell arrays of character vectors.

```
a = WeekDays.Monday;
isequal(a,"Monday")
ans =
    logical
1
```

When comparing an enumeration array to a single item, the behavior of isequal differs slightly from eq and ne. The isequal method requires that the two values being compared are the same size. Therefore, isequal returns false when comparing an enumeration array to a char vector or string scalar, even if the text matches one of the enumeration members in the array.

```
wd = [WeekDays.Monday WeekDays.Wednesday WeekDays.Friday];
isequal(wd,"Friday")
ans =
    logical
0
```

Enumerations in switch Statements

Equality (eq) and inequality (ne) functions enable you to use enumeration members in switch statements. For example, using the WeekDays enumeration defined previously, construct a switch statement:

Pass a member of the WeekDays enumeration class to the Reminder function:

```
today = WeekDays.Wednesday;
Reminder(today)
ans =
Team meeting at 2:00
```

For more information, see "Objects in Conditional Statements" on page 5-20.

Substitute Strings or char Vectors

You can use strings or char vectors to represent specific enumeration members:

```
function c = Reminder2(day)
    switch(day)
    case 'Monday'
        c = 'Department meeting at 10:00';
    case 'Tuesday'
        c = 'Meeting Free Day!';
    case {'Wednesday' 'Friday'}
        c = 'Team meeting at 2:00';
    case 'Thursday'
        c = 'Volleyball night';
    end
end
```

Although you can use char vectors or strings instead of specifying enumerations explicitly, MATLAB must convert the text format to an enumeration. Eliminate the need for this conversion if it is not necessary.

Enumeration Set Membership

Enumeration classes provide methods to determine set membership.

- ismember True for elements of an enumeration array if in a set
- setdiff Set difference for enumeration arrays
- intersect Set intersection for enumeration arrays
- setxor Set exclusive-or for enumeration arrays
- union Set union for enumeration arrays

Determine if today is a meeting day for your team. Create a set of enumeration members corresponding to the days on which the team has meetings.

```
today = WeekDays.Tuesday;
teamMeetings = [WeekDays.Wednesday WeekDays.Friday];
Use ismember to determine if today is part of the teamMeetings set:
ismember(today,teamMeetings)
ans =
```

Mixed Sets of Enumeration and Text

If you pass both enumeration members and text values to an enumeration class method, the class attempts to convert the text value to the class of the enumeration.

Determine if the char vector 'Friday' is a member of the enumeration array.

```
teamMeetings = [WeekDays.Wednesday WeekDays.Friday];
ismember('Friday', teamMeetings)
ans =
  logical
  1
```

Determine if the enumeration member is a member of the string array.

```
ismember(WeekDays.Friday,["Wednesday" "Friday"])
ans =
  logical
  1
```

Enumeration Text Comparison Methods

Enumeration classes provide methods to compare enumeration members with text. One of the arguments to the string comparison methods must be a char vector or a string. Comparing two enumeration members returns false.

- strcmp Compare enumeration members
- strncmp Compare first n characters of enumeration members
- strcmpi Case insensitive comparison of enumeration members
- strncmpi Case insensitive first n character comparison of enumeration members

Comparing Enumeration Member with Strings or char Vectors

The string comparison methods can compare enumeration members with char vectors and strings.

```
today = WeekDays.Tuesday;
strcmp(today, 'Friday')
ans =
    0
strcmp(today, "Tuesday")
ans =
    1
```

Get Information About Enumerations

Obtain information about enumeration classes using the enumeration function. For example:

```
enumeration WeekDays

Enumeration members for class 'WeekDays':
    Monday
    Tuesday
    Wednesday
    Thursday
    Friday
```

For more information on how class introspection works with enumerations, see "Metaclass EnumeratedValues Property" on page 16-7.

Testing for an Enumeration

```
To determine if a value is an enumeration, use the isenum function. For example:
```

```
today = WeekDays.Wednesday;
isenum(today)
ans =
     1
isenum returns true for empty enumeration objects:
noday = WeekDays.empty;
isenum(noday)
ans =
To determine if a class is an enumeration class, use the matlab.metadata.Class object.
today = WeekDays.Wednesday;
mc = metaclass(today);
mc.Enumeration
ans =
     1
```

See Also

Related Examples

"Enumeration Class Restrictions" on page 14-26

Hide Enumeration Members

Hiding enumeration members enables class authors to change enumeration member names without causing incompatibilities in existing code. To hide members, create an enumeration block that sets the Hidden attribute. Members defined in a Hidden enumeration block are not visible when enumeration members are gueried using the enumeration function.

When an enumeration class derives from another class, such as a numeric or logical class, then each member can have a value associated with it. If two members have the same value assigned to them, then the member defined first in the class definition masks the second member. Both names are valid enumeration members, but the first one defined is the primary member. While masking makes it possible to use one member name in place of another, it does not hide the secondary name from the class users.

Using the Hidden attribute removes the masked member names from user view. For example, the HighlightColor class defines enumeration members that represent syntax highlighting colors.

```
classdef HighlightColor < int32
    enumeration
        red (1)
        green (2)
        blue (3)
    end
end</pre>
```

A new version of the class uses more descriptive member names, but the class needs to avoid breaking existing code that uses the original member names, red, green, and blue. Using the Hidden attribute for enumeration members enables the class to hide the original members.

```
classdef HighlightColor < int32
    enumeration
        error (1)
        comment (2)
        keyword (3)
    end
    enumeration (Hidden)
        red (1)
        green (2)
        blue (3)
    end
end</pre>
```

Code that uses the original member names continues to work. For example, existing references to the now-hidden member HighlightColor.blue is compatible with the same-valued nonhidden member HighlightColor.keyword.

```
a = HighlightColor.blue
a =
  HighlightColor enumeration
   keyword
a == HighlightColor.Keyword
ans =
```

```
logical
```

For enumeration members that represent values, the first member defined in the class is the primary member for that value. For example, in the HighlightColor class, keyword is the primary member and blue is the secondary member, both representing the value 3. Typically, the primary member is not hidden while the secondary member is hidden. However, if the class design requires that the primary member is hidden, then the secondary member must be hidden too.

Hide Pure Enumerations

Pure enumeration members have no underlying values, so there is no way to identify one member as a replacement for another. However, you can use the Hidden attribute to remove a member from the user view while avoiding incompatibilities with existing uses of the hidden member.

For example, the PCComponents class defines enumerations that are used in an online form for a computer order. While the FloppyDrive component is obsolete, the enumeration member can remain in the class as a hidden member. The form can exclude FloppyDrive from the list of choices, but the class author can keep this member available so that existing forms that refer to FloppyDrive are still valid.

```
classdef PCComponents
    enumeration
        USBSlots
        CDPlayer
    end
    enumeration (Hidden)
        FloppyDrive
    end
end
```

Find Hidden Enumeration Members

Find information about hidden enumeration members using class metadata. The matlab.metadata.EnumerationMember class provides information on enumeration members. For example, accessing the metadata for the HighlightColor class used in preceding examples can show the names of hidden members.

Each enumeration member is described by a matlab.metadata.EnumerationMember object that is contained in the EnumerationMemberList property. For example, the fourth element in the EnumerationMemberList array contains the matlab.metadata.EnumerationMember object for the member with the name red.

To list the names of all hidden members, use the handle class findobj method:

```
findobj(mc.EnumerationMemberList, 'Hidden', true).Name
```

```
ans =
    'red'
ans =
    'green'
ans =
    'blue'
```

See Also

findobj | enumeration

Enumeration Class Restrictions

Enumeration classes restrict certain aspects of their use and definition:

- Enumeration classes are implicitly Sealed. You cannot define a subclass of an enumeration class because doing so would expand the set.
- The properties of value-based enumeration classes are immutable. Only the constructor can assign
 property values. MATLAB implicitly defines the SetAccess attributes of all properties defined by
 value-based enumeration classes as immutable. You cannot set the SetAccess attribute to any
 other value.
- All properties inherited by a value-based enumeration class that are not defined as Constant must have immutable SetAccess.
- The properties of handle-based enumeration classes are mutable. You can set property values on instances of the enumeration class. See "Mutable Handle vs. Immutable Value Enumeration Members" on page 14-32.
- An enumeration member cannot have the same name as a property, method, or event defined by the same class or inherited from a superclass. For example, an enumeration class that inherits from a built-in numeric superclass inherits the full method from the superclass, so "full" is not a valid member name.
- Enumerations do not support colon (a:b) operations. For example,
 FlowRate.Low:FlowRate.High causes an error even if the FlowRate class derives from a numeric superclass.
- Classes that define enumerations cannot restrict properties of the same class to an enumeration type. Create a separate enumeration class to restrict property values to an enumeration. For information on restricting property values, see "Example of Restricted Property" on page 14-14.
- If the primary enumeration member sets the Hidden attribute, then the secondary member (one with the same underlying value) must also set the Hidden attribute. For more information, see "Hide Enumeration Members" on page 14-23.

See Also

Related Examples

"Enumerations Derived from Built-In Classes" on page 14-27

Enumerations Derived from Built-In Classes

```
"Subclassing Built-In Classes" on page 14-27

"Derive Enumeration Class from Numeric Class" on page 14-27

"How to Alias Enumeration Names" on page 14-28

"Superclass Constructor Returns Underlying Value" on page 14-29

"Default Converter" on page 14-30
```

Subclassing Built-In Classes

Enumeration classes can subclass MATLAB built-in classes. Deriving an enumeration class from built-in classes is useful to extend the usefulness of the enumeration members.

- Enumerations inherit functionality from the built-in class.
- You can associate a numeric or logical value with enumeration members.

For a more basic discussion of enumeration classes, see "Define Enumeration Classes" on page 14-4.

Derive Enumeration Class from Numeric Class

Note Enumeration classes derived from built-in numeric and logical classes cannot define properties.

If an enumeration class subclasses a built-in numeric class, the subclass inherits ordering and arithmetic operations that you can apply to the enumerated names.

For example, the Results class subclasses the int32 built-in class. This class associates an integer value with each of the four enumeration members — First, Second, Third, and NoPoints.

```
classdef Results < int32
  enumeration
    First (100)
    Second (50)
    Third (10)
    NoPlace (0)
  end
end</pre>
```

The enumeration member inherits the methods of the int32 class (except the colon operator). Use these enumerations like numeric values (summed, sorted, averaged).

```
isa(Results.Second, 'int32')
ans =
1
```

For example, use enumeration names instead of numbers to rank two teams:

```
Team1 = [Results.First, Results.NoPlace, Results.Third, Results.Second];
Team2 = [Results.Second, Results.Third, Results.First, Results.First];
```

Perform int32 operations on these Results enumerations:

```
sum(Team1)
ans =
   160
mean(Team1)
ans =
    40
sort(Team2, 'descend')
ans =
                                        Third
    First
                First
                            Second
Team1 > Team2
ans =
     1
           0
                  0
                         0
sum(Team1) < sum(Team2)
ans =
     1
```

How to Create Enumeration Instances

When you first refer to an enumeration class that derives from a built-in class such as, int32, MATLAB passes the input arguments associated with the enumeration members to the superclass constructor. For example, referencing the Second Results member, defined as:

```
Second (50)
means that MATLAB calls:
int32(50)
to initialize the int32 aspect of this Results object.
```

How to Alias Enumeration Names

Enumeration classes that derive from MATLAB built-in numeric and logical classes can define more than one name for an underlying value. The first name in the enumeration block with a given underlying value is the actual name for that underlying value and subsequent names are aliases.

Specify aliased names with the same superclass constructor argument as the actual name:

```
classdef Bool < logical
  enumeration
    No (0)
    Yes (1)
    off (0)</pre>
```

```
on (1)
end
end
```

For example, the actual name of an instance of the Bool.off enumeration member is No:

```
a = Bool.No
a =
    No
b = Bool.off
b =
    No
```

Superclass Constructor Returns Underlying Value

The actual underlying value associated with an enumeration member is the value returned by the built-in superclass. For example, consider the Bool class defined with constructor arguments that are of class double:

```
classdef Bool < logical
   enumeration
    No (0)
    Yes (100)
   end
end</pre>
```

This class derives from the built-in logical class. Therefore, underlying values for an enumeration member depend only on what value logical returns when passed that value:

```
a = Bool.Yes
a =
    Yes
logical(a)
ans =
    1
```

How to Subclass Numeric Built-In Classes

The FlowRate enumeration class defines three members, Low, Medium, and High.

```
classdef FlowRate < int32
  enumeration
    Low (10)
    Medium (50)
    High (100)
  end
end</pre>
```

Reference an instance of an enumeration member:

```
setFlow = FlowRate.Medium;
```

This statement causes MATLAB to call the default constructor with the argument value of 50. MATLAB passes this argument to the first superclass constructor (int32(50) in this case). The result is an underlying value of 50 as a 32-bit integer for the FlowRate.Medium member.

Because FlowRate subclasses a built-in numeric class (int32), this class cannot define properties. However FlowRate inherits int32 methods including a converter method. Programs can use the converter to obtain the underlying value:

```
setFlow = FlowRate.Medium;
int32(setFlow)
ans =
```

Default Converter

If an enumeration is a subclass of a built-in numeric class, you can convert from built-in numeric data to the enumeration using the name of the enumeration class. For example:

```
a = Bool(1)
a =
Yes
```

An enumerated class also accepts enumeration members of its own class as input arguments:

```
Bool(a)
ans =
Yes
```

The converter returns an object of the same size as in input:

```
Bool([0,1])
ans =
     No Yes
```

Create an empty enumeration array using the empty static method:

```
Bool.empty
ans =
   0x0 empty Boolean enumeration.
```

See Also

Related Examples

- "Mutable Handle vs. Immutable Value Enumeration Members" on page 14-32
- "Fundamental MATLAB Classes"

Mutable Handle vs. Immutable Value Enumeration Members

```
In this section...

"Select Handle- or Value-Based Enumerations" on page 14-32

"Value-Based Enumeration Classes" on page 14-32

"Handle-Based Enumeration Classes" on page 14-33

"Represent State with Enumerations" on page 14-35
```

Select Handle- or Value-Based Enumerations

Use a handle enumeration to enumerate a set of objects whose state can change over time. Use a value enumeration to enumerate a set of abstract (and immutable) values. For information about handle and value classes, see "Comparison of Handle and Value Classes" on page 7-2.

Value-Based Enumeration Classes

A value-based enumeration class has a fixed set of specific values. Modify these values by changing the values of properties. Doing so expands or changes the fixed set of values for this enumeration class.

Inherited Property SetAccess Must Be Immutable

Value-based enumeration classes implicitly define the SetAccess attributes of all properties as immutable. You cannot set the SetAccess attribute to any other value.

However, all superclass properties must explicitly define property SetAccess as immutable.

Enumeration Members Remain Constant

An instance of a value-based enumeration class is unique until the class is cleared and reloaded. For example, given this class:

```
classdef WeekDays
    enumeration
        Monday, Tuesday, Wednesday, Thursday, Friday
    end
end

MATLAB considers a and b as equivalent:

a = WeekDays.Monday;
b = WeekDays.Monday;
isequal(a,b)

ans =

1

a == b
```

```
ans =
```

Enumeration Member Properties Remain Constant

Value-based enumeration classes that define properties are immutable. For example, the Colors enumeration class associates RGB values with color names.

```
classdef Colors
   properties
      R = 0
      G = 0
      B = 0
   end
   methods
      function c = Colors(r,g,b)
        c.R = r; c.G = g; c.B = b;
   end
   enumeration
     Red
           (1, 0, 0)
      Green (0, 1, 0)
      Blue (0, 0, 1)
   end
end
```

The constructor assigns the input arguments to R, G, and B properties:

You cannot change a property value:

```
red.G = 1;
```

You cannot set the read-only property 'G' of Colors.

Handle-Based Enumeration Classes

Handle-based enumeration classes that define properties are mutable. Derive enumeration classes from the handle class when you must be able to change property values on instances of that class.

Note You cannot derive an enumeration class from matlab.mixin.Copyable because the number of instances you can create are limited to the ones defined inside the enumeration block.

An Enumeration Member Remains Constant

Given a handle-based enumeration class with properties, changing the property value of an instance causes all references to that instance to reflect the changed value.

For example, the HandleColors enumeration class associates RGB values with color names, the same as the Colors class in the previous example. However, HandleColors derives from handle:

```
classdef HandleColors < handle</pre>
   properties
      R = 0
      G = 0
      B = 0
   methods
      function c = HandleColors(r, g, b)
         c.R = r; c.G = g; c.B = b;
      end
   end
   enumeration
            (1, 0, 0)
      Red
      Green (0, 1, 0)
      Blue (0, 0, 1)
   end
end
```

Create an instance of HandleColors.Red and return the value of the R property:

```
a = HandleColors.Red;
a.R
ans =
```

MATLAB constructs the HandleColors.Red enumeration member, which sets the R property to 1, the G property to 0, and the B property to 0.

Change the value of the R property to 0.8:

```
a.R = 0.8;
```

After setting the value of the R property to 0.8, create another instance, b, of HandleColors.Red:

```
b = HandleColors.Red;
b.R
ans =
    0.8000
```

The value of the R property of the newly created instance is also 0.8. A MATLAB session has only one value for any enumeration member at any given time.

Clearing the workspace variables does not change the current definition of the enumeration member HandleColors.Red:

```
clear
a = HandleColors.Red;
a.R
ans =
0.8000
```

Clear the class to reload the definition of the HandleColors class:

```
clear classes
a = HandleColors.Red;
a.R
ans =
1
```

To prevent reassignment of a given property value, set that property's SetAccess attribute to immutable.

Equality of Handle-Based Enumerations

Assign two variables to a particular enumeration member:

```
a = HandleColors.Red;
b = HandleColors.Red;
Compare a and b using isequal:
isequal(a,b)
ans =
```

The property values of a and b are the same, so isequal returns true. However, unlike handle classes that are not enumeration classes, a and b are the same handle because there is only one enumeration member. Determine handle equality using == (the handle eq method).

```
a == b
ans =
```

See the handle eq method for information on how isequal and == differ when used with handles.

Represent State with Enumerations

The MachineState class defines two enumeration members to represent the state of a machine, either running or not running.

```
classdef MachineState
   enumeration
      Running
      NotRunning
   end
end
```

The Machine class represents a machine with start and stop operations. The MachineState enumerations are easy to work with because of their eq and char methods, and they result in code that is easy to read.

```
classdef Machine < handle
  properties (SetAccess = private)</pre>
```

```
State = MachineState.NotRunning
   end
   methods
      function start(machine)
         if machine.State == MachineState.NotRunning
            machine.State = MachineState.Running;
         end
         disp (machine.State.char)
      function stop(machine)
         if machine.State == MachineState.Running
            machine.State = MachineState.NotRunning;
         disp (machine.State.char)
      end
   end
end
Create a Machine object and call start and stop methods
m = Machine;
m.start
Running
m.stop
NotRunning
```

See Also

Related Examples

• "Enumerations That Encapsulate Data" on page 14-37

Enumerations That Encapsulate Data

```
In this section...

"Enumeration Classes with Properties" on page 14-37

"Store Data in Properties" on page 14-37
```

Enumeration Classes with Properties

Enumeration classes can define properties to store data values. The enumeration members represent specific values for these properties, which MATLAB assigns in the class constructor. For information on defining enumeration classes, see "Define Enumeration Classes" on page 14-4.

Store Data in Properties

Note Enumeration classes that subclass built-in numeric or logical classes cannot define or inherit properties. For more information on this kind of enumeration class, see "Enumerations Derived from Built-In Classes" on page 14-27.

Define properties in an enumeration class if you want to associate specific data with enumeration members, but do not need to inherit arithmetic, ordering, or other operations that MATLAB defines for specific built-in classes.

Representing Colors

Define an enumeration class to represent the RGB values of the colors in a color set. The Colors class defines names for the colors, each of which uses the RGB values as arguments to the class constructor:

```
classdef Colors
   properties
      R = 0
      G = 0
      B = 0
   methods
      function c = Colors(r, q, b)
         c.R = r; c.G = g; c.B = b;
      end
   end
   enumeration
      Blueish
                (18/255, 104/255, 179/255)
                (237/255,36/255,38/255)
      Reddish
      Greenish (155/255,190/255,61/255)
      Purplish (123/255,45/255,116/255)
      Yellowish (1,199/255,0)
      LightBlue (77/255, 190/255, 238/255)
end
```

You can access the property values via the enumeration member:

```
Colors.Reddish.R
```

```
ans = 0.9294
```

Suppose that you want to create a plot with the new shade of red named Reddish:

```
a = Colors.Reddish;
[a.R,a.G,a.B]
ans =
0.9294  0.1412  0.1490
```

Use these values by accessing the enumeration member properties. For example, the myPlot function accepts a Colors enumeration member as an input argument. The function accesses the RGB values defining the color from the property values.

```
function h = myPlot(x,y,LineColor)
  h = line('XData',x,'YData',y);
  r = LineColor.R;
  g = LineColor.G;
  b = LineColor.B;
  h.Color = [r g b];
end
```

Create a plot using a reddish color line:

```
h = myPlot(1:10,1:10,Colors.Reddish);
```

The Colors class encapsulates the definitions of a standard set of colors. You can change the enumeration class definition of the colors and not affect functions that use the enumerations.

Enumerations Defining Categories

The Cars class defines categories used to inventory automobiles. The Cars class derives from the CarPainter class, which derives from handle. The abstract CarPainter class defines a paint method, which modifies the Color property when a car is painted another color.

The Cars class uses the Colors enumeration members to specify a finite set of available colors. The exact definition of any given color can change independently of the Cars class.

```
classdef Cars < CarPainter</pre>
   enumeration
      Hybrid (2, 'Manual', 55, Colors. Reddish)
      Compact(4, 'Manual', 32, Colors.Greenish)
      MiniVan(6, 'Automatic', 24, Colors .Blueish)
              (8, 'Automatic', 12, Colors. Yellowish)
      SUV
   properties (SetAccess = private)
      Cylinders
      Transmission
      MPG
      Color
   methods
      function obj = Cars(cyl,trans,mpg,colr)
         obj.Cylinders = cyl;
         obj.Transmission = trans;
```

```
obj.MPG = mpg;
          obj.Color = colr;
      function paint(obj,colorobj)
          if isa(colorobj, 'Colors')
             obj.Color = colorobj;
          else
             [~,cls] = enumeration('Colors');
             disp('Not an available color')
             disp(cls)
          end
      end
   end
end
The CarPainter class requires its subclasses to define a method called paint:
classdef CarPainter < handle</pre>
   methods (Abstract)
      paint(carobj,colorobj)
   end
end
Define an instance of the Cars class:
c1 = Cars.Compact;
The color of this car is Greenish, as defined by the Colors. Greenish enumeration:
c1.Color
ans =
    Greenish
Use the paint method to change the car color:
c1.paint(Colors.Reddish)
c1.Color
ans =
    Reddish
```

See Also

Related Examples

- "Save and Load Enumerations" on page 14-40
- "Enumerations for Property Values" on page 14-14

Save and Load Enumerations

In this section...

"Basic Knowledge" on page 14-40

"Built-In and Value-Based Enumeration Classes" on page 14-40

"Simple and Handle-Based Enumeration Classes" on page 14-40

"Causes: Load as struct Instead of Object" on page 14-40

Basic Knowledge

See the save and load functions and "Default Save and Load Process for Objects" on page 13-2 for general information on saving and loading objects.

To see a list of enumeration names defined by a class, use the enumeration function.

Built-In and Value-Based Enumeration Classes

When you save enumerations that derive from built-in classes or that are value-based classes with properties, MATLAB saves the names of the enumeration members and the definition of each member.

When loading these enumerations, MATLAB preserves names over underlying values. If the saved named value is different from the current class definition, MATLAB uses the value defined in the current class, and then issues a warning.

Simple and Handle-Based Enumeration Classes

When you save simple enumerations that have no properties, superclasses, or values associated with the member names or enumerations derived from the handle class, MATLAB saves the names and any underlying values.

When loading these types of enumerations, MATLAB does not check the values associated with the names in the current class definition. This behavior results from the fact that simple enumerations have no underlying values and handle-based enumerations can legally have values that are different than those values defined by the class.

Causes: Load as struct Instead of Object

If you add a new named value or a new property to a class after saving an enumeration, MATLAB does not warn during load.

If the changes to the enumeration class definition do not prevent MATLAB from loading the object (that is, all the named values in the MAT-File are present in the modified class definition), then MATLAB issues a warning that the class has changed and loads the enumeration.

In these five cases, MATLAB issues a warning. In case 1, there are no defined results. In cases 2 through 5, MATLAB loads as much of the saved data as possible as a struct:

1 MATLAB cannot find the class definition.

- **2** The class is no longer an enumeration class.
- **3** MATLAB cannot initialize the class.
- 4 There are one or more enumeration members in the loaded enumeration that is not in the class definition.
- 5 If the class is a value-based enumeration with properties and a property that exists in the file, is not present in the class definition.

struct Fields

In cases 2 through 5, the returned struct has these fields:

- ValueNames A cell array of strings, one per unique value in the enumeration array.
- Values An array of the same dimension as ValueNames containing the corresponding values
 of the enumeration members named in ValueNames. Depending on the kind of enumeration class,
 Values can be one of these:
 - If the enumeration class derives from a built-in class, the array class is the same as the built-in class. The values in the array are the underlying values of each enumeration member.
 - Otherwise, a struct array representing the property name property values pairs of each enumeration member. For simple and handle-based enumerations, the struct array has no fields.
- ValueIndices a uint32 array of the same size as the original enumeration. Each element is an index into the ValueNames and Values arrays. The content of ValueIndices represents the value of each object in the original enumeration array.

See Also

More About

• "Named Values" on page 14-2

Constant Properties

Define Class Properties with Constant Values

```
In this section...

"Defining Named Constants" on page 15-2

"Constant Property Assigned a Handle Object" on page 15-3

"Constant Property Assigned Any Object" on page 15-4

"Constant Properties Do Not Support Events" on page 15-5
```

Defining Named Constants

You can define constants that you can refer to by name by creating a MATLAB class that defines constant properties.

Use constant properties to define constant values that you can access by name. Create a class with constant properties by declaring the Constant attribute in the property blocks. Setting the Constant attribute means that, once initialized to the value specified in the property block, the value cannot be changed.

Assigning Values to Constant Properties

Assign any value to a Constant property, including a MATLAB expression. For example:

```
classdef NamedConst
  properties (Constant)
    R = pi/180
    D = 1/NamedConst.R
    AccCode = '0145968740001110202NPQ'
    RN = rand(5)
  end
end
```

MATLAB evaluates the expressions when loading the class. Therefore, the values MATLAB assigns to RN are the result of a single call to the rand function and do not change with subsequent references to NamedConst.RN. Calling clear classes causes MATLAB to reload the class and reinitialize the constant properties.

Referencing Constant Properties

Refer to the constant using the class name and the property name:

```
ClassName.PropName
```

For example, to use the NamedConst class defined in the previous section, reference the constant for the degree to radian conversion, R:

```
radi = 45*NamedConst.R
radi =
    0.7854
```

Constants in Namespaces

To create a library for constant values that you can access by name, first create a namespace folder, then define the various classes to organize the constants. For example, to implement a set of constants that are useful for making astronomical calculations, define a AstroConstants class in a namespace called constants:

+constants/@AstroConstants/AstroConstants.m

The class defines a set of Constant properties with values assigned:

To use this set of constants, reference them with a fully qualified class name. For example, the following function uses some of the constants defined in AstroContants:

Importing the namespace into the function eliminates the need to repeat the namespace name (see import):

Constant Property Assigned a Handle Object

If a class defines a constant property with a value that is a handle object, you can assign values to the handle object properties. To access the handle object, create a local variable.

For example, the ConstMapClass class defines a constant property. The value of the constant property is a handle object (a containers.Map object).

```
classdef ConstMapClass < handle
   properties (Constant)
        ConstMapProp = containers.Map
   end
end</pre>
```

To assign the current date to the <code>Date</code> key, return the handle from the constant property, then make the assignment using the local variable on the left side of the assignment statement:

```
localMap = ConstMapClass.ConstMapProp
localMap('Date') = datestr(clock);
```

You cannot use a reference to a constant property on the left side of an assignment statement. For example, MATLAB interprets the following statement as the creation of a struct named ConstMapClass with a field ConstMapProp:

```
ConstMapClass.ConstMapProp('Date') = datestr(clock);
```

Constant Property Assigned Any Object

You can assign an instance of the defining class to a constant property. MATLAB creates the instance assigned to the constant property when loading the class. Use this technique only when the defining class is a handle class.

The MyProject is an example of such a class:

```
classdef MyProject < handle</pre>
   properties (Constant)
      ProjectInfo = MyProject
   properties
      Date
      Department
      ProjectNumber
   end
   methods (Access = private)
      function obj = MyProject
         obj.Date = datestr(clock);
         obj.Department = 'Engineering';
         obj.ProjectNumber = 'P29.367';
      end
   end
end
```

Reference property data via the Constant property:

```
MyProject.ProjectInfo.Date
ans =
```

18-Apr-2002 09:56:59

Because MyProject is a handle class, you can get the handle to the instance that is assigned to the constant property:

```
p = MyProject.ProjectInfo;
```

Access the data in the MyProject class using this handle:

```
p.Department
ans =
Engineering
```

Modify the nonconstant properties of the MyProject class using this handle:

```
p.Department = 'Quality Assurance';
```

p is a handle to the instance of MyProject that is assigned to the ProjectInfo constant property:

MyProject.ProjectInfo.Department

```
ans =
```

Quality Assurance

Clearing the class results in the assignment of a new instance of MyProject to the ProjectInfo property.

```
clear classes
MyProject.ProjectInfo.Department
ans =
Engineering
```

You can assign an instance of the defining class as the default value of a property only when the property is declared as Constant

Constant Properties Do Not Support Events

Constant properties do not support property events. MATLAB issues a warning during class initialization if you set the GetObservable or SetObservable attribute of a Constant property to true.

See Also

Related Examples

"Static Data" on page 4-2

More About

• "Named Values" on page 14-2

Information from Class Metadata

- "Class Metadata" on page 16-2
- "Class Introspection with Metadata" on page 16-5
- "Find Objects with Specific Values" on page 16-9
- "Get Information About Properties" on page 16-12
- "Find Default Values in Property Metadata" on page 16-17

Class Metadata

```
#What Is Class Metadata?" on page 16-2

"The matlab.metadata Namespace" on page 16-2

"Metaclass Objects" on page 16-3

"Metaclass Object Lifecycle" on page 16-3
```

What Is Class Metadata?

Class metadata is information about class definitions that is available from various metaclasses objects. Use metaclass objects to obtain information without having to create instances of the class. Metadata enables the programmatic inspection of classes. Each metaclass has properties, methods, and events that contain information about the class or class component it describes.

All class components have an associated metaclass, which you access from the matlab.metadata.Class object. For example, create the matlab.metadata.Class object for the matlab.alias.AliasFileManager class:

```
mc = ?matlab.alias.AliasFileManager
  Class with properties:
                      Name: 'matlab.alias.AliasFileManager'
      Description: 'Create and edit alias definition files'
DetailedDescription: 'Use an AliasFileManager object to create...'
                    Sealed: 1
                  Abstract: 0
              Fnumeration: 0
          ConstructOnLoad: 0
         HandleCompatible: 1
          InferiorClasses: [0×1 matlab.metadata.Class]
                 Namespace: [1×1 matlab.metadata.Namespace]
                   Aliases: [0×1 string]
     RestrictsSubclassing: 1
              PropertyList: [1×1 matlab.metadata.Property]
               MethodList: [28×1 matlab.metadata.Method]
                 EventList: [1x1 matlab.metadata.Event]
    EnumerationMemberList: [0×1 matlab.metadata.EnumerationMember]
           SuperclassList: [1x1 matlab.metadata.Class]
```

The matlab.metadata Namespace

The matlab.metadata namespace contains metaclasses that describe the definition of classes and class components. The class name indicates the component described by the metaclass. For example, each class property has a matlab.metadata.Property associated with it. Attributes defined for class components correspond to properties in the respective metaclass object.

- matlab.metadata.Namespace Access from matlab.metadata.Class Namespace property.
- matlab.metadata.Class Create from class name or class object using metaclass function or ? operator.
- matlab.metadata.Property Access from matlab.metadata.Class PropertyList property.

- matlab.metadata.DynamicProperty Obtain from the addprop method.
- matlab.metadata.Method Access from matlab.metadata.Class MethodList property.
- matlab.metadata.Event Access from matlab.metadata.Class EventList property.
- matlab.metadata.EnumerationMember Access from matlab.metadata.Class EnumerationMemberListList property.

Metaclass Objects

You cannot instantiate metaclasses directly by calling the respective class constructor. Create metaclass objects from class instances or from the class name.

- ?ClassName Returns a matlab.metadata.Class object for the named class. Use matlab.metadata.Class.fromName with class names stored as characters in variables.
- matlab.metadata.Class.fromName('ClassName') returns the
 matlab.metadata.Class object for the named class (matlab.metadata.Class.fromName is
 a matlab.metadata.Class method).
- metaclass(obj) Returns a metaclass object for the class instance (metaclass)

Create matlab.metadata.Class object from class name using the ? operator:

```
mc = ?MyClass;
```

Create matlab.metadata.Class object from class name using the fromName method:

```
mc = matlab.metadata.Class.fromName('MyClass');
```

Create matlab.metadata.Class object from class instance

```
obj = MyClass;
mc = metaclass(obj);
```

The metaclass function returns the matlab.metadata.Class object (that is, an object of the matlab.metadata.Class class). You can obtain other metaclass objects (matlab.metadata.Property, matlab.metadata.Method, and so on) from the matlab.metadata.Class object.

Note Metaclass is a term used here to refer to all the classes in the matlab.metadata namespace. matlab.metadata.Class is a class in the matlab.metadata namespace whose instances contain information about MATLAB classes. Metadata is information about classes contained in metaclasses.

Metaclass Object Lifecycle

When you change a class definition, MATLAB reloads the class definition. If instances of the class exist, MATLAB updates those objects according to the new definition.

However, MATLAB does not update existing metaclass objects to the new class definition. If you change a class definition while metaclass objects of that class exist, MATLAB deletes the metaclass objects and their handles become invalid. You must create a new metaclass object after updating the class.

For information on how to modify and reload classes, see "Automatic Updates for Modified Classes" on page 5-27.

See Also

Related Examples

- "Class Introspection with Metadata" on page 16-5
- "Find Objects with Specific Values" on page 16-9
- "Get Information About Properties" on page 16-12
- "Find Default Values in Property Metadata" on page 16-17

Class Introspection with Metadata

```
### In this section...

#Using Class Metadata" on page 16-5

#Inspect the EmployeeData Class" on page 16-5

#Metaclass EnumeratedValues Property" on page 16-7
```

Using Class Metadata

Use class metadata to get information about classes and objects programmatically. For example, you can determine attribute values for class members or get a list of events defined by the class. For basic information about metadata, see "Class Metadata" on page 16-2.

Inspect the EmployeeData Class

The EmployeeData class is a handle class with two properties, one of which has private Access and defines a set access method.

```
classdef EmployeeData < handle</pre>
   properties
      EmployeeName
   properties (Access = private)
      EmployeeNumber
   methods
      function obj = EmployeeData(name,ss)
         if nargin > 0
            obj.EmployeeName = name;
            obj.EmployeeNumber = ss;
         end
      end
      function set.EmployeeName(obj,name)
         if ischar(name)
            obj.EmployeeName = name;
            error('Employee name must be a char vector')
         end
      end
   end
end
```

Inspect Class Definition

Using the EmployeeData class, create a matlab.metadata.Class object using the ? operator:

```
mc = ?EmployeeData;
```

Determine from what classes EmployeeData derives. The returned value is a matlab.metadata.Class object for the handle superclass:

```
a = mc.SuperclassList;
a.Name
```

```
ans =
```

The EmployeeData class has only one superclass. For classes having more than one direct superclass, a contains a matlab.metadata.Class object for each superclass.

Use an indexed reference to refer to any particular superclass:

```
a(1).Name
or, directly from mc:
mc.SuperclassList(1).Name
ans =
handle
```

The SuperclassList property contains only direct superclasses.

Inspect Properties

Find the names of the properties defined by the EmployeeData class. First obtain an array of matlab.metadata.Property objects from the matlab.metadata.Class PropertyList property.

```
mc = ?EmployeeData;
mpArray = mc.PropertyList;
```

The length of mpArray indicates that there are two matlab.metadata.Properties objects, one for each property defined by the EmployeeData class:

The Name property of the matlab.metadata.Property object identifies the class property represented by that matlab.metadata.Property object.

Query other matlab.metadata.Property object properties to determine the attributes of the EmployeeName properties.

Find Component with Specific Attribute

You can use indexing techniques to list class components that have specific attribute values. For example, this code lists the methods in the EmployeeData class that have private access:

```
mc = ?EmployeeData;
mc.PropertyList(ismember({mc.PropertyList(:).SetAccess},'private')).Name
```

```
ans =
EmployeeNumber
```

Access is not a property of the matlab.metadata.Property class. Use SetAccess and GetAccess, which are properties of the matlab.metadata.Property class.

Find components with attributes that are logical values using a statement like this one:

```
mc = ?handle;
mc.MethodList(ismember([mc.MethodList(:).Hidden],true)).Name
ans =
empty
```

Inspect Class Instance

Create an EmployeeData object and determine property access settings:

```
Ed0bj = EmployeeData('My Name',1234567);
mcEd0bj = metaclass(Ed0bj);
mpArray = mcEd0bj.PropertyList;
Ed0bj.(mpArray(1).Name) % Dynamic field names work with objects
```

The value of the EmployeeName property is the text My Name, which was assigned in the constructor.

```
ans =
My Name
```

The value of the EmployeeNumber property is not accessible because the property has private Access.

```
EdObj.(mpArray(2).Name)
You cannot get the 'EmployeeNumber' property of EmployeeData.
mpArray(2).GetAccess
ans =
   private
```

Obtain a function handle to the EmployeeName property set access function:

```
mpArray(1).SetMethod
ans =
    @D:\MyDir\@EmployeeData\EmployeeData.m>EmployeeData.set.EmployeeName
```

Metaclass EnumeratedValues Property

The matlab.metadata.Class EnumerationMemberList property contains an array of matlab.metadata.EnumerationMember objects, one for each enumeration member. Use the matlab.metadata.EnumerationMember Name property to obtain the enumeration member names defined by an enumeration class. For example, given the WeekDays enumeration class:

```
classdef WeekDays
  enumeration
    Monday, Tuesday, Wednesday, Thursday, Friday
```

```
end
end
```

Query enumeration names from the matlab.metadata.Class object:

```
mc = ?WeekDays;
mc.EnumerationMemberList(2).Name
ans =
Tuesday
```

See Also

Related Examples

"Find Objects with Specific Values" on page 16-9

Find Objects with Specific Values

```
In this section...

"Find Handle Objects" on page 16-9

"Find by Attribute Settings" on page 16-10
```

Find Handle Objects

Use the handle class findobj method to find objects that have properties with specific values. For example, the following class defines a PhoneBook object to represent a telephone book entry in a data base. The PhoneBook class subclasses the dynamicprops class, which derives from handle.

```
classdef PhoneBook < dynamicprops
  properties
    Name
    Address
    Number
end
methods
    function obj = PhoneBook(n,a,p)
    obj.Name = n;
    obj.Address = a;
    obj.Number = p;
end
end</pre>
```

Here are three of the PhoneBook entries in the database:

```
PB(1) = PhoneBook('Nancy Vidal','123 Washington Street','5081234567');
PB(2) = PhoneBook('Nancy Vidal','123 Main Street','5081234568');
PB(3) = PhoneBook('Nancy Wong','123 South Street','5081234569');
```

One of these three PhoneBook objects has a dynamic property:

```
PB(2).addprop('HighSpeedInternet');
PB(2).HighSpeedInternet = '1M';
```

Find Property/Value Pairs

Find the object representing employee Nancy Wong and display the name and number by concatenating the strings:

```
NW = findobj(PB,'Name','Nancy Wong');
[NW.Name,' - ',NW.Number]
ans =
Nancy Wong - 5081234569
```

Find Objects with Specific Property Names

Search for objects with specific property names using the -property option:

```
H = findobj(PB,'-property','HighSpeedInternet');
H.HighSpeedInternet
```

```
ans =
```

The -property option enables you to omit the value of the property and search for objects using only the property name.

Using Logical Expressions

Search for specific combinations of property names and values:

```
H = findobj(PB,'Name','Nancy Vidal','-and','Address','123 Main Street');
H.Number
ans =
5081234568
```

Find by Attribute Settings

All metaclasses derive from the handle class. You can use the handle findobj method to find class members that have specific attribute settings.

For example, find the abstract methods in a class definition by searching the matlab.metadata.Class MethodList for matlab.metadata.Method objects with their Abstract property set to true:

Use the class name in character format because class is abstract. You cannot create an object of the class:

```
mc = matlab.metadata.Class.fromName('MyClass');
```

Search the MethodList list of matlab.metadata.Method objects for those methods that have their Abstract property set to true:

```
absMethods = findobj(mc.MethodList,'Abstract',true);
methodNames = {absMethods.Name};
```

The cell array, methodNames, contains the names of the abstract methods in the class.

Find Properties That Have Public Get Access

Find the names of all properties in the containers. Map class that have public GetAccess:

- Get the matlab.metadata.Class object.
- Use findobj to search the array of matlab.metadata.Property objects.
- Use braces to create a cell array of property names.

```
mc = ?containers.Map;
mpArray = findobj(mc.PropertyList,'GetAccess','public');
names = {mpArray.Name};
```

Display the names of all containers. Map properties that have public GetAccess:

```
celldisp(names)
names{1} =
```

```
Count
  names{2} =
KeyType
names{3} =
ValueType
```

Find Static Methods

Determine if any containers. Map class methods are static:

```
~isempty(findobj([mc.MethodList(:)],'Static',true))
ans =
1
```

findobj returns an array of matlab.metadata.Method objects for the static methods. In this case, the list of static methods is not empty. Therefore, there are static methods defined by this class.

Get the names of any static methods from the matlab.metadata.Method array:

```
staticMethodInfo = findobj([mc.MethodList(:)],'Static',true);
staticMethodInfo(:).Name
ans =
empty
```

The name of the static method (there is only one in this case) is empty. Here is the information from the matlab.metadata.Method object for the empty method:

staticMethodInfo

```
method with properties:

Name: 'empty'

Description: 'Returns an empty object array of the given size'

DetailedDescription: '

Access: 'public'

Static: 1

Abstract: 0

Sealed: 0

Hidden: 1

InputNames: {'varargin'}

OutputNames: {'E'}

DefiningClass: [lx1 matlab.metadata.Class]
```

See Also

empty

Related Examples

• "Get Information About Properties" on page 16-12

Get Information About Properties

```
In this section...
"The matlab.metadata.Property Object" on page 16-12
"How to Find Properties with Specific Attributes" on page 16-15
```

The matlab.metadata.Property Object

Use the matlab.metadata.Property class to determine the values of property attributes. The writable properties of a matlab.metadata.Property object correspond to the attributes of the associated property. The values of the writable matlab.metadata.Property properties correspond to the attribute values specified in the class definition.

You can get the matlab.metadata.Property object for a property from the matlab.metadata.Class object. To get the matlab.metadata.Class object for a class:

- Use the metaclass function on an object of the class.
- Use the ? operator with the class name.

For example, the BasicHandle class defines one public and two private properties:

Create the matlab.metadata.Class object using the ? operator with the class name:

```
mc = ?BasicHandle
mc =
```

```
Class with properties:

Name: 'BasicHandle'
Description: 'Inherits from handle superclass'
DetailedDescription: 'Defines 1 public and 2 private properties.'
Hidden: 0
Sealed: 0
Abstract: 0
Enumeration: 0
ConstructOnLoad: 0
HandleCompatible: 1
InferiorClasses: [0×1 matlab.metadata.Class]
Namespace: [0×0 matlab.metadata.Namespace]
Aliases: [0×1 string]
RestrictsSubclassing: 0
```

```
PropertyList: [3×1 matlab.metadata.Property]

MethodList: [24×1 matlab.metadata.Method]

EventList: [1×1 matlab.metadata.Event]

EnumerationMemberList: [0×1 matlab.metadata.EnumerationMember]

SuperclassList: [1×1 matlab.metadata.Class]
```

The matlab.metadata.Class object property named PropertyList contains an array of matlab.metadata.Property objects, one for each property defined by the class. For example, the name of the property associated with the matlab.metadata.Property object in element 1 is:

```
mc.PropertyList(1).Name
ans =
Date
```

The matlab.metadata.Class object contains a matlab.metadata.Property object for all properties, including hidden properties. The properties function returns only public properties.

For a handle class, use the handle findprop method to get the matlab.metadata.Property object for a specific property.

For example, find the matlab.metadata.Property object for the Category property of the BasicHandle class.

```
h = BasicHandle;
mp = findprop(h, 'Category')
mp =
  Property with properties:
                    Name: 'Category'
             Description: ''
     DetailedDescription: ''
               GetAccess: 'public'
               SetAccess: 'public'
               Dependent: 0
                Constant: 0
                Abstract: 0
               Transient: 0
                  Hidden: 0
           GetObservable: 0
           SetObservable: 0
                AbortSet: 0
             NonCopyable: 0
    PartialMatchPriority: 1
               GetMethod: []
               SetMethod: []
              HasDefault: 1
            DefaultValue: 'new'
              Validation: [1×1 matlab.metadata.Validation]
           DefiningClass: [1x1 matlab.metadata.Class]
```

The matlab.metadata.Property display shows that a default BasicHandle object Category property:

- Has public GetAccess and SetAccess
- · Has a default value of new

For a list of property attributes, see "Table of Property Attributes" on page 8-8.

How to Index Metaclass Objects

Access other metaclass objects directly from the matlab.metadata.Class object properties. For example, the statement:

```
example, the statement:
mc = ?containers.Map;
returns a matlab.metadata.Class object:
class(mc)
ans =
matlab.metadata.Class
Referencing the PropertyList matlab.metadata.Class property returns an array with one matlab.metadata.Property object for each property of the containers.Map class:
class(mc.PropertyList)
ans =
matlab.metadata.Property
Each array element is a single matlab.metadata.Property object:
mc.Properties(1)
ans =
```

The Name property of the matlab.metadata.Property object contains a char vector that is the name of the property:

```
class(mc.PropertyList(1).Name)
ans =
char
```

[1x1 matlab.metadata.Property]

Apply standard MATLAB indexing to access information in metaclass objects.

For example, the matlab.metadata.Class PropertyList property contains an array of matlab.metadata.Property objects. The following expression accesses the first matlab.metadata.Property object in this array and returns the first and last letters (C and t) of the char vector contained in the matlab.metadata.Property Name property.

```
mc.PropertyList(1).Name([1 end])
ans =
Ct
```

How to Find Properties with Specific Attributes

This example implements a function that finds properties with specific attribute values. For example, you can:

- Find objects that define constant properties (Constant attribute set to true).
- Determine what properties are read-only (GetAccess = public, SetAccess = private).

The findAttrValue function returns a cell array of property names that set the specified attribute. The function accesses information from metadata using these techniques:

- If input argument, obj, is a char vector, use the matlab.metadata.Class.fromName static method to get the matlab.metadata.Class object.
- If input argument, obj, is an object, use the metaclass function to get the matlab.metadata.Class object.
- Every property has an associated matlab.metadata.Property object. Obtain these objects from the matlab.metadata.Class PropertyList property.
- Use the handle class findprop method to determine if the requested property attribute is a valid attribute name. All property attributes are properties of the matlab.metadata.Property object. The statement, findobj (mp, 'PropertyName') determines whether the matlab.metadata.Property object, mp, has a property called PropertyName.
- Reference matlab.metadata.Property object properties using dynamic field names. For example, if attrName = 'Constant', then MATLAB converts the expression mp.(attrName) to mp.Constant
- The optional third argument enables you to specify the value of attributes whose values are not logical true or false (such as GetAccess and SetAccess).

```
function cl_out = findAttrValue(obj,attrName,varargin)
  if ischar(obi)
     mc = matlab.metadata.Class.fromName(obj);
  elseif isobject(obj)
     mc = metaclass(obj);
  ii = 0; numb props = length(mc.PropertyList);
  cl array = cell(1,numb props);
   for c = 1:numb props
      mp = mc.PropertyList(c);
      if isemptv (findprop(mp.attrName))
         error('Not a valid attribute name')
      attrValue = mp.(attrName);
      if attrValue
         if islogical(attrValue) || strcmp(varargin{1},attrValue)
            ii = ii + 1;
            cl array(ii) = {mp.Name};
         end
     end
  end
   cl_out = cl_array(1:ii);
```

Find Property Attributes

Define a containers. Map object:

```
mapobj = containers.Map({'rose', 'bicycle'}, {'flower', 'machine'});
Find properties with private SetAccess:
findAttrValue(mapobj, 'SetAccess', 'private')
ans =
    'Count'
              'KeyType'
                            'ValueType' 'serialization'
Find properties with public GetAccess:
findAttrValue(mapobj,'GetAccess','public')
ans =
    'Count'
             'KeyType' 'ValueType'
```

See Also

Related Examples

"Find Default Values in Property Metadata" on page 16-17

Find Default Values in Property Metadata

```
In this section...

"Default Values" on page 16-17

"matlab.metadata.Property Data" on page 16-17
```

Default Values

Class definitions can specify explicit default values for properties (see "Define Properties with Default Values" on page 8-14). Determine if a class defines an explicit default value for a property and what the value of the default is from the property matlab.metadata.Property object.

matlab.metadata.Property Data

The matlab.metadata.Class object for a class contains a matlab.metadata.Property object for every property defined by the class, including properties with private and protected access.

For example, get the matlab.metadata.Class object for the PropertyWithDefault class shown here:

```
classdef PropertyWithDefault
  properties
     Date = date
     RandNumber = randi(9)
  end
end
```

Get an array of matlab.metadata.Property objects from the matlab.metadata.Class object:

```
mc = ?PropertyWithDefault; % matlab.metadata.Class object
mp = mc.PropertyList; % matlab.metadata.Property array
```

The second element in the mp array is the matlab.metadata.Property object for the RandNumber property. Listing the matlab.metadata.Property object shows the information contained in its properties:

mp(2)

property with properties:

```
Name: 'RandNumber'

Description: ''

DetailedDescription: ''

GetAccess: 'public'

SetAccess: 'public'

Dependent: 0

Constant: 0

Abstract: 0

Transient: 0

Hidden: 0

GetObservable: 0

SetObservable: 0

AbortSet: 0

NonCopyable: 0
```

```
GetMethod: []
    SetMethod: []
   HasDefault: 1
DefaultValue: 5
DefiningClass: [1x1 matlab.metadata.Class]
```

Two of the listed matlab.metadata.Property properties provide information on default values:

- HasDefault true (displayed as 1) if the class specifies a default value for the property, false if it does not.
- DefaultValue Contains the default value, when the class defines a default value for the property. If the default value is an expression, the value of DefaultValue is the result of evaluating the expression.

For more information on the evaluation of property default values defined by expressions, see "Evaluation of Expressions in Class Definitions" on page 6-9.

These properties provide a programmatic way to obtain property default values without opening class definition files. Use these matlab.metadata.Property object properties to obtain property default values for both built-in classes and classes defined in MATLAB code.

Query Default Value

The procedure for querying a default value involves:

- Getting the matlab.metadata.Property object for the property whose default value you want to query.
- Testing the logical value of the matlab.metadata.Property HasDefault property to determine if the property defines a default value. MATLAB returns an error when you query the DefaultValue property if the class does not define a default value for the property.
- Obtaining the default value from the matlab.metadata.Property DefaultValue property if the HasDefault value is true.

Use the ? operator, the metaclass function, or the matlab.metadata.Class.fromName static method (works with char vector variable) to obtain a matlab.metadata.Class object.

The matlab.metadata.Class object PropertyList contains an array of matlab.metadata.Property objects, Identify which property corresponds to which matlab.metadata.Property object using the matlab.metadata.Property Name property.

For example, this class defines properties with default values:

```
classdef MyDefs
   properties
      Material = 'acrylic'
      InitialValue = 1.0
   end
end
```

Follow these steps to obtain the default value defined for the Material property. Include any error checking that is necessary for your application.

Get the matlab.metadata.Class object for the class:

```
mc = ?MyDefs;
```

2 Get an array of matlab.metadata.Property objects from the matlab.metadata.Class PropertyList property:

```
mp = mc.PropertyList;
```

3 The length of the mp array equals the number of properties. You can use the matlab.metadata.Property Name property to find the property of interest:

```
for k = 1:length(mp)
   if (strcmp(mp(k).Name,'Material')
```

Before querying the default value of the Material property, test the HasDefault matlab.metadata.Property to determine if MyClass defines a default value for this property:

```
if mp(k).HasDefault
    dv = mp(k).DefaultValue;
end
```

The DefaultValue property is read-only. Changing the default value in the class definition changes the value of DefaultValue property. You can query the default value of a property regardless of its access settings.

Abstract and dynamic properties cannot define default values. Therefore, MATLAB returns an error if you attempt to query the default value of properties with these attributes. Always test the logical value of the matlab.metadata.Property HasDefault property before querying the DefaultValue property to avoid generating an error.

Default Values Defined as Expressions

Class definitions can define property default values as MATLAB expressions (see "Evaluation of Expressions in Class Definitions" on page 6-9 for more information). MATLAB evaluates these expressions the first time the default value is needed, such as the first time you create an instance of the class.

Querying the matlab.metadata.Property DefaultValue property causes MATLAB to evaluate a default value expression, if it had not yet been evaluated. Therefore, querying a property default value can return an error or warning if errors or warnings occur when MATLAB evaluates the expression. See "Property with Expression That Errors" on page 16-20 for an example.

Property with No Explicit Default Value

MyClass does not explicitly define a default value for the Foo property:

```
classdef MyFoo
    properties
        Foo
    end
end
```

The matlab.metadata.Property instance for property Foo has a value of false for HasDefault. Because the class does not explicitly define a default value for Foo, attempting to access the DefaultValue property causes an error:

```
mc = ?MyFoo;
mp = mc.PropertyList(1);
mp.HasDefault
```

```
ans =
    (-)
dv = mp.DefaultValue;
No default value has been defined for property Foo
```

Abstract Property

MyClass defines the Foo property as Abstract:

```
classdef MyAbst
   properties (Abstract)
      Foo
   end
end
```

The matlab.metadata.Property instance for property Foo has a value of false for its HasDefault property because you cannot define a default value for an Abstract property. Attempting to access DefaultValue causes an error:

```
mc = ?MyAbst;
mp = mc.PropertyList(1);
mp.HasDefault
ans =
    (-)
dv = mp.DefaultValue;
Property Foo is abstract and therefore cannot have a default value.
```

Property with Expression That Errors

MyPropEr defines the Foo property default value as an expression that errors when evaluated.

```
classdef MyPropEr
   properties
      Foo = sin(pie/2)
   end
end
```

The matlab.metadata.Property object for property Foo has a value of true for its HasDefault property because Foo does have a default value:

```
sin(pie/2)
```

However, this expression returns an error (pie is a function that creates a pie graph, not the value pi).

```
mc = ?MyPropEr;
mp = mc.PropertyList(1);
mp.HasDefault
ans =
    1
```

```
dv = mp.DefaultValue;
Error using pie (line 29)
Not enough input arguments.
```

Querying the default value causes the evaluation of the expression and returns the error.

Property With Explicitly Defined Default Value of Empty

MyEmptyProp assigns a default of [] (empty double) to the Foo property:

```
classdef MyEmptyProp
  properties
    Foo = []
  end
end
```

The matlab.metadata.Property object for property Foo has a value of true for its HasDefault property. Accessing DefaultValue returns the value []:

See Also

Related Examples

• "Get Information About Properties" on page 16-12

Specialize Object Behavior

- "Methods That Modify Default Behavior" on page 17-2
- "Concatenation Methods" on page 17-4
- "Object Converters" on page 17-5
- "Customize Object Indexing" on page 17-7
- "Code Patterns for subsref and subsasgn Methods" on page 17-9
- "Overload end for Classes" on page 17-15
- "Objects in Index Expressions" on page 17-17
- "Operator Overloading" on page 17-19
- "Customize Parentheses Indexing for Mapping Class" on page 17-23
- "Forward Indexing Operations" on page 17-30

Methods That Modify Default Behavior

In this section...

"How to Customize Class Behavior" on page 17-2

"Which Methods Control Which Behaviors" on page 17-2

"Overload Functions and Override Methods" on page 17-3

How to Customize Class Behavior

There are functions that MATLAB calls implicitly when you perform certain actions with objects. For example, a statement like [B(1);A(3)] involves indexed reference and vertical concatenation.

You can change how user-defined objects behave by defining methods that control specific behaviors. To change a behavior, implement the appropriate method with the name and signature of the MATLAB function.

Which Methods Control Which Behaviors

The following table lists the methods to implement for your class and describes the behaviors that they control.

Class Method to Implement	Description
Concatenating Objects	
cat, horzcat, and vertcat	Customize behavior when concatenating objects
	See "Subclasses of Built-In Types with Properties" on page 12-53.
Creating Empty Arrays	
empty	Create empty arrays of the specified class.
Displaying Objects	
display	MATLAB calls display when an expression or
disp	statement is not terminated by a semicolon. This displays the result and any relevant variable names.
	<pre>disp(E) displays only the result of the expression. Overloading disp is one way to customize how your objects are displayed.</pre>
	See "Overloading the disp Function" on page 18-34.
Converting Objects to Other Classes	
converters like double and char	Convert an object to a MATLAB built-in class
	See "The Character Converter" on page 19-10 and "The Double Converter" on page 19-10.
Saving and Loading Objects	

Class Method to Implement	Description
loadobj and saveobj	Customize behavior when loading and saving objects
	See "Object Save and Load".
Reshape and Rearrange	
permute	Rearrange dimensions of N-D array
transpose	Transpose vector or matrix
ctranspose	Complex conjugate transpose
reshape	Reshape array
repmat	Replicate array along specified dimensions
Determine Size and Shape	
isscalar	Determine if the input is a scalar
isvector	Determine if the input is a vector
ismatrix	Determine if the input is a matrix
isempty	Determine if the input is empty

Overload Functions and Override Methods

Overloading and overriding are terms that describe techniques for customizing class behavior. Here is how we use these terms in MATLAB.

Overloading

Overloading means that there is more than one function or method having the same name within the same scope. MATLAB dispatches to a particular function or method based on the dominant argument. For example, the timeseries class overloads the MATLAB plot function. When you call plot with a timeseries object as an input argument, MATLAB calls the timeseries class method named plot.

To call the nonoverloaded function, use the builtin function.

Overriding

Overriding means redefining a method inherited from a superclass. MATLAB dispatches to the most specific version of the method. That is, if the dominant argument is an object of the subclass, then MATLAB calls the subclass method.

To control class dominance, use the InferiorClasses attribute.

See Also

Related Examples

- "Overload Functions in Class Definitions" on page 9-26
- "Method Invocation" on page 9-11
- "Operator Overloading" on page 17-19

Concatenation Methods

In this section...

"Default Concatenation" on page 17-4

"Methods to Overload" on page 17-4

Default Concatenation

You can concatenate objects into arrays. For example, suppose that you have three instances of the class MyClass, obj1, obj2, obj3. You can form arrays of these objects using brackets. Horizontal concatenation calls horzcat:

```
HorArray = [obj1,obj2,obj3];
```

HorArray is a 1-by-3 array of class MyClass. You can concatenate the objects along the vertical dimension, which calls vertcat:

```
VertArray = [obj1;obj2;obj3]
```

VertArray is a 3-by-1 array of class MyClass. To concatenate arrays along different dimensions, use the cat function. For example:

```
ndArray = cat(3,HorArray,HorArray);
```

ndArray is a 1-by-3-by-2 array.

Methods to Overload

Overload horzcat, vertcat, and cat to produce specialized behaviors in your class. Overload both horzcat and vertcat whenever you want to modify object concatenation because MATLAB uses both functions for any concatenation operation.

See Also

Related Examples

"Subclasses of Built-In Types with Properties" on page 12-53

Object Converters

```
#Why Implement Converters" on page 17-5

"Converters for Namespace Classes" on page 17-5

"Converters and Subscripted Assignment" on page 17-6

"Converter for Heterogeneous Arrays" on page 17-6
```

Why Implement Converters

You can convert an object of one class to an object of another class. A converter method has the same name as the class it converts to, such as char or double. Think of a converter method as an overloaded constructor method of another class. The converter takes an instance of its own class and returns an object of a different class.

Converters enable you to:

- Use methods defined for another class
- Ensure that expressions involving objects of mixed class types execute properly
- Control how instances are interpreted in other contexts

Suppose that you define a polynomial class. If you create a double method for the polynomial class, you can use it to call other functions that require inputs of type double.

```
p = polynomial(...);
dp = double(p);
roots(dp)
```

p is a polynomial object, double is a method of the polynomial class, and roots is a standard MATLAB function whose input arguments are the coefficients of a polynomial.

Converters for Namespace Classes

Classes defined in namespaces can have names that are a dot-separated list of names. The last name is a class and preceding names are namespaces. Name the conversion methods using the namespace qualifiers in the method names. For example, a conversion method to convert objects of MyClass to objects of the nsp.NspClass class uses this method name:

```
classdef MyClass
    ...
    methods
        function objNspClass = nspname.NspClass(objMyclass)
        end
    end
end
end
```

You cannot define a converter method that uses dots in the name in a separate file. Define namespace-class converters in the classdef file.

Converters and Subscripted Assignment

When you make a subscripted assignment statement like:

```
A(1) = myobj;
```

MATLAB compares the class of the Right-Side variable to the class of the Left-Side variable. If the classes are different, MATLAB attempts to convert the Right-Side variable to the class of the Left-Side variable. To do this conversion, MATLAB first searches for a method of the Right-Side class that has the same name as the Left-Side class. Such a method is a converter method, which is similar to a typecast operation in other languages.

If the Right-Side class does not define a method to convert from the Right-Side class to the Left-Side class, MATLAB calls the Left-Side class constructor. passing it the Right-Side variable.

For example, suppose that you make the following assignments:

```
A(1) = objA;

A(2) = objB;
```

MATLAB attempts to call a method of ClassB named ClassA. If no such converter method exists, MATLAB software calls the ClassA constructor, passing objB as an argument. If the ClassA constructor cannot accept objB as an argument, then MATLAB returns an error.

Use cell arrays to store objects of different classes.

Converter for Heterogeneous Arrays

To support the formation of heterogeneous arrays using objects that are not part of the heterogeneous hierarchy, implement a convertObject method in the root superclass. The convertObject method must convert the nonmember object to a valid member of the heterogeneous hierarchy.

For details on implementing the convertObject method, see matlab.mixin.Heterogeneous.

See Also

Related Examples

- "Converter Methods" on page 10-16
- "The Double Converter" on page 19-10

Customize Object Indexing

In this section...

"Default Object Indexing" on page 17-7

"Customize Object Indexing With Modular Indexing Classes" on page 17-8

Default Object Indexing

MATLAB classes support object array indexing by default. Many class designs require no modification to this behavior.

Arrays enable you to reference and assign elements of the array using a subscripted notation. This notation specifies the indices of specific array elements. For example, suppose that you create two arrays of numbers (using randi and concatenation).

Create a 3-by-4 array of integers from 1 through 9:

Create a 1-by-3 array of the numbers 3, 6, 9:

```
B = [3 6 9];
```

Reference and assign elements of either array using index values in parentheses:

```
B(2) = A(3,4);
B
B = 3 7 9
```

The MATLAB default behavior also works with user-defined objects. For example, create an array of objects of the same class:

```
for k=1:3
  objArray(k) = MyClass;
end
```

Referencing the second element in the object array, objArray, returns the object constructed when k = 2:

```
D = objArray(2);
class(D)
ans =
MyClass
```

You can assign an object to an array of objects of the same class, or an uninitialized variable:

```
newArray(3,4) = D;
```

Arrays of objects behave much like numeric arrays in MATLAB. You do not need to implement any special methods to provide standard array behavior with your class.

For general information about array indexing, see "Array Indexing".

Customize Object Indexing With Modular Indexing Classes

Since R2021b. Recommended over "Code Patterns for subsref and subsasgn Methods" on page 17-9.

To modify indexing behavior for your class, inherit from one or more modular indexing mixin classes. Each class is responsible for one group of indexing operations:

- matlab.mixin.indexing.RedefinesParen—parentheses reference, assignment, and deletion
- matlab.mixin.indexing.RedefinesDot—dot property reference, method call, and assignment
- matlab.mixin.indexing.RedefinesBrace—brace reference and assignment

Each class defines abstract methods that handle the details of each indexing operation the class defines. Implement these methods to perform the operations your design requires.

You can inherit from these classes independently. For example, you can customize only parentheses indexing by inheriting only from RedefinesParen. The dot and brace indexing behaviors in that case are the default MATLAB behaviors.

You can also choose to customize just one or two levels of indexing and forward additional operations to another MATLAB object. For example, you can author a class that customizes parentheses indexing (using RedefinesParen) but uses the default behavior for dot method calls:

```
myInstance(2,1).value
```

See "Customize Parentheses Indexing" for an example of this behavior.

See Also

Related Examples

• "Customize Parentheses Indexing for Mapping Class" on page 17-23

Code Patterns for subsref and subsasgn Methods

In this section...

"Customize Indexed Reference and Assignment" on page 17-9

"Syntax for subsref and subsasgn Methods" on page 17-9

"Indexing Structure Describes Indexing Expressions" on page 17-9

"Values of the Indexing Structure" on page 17-10

"Typical Patterns for Indexing Methods" on page 17-11

For R2021b and later, the recommended process for customizing indexing is to use the modular indexing superclasses instead of overloading subsref and subsasgn. For more information, see "Customize Object Indexing" on page 17-7.

Customize Indexed Reference and Assignment

User-defined classes have the same indexing behaviors as that of built-in classes. Classes can customize indexing operations by overloading the functions that MATLAB calls to evaluate indexing expressions. Overload the subsref and subsasgn functions when you want to define special behaviors for indexed reference and assignment.

Syntax for subsref and subsasgn Methods

MATLAB calls the subsref and subsasan methods of your class with these arguments.

Method	Input	Output
b = subsref(obj,s)	obj — Object or object array used in indexing expression	b — Result of indexing expression
	• s — Indexing structure	
obj = subsasgn(obj,s,b)		obj — Object or object array after assignment
	• s — Indexing structure	
	• b — Value being assigned	

Modifying Number of Arguments

If your class design requires that indexing operations return or assign a different number of values than the number defined by the default indexing operation, overload the numArgumentsFromSubscript function to control nargout for subsref and nargin for subsasgn. For more information and examples, see numArgumentsFromSubscript.

Indexing Structure Describes Indexing Expressions

The indexing structure contains information that describes the indexing expression. Class methods use the information in the indexing structure to evaluate the expression and implement custom behavior.

For example, the CustomIndex class defines a property that you can use in indexing expressions.

```
classdef CustomIndex
   properties
       DataArray
   end
end
```

Create an object and assign a 5-by-5 matrix created by the magic function to the DataArray property.

```
a = CustomIndex;
a.DataArray = magic(5);
```

This subscripted reference expression returns the first row of the 5-by-5 matrix.

This expression assigns new values to the first row of the array stored in the DataArray property.

```
a.DataArray(1,:) = [1 2 3 4 5];
```

This assignment statement uses:

- A '.' type reference
- A property name following the dot (that is, DataArray)
- A range of indices (1,:) within parentheses

The indexing structure contains this information in the type and subs fields.

Values of the Indexing Structure

When executing an indexing expression, MATLAB calls the class subsref or subsasgn method, if the class overloads these functions. One of the arguments passed to the method is the indexing structure. The indexing structure has two fields:

- type One of the three possible indexing types: '.', '()', '{}'
- subs A char vector with the property name or cell array of the indices used in the expression, including: and end.

If the indexing expression is a compound expression, then MATLAB passes an array of structures, one struct for each level of indexing. For example, in this expression:

```
a.DataArray(1,:)
```

the indexing structure array S has these values:

- S(1).type is set to '.', indicating that the first indexing operation is a dot.
- s(1).subs is set to the property name, 'DataArray'

The second level of indexing is in the second element of the indexing structure:

S(2).types is set to '()' indicating the second indexing operation is parentheses indexing

• S(2).subs is set to a cell array containing the indices {[1],[:]}

Typical Patterns for Indexing Methods

To overload the subsref and subasgn functions:

- Determine the full indexing expression using the types and subs fields of the indexing structure.
- Implement the specialized behaviors for the indexing operations supported by the class.
- Return the appropriate values or modified objects in response to the call by MATLAB.

A switch statement is a convenient way to detect the first level of indexing. There are three types of indexing—dot, parentheses, and braces. Each case block in the switch statement implements all indexing expressions that begin with that first-level type of indexing.

The methods must implement all indexing expressions that the class supports. If you do not customize a particular type of indexing, call the built-in function to handle that expression.

Use the length of the indexing structure array and indexing type define conditional statements for compound indexing expressions.

Code Framework for subsref Method

The following framework for the subsref method shows how to use information in the indexing structure in conditional statements. Your application can involve other expressions not shown here.

```
function varargout = subsref(obj,s)
   switch s(1).type
      case
         if length(s) == 1
            % Implement obj.PropertyName
         elseif length(s) == 2 && strcmp(s(2).type,'()')
            % Implement obj PropertyName(indices)
         else
            [varargout{1:nargout}] = builtin('subsref',obj,s);
         end
      case '()'
         if length(s) == 1
            % Implement obj(indices)
         elseif length(s) == 2 && strcmp(s(2).type,'.')
            % Implement obj(ind).PropertyName
         elseif length(s) == 3 \&\& strcmp(s(2).type, '.') \&\& strcmp(s(3).type, '()')
           % Implement obj(indices).PropertyName(indices)
            % Use built-in for any other expression
            [varargout{1:nargout}] = builtin('subsref',obj,s);
         end
      case '{}'
         if length(s) == 1
            % Implement obj{indices}
         elseif length(s) == 2 && strcmp(s(2).type,'.')
           % Implement obj{indices}.PropertyName
         else
            % Use built-in for any other expression
            [varargout{1:nargout}] = builtin('subsref',obj,s);
         end
      otherwise
```

```
error('Not a valid indexing expression')
end
```

Using varargout for the returned value enables the method to work with object arrays. For example, suppose that you want to support the return of a comma-separated list with an expression like this one:

```
[x1,...xn] = objArray.PropertyName(Indices)
```

This expression results in a two-element indexing structure array. The first-level type is dot ('.') and the second level is parentheses ('()'). Build the varargout cell array with each value in the array.

```
case '.'
...
if length(s)==2 && strcmp(s(2).type,'()')
   prop = s(1).subs; % Property name
   n = numel(obj); % Number of elements in array
   varargout = cell(1,n); % Preallocate cell array
   for k = 1:n
      varargout{k} = obj(k).(prop).(s(2).subs);
   end
end
...
end
```

subsasgn Pattern

The following framework for the subsasgn method shows how to use the indexing structure in conditional statements that implement assignment operations.

```
function obj = subsasgn(obj,s,varargin)
  % Allow subscripted assignment to uninitialized variable
  if isequal(obj,[])
      % obj = ClassName.empty;
  end
  switch s(1).type
     case
        if length(s) == 1
           % Implement obj.PropertyName = varargin{:};
        elseif length(s) == 2 && strcmp(s(2).type,'()')
           % Implement obj.PropertyName(indices) = varargin{:};
        else
            % Call built-in for any other case
           obj = builtin('subsasgn',obj,s,varargin{:});
        end
     case '()'
        if length(s) == 1
           % Implement obj(indices) = varargin{:};
        elseif length(s) == 2 && strcmp(s(2).type,'.')
           % Implement obj(indices).PropertyName = varargin{:};
        elseif length(s) == 3 \& strcmp(s(2).type,'.') \& strcmp(s(3).type,'()')
           % Implement obj(indices).PropertyName(indices) = varargin{:};
            % Use built-in for any other expression
           obj = builtin('subsasgn',obj,s,varargin{:});
        end
        if length(s) == 1
           % Implement obj{indices} = varargin{:}
```

Using varargin for the right-side value of the assignment statement enables the method to work with object arrays. For example, suppose that you want to support the assignment of a commaseparated list with an expression like this one:

```
C = {'one';'two';'three'};
[objArray.PropertyName] = C{:}
```

This expression results in an indexing structure with the dot type ('.') indexing The cell array C on the right side of the assignment statement produces a comma-separated list. This code assigns one list item to each property in the object array.

```
case '.'
  if length(s)==1
    prop = s(1).subs; % Property name
    n = numel(obj); % Number of elements in array
    for k = 1:n
        obj(k).(prop) = varargin{k};
    end
  end
end
```

Subscripted Assignment with an Uninitialized Variable

Assigning to an element of an uninitialized variable results in a call to the subsasgn method of the class on the right side of the assignment. For example, this class defines a subsasgn method that simply calls the built-in subsasgn method for parenthesis indexing.

```
classdef MyClass
  methods
    function obj = subsasgn(obj,s,varargin)
        switch s(1).type
        case '()'
        obj = builtin('subsasgn',obj,s,varargin{:});
        end
        end
    end
end
```

When attempting to assign an object of MyClass to the first element of the uninitialized variable, B(1) in the following statement, MATLAB calls the subsasgn method of MyClass with an empty double ([]) as the first argument. The assignment can cause an error because the subsasgn method must be passed an object of the class.

```
clear B
B(1) = MyClass;
The following error occurred converting from MyClass to double:
Conversion to double from MyClass is not possible.
```

The subsasgn method can detect this situation and take the appropriate action, such as returning a useful error message if the class does not support this type of assignment, or converting the input to an object of the class and passing it to subsasgn.

For example, because MyClass can allow subscripted assignment to an uninitialized variable, the subsasgn method can change the first argument from the empty double to an empty MyClass object.

Use the isequal function to check the input and the empty static method to create the empty object.

```
classdef MyClass
    methods
    function obj = subsasgn(obj,s,varargin)
        if isequal(obj,[])
            obj = MyClass.empty;
        end
        obj = builtin('subsasgn',obj,s,varargin{:});
    end
end
end
```

Subscripted assignment to an uninitialized variable now avoids the previous error.

```
clear B
B(1) = MyClass;
B =
    MyClass with no properties.
```

See Also

Related Examples

• "Subclasses of Built-In Types with Properties" on page 12-53

Overload end for Classes

```
In this section...

"Syntax and Default Behavior" on page 17-15

"How RedefinesParen Overloads end " on page 17-15
```

In a standard MATLAB indexing expression, end returns the index value of the last element in the dimension in which end appears. For example, in A(4,end), the end method returns the index of the last element in the second dimension of A. You can overload end in classes for specialized behavior.

Syntax and Default Behavior

This is the syntax MATLAB uses to call the end method.

```
ind = end(A,k,n)
```

- A is the object being indexed into.
- k is the dimension in the indexing expression where end appears.
- n is the total number of indices in the expression.
- ind is the index value to use in the expression.

Note You cannot call the end method directly using this syntax. MATLAB automatically calls the method when it encounters end in an indexing expression.

For example, A is a 2-by-3 array of doubles. When MATLAB encounters the expression A(end,1), it calls the end method with these arguments.

```
end(A,1,2)
```

- A is the object.
- k = 1 because end appears in the first dimension of the indexing expression.
- n = 2 because the expression has two indices.

The end method returns 2, which is the index of the last element in the first dimension of A.

How RedefinesParen Overloads end

Any overload of the end method must have the calling syntax ind = end(A,k,n). For example, the modular indexing class matlab.mixin.indexing.RedefinesParen has a built-in overload of end.

```
function ind = end(obj,k,n)
    sz = size(obj);
    if k < n
        ind = sz(k);
    else
        ind = prod(sz(k:end));
    end
end</pre>
```

The if-else statement calculates the return value based on where the end appears in the indexing expression and whether the indexing expression has values for all of the dimensions of the object array. For example, when B is a 2-by-3-by-2 object array of a type that inherits from RedefinesParen:

- k < n: When end is not the last value in the indexing expression, the overload returns the last value in that dimension. For B(1,end,4), end returns the size of the second dimension, 3.
- k = n: When end is the last element in the indexing expression, the overload handles two cases:
 - If the indexing expression references all the indices, then prod(sz(k:end)) gives the same result as sz(k). For example, in B(1,2,end), end returns 2.
 - If the indexing expression does not reference all the indices, then prod(sz(k:end)) returns the product of the size of dimension k and the sizes of all unreferenced dimensions. For example, in B(1,end), end returns the product of the sizes of the second and third dimensions, 6.

RedefinesParen defines size as an abstract method for the class author to implement, so the two methods are dependent on one another for the final behavior. See the "Customize Parentheses Indexing" example for a class that implements a size method that provides the expected end behavior with an array.

See Also

Related Examples

"Objects in Index Expressions" on page 17-17

Objects in Index Expressions

In this section... "Objects as Indexes" on page 17-17 "Ways to Implement Objects as Indices" on page 17-17 "subsindex Implementation" on page 17-17

Objects as Indexes

MATLAB can use objects as indices in indexed expressions. The rules of array indexing apply — indices must be positive integers. Therefore, MATLAB must be able to derive a value from the object that is a positive integer for use in the indexed expression.

Indexed expressions like X(A), where A is an object, cause MATLAB to call the subsindex function. However, if an indexing expression results in a call to an overloaded method from matlab.mixin.indexing.RedefinesParen, matlab.mixin.indexing.RedefinesDot, or matlab.mixin.indexing.RedefinesBrace defined by class X, then MATLAB does not call subsindex.

Ways to Implement Objects as Indices

There are several ways to implement indexing of one object by another object, X(A):

- Define a subsindex method in the class of A that converts A to an integer. MATLAB calls A's subsindex method to perform indexing operations when the class of X does not overload methods from matlab.mixin.indexing.RedefinesParen, matlab.mixin.indexing.RedefinesDot, or matlab.mixin.indexing.RedefinesBrace.
- If the class of X overloads methods from RedefinesParen, RedefinesDot, or RedefinesBrace these methods can call the subsindex method of A explicitly. The class of A must implement a subsindex method that returns an appropriate value.

subsindex Implementation

subsindex must return the value of the object as a zero-based integer index value in the range 0 to prod(size(X)) - 1.

Suppose that you want to use object A to index into object B. B can be a single object or an array, depending on the class designs.

```
C = B(A);
```

Here are two examples of subsindex methods. The first assumes you can convert class A to a uint8. The second assumes class A stores an index value in a property.

 The subsindex method implemented by class A can convert the object to numeric format to be used as an index:

```
function ind = subsindex(obj)
  ind = uint8(obj);
end
```

The class of obj implements a uint8 method to provide the conversion from the object to an integer value.

• Class A implements subsindex to return a numeric value that is stored in a property:

```
function ind = subsindex(obj)
  ind = obj.ElementIndex;
end
```

Note subsindex values are 0-based, not 1-based.

See Also

matlab.mixin.indexing.RedefinesParen | matlab.mixin.indexing.RedefinesDot |
matlab.mixin.indexing.RedefinesBrace

Related Examples

• "Overload end for Classes" on page 17-15

Operator Overloading

In this section...

"Why Overload Operators" on page 17-19

"How to Define Operators" on page 17-19

"Sample Implementation — Addable Objects" on page 17-20

"MATLAB Operators and Associated Functions" on page 17-21

Why Overload Operators

By implementing operators that are appropriate for your class, you can integrate objects of your class into the MATLAB language. For example, objects that contain numeric data can define arithmetic operations like +, *, - so that you can use these objects in arithmetic expressions. By implementing relational operators, you can use objects in conditional statements, like switch and if statements.

How to Define Operators

You can implement MATLAB operators to work with objects of your class. To implement operators, define the associated class methods.

Each operator has an associated function (e.g., the + operator has an associated plus.m function). You can implement any operator by creating a class method with the appropriate name. This method can perform whatever steps are appropriate for the operation being implemented.

For a list of operators and associated function names, see "MATLAB Operators and Associated Functions" on page 17-21.

Object Precedence in Operations

User-defined classes have a higher precedence than built-in classes. For example, suppose q is an object of class double and p is a user-defined class. Both of these expressions generate a call to the plus method in the user-define class, if it exists:

q + p

p + q

Whether this method can add objects of class double and the user-defined class depends on how you implement the method.

When p and q are objects of different classes, MATLAB applies the rules of precedence to determine which method to use.

For more information on how MATLAB determines which method to call, see "Method Invocation" on page 9-11.

Operator Precedence

Overloaded operators retain the original MATLAB precedence for the operator. For information on operator precedence, see "Operator Precedence".

Sample Implementation — Addable Objects

The Adder class implements addition for objects of this class by defining a plus method. Adder defines addition of objects as the addition of the NumericData property values. The plus method constructs and returns an Adder object whose NumericData property value is the result of the addition.

The Adder class also implements the less than operator (<) by defining a lt method. The lt method returns a logical value after comparing the values in each object NumericData property.

```
classdef Adder
   properties
      NumericData
   end
   methods
      function obj = Adder(val)
         obj.NumericData = val;
      end
      function r = plus(obj1,obj2)
         a = double(obj1);
         b = double(obj2);
         r = Adder(a + b);
      function d = double(obj)
         d = obj.NumericData;
      function tf = lt(obj1,obj2)
         if obj1.NumericData < obj2.NumericData</pre>
            tf = true;
         else
            tf = false;
         end
      end
   end
end
```

Using a double converter enables you to add numeric values to Adder objects and to perform addition on objects of the class.

```
a = Adder(1:10)
a =
   Adder with properties:
        NumericData: [1 2 3 4 5 6 7 8 9 10]
Add two objects:
a + a
ans =
   Adder with properties:
        NumericData: [2 4 6 8 10 12 14 16 18 20]
```

Add an object with any value that can be cast to double:

```
b = uint8(255) + a

b =
   Adder with properties:
      NumericData: [256 257 258 259 260 261 262 263 264 265]

Compare objects a and b using the < operator:
a < b
ans =
      1</pre>
```

Ensure that your class provides any error checking required to implement your class design.

MATLAB Operators and Associated Functions

The following table lists the function names for MATLAB operators. Implementing operators to work with arrays (scalar expansion, vectorized arithmetic operations, and so on), can also require modifying indexing and concatenation. Use the links in this table to find specific information on each function.

Operation	Method to Define	Description
a + b	plus(a,b)	Binary addition
a - b	minus(a,b)	Binary subtraction
- a	uminus(a)	Unary minus
+a	uplus(a)	Unary plus
a.*b	times(a,b)	Element-wise multiplication
a*b	<pre>mtimes(a,b)</pre>	Matrix multiplication
a./b	rdivide(a,b)	Right element-wise division
a.\b	ldivide(a,b)	Left element-wise division
a/b	mrdivide(a,b)	Matrix right division
a\b	mldivide(a,b)	Matrix left division
a.^b	power(a,b)	Element-wise power
a^b	mpower(a,b)	Matrix power
a < b	lt(a,b)	Less than
a > b	gt(a,b)	Greater than
a <= b	le(a,b)	Less than or equal to
a >= b	ge(a,b)	Greater than or equal to
a ~= b	ne(a,b)	Not equal to
a == b	eq(a,b)	Equality
a & b	and(a,b)	Logical AND
a b	or(a,b)	Logical OR

Operation	Method to Define	Description
~a	not(a)	Logical NOT
a:d:b	colon(a,d,b)	Colon operator
a:b	colon(a,b)	
a'	ctranspose(a)	Complex conjugate transpose
a.'	transpose(a)	Matrix transpose
[a b]	horzcat(a,b,)	Horizontal concatenation
[a; b]	vertcat(a,b,)	Vertical concatenation
a(s1,s2,sn)	subsref(a,s)	Subscripted reference
a(s1,,sn) = b	subsasgn(a,s,b)	Subscripted assignment
b(a)	subsindex(a)	Subscript index

See Also

Related Examples

- "Define Arithmetic Operators" on page 19-12
- "Methods That Modify Default Behavior" on page 17-2

Customize Parentheses Indexing for Mapping Class

This example shows how to customize parentheses indexing for a class. The MyMap class stores strings ("keys") that are associated with elements ("values") of a cell array. The class inherits from matlab.mixin.indexing.RedefinesParen to define custom behavior for indexing with parentheses. The class supports three customized indexing operations:

- instanceName("keyName") returns the value associated with the key.
- instanceName("keyName") = value adds a new key and associated value.
- instanceName("keyName") = [] deletes the key and its associated value.

The full code for the class and its helper function, validateKeys, is available at the end of the example.

MyMap Class	Explanation
<pre>classdef MyMap < matlab.mixin.indexing.RedefinesParen</pre>	Define MyMap as a subclass of RedefinesParen. and implement its abstract methods
<pre>properties (Access = private) Keys (:,1) string Values (:,1) cell end</pre>	The private properties Keys and Values are n -by-1 vectors.
<pre>methods (Static, Access = public) function obj = empty(varargin) if nargin == 0 obj = MyMap(string.empty(0,1),cell.ereturn; end</pre>	Implementation of the static, abstract method empty, which creates a MyMap object with no keys or values. empty(0,1));
<pre>keys = string.empty(varargin{:}); if ~all(size(keys) == [0, 1]) error("MyMap:MustBeEmptyColumnVector</pre>	
<pre>obj = MyMap(keys,cell.empty(varargin{:] end end</pre>	}));

MyMap Class

methods (Access = public) The constructor accepts the keys and values as function obj = MyMap(keys_in,values_in) input arguments and ensures the arrays are if nargin == 0 the same size. obj = MyMap.empty(0,1); return; end narginchk(2,2); if ~all(size(keys in) == size(values in)) error("MyMap:InputSizesDoNotMatch",... "The sizes of the input keys and values must match."); end obj.Keys = keys_in; obj.Values = values in; end end function keys = getKeys(obj) Two public methods provide read access to the keys = obj.Keys; keys and values. end function values = getValues(obj) values = obj.Values; function varargout = size(obj,varargin) Implementation of the abstract methods size, [varargout{1:nargout}] = size(obj.Keys,veরক্রের্নাম্র(ehd; In this example, cat and end end are not supported. function C = cat(dim, varargin) error("MyMap:ConcatenationNotSupported",... "Concatenation is not supported."); end function lastKey = end(\sim , \sim , \sim) error("MyMap:EndNotSupported",... "Using end with MyMap objects is not supported."); end methods (Access = private) The parenReference, parenAssign, function [keyExists,idx] = convertKeyToInd@afenDekeyfe,laAdn@afenListLength arguments methods use the convertKeyToIndex helper obi method. convertKeyToIndex uses keyCellArray cell {validateKeys} validateKeys to ensure that keyCellArray end contains only one key. (See the code for validateKeys after the end of the class.) requestedKey = keyCellArray{1}; ${\tt idx = find(contains(obj.Keys, requested KeQNyertKeyToIndex\ returns\ a\ logical\ that}$ indicates whether or not the input key exists keyExists = ~isempty(idx); and, if it does, the index of the key. end

Explanation

end

MyMap Class Explanation methods (Access = protected)

```
[keyExists,idx] = convertKeyToIndex(obj,indexing(1)prodicts of the form
   if ~keyExists
      error("MyMap:KeyDoesNotExist",...
         "The requested key does not exist
   end
   if numel(index0p) == 1
      nargoutchk(0,1);
      varargout{1} = obj.Values{idx};
      % Additional operations
   end
end
function obj = parenAssign(obj,indexOp,varaImphe)mentation of the abstract method
   indicesCell = indexOp(1).Indices;
   [keyExists,idx] = convertKeyToIndex(obj,indexingCexpressions of the form
   if numel(index0p) == 1
      value = varargin{1};
      if keyExists
         obj.Values{idx} = value;
      else
         obj.Keys(end+1) = indicesCell{1}; the key and value are added to the list.
         obj.Values{end+1} = value;
      end
      return:
   end
   if ~keyExists
      error("MyMap:MultiLevelAssignKeyDoesNotExist", ...
         "Assignment failed because key %s does not exist",...
            indicesCell{1});
   end
   [obj.Values{idx}.(indexOp(2:end))] = varargin{:};
function obj = parenDelete(obj,indexOp)
   [keyExists,idx] = convertKeyToIndex(obj, jagdex(De(12) tendine) handles deletion
   if keyExists
      obj.Keys(idx) = [];
      obj.Values(idx) = [];
      error("MyMap:DeleteNonExistentKey",.
         indexOp(1).Indices{1});
   end
end
```

Implementation of the abstract method function varargout = parenReference(obj,index@ehReference, which handles reference instanceName("keyName"). The method takes an IndexingOperation instance as input. That instance, index0p, includes the indexing type (in this case, parentheses) and the index value from the expression being interpreted. parenReference passes the index in indexOp to convertKeyToIndex to verify that the key exists and, if so, return the index of that key idx. The method then % Additional operations
[varargout{1:nargout}] = obj.Values{idx}.(indexOp(2:end))
[f there is more than one indexing operation in indexOp, the line labeled "Additional operations" forwards the handling of those operations to MATLAB.

> parenAssign, which handles assignment instanceName("keyName") = value. If the key referenced exists, then the method assigns the value from the right-hand side of the expression to that key. If the key does not exist and there is only one level of indexing, then

Implementation of the abstract method indexing expressions of the form instanceName("keyName") = []. If thekey referenced exists, then the method deletes the key and its associated value. If the key "Unable to perform deletion. The kdoes not exist then the method issues an error.

MyMap Class Explanation

```
function n = parenListLength(obj,indexOp,indamphaGentanth of the abstract method
                  [keyExists,idx] = convertKeyToIndex(obj,index@n(li)stneheden), which determines the
                 if ~keyExists
                                                                                                                                                                                                  number of values to return from parentheses
                         if indexingContext == matlab.indexing.IndexingContext Assignment indexingContext assignment indexing expressions. The method takes an
                                      error("MyMap:MultiLevelAssignKeyDoesNotExist" ...
"Unable to perform assignment. Key ** 1005 not ** 10
                                                                                                                                                                                                  matlab.indexing.IndexingContext as
                                                               index0p(1).Indices{1});
                                                                                                                                                                                                 input to determine whether the reference is
                          end
                                                                                                                                                                                                 used in a statement, as a list of arguments to a
                          error("MyMap:KeyDoesNotExist",...
                                       "The requested key does not exist."); function, or in an assignment operation.
                n = listLength(obj.Values{idx},indexOp(2:end),indexingContext);
        end
end
```

Expand for Class and Helper Function Code

```
classdef MyMap...
 < matlab.mixin.indexing.RedefinesParen
    properties (Access = private)
        Keys (:,1) string
        Values (:,1) cell
   methods (Static, Access = public)
        function obj = empty(varargin)
            if nargin == 0
                obj = MyMap(string.empty(0,1),cell.empty(0,1));
                return;
            keys = string.empty(varargin{:});
            if ~all(size(keys) == [0, 1])
                error("MyMap:MustBeEmptyColumnVector",...
                    "The only supported empty size is 0x1.");
            obj = MyMap(keys,cell.empty(varargin{:}));
        end
   end
   methods (Access = public)
        function obj = MyMap(keys_in,values_in)
            if nargin == 0
                obj = MyMap.empty(0,1);
                return;
            end
            narginchk(2,2);
            if ~all(size(keys in) == size(values in))
                error("MyMap:InputSizesDoNotMatch",...
                    "The sizes of the input keys and values must match.");
            obj.Keys = keys_in;
            obj.Values = values in;
        function keys = getKeys(obj)
            keys = obj.Keys;
        function values = getValues(obj)
            values = obj.Values;
```

```
end
    function varargout = size(obj,varargin)
         [varargout{1:nargout}] = size(obj.Keys,varargin{:});
    function C = cat(dim,varargin)
        error("MyMap:ConcatenationNotSupported",...
             "Concatenation is not supported.");
    end
    function lastKey = end(\sim,\sim,\sim)
        error("MyMap:EndNotSupported",...
             "Using end with MyMap objects is not supported.");
    end
end
methods (Access = private)
    function [keyExists,idx] = convertKeyToIndex(obj,keyCellArray)
        arguments
             keyCellArray cell {validateKeys}
        end
         requestedKey = keyCellArray{1};
         idx = find(contains(obj.Keys,requestedKey));
         keyExists = ~isempty(idx);
    end
end
methods (Access = protected)
    function varargout = parenReference(obj,indexOp)
  [keyExists,idx] = convertKeyToIndex(obj,indexOp(1).Indices);
        if ~keyExists
            error("MyMap:KeyDoesNotExist",...
                 "The requested key does not exist.");
        if numel(index0p) == 1
             nargoutchk(0,1);
            varargout{1} = obj.Values{idx};
        el se
             [varargout{1:nargout}] = obj.Values{idx}.(indexOp(2:end));
         end
    end
    function obj = parenAssign(obj,indexOp,varargin)
         indicesCell = indexOp(1).Indices;
        [keyExists,idx] = convertKeyToIndex(obj,indicesCell);
        if numel(index0p) == 1
            value = varargin{1};
             if keyExists
                 obj.Values{idx} = value;
                 obj.Keys(end+1) = indicesCell{1};
                 obj.Values{end+1} = value;
            end
             return;
        end
        if ~keyExists
            error("MyMap:MultiLevelAssignKeyDoesNotExist", ...
                  Assignment failed because key %s does not exist",...
             indicesCell{1});
        end
         [obj.Values{idx}.(indexOp(2:end))] = varargin{:};
    function obj = parenDelete(obj,indexOp)
```

```
[keyExists,idx] = convertKeyToIndex(obj,index0p(1).Indices);
           if keyExists
              obj.Keys(idx) = [];
              obj.Values(idx) = [];
              error("MyMap:DeleteNonExistentKey",...
                  "Unable to perform deletion. The key %s does not exist.",...
              indexOp(1).Indices{1});
           end
      end
      function n = parenListLength(obj,indexOp,indexingContext)
           [keyExists,idx] = convertKeyToIndex(obj,indexOp(1).Indices);
           if ~keyExists
              if indexingContext == matlab.indexing.IndexingContext.Assignment
                  error("MyMap:MultiLevelAssignKeyDoesNotExist",
                      "Unable to perform assignment. Key %s does not exist",...
                  indexOp(1).Indices{1});
              end
              error("MyMap:KeyDoesNotExist",...
                   'The requested key does not exist.");
           end
          n = listLength(obj.Values{idx},indexOp(2:end),indexingContext);
       end
   end
end
function validateKeys(requestedKeysCell)
   if numel(requestedKeysCell) == 0
      error("MyMap:MustProvideAtLeastOneKey",...
         "At least one key must be provided.");
   end
   if numel(requestedKeysCell) > 1
      error("MyMap:MustUseOnlyOneSubscript",...
         "Indexing with more than one subscript not supported.");
   end
   requestedKeys = requestedKeysCell{1};
   if ~isstring(requestedKeys)
      error("MyMap:InvalidKey", "Keys must be strings.");
   end
   if numel(requestedKeys) == 0
      error("MyMap:MustProvideAtLeastOneKey",...
           "At least one key must be provided.");
   end
   if numel(requestedKeys) > 1
      error("MyMap:UnableToUseMoreThanOneKey",...
           "Unable to use more than one key.");
   end
end
Save the code for MyMap and validateKeys in your MATLAB path. Create an instance of MyMap
with an initial list of three keys and values.
map = MyMap(["apple", "cherry", "orange"], {1,3,15});
Use the map("keyName") syntax to return the value corresponding to a specific key.
map("cherry")
```

```
ans =
    3
Use the map("keyName") = value to add a new key to the array.
map("banana") = 2;
map("banana")
ans =
    2
Use the map("keyName") = [] to delete a key and its associated value from the array. Confirm the key is no longer in the array.
map("orange") = [];
map("orange")
Error using MyMap/parenReference (line 88)
The requested key does not exist.
```

See Also

matlab.mixin.indexing.RedefinesParen | matlab.indexing.IndexingOperation

Forward Indexing Operations

The three mixin classes that enable customizing indexing operations—
matlab.mixin.indexing.RedefinesParen, matlab.mixin.indexing.RedefinesDot, and
matlab.mixin.indexing.RedefinesBrace—work independently. You can implement all three
indexing operations, but you also have the option of just implementing one or two of them. You can
also choose to customize just one or two levels of indexing and forward additional operations to
another MATLAB object.

For example, this expression shows three levels of indexing:

```
obj(1).prop{7}
```

You can choose to customize only the parentheses indexing by inheriting from RedefinesParen and then forward the remaining indexing operations (dot and brace) to the default behaviors. This class fragment inherits from RedefinesParen:

```
classdef MyClass < matlab.mixin.indexing.RedefinesParen
    properties (Access = private)
        prop
    end

methods (Access = protected)
    function varargout = parenReference(A,indexOp)
        idx = indexop(1).Indices;

    % Handle customized parentheses indexing
        temp = A.prop(idx);

    % Forward remaining indexing to temp
    [varargout{1:nargout}] = temp.(indexOp(2:end));
    end
end
end</pre>
```

The forwarding syntax is the dynamic dot indexing syntax with the IndexingOperation instance:

```
temp.(indexOp(2:end))
```

This expression handles all of the indexing operations after the first parentheses. In other words, the indexing expression described by indexOp(2:end) is forwarded to temp. In this example, indexOp(2) and indexOp(3) are the dot and brace indexing operations, respectively. temp. (indexOp(2:end)) translates to:

```
temp.prop{7}
```

For customized dot indexing, the forwarding syntax maintains the access permissions from the original context of the main indexing expression. For example, after the parentheses indexing $obj(1).prop\{7\}$ is handled, MATLAB handles the dot indexing, $temp.prop\{7\}$, using the same context that the initial indexing expression started with. When you call $obj(1).prop\{7\}$ inside the class, the private property prop is accessible. When you call $obj(1).prop\{7\}$ outside of the class, prop is not accessible.

See Also

matlab.mixin.indexing.RedefinesParen | matlab.mixin.indexing.RedefinesDot |
matlab.mixin.indexing.RedefinesBrace | matlab.indexing.IndexingOperation

Related Examples

"Customize Parentheses Indexing for Mapping Class" on page 17-23

Customizing Object Display

- "Custom Display Interface" on page 18-2
- "How CustomDisplay Works" on page 18-7
- "Role of size Function in Custom Displays" on page 18-9
- "Customize Display for Heterogeneous Arrays" on page 18-10
- "Class with Default Object Display" on page 18-11
- "Choose a Technique for Display Customization" on page 18-15
- "Customize Property Display" on page 18-18
- "Customize Header, Property List, and Footer" on page 18-21
- "Customize Display of Scalar Objects" on page 18-26
- "Customize Display of Object Arrays" on page 18-30
- "Overloading the disp Function" on page 18-34
- "Custom Compact Display Interface" on page 18-36

Custom Display Interface

In this section...

"Command Window Display" on page 18-2

"Default Object Display" on page 18-2

"CustomDisplay Class" on page 18-3

"Methods for Customizing Object Display" on page 18-3

Command Window Display

MATLAB displays information in the command window when a statement that is not terminated with a semicolon returns a variable. For example, this statement creates a structure with a field that contains the number 7.

```
a.field1 = 7
```

MATLAB displays the variable name, class, and the value.

```
a =
 struct with fields:
    field1: 7
```

MATLAB provides user-defined classes with similar display functionality. User-defined classes can customize how MATLAB displays objects of the class using the API provided by the matlab.mixin.CustomDisplay class. To use this API, derive your class from matlab.mixin.CustomDisplay.

Default Object Display

MATLAB adds default methods named disp and display to all MATLAB classes that do not implement their own methods with those names. These methods are not visible, but create the default simple display.

The default simple display consists of the following parts:

- A header showing the class name, and the dimensions for nonscalar arrays.
- A list of all nonhidden public properties, shown in the order of definition in the class.

The actual display depends on whether the object is scalar or nonscalar. Also, there are special displays for a scalar handle to a deleted object and empty object arrays. Objects in all of these states are displayed differently if the objects have no properties.

The details function creates the default detailed display. The detailed display adds these items to the simple display:

- · Use of fully qualified class names
- Link to handle class, if the object is a handle
- Links to methods, events, and superclasses functions executed on the object.

See "Class with Default Object Display" on page 18-11 for an example of how MATLAB displays objects.

Properties Displayed by Default

MATLAB displays object properties that have public get access and are not hidden (see "Property Attributes" on page 8-8). Inherited abstract properties are excluded from display. When the object being displayed is scalar, any dynamic properties attached to the object are also included.

CustomDisplay Class

The matlab.mixin.CustomDisplay class provides an interface that you can use to customize object display for your class. To use this interface, derive your class from CustomDisplay:

classdef MyClass < matlab.mixin.CustomDisplay</pre>

The CustomDisplay class is HandleCompatible, so you can use it in combination with both value and handle superclasses.

Note You cannot use matlab.mixin.CustomDisplay to derive a custom display for enumeration classes.

disp, display, and details

The CustomDisplay interface does not allow you to override disp, display, and details. Instead, override any combination of the customization methods defined for this purpose.

Methods for Customizing Object Display

There are two groups of methods that you use to customize object display for your class:

- Part builder methods build the strings used for the standard display. Override any of these methods to change the respective parts of the display.
- State handler methods are called for objects in specific states, like scalar, nonscalar, and so on. Override any of these methods to handle objects in a specific state.

All of these methods have protected access and must be defined as protected in your subclass of CustomDisplay (that is, Access = protected).

Parts of an Object Display

There are three parts that makeup the standard object display — header, property list, and footer

For example, here is the standard object display for a containers. Map object:

```
>> map1 = containers.Map({'Apr', 'Jul', 'Nov'}, [4,7,11])
map1 =
 Map with properties: Header
   KeyType: char Property List
```

The default object display does not include a footer. The detailed display provides more information:

```
>> details(map1)
 3x1 containers.Map handle array with properties:
       Count: 3
     KevTvpe: 'char'
   ValueType: 'double'
 Methods, Events, Superclasses 	Footer
```

You can customize how MATLAB displays objects as a result of expressions that display objects in the command window such as unterminated statements that return objects or calls to disp and display. The results displayed when calling details on an object or object array are not changed by the CustomDisplay API.

Part Builder Methods

Each part of the object display has an associated method that assembles the respective part of the display.

Method	Purpose	Default
getHeader	Create the text used for the header.	Returns the char vectors, [class(obj), 'with properties:'] linking the class name to a help popup
getPropertyGroups	Define how and what properties display, including order, values, and grouping.	Returns an array of PropertyGroup objects, which determines how to display the properties
getFooter	Create the text used for the footer.	There are two footers: • Simple display — Returns an empty char vector • Detailed display — Returns linked calls to methods, events, and superclasses for this class

Object States That Affect Display

There are four object states that affect how MATLAB displays objects:

- Valid scalar object
- Nonscalar object array
- Empty object array
- · Scalar handle to a deleted object

State Handler Methods

Each object state has an associated method that MATLAB calls whenever displaying objects that are in that particular state.

State Handler Method	Called for Object in This State
displayScalarObject	<pre>(isa(obj,'handle') && isvalid(obj)) && prod(size(obj)) == 1</pre>
displayNonScalarObject	<pre>prod(size(obj)) > 1</pre>
displayEmptyObject	<pre>prod(size(obj)) == 0</pre>
displayScalarHandleToDeletedObject	isa(obj,'handle') && isscalar(obj) && ~isvalid(obj)

Utility Methods

The CustomDisplay class provides utility methods that return strings that are used in various parts of the different display options. These static methods return text that simplifies the creation of customized object displays.

If the computer display does not support hypertext linking, the strings are returned without the links.

Method	Inputs	Outputs
convertDimensionsToString	Valid object array	Object dimensions converted to a char vector; determined by calling size(obj)
displayPropertyGroups	PropertyGroup array	Displays the titles and property groups defined
getClassNameForHeader	Object	Simple class name linked to the object's documentation
getDeletedHandleText	None	Text 'handle to deleted' linked to the documentation on deleted handles
getDetailedFooter	Object	Text containing phrase 'Methods, Events, Superclasses', with each link executing the respective command on the input object
getDetailedHeader	Object	Text containing linked class name, link to handle page (if handle class) and 'with properties:'

Method	Inputs	Outputs
getHandleText	None	Text 'handle' linked to a section of the documentation that describes handle objects
getSimpleHeader	Object	Text containing linked class name and the phrase 'with properties:'

See Also

Related Examples

"How Custom Display Works" on page 18-7

How CustomDisplay Works

In this section... "Steps to Display an Object" on page 18-7 "Methods Called for a Given Object State" on page 18-7

Steps to Display an Object

When displaying an object, MATLAB determines the state of the object and calls the appropriate method for that state (see "Object States That Affect Display" on page 18-5).

For example, suppose obj is a valid scalar object of a class derived from CustomDisplay. If you type obj at the command line without terminating the statement with a semicolon:

```
>> obj
```

The following sequence results in the display of obj:

- 1 MATLAB determines the class of obj and calls the disp method to display the object.
- 2 disp calls size to determine if obj is scalar or nonscalar
- When obj is a scalar handle object, disp calls isvalid to determine if obj is the handle of a deleted object. Deleted handles in nonscalar arrays do not affect the display.
- **4 disp** calls the state handler method for an object of the state of **obj**. In this case, **obj** is a valid scalar that results in a call to:

```
displayScalarObject(obj)
```

5 displayScalarObject calls the display part-builder methods to provide the respective header, property list, and footer.

```
header = getHeader(obj);
disp(header)
...
groups = getPropertyGroups(obj)
displayPropertyGroups(obj,groups)
...
footer = getFooter
disp(footer)
```


MATLAB follows a similar sequence for nonscalar object arrays and empty object arrays.

In the case of scalar handles to deleted objects, disp calls the displayScalarHandleToDeletedObject method, which displays the default text for handles to deleted objects without calling any part-builder methods.

Methods Called for a Given Object State

The following diagram illustrates the methods called to display an object that derives from <code>CustomDisplay</code>. The <code>disp</code> method calls the state handler method that is appropriate for the state of the object or object array being displayed.

Only an instance of a handle class can be in a state of scalar handle to a deleted object.



See Also

Related Examples

"Class with Default Object Display" on page 18-11

Role of size Function in Custom Displays

In this section...

"How size Is Used" on page 18-9

"Precautions When Overloading size" on page 18-9

How size Is Used

In the process of building the custom display, CustomDisplay methods call the size function at several points:

- disp calls size to determine which state handler method to invoke.
- The default getHeader method calls size to determine whether to display a scalar or nonscalar header.
- The default displayPropertyGroups method calls size to determine if it should look up property values when the property group is a cell array of property names. By default, only scalar objects display the values of properties.

Precautions When Overloading size

If your class overloads the size function, then MATLAB calls the overloading version. You must ensure that the implementation of size is consistent with the way you want to display objects of the class.

An unusual or improper implementation of size can result in undesirable display behavior. For example, suppose a class overloads size reports an object as scalar when it is not. In this class, a property list consisting of a cell array of strings results in the property values of the first object of the array being displayed. This behavior can give the impression that all objects in the array have the same property values.

However, reporting an object as scalar when in fact the object is empty results in the object displaying as an empty object array. The default methods of the CustomDisplay interface always determine if the input is an empty array before attempting to access property values.

As you override CustomDisplay methods to implement your custom object display, consider how an overloading size method can affect the result.

See Also

Related Examples

"Methods That Modify Default Behavior" on page 17-2

Customize Display for Heterogeneous Arrays

You can call only sealed methods on nonscalar heterogeneous arrays. If you want to customize classes that are part of a heterogeneous hierarchy, you must override and declare as Sealed all the methods that are part of the CustomDisplay interface.

The versions of disp and display that are inherited from matlab.mixin.CustomDisplay are sealed. However, these methods call all of the part builder ("Part Builder Methods" on page 18-4) and state handler methods ("State Handler Methods" on page 18-5).

To use the CustomDisplay interface, the root class of the heterogeneous hierarchy can declare these methods as Sealed and Access = protected.

If you do not need to override a particular method, then call the superclass method, as shown in the following code.

For example, the following code shows modifications to the getPropertyGroups and displayScalarObject methods, while using the superclass implementation of all others.

```
classdef RootClass < matlab.mixin.CustomDisplay & matlab.mixin.Heterogeneous</pre>
  methods (Sealed, Access = protected)
      function header = getHeader(obj)
         header = getHeader@matlab.mixin.CustomDisplay(obj);
      function groups = getPropertyGroups(obj)
         % Override of this method
      end
      function footer = getFooter(obj)
         footer = getFooter@matlab.mixin.CustomDisplay(obj);
      function displayNonScalarObject(obj)
         displayNonScalarObject@matlab.mixin.CustomDisplay(obj);
      function displayScalarObject(obj)
         % Override of this method
      function displayEmptyObject(obj)
         displayEmptyObject@matlab.mixin.CustomDisplay(obj);
      function displayScalarHandleToDeletedObject(obj)
        displayScalarHandleToDeletedObject@matlab.mixin.CustomDisplay(obj);
      end
   end
end
```

You do not need to declare the inherited static methods as Sealed.

See Also

Related Examples

"Designing Heterogeneous Class Hierarchies" on page 10-19

Class with Default Object Display

```
In this section...

"The EmployeeInfo Class" on page 18-11

"Default Display — Scalar" on page 18-11

"Default Display — Nonscalar" on page 18-12

"Default Display — Empty Object Array" on page 18-12

"Default Display — Handle to Deleted Object" on page 18-13

"Default Display — Detailed Display" on page 18-13
```

The EmployeeInfo Class

The EmployeeInfo class defines a number of properties to store information about company employees. This simple class serves as the example class used in display customization sample classes.

EmployeeInfo derives from the matlab.mixin.CustomDisplay class to enable customization of the object display.

EmployeeInfo is also a handle class. Therefore instances of this class can be in the state referred to as a handle to a deleted object. This state does not occur with value classes (classes not derived from handle).

```
classdef EmployeeInfo < handle & matlab.mixin.CustomDisplay</pre>
  properties
     Name
      JobTitle
     Department
     Salary
      Password
  end
  methods
      function obj = EmployeeInfo
         obj.Name
                    = input('Name: ');
         obj.JobTitle = input('Job Title: ');
         obj.Department = input('Department: ');
         obj.Salary = input('Salary: ');
         obj.Password = input('Password: ');
      end
  end
end
```

The matlab.mixin.CustomDisplay is handle compatible. Therefore, subclasses can be either handle or value classes.

Default Display — Scalar

Here is the creation and display of a scalar EmployeeInfo object. By default, MATLAB displays properties and their values for scalar objects.

Provide inputs for the constructor:

Testing for Scalar Objects

To test for scalar objects, use isscalar.

Default Display — Nonscalar

The default display for an array of objects does not show property values. For example, concatenating two EmployeeInfo objects generates this display:

```
>>[Emp123,Emp124]
ans

1x2 EmployeeInfo array with properties:

   Name
    JobTitle
    Department
   Salary
   Password
```

Testing for Nonscalar Objects

To test for nonscalar objects, use a negated call to isscalar.

Default Display — Empty Object Array

An empty object array has at least one dimension equal to zero.

```
>> Empt = EmployeeInfo.empty(0,5)
Empt =
    0x5 EmployeeInfo array with properties:
    Name
```

```
JobTitle
Department
Salary
Password
```

Testing for Empty Object Arrays

Use isempty to test for empty object arrays. An empty object array is not scalar because its dimensions can never be 1-by-1.

```
>> emt = EmployeeInfo.empty
emt =
    0x0 EmployeeInfo array with properties:
    Name
    JobTitle
    Department
    Salary
    Password
>> isscalar(emt)
ans =
    0
```

Default Display — Handle to Deleted Object

When a handle object is deleted, the handle variable can remain in the workspace.

```
>> delete(Emp123)
>> Emp123
Emp123 =
  handle to deleted EmployeeInfo
```

Testing for Handles to Deleted Objects

To test for a handle to a deleted object, use isvalid.

Note isvalid is a handle class method. Calling isvalid on a value class object causes an error.

Default Display — Detailed Display

The details method does not support customization and always returns the standard detailed display:

```
details(Emp123)
   EmployeeInfo handle with properties:
        Name: 'Bill Tork'
        JobTitle: 'Software Engineer'
        Department: 'Product Development'
        Salary: 1000
        Password: 'bill123'
```

Methods, Events, Superclasses

See Also

Related Examples

"Custom Display Interface" on page 18-2

Choose a Technique for Display Customization

In this section...

"Ways to Implement a Custom Display" on page 18-15

"Sample Approaches Using the Interface" on page 18-15

Ways to Implement a Custom Display

The way you customize object display using the matlab.mixin.CustomDisplay class depends on:

- What parts of the display you want to customize
- What object states you want to use the custom display

If you are making small changes to the default layout, then override the relevant part builder methods ("Part Builder Methods" on page 18-4). For example, suppose you want to:

- Change the order or value of properties, display a subset of properties, or create property groups
- Modify the header text
- · Add a footer

If you are defining a nonstandard display for a particular object state (scalar, for example), then the best approach is to override the appropriate state handler method ("State Handler Methods" on page 18-5).

In some cases, a combination of method overrides might be the best approach. For example, your implementation of displayScalarObject might

- Use some of the utility methods ("Utility Methods" on page 18-5) to build your own display strings using parts from the default display
- Call a part builder method to get the default text for that particular part of the display
- Implement a completely different display for scalar objects.

Once you override any CustomDisplay method, MATLAB calls your override in all cases where the superclass method would have been called. For example, if you override the getHeader method, your override must handle all cases where a state handler method calls getHeader. (See "Methods Called for a Given Object State" on page 18-7)

Sample Approaches Using the Interface

Here are some simple cases that show what methods to use for the particular customized display.

Change the Display of Scalar Objects

Use a nonstandard layout for scalar object display that is fully defined in the displayScalarObject method:

```
classdef MyClass < matlab.mixin.CustomDisplay
   ...
methods (Access = protected)
   function displayScalarObject(obj)
   % Implement the custom display for scalar obj</pre>
```

```
end
end
end
```

Custom Property List with Standard Layout

Use standard display layout, but create a custom property list for scalar and nonscalar display:

```
classdef MyClass < matlab.mixin.CustomDisplay
   ...
  methods(Access = protected)
     function groups = getPropertyGroups(obj)
        % Return PropertyGroup instances
    end
  end
end</pre>
```

Custom Property List for Scalar Only

Use standard display layout, but create a custom property list for scalar only. Call the superclass getPropertyGroups for the nonscalar case.

```
classdef MyClass < matlab.mixin.CustomDisplay</pre>
  properties
     Prop1
      Prop2
      Prop3
  end
  methods(Access = protected)
      function groups = getPropertyGroups(obj)
         if isscalar(obj)
            % Scalar case: change order
            propList = {'Prop2','Prop1','Prop3'};
            groups = matlab.mixin.util.PropertyGroup(propList)
         else
            % Nonscalar case: call superclass method
            groups = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
         end
      end
  end
end
```

Custom Property List with Modified Values

Change the values displayed for some properties in the scalar case by creating property/value pairs in a struct. This getPropertyGroups method displays only Prop1 and Prop2, and displays the value of Prop2 as Prop1 divided by Prop3.

```
classdef MyClass < matlab.mixin.CustomDisplay</pre>
   properties
      Prop1
      Prop2
      Prop3
   end
   methods(Access = protected)
      function groups = getPropertyGroups(obj)
         if isscalar(obj)
             % Specify the values to be displayed for properties
             propList = struct('Prop1',obj.Prop1,...
'Prop2',obj.Prop1/obj.Prop3);
             groups = matlab.mixin.util.PropertyGroup(propList)
         else
             % Nonscalar case: call superclass method
             groups = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
         end
      end
```

end end

Complete Class Definitions

For complete class implementations, see these sections:

• "Customize Property Display" on page 18-18

"Customize Header, Property List, and Footer" on page 18-21

"Customize Display of Scalar Objects" on page 18-26

"Customize Display of Object Arrays" on page 18-30

Customize Property Display

```
In this section...

"Objective" on page 18-18

"Change the Property Order" on page 18-18

"Change the Values Displayed for Properties" on page 18-18
```

Objective

Change the order and number of properties displayed for an object of your class.

Change the Property Order

Suppose your class definition contains the following property definition:

```
properties
Name
JobTitle
Department
Salary
Password
```

In the default scalar object display, MATLAB displays all the public properties along with their values. However, you want to display only Department, JobTitle, and Name, in that order. You can do this by deriving from CustomDisplay and overriding the getPropertyGroups method.

Your override

- Defines method Access as protected to match the definition in the CustomDisplay superclass
- · Creates a cell array of property names in the desired order
- Returns a PropertyGroup object constructed from the property list cell array

```
methods (Access = protected)
  function propgrp = getPropertyGroups(~)
    proplist = {'Department','JobTitle','Name'};
    propgrp = matlab.mixin.util.PropertyGroup(proplist);
  end
end
```

When you create a PropertyGroup object using a cell array of property names, MATLAB automatically

- Adds the property values for a scalar object display
- Uses the property names without values for a nonscalar object display (including empty object arrays)

The <code>getPropertyGroups</code> method is not called to create the display for a scalar handle to a deleted object.

Change the Values Displayed for Properties

Given the same class properties used in the previous section, you can change the value displayed for properties by building the property list as a struct and specifying values for property names. This

override of the getPropertyGroups method uses the default property display for nonscalar objects by calling the superclass getPropertyGroups method. For scalar objects, the override:

- Changes the value displayed for the Password property to a '*' character for each character in the password.

```
Displays the text 'Not Available' for the Salary property.
methods (Access = protected)
   function propgrp = getPropertyGroups(obj)
      if ~isscalar(obj)
         propgrp = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
         pd(1:length(obj.Password)) = '*';
         propList = struct('Department',obj.Department,...
              JobTitle',obj.JobTitle,...
             'Name',obj.Name,...
             'Salary','Not available',...
'Password',pd);
         propgrp = matlab.mixin.util.PropertyGroup(propList);
      end
   end
end
The object display looks like this:
  EmployeeInfo with properties:
     Department: 'Product Development'
       JobTitle: 'Software Engineer'
Name: 'Bill Tork'
Salary: 'Not available'
Password: '*******
Full Class Listing
classdef EmployeeInfo < handle & matlab.mixin.CustomDisplay</pre>
   properties
      Name
      JobTitle
      Department
      Salary
      Password
   methods
      function obj = EmployeeInfo
         obj.Name
                       = input('Name: ');
         obj.JobTitle = input('Job Title: ');
obj.Department = input('Department: ');
                         = input('Salary: ');
         obj.Salary
         obj.Password
                         = input('Password: ');
      end
   end
   methods (Access = protected)
      function propgrp = getPropertyGroups(obj)
         if ~isscalar(obi)
             propgrp = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
             pd(1:length(obj.Password)) = '*';
             propList = struct('Department',obj.Department,...
                 JobTitle',obj.JobTitle,...
```

Name', obj. Name, ...

end end end end

'Salary','Not available',...
'Password',pd);

propgrp = matlab.mixin.util.PropertyGroup(propList);

See Also

Related Examples

"Choose a Technique for Display Customization" on page 18-15

Customize Header, Property List, and Footer

In this section...

"Objective" on page 18-21

"Design of Custom Display" on page 18-21

"getHeader Method Override" on page 18-22

"getPropertyGroups Override" on page 18-23

"getFooter Override" on page 18-23

Objective

Customize each of the three parts of the display — header, property groups, and footer.

Design of Custom Display

Note This example uses the EmployeeInfo class described in the "Class with Default Object Display" on page 18-11 section.

For the header:

- Use default header for nonscalar object arrays.
- Build header text with linked class name and department name (from Department property)

For properties:

- Nonscalar object arrays display a subset of property names in a different order than the default.
- Scalar objects create two property groups that have titles (Public Info and Personal Info).

For the footer:

• Add a footer to the display, only when the object is a valid scalar that displays property values.

Here is the customized display of an object of the EmployeeInfo class.

Emp123 =

EmployeeInfo Dept: Product Development

Public Info

Name: 'Bill Tork'

JobTitle: 'Software Engineer'

Personal Info Salary: 1000 Password: 'bill123'

Company Private

Here is the custom display of an array of EmployeeInfo objects:

```
[Emp123, Emp124]
ans =
  1x2 EmployeeInfo array with properties:
    Department
    Name
    JobTitle
Here is the display of an empty object array:
>> EmployeeInfo.empty(0,5)
ans =
  0x5 EmployeeInfo array with properties:
    Department
    Name
    JobTitle
Here is the display of a handle to a deleted object (EmployeeInfo is a handle class):
>> delete(Emp123)
>> Emp123
Emp123 =
  handle to deleted EmployeeInfo
```

Implementation

The EmployeeInfo class overrides three matlab.mixin.CustomDisplay methods to implement the display shown:

- getHeader
- getPropertyGroups
- getFooter

Each method must produce the desired results with each of the following inputs:

- Scalar object
- Nonscalar object array
- Empty object array

getHeader Method Override

MATLAB calls getHeader to get the header text. The EmployeeInfo class overrides this method to implement the custom header for scalar display. Here is how it works:

- Nonscalar (including empty object) arrays call the superclass getHeader, which returns the default header.
- Scalar handles to deleted objects do not result in a call to getHeader.

• Scalar inputs build a custom header using the getClassNameForHeader static method to return linked class name text, and the value of the Department property.

Here is the EmployeeInfo override of the getHeader method. The required protected access is inherited from the superclass.

```
methods (Access = protected)
  function header = getHeader(obj)
    if ~isscalar(obj)
     header = getHeader@matlab.mixin.CustomDisplay(obj);
    else
        className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
        newHeader = [className, 'Dept: ',obj.Department];
        header = sprintf('%s\n',newHeader);
    end
end
```

getPropertyGroups Override

MATLAB calls getPropertyGroups to get the PropertyGroup objects, which control how properties are displayed. This method override defines two different property lists depending on the object's state:

- For nonscalar inputs, including empty arrays and arrays containing handles to deleted objects, create a property list as a cell array to reorder properties.
 - By default, MATLAB does not display property values for nonscalar inputs.
- For scalar inputs, create two property groups with titles. The scalar code branch lists properties in a different order than the nonscalar case and includes Salary and Password properties.
 MATLAB automatically assigns property values.
- Scalar handles to deleted objects do not result in a call to getPropertyGroups.

Both branches return a matlab.mixin.util.PropertyGroup object, which determines how to displays the object properties.

Here is the EmployeeInfo override of the getPropertyGroups method. The protected access is inherited from the superclass.

```
methods (Access = protected)
  function propgrp = getPropertyGroups(obj)
    if ~isscalar(obj)
        propList = {'Department', 'Name', 'JobTitle'};
        propgrp = matlab.mixin.util.PropertyGroup(propList);
    else
        gTitle1 = 'Public Info';
        gTitle2 = 'Personal Info';
        propList1 = {'Name', 'JobTitle'};
        propList2 = {'Salary', 'Password'};
        propgrp(1) = matlab.mixin.util.PropertyGroup(propList1,gTitle1);
        propgrp(2) = matlab.mixin.util.PropertyGroup(propList2,gTitle2);
    end
    end
end
```

getFooter Override

MATLAB calls getFooter to get the footer text. The EmployeeInfo getFooter method defines a footer for the display, which is included only when the input is a valid scalar object. In all other cases, getFooter returns an empty char vector.

Scalar handles to deleted objects do not result in a call to getFooter.

```
methods (Access = protected)
  function footer = getFooter(obj)
    if isscalar(obj)
      footer = sprintf('%s\n','Company Private');
  else
      footer = '';
  end
  end
end
```

Complete Class Listing

```
classdef EmployeeInfo < handle & matlab.mixin.CustomDisplay</pre>
   properties
      Name
      JobTitle
      Department
      Salary
      Password
   end
   methods
      function obj = EmployeeInfo
                          = input('Name: ');
          obj.Name
          obj.JobTitle = input('Job Title: ');
          obj.Department = input('Department: ');
obj.Salary = input('Salary: ');
          obj.Password = input('Password: ');
      end
   end
   methods (Access = protected)
      function header = getHeader(obj)
          if ~isscalar(obj)
             header = getHeader@matlab.mixin.CustomDisplay(obj);
             className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
             newHeader = [className,' Dept: ',obj.Department];
header = sprintf('%s\n',newHeader);
          end
      end
       function propgrp = getPropertyGroups(obj)
          if ~isscalar(obj)
             propList = {'Department', 'Name', 'JobTitle'};
             propgrp = matlab.mixin.util.PropertyGroup(propList);
          else
             gTitle1 = 'Public Info';
             gTitle2 = 'Personal Info';
             propList1 = {'Name','JobTitle'};
propList2 = {'Salary','Password'};
             propgrp(1) = matlab.mixin.util.PropertyGroup(propList1,gTitle1);
             propgrp(2) = matlab.mixin.util.PropertyGroup(propList2,gTitle2);
          end
      end
      function footer = getFooter(obj)
          if isscalar(obj)
             footer = sprintf('%s\n','Company Private');
          else
             footer = '';
          end
      end
   end
end
```

See Also

Related Examples

• "Choose a Technique for Display Customization" on page 18-15

Customize Display of Scalar Objects

"Objective" on page 18-26

"Design of Custom Display" on page 18-26

"displayScalarObject Method Override" on page 18-27

"getPropertyGroups Override" on page 18-27

Objective

Customize the display of scalar objects.

Design of Custom Display

Note This example uses the EmployeeInfo class described in the "Class with Default Object Display" on page 18-11 section.

The objective of this customized display is to:

- Modify the header to include the department name obtained from the Department property
- Group properties into two categories titled Public Info and Personal Info.
- · Modify which properties are displayed
- Modify the values displayed for Personal Info category
- Use the default displayed for nonscalar objects, including empty arrays, and scalar deleted handles

For example, here is the customized display of an object of the EmployeeInfo class.

```
Emp123 =
```

EmployeeInfo Dept: Product Development

```
Public Info
Name: 'Bill Tork'
JobTitle: 'Software Engineer'

Personal Info
Salary: 'Level: 10'
Password: '*******
```

Implementation

The EmployeeInfo class overrides two matlab.mixin.CustomDisplay methods to implement the display shown:

- displayScalarObject Called to display valid scalar objects
- getPropertyGroups Builds the property groups for display

displayScalarObject Method Override

MATLAB calls displayScalarObject to display scalar objects. The EmployeeInfo class overrides this method to implement the scalar display. Once overridden, this method must control all aspects of scalar object display, including creating the header, property groups, and footer, if used.

This implementation:

- Builds a custom header using the getClassNameForHeader static method to return linked class name text and the value of the Department property to get the department name.
- Uses sprintf to add a new line to the header text
- Displays the header with the built-in disp function.
- Calls the getPropertyGroups override to define the property groups (see following section).
- Displays the property groups using the displayPropertyGroups static method.

Here is the EmployeeInfo override of the displayScalarObject method. The required protected access is inherited from the superclass.

```
methods (Access = protected)
   function displayScalarObject(obj)
     className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
     scalarHeader = [className, 'Dept: ',obj.Department];
     header = sprintf('%s\n',scalarHeader);
     disp(header)
     propgroup = getPropertyGroups(obj);
     matlab.mixin.CustomDisplay.displayPropertyGroups(obj,propgroup)
   end
end
```

getPropertyGroups Override

MATLAB calls getPropertyGroups when displaying scalar or nonscalar objects. However, MATLAB does not call this method when displaying a scalar handle to a deleted object.

The EmployeeInfo class overrides this method to implement the property groups for scalar object display.

This implementation calls the superclass getPropertyGroups method if the input is not scalar. If the input is scalar, this method:

- Defines two titles for the two groups
- Creates a cell array of property names that are included in the first group. MATLAB adds the property values for the display
- Creates a struct array of property names with associated property values for the second group.
 Using a struct instead of a cell array enables you to replace the values that are displayed for the Salary and Password properties without changing the personal information stored in the object properties.
- Constructs two matlab.mixin.util.PropertyGroup objects, which are used by the displayScalarObject method.

Here is the <code>EmployeeInfo</code> override of the <code>getPropertyGroups</code> method. The required protected access is inherited from the superclass.

```
methods (Access = protected)
  function propgrp = getPropertyGroups(obj)
```

end methods

function obj = EmployeeInfo4

obj.Name

```
if ~isscalar(obj)
         propgrp = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
         gTitle1 = 'Public Info';
         gTitle2 = 'Personal Info';
         propList1 = {'Name', 'JobTitle'};
         pd(1:length(obj.Password)) = '*
         level = round(obj.Salary/100);
         propList2 = struct('Salary',...
  ['Level: ',num2str(level)],...
'Password',pd);
         propgrp(1) = matlab.mixin.util.PropertyGroup(propList1,gTitle1);
         propgrp(2) = matlab.mixin.util.PropertyGroup(propList2,gTitle2);
      end
   end
end
Complete Class Listing
classdef EmployeeInfo4 < handle & matlab.mixin.CustomDisplay</pre>
   properties
      Name
      JobTitle
      Department
      Salary
      Password
```

= input('Name: ');

```
obj.JobTitle = input('Job Title: ');
obj.Department = input('Department: ');
obj.Salary = input('Salary: ');
          obj.Password
                           = input('Password: ');
       end
   end
   methods (Access = protected)
       function displayScalarObject(obj)
          className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
          scalarHeader = [className, ' Dept: ',obj.Department];
          header = sprintf('%s\n',scalarHeader);
          disp(header)
          propgroup = getPropertyGroups(obj);
          matlab.mixin.CustomDisplay.displayPropertyGroups(obj,propgroup)
       end
       function propgrp = getPropertyGroups(obj)
          if ~isscalar(obj)
              propgrp = getPropertyGroups@matlab.mixin.CustomDisplay(obj);
          else
              % property groups for scalars
gTitle1 = 'Public Info';
              gTitle2 = 'Personal Info';
              propList1 = {'Name','JobTitle'};
              pd(1:length(obj.Password)) = '*
              level = round(obj.Salary/100);
             propList2 = struct('Salary',...
  ['Level: ',num2str(level)],...
'Password',pd);
              propgrp(1) = matlab.mixin.util.PropertyGroup(propList1,gTitle1);
              propgrp(2) = matlab.mixin.util.PropertyGroup(propList2,gTitle2);
          end
      end
   end
end
```

See Also

Related Examples

• "Choose a Technique for Display Customization" on page 18-15

Customize Display of Object Arrays

In this section...

"Objective" on page 18-30

"Design of Custom Display" on page 18-30

"The displayNonScalarObject Override" on page 18-31

"The displayEmptyObject Override" on page 18-32

Objective

Customize the display of nonscalar objects, including empty object arrays.

Design of Custom Display

Note This example uses the EmployeeInfo class described in the "Class with Default Object Display" on page 18-11 section.

The objective of this customized display is to:

- Construct a custom header using some elements of the default header
- Display a subset of property-specific information for each object in the array.
- List handles to deleted objects in the array using a char vector with links to documentation for handle objects and the class.
- · Display empty objects with a slight modification to the default header

Here is the customized display of an array of three EmployeeInfo objects

```
1x3 EmployeeInfo array with members:
```

1. Employee:

Name: 'Bill Tork'

Department: 'Product Development'

2. Employee:

Name: 'Alice Blackwell'

Department: 'QE'

3. Employee:

Name: 'Nancy Green'
Department: 'Documentation'

Deleted object handles in the array indicate their state:

1x3 EmployeeInfo members:

1. Employee:

Name: 'Bill Tork'

Department: 'Product Development'

2. handle to deleted EmployeeInfo

```
3. Employee:
            Name: 'Nancy Green'
            Department: 'Documentation'
```

To achieve the desired result, the EmployeeInfo class overrides the following methods of the matlab.mixin.CustomDisplay class:

- displayNonScalarObject Called to display nonempty object arrays
- displayEmptyObject Called to display empty object arrays

The displayNonScalarObject Override

MATLAB calls the displayNonScalarObject method to display object arrays. The override of this method in the EmployeeInfo class:

- Builds header text using convertDimensionsToString to obtain the array size and getClassNameForHeader to get the class name with a link to the help for that class.
- Displays the modified header text.
- Loops through the elements in the array, building two different subheaders depending on the individual object state. In the loop, this method:
 - Detects handles to deleted objects (using the isvalid handle class method). Uses getDeletedHandleText and getClassNameForHeader to build text for array elements that are handles to deleted objects.
 - Builds a custom subheader for valid object elements in the array
- Creates a PropertyGroup object containing the Name and Department properties for valid objects
- Uses the displayPropertyGroups static method to generate the property display for valid objects.

Here is the implementation of displayNonScalarObjects:

```
methods (Access = protected)
   function displayNonScalarObject(objAry)
      dimStr = matlab.mixin.CustomDisplay.convertDimensionsToString(objAry);
      cName = matlab.mixin.CustomDisplay.getClassNameForHeader(objAry);
      headerStr = [dimStr, '
                            ',cName,' members:'];
      header = sprintf('%s\n',headerStr);
      disp(header)
      for ix = 1:length(objAry)
         o = objAry(ix);
         if ~isvalid(o)
            str1 = matlab.mixin.CustomDisplay.getDeletedHandleText;
            str2 = matlab.mixin.CustomDisplay.getClassNameForHeader(o);
            headerInv = [str1, ' ',str2];
            tmpStr = [num2str(ix),'.',headerInv];
           numStr = sprintf('%s\n',tmpStr);
            disp(numStr)
            numStr = [num2str(ix),'. Employee:'];
            disp(numStr)
            propList = struct('Name', o.Name,...
               'Department', o. Department);
            propgrp = matlab.mixin.util.PropertyGroup(propList);
            matlab.mixin.CustomDisplay.displayPropertyGroups(o,propgrp);
         end
      end
   end
end
```

The displayEmptyObject Override

MATLAB calls the displayEmptyObject method to display empty object arrays. The implementation of this method in the EmployeeInfo class builds a custom header for empty objects following these steps:

- Gets the array dimensions in character format using the convertDimensionsToString static method
- Gets text with the class name linked to the helpPopup function using the getClassNameForHeader static method.
- Builds and displays the custom text for empty arrays.

```
methods (Access = protected)
  function displayEmptyObject(obj)
    dimstr = matlab.mixin.CustomDisplay.convertDimensionsToString(obj);
    className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
    emptyHeader = [dimstr,' ',className,' with no employee information'];
    header = sprintf('%s\n',emptyHeader);
    disp(header)
  end
end
```

For example, an empty EmployeeInfo object displays like this:

```
Empt = EmployeeInfo.empty(0,5)
Empt =
```

0x5 EmployeeInfo with no employee information

Complete Class Listing

```
classdef EmployeeInfo < handle & matlab.mixin.CustomDisplay</pre>
  properties
      Name
      JobTitle
      Department
      Salary
      Password
  methods
      function obj = EmployeeInfo
                        = input('Name: ');
         obj.Name
         obj.JobTitle = input('Job Title: ');
obj.Department = input('Department: ');
         obj.Salary
                         = input('Salary: ');
                        = input('Password: ');
         obj.Password
      end
  end
  methods (Access = protected)
      function displayNonScalarObject(objAry)
         dimStr = matlab.mixin.CustomDisplay.convertDimensionsToString(objAry);
         cName = matlab.mixin.CustomDisplay.getClassNameForHeader(objAry);
         headerStr = [dimStr, ' ',cName, ' members: '];
         header = sprintf('%s\n',headerStr);
         disp(header)
         for ix = 1:length(objAry)
            o = objAry(ix);
             if ~isvalid(o)
                str1 = matlab.mixin.CustomDisplay.getDeletedHandleText;
                str2 = matlab.mixin.CustomDisplay.getClassNameForHeader(o);
                headerInv = [str1, ' ',str2];
                tmpStr = [num2str(ix), ', headerInv];
                numStr = sprintf('%s\n',tmpStr);
                disp(numStr)
```

```
else
                   numStr = [num2str(ix),'. Employee'];
                   disp(numStr)
                   propList = struct('Name', o.Name,...
                       'Department', o. Department);
                   propgrp = matlab.mixin.util.PropertyGroup(propList);
                   matlab.mixin.CustomDisplay.displayPropertyGroups(o,propgrp);
           end
       end
       function displayEmptyObject(obj)
           dimstr = matlab.mixin.CustomDisplay.convertDimensionsToString(obj);
className = matlab.mixin.CustomDisplay.getClassNameForHeader(obj);
           emptyHeader = [dimstr,' ',className,' with no employee information'];
header = sprintf('%s\n',emptyHeader);
           disp(header)
       end
   end
end
```

See Also

Related Examples

"Choose a Technique for Display Customization" on page 18-15

Overloading the disp Function

In this section...

"Display Methods" on page 18-34

"Overloaded disp" on page 18-34

"Relationship Between disp and display" on page 18-34

Display Methods

Subclassing matlab.mixin.CustomDisplay is the best approach to customizing object display. However, if you do not derive your class from matlab.mixin.CustomDisplay, overload the disp function to change how MATLAB displays objects of your class.

MATLAB calls the display function whenever an object is referred to in a statement that is not terminated by a semicolon. For example, the following statement creates the variable a. MATLAB calls display, which displays the value of a in the command line.

```
a = 5
```

display then calls disp.

Overloaded disp

The built-in display function prints the name of the variable that is being displayed, if an assignment is made, or otherwise uses ans as the variable name. Then display calls disp to handle the actual display of the values.

If the variable that is being displayed is an object of a class that overloads disp, then MATLAB always calls the overloaded method. MATLAB calls display with two arguments and passes the variable name as the second argument.

Relationship Between disp and display

MATLAB invokes the built-in display function when the following occur:

- MATLAB executes a statement that returns a value and is not terminated with a semicolon.
- There is no left-side variable, then MATLAB prints ans = followed by the value.
- Code explicitly invokes the display function.

When invoking display:

- If the input argument is an existing variable, display prints the variable name and equal sign, followed by the value.
- If the input is the result of an expression, display does not print ans =.

MATLAB invokes the built-in disp function when the following occurs:

- The built-in display function calls disp.
- Code explicitly invokes disp.

For empty built-in types (numeric types, char, struct, and cell) the display function displays:

- [] for numeric types
- "0x0 struct array with no fields." for empty structs.
- "0x0 empty cell array" for empty cell arrays.
- "0x0 empty char array" for empty char arrays
- "0x0 empty string array" for empty string arrays

disp differs from display in these ways:

- disp does not print the variable name or ans.
- disp prints nothing for built-in types (numeric types, char, struct, and cell) when the value is empty.

See Also

Related Examples

- "Custom Display Interface" on page 18-2
- "Overload disp for DocPolynom" on page 19-11

Custom Compact Display Interface

In addition to the custom display options described in "Custom Display Interface" on page 18-2, you can also customize the way MATLAB displays objects in compact display scenarios. Compact display scenarios occur when an object array is inside a container, such as a structure, cell array, or table. You can customize the way object arrays are displayed in a compact display by inheriting from matlab.mixin.CustomCompactDisplayProvider.

(Since R022b) The rules implemented by CustomCompactDisplayProvider are honored by the Live Editor, the Variables editor in MATLAB Online, and the single-line 'Value' field in the Workspace panel in MATLAB Online.

Customization Options Available for Compact Display

CustomCompactDisplayProvider provides customization options in two main areas of compact displays:

- **Single-line layout** The display of the object array is confined to a single line. This display layout occurs when the object array is contained within a structure, cell array, or property of a MATLAB object. Override the CustomCompactDisplayProvider method compactRepresentationForSingleLine to customize this layout.
- Columnar layout The object array is displayed in multiple rows as part of column-oriented or tabular data. This display layout occurs when the object array is contained within a table variable. Override the CustomCompactDisplayProvider method compactRepresentationForColumn to customize this layout.

Three additional CustomCompactDisplayProvider utility methods enable you to control how much of the data is used to construct a display of the object array:

- partialDataRepresentation The compact display of the object array is constructed from only the leading elements of the data set or only the leading and trailing elements, omitting the values in between.
- fullDataRepresentation The compact display of the object array is constructed based on the entire set of data.
- widthConstrainedDataRepresentation The compact display of the object array is constructed from the data based on a width constraint you provide.

Each of these three utility methods also provides an Annotation name-value argument, which enables you to include a row vector of strings to serve as descriptors in your compact displays. For example, in the case of a class representing polynomials, adding an annotation can be useful when only the dimensions and class of the data fit in the display:

```
struct with fields:
   prop1: [1x3 sym] (Third-order polynomial)
```

Designing a Class with a Customized Compact Display

When considering how to customize the compact display for a class, first write the class without any customization and test to see if the default display options need to be changed for your application. For example, this class stores a single polynomial as a string and its order as a double.

```
classdef Polynomial
  properties
     polynomialString string {mustBeScalarOrEmpty};
     polynomialOrder double {mustBeScalarOrEmpty};
  end
  methods
     function obj = Polynomial(polyString,polyOrder)
          obj.polynomialString = polyString;
          obj.polynomialOrder = polyOrder;
  end
  end
end
```

{1×1 Polynomial}

The full code of this class with customized compact display functionality is available at the end of the example.

Create an instance of Polynomial. Display the instance in a cell array to check the single-line layout.

```
 \begin{aligned} &\text{poly} = \text{"}(x^10)/100 + 300*x^9 + 200*x^8 + 4000*x^7 + 600*x^6 + 700*x^5 + 45*x^4 + 90*x^3 + 4*x^2 \\ &\text{a} = \text{Polynomial(poly,10);} \\ &\text{als} \end{aligned}   &\text{ans} = \\ &1 \times 1 \text{ cell array}
```

The single-line layout does not provide users with much information. Change Polynomial to inherit from matlab.mixin.CustomCompactDisplayProvider and override the compactRepresentationForSingleLine method. Call the utility method widthConstrainedDataRepresentation with AllowTruncatedDisplayForScalar set to true. MATLAB now truncates the polynomial string based on the width available.

```
function displayRep = compactRepresentationForSingleLine(obj,displayConfiguration,width)
    displayRep = widthConstrainedDataRepresentation(obj,displayConfiguration,width,...
    StringArray=obj.polynomialString,AllowTruncatedDisplayForScalar=true);
end
```

Now, the display of the instance in a cell array contains as much of the string as possible.

```
{a} ans = 1 \times 1 \text{ cell array} \{ [(x^10)/100 + 300*x^9 + 200*x^8 + 4000*x^7 + 600*x^6 + 700*x^5 + 45*x^4 + 90*x^3 + 4*x^2 + 4000*x^6 + 700*x^6 + 700*x^6
```

For a table display, the default shows only the class and dimensions, so override compactRepresentationForColumn. The method returns an instance of matlab.display.DimensionsAndClassNameRepresentation with an annotation, which in this case identifies the order of the polynomial. To cover the case when a table has a row vector of Polynomial instances in a single entry, the method reshapes the polynomialOrder property to match the shape of the instance and then finds the maximum order in that row for display.

```
function displayRep = compactRepresentationForColumn(obj,displayConfig,width)
import matlab.display.DimensionsAndClassNameRepresentation;
```

With this code in place, you can create a table of estimation results, for example, that identifies the order of the polynomial. Create a second Polynomial, b. Then create two tables, one with a and b in a column, and one with a and b in the same row.

With a and b in the same row, only the maximum order is displayed.

```
Result = 1;
Estimate = [a b];
T1 = table(Result, Estimate)

T1 =

1×2 table

Result Estimate

1 1×2 Polynomial (Polynomial of order 10)
```

Complete Polynomial Class

```
classdef Polynomial < matlab.mixin.CustomCompactDisplayProvider
    properties
        polynomialString string {mustBeScalarOrEmpty};
        polynomialOrder double {mustBeScalarOrEmpty};
    end
    methods
    function obj = Polynomial(polyString, polyOrder)
        obj.polynomialString = polyString;
        obj.polynomialOrder = polyOrder;
    end

function displayRep = compactRepresentationForSingleLine(obj,displayConfiguration,width)
        displayRep = widthConstrainedDataRepresentation(obj,displayConfiguration,width,...
        StringArray=obj.polynomialString,AllowTruncatedDisplayForScalar=true);
    end

function displayRep = compactRepresentationForColumn(obj,displayConfig,width)
        import matlab.display.DimensionsAndClassNameRepresentation;
        polOrder = reshape([obj.polynomialOrder],size(obj));
        maxPolOrderPerRow = max(polOrder,[],2);</pre>
```

See Also

Related Examples

matlab.mixin.CustomCompactDisplayProvider

Defining Custom Data Types

Representing Polynomials with Classes

In this section...

"Class Requirements" on page 19-2

"DocPolynom Class Members" on page 19-2

"DocPolynom Class Synopsis" on page 19-4

"The DocPolynom Constructor" on page 19-9

"Convert DocPolynom Objects to Other Classes" on page 19-10

"Overload disp for DocPolynom" on page 19-11

"Display Evaluated Expression" on page 19-11

"Define Arithmetic Operators" on page 19-12

"Redefine Parentheses Indexing" on page 19-13

You can use classes to define new data types. This example implements a class that represents polynomials. The class stores the coefficients of the polynomial terms in a vector and overrides the default MATLAB display to show the polynomials as powers of x. Using customized indexing, the class also enables you to evaluate the polynomials at one or more values of x using parentheses indexing syntax.

Class Requirements

The design requirements for the DocPolynom class are:

- Value class behavior —Behave like MATLAB numeric variables when copied and passed to functions.
- Scalar object behavior Polynomial objects cannot be concatenated, and polynomial array size must always be (1,1).
- Customized indexing behavior Evaluate a polynomial using parentheses indexing syntax. p(x) evaluates the polynomial represented by object p at each value in x.
- Specialized display Use the coefficients stored in the polynomial object to display the polynomial as an algebraic expression.
- Override addition, subtraction, and multiplication Adding, subtracting, or multiplying
 polynomial objects returns the result of the corresponding algebraic operation on the two
 polynomials.
- Double converter Convert a polynomial object to a double array so it can be used with existing MATLAB functions that accept numeric inputs.

DocPolynom Class Members

The class defines the property **coef** for storage of the polynomial coefficients.

DocPolynom Class Properties

Name	Class	Default	Description
coef	double	[]	Vector of polynomial coefficients, in order of the highest exponent of x to lowest.

This table summarizes the methods for the DocPolynom class.

DocPolynom Class Methods

Name	Description
DocPolynom	Class constructor
double	Converts the DocPolynom object to a double. In other words, this method returns the coefficients in a vector of double values.
char	Creates a formatted display of the $DocPolynom$ object as powers of x . This method is used by the $disp$ method.
disp	Defines how MATLAB displays DocPolynom objects on the command line.
plus	Adds DocPolynom objects.
minus	Subtracts DocPolynom objects.
mtimes	Multiplies DocPolynom objects.
dispPoly	Evaluates the polynomial for one or more values and returns the results in an organized list instead of a vector of double values.
parenReference	Enables evaluation of a polynomial using parentheses indexing syntax. $p(x)$ evaluates the polynomial object p at each value in x .

Using the DocPolynom Class

These examples show the basic use of the DocPolynom class. Create DocPolynom objects to represent $f(x) = x^3 - 2x - 5$ and $f(x) = 2x^4 + 3x^2 + 2x - 7$.

```
p1 = DocPolynom([1 0 -2 -5])
p1 =
     x^3 - 2*x - 5

p2 = DocPolynom([2 0 3 2 -7])
p2 =
     2*x^4 + 3*x^2 + 2*x - 7
```

Find the roots of the polynomial p1. Use the double method of the object and pass the result to the roots function.

```
roots(double(p1))
ans =
   2.0946 + 0.0000i
   -1.0473 + 1.1359i
   -1.0473 - 1.1359i
```

Add the two polynomials p1 and p2. MATLAB calls the plus method defined for the DocPolynom class when you add two DocPolynom objects.

```
p1 + p2
ans =
2*x^4 + x^3 + 3*x^2 - 12
```

DocPolynom Class Synopsis

Class Code	Description
<pre>classdef DocPolynom < matlab.mixin.Scalar</pre>	Value class that implements a data type for polynomials. The class inherits from matlab.mixin.Scalar, which enforces scalar class behavior and also provides functionality to customize parentheses indexing. For more information on the superclass, see matlab.mixin.Scalar.
properties coef end	Vector of polynomial coefficients.
<pre>methods function obj = DocPolynom(c) if nargin > 0 if isa(c,'DocPolynom') obj.coef = c.coef; else obj.coef = c(:).'; end end end</pre>	Class constructor that creates objects using either: • An existing DocPolynom object • A vector of doubles For more information, see "The DocPolynom Constructor" on page 19-9.
<pre>function obj = set.coef(obj,val) if ~isa(val,'double') error('Coefficients must be doubles.') end ind = find(val(:).'~=0); if isempty(ind) obj.coef = val; else obj.coef = val(ind(1):end); end end</pre> function c = double(obj)	Set method for coef property: Restricts coefficients to type double Removes leading zeros from the coefficient vector For more information, see "Remove Leading Zeros" on page 19-9. Convert DocPolynom object to
c = obj.coef; end	double by returning the coefficients. For more information, see "Convert DocPolynom Objects to Other Classes" on page 19-10.

```
Class Code
                                                           Description
      function str = char(obj)
                                                           Convert DocPolynom object to char.
         if all(obj.coef == 0)
                                                           For more information, see "Convert
             s = '0';
                                                           DocPolynom Objects to Other
             str = s;
                                                           Classes" on page 19-10.
             return
         else
             d = length(obj.coef) - 1;
             s = cell(1,d);
             ind = 1;
             for a = obj.coef
                if a ~= 0
                   if ind \sim=1
                      if a > 0
                          s(ind) = {' + '};
                          ind = ind + 1;
                      else
                          s(ind) = {' - '};
                          a = -a;
                          ind = ind + 1;
                      end
                   end
                   if a \sim= 1 || d == 0
                      if a == -1
                          s(ind) = {'-'};
                          ind = ind + 1;
                      else
                          s(ind) = \{num2str(a)\};
                          ind = ind + 1;
                          if d > 0
                             s(ind) = {'*'};
                             ind = ind + 1;
                          end
                      end
                   end
                   if d >= 2
                      s(ind) = \{['x^{'} int2str(d)]\};
                      ind = ind + 1;
                   elseif d == 1
                      s(ind) = {'x'};
                      ind = ind + 1;
                   end
                end
                d = d - 1;
             end
         end
         str = [s{:}];
      end
      function disp(obj)
                                                           Overload disp function. This method
         c = char(obj);
                                                           displays objects as output of the
         if iscell(c)
                                                           char method.
             disp(['
                          ' c{:}])
         else
                                                           For more information, see "Overload
             disp(c)
                                                           disp for DocPolynom" on page 19-
         end
                                                           11.
      end
```

```
Class Code
                                                            Description
      function dispPoly(obj,x)
                                                            Return evaluated polynomial with
          p = char(obj);
                                                            formatted output. This method uses
          y = zeros(length(x));
                                                            polyval in a loop to evaluate the
          disp(['f(x) = ',p])
                                                            polynomial at specified values of the
          for k = 1:length(x)
                                                            independent variable.
             y(k) = polyval(obj.coef,x(k));
                       f(', \text{num2str}(x(k)), ') = ', \text{num2str}(y(k))]
For more information, see "Display
          end
                                                            Evaluated Expression" on page 19-
      end
                                                            11.
      function r = plus(obj1,obj2)
                                                            Define three arithmetic operators:
          obj1 = DocPolynom(obj1);
         obj2 = DocPolynom(obj2);
                                                               Polynomial addition
         k = length(obj2.coef) - length(obj1.coef);
                                                              Polynomial subtraction
         zp = zeros(1,k);

    Polynomial multiplication

          zm = zeros(1,-k);
          r = DocPolynom([zp,obj1.coef] + [zm,obj2.coef]);
                                                            For information about this code, see
                                                            "Define Arithmetic Operators" on
      function r = minus(obj1,obj2)
                                                            page 19-12.
          obj1 = DocPolynom(obj1);
         obj2 = DocPolynom(obj2);
                                                            For general information about
         k = length(obj2.coef) - length(obj1.coef);
                                                            defining operators, see "Operator
         zp = zeros(1,k);
                                                            Overloading" on page 17-19.
          zm = zeros(1,-k);
          r = DocPolynom([zp,obj1.coef] - [zm,obj2.coef]);
      end
      function r = mtimes(obj1,obj2)
          obj1 = DocPolynom(obj1);
          obj2 = DocPolynom(obj2);
          r = DocPolynom(conv(obj1.coef,obj2.coef));
      end
   end
   methods (Access = protected)
                                                            Customize parentheses reference for
         function f = parenReference(obj,indexOp)
                                                            DocPolynom objects. This
             n = cell2mat(index0p(1).Indices);
                                                            implementation of parenReference
             if numel(indexOp) == 1
                                                            enables users to evaluate a
                 f = polyval(obj.coef,n);
                                                            polynomial using parentheses
             else
                 f = polyval(obj.coef,n).(indexOp(2:end)) dexing syntax. p(x) evaluates the
                                                            polynomial represented by object p
             end
                                                            for each value in x.
        end
   end
                                                            For more information, see "Redefine"
end
                                                            Parentheses Indexing" on page 19-
                                                            13.
```

Expand for Class Code

```
classdef DocPolynom < matlab.mixin.Scalar
  properties
       coef
  end</pre>
```

```
methods
   function obj = DocPolynom(c)
      if nargin > 0
         if isa(c,'DocPolynom')
            obj.coef = c.coef;
         else
            obj.coef = c(:).';
         end
      end
   end
   function obj = set.coef(obj,val)
      if ~isa(val,'double')
         error('Coefficients must be doubles.')
      end
      ind = find(val(:).^{\sim}=0);
      if isempty(ind)
         obj.coef = val;
      else
         obj.coef = val(ind(1):end);
      end
   end
   function c = double(obj)
      c = obj.coef;
   function str = char(obj)
      if all(obj.coef == 0)
         s = '0';
         str = s;
         return
      else
         d = length(obj.coef) - 1;
         s = cell(1,d);
         ind = 1;
         for a = obj.coef
            if a ~= 0
               if ind ~= 1
                  if a > 0
                      s(ind) = {' + '};
                      ind = ind + 1;
                  else
                      s(ind) = {' - '};
                     a = -a;
                     ind = ind + 1;
                  end
               end
               if a ~= 1 || d == 0
                  if a == -1
                     s(ind) = {'-'};
                      ind = ind + 1;
                  else
                     s(ind) = {num2str(a)};
                      ind = ind + 1;
                     if d > 0
                         s(ind) = {'*'};
```

```
ind = ind + 1;
                  end
               end
            end
            if d >= 2
               s(ind) = \{['x^' int2str(d)]\};
               ind = ind + 1;
            elseif d == 1
               s(ind) = \{'x'\};
               ind = ind + 1;
            end
         end
         d = d - 1;
      end
   end
   str = [s{:}];
end
function disp(obj)
   c = char(obj);
   if iscell(c)
                  ' c{:}])
      disp(['
   else
      disp(c)
   end
end
function dispPoly(obj,x)
   p = char(obj);
   y = zeros(length(x));
   disp(['f(x) = ',p])
   for k = 1:length(x)
      y(k) = polyval(obj.coef,x(k));
      disp([' f(',num2str(x(k)),') = ',num2str(y(k))])
   end
end
function r = plus(obj1,obj2)
   obj1 = DocPolynom(obj1);
   obj2 = DocPolynom(obj2);
   k = length(obj2.coef) - length(obj1.coef);
   zp = zeros(1,k);
   zm = zeros(1,-k);
   r = DocPolynom([zp,obj1.coef] + [zm,obj2.coef]);
end
function r = minus(obj1,obj2)
   obj1 = DocPolynom(obj1);
   obj2 = DocPolynom(obj2);
   k = length(obj2.coef) - length(obj1.coef);
   zp = zeros(1,k);
   zm = zeros(1,-k);
   r = DocPolynom([zp,obj1.coef] - [zm,obj2.coef]);
function r = mtimes(obj1,obj2)
   obj1 = DocPolynom(obj1);
   obj2 = DocPolynom(obj2);
```

```
r = DocPolynom(conv(obj1.coef,obj2.coef));
end
end

methods (Access = protected)
  function f = parenReference(obj,index0p)
    n = cell2mat(index0p(1).Indices);
  if numel(index0p) == 1
    f = polyval(obj.coef,n);
  else
    f = polyval(obj.coef,n).(index0p(2:end));
  end
end
end
end
```

The DocPolynom Constructor

This is the DocPolynom class constructor:

```
function obj = DocPolynom(c)
   if nargin > 0
      if isa(c,'DocPolynom')
      obj.coef = c.coef;
   else
      obj.coef = c(:).';
   end
  end
end
```

Constructor Calling Syntax

The DocPolynom constructor can accept two different input arguments:

- An existing DocPolynom object Calling the constructor with an existing DocPolynom object as an input argument returns a new DocPolynom object with the same coefficients as the input argument. The isa function checks for this input.
- Coefficient vector When the input argument is not a DocPolynom object, the constructor attempts to reshape the values into a row vector and assign them to the coef property.

The coef property set method restricts property values to doubles. See "Remove Leading Zeros" on page 19-9 for a description of the property set method.

This example uses a vector as the input argument to the DocPolynom constructor:

```
p = DocPolynom([1 0 -2 -5])
p =
    x^3 - 2*x -5
```

This statement creates an instance of the DocPolynom class with the specified coefficients. The display of the object shows the equivalent polynomial using MATLAB language syntax. The DocPolynom class implements this display using the disp and char class methods.

Remove Leading Zeros

The DocPolynom class represents polynomials as row vectors containing coefficients ordered by descending powers. Zeros in the coefficient vector represent terms that are not in the polynomial.

Leading zeros, therefore, can be ignored when forming the polynomial. In fact, some <code>DocPolynom</code> class methods use the length of the coefficient vector to determine the degree of the polynomials, so removing leading zeros from the coefficient vector ensures that the vector length represents the correct polynomial degree.

The DocPolynom class stores the coefficient vector in a property that uses a set method to remove leading zeros from the specified coefficients before setting the property value.

```
function obj = set.coef(obj,val)
   if ~isa(val,'double')
      error('Coefficients must be doubles.')
   end
   ind = find(val(:).'~=0);
   if isempty(ind)
      obj.coef = val;
   else
      obj.coef = val(ind(1):end);
   end
end
```

Convert DocPolynom Objects to Other Classes

The DocPolynom class defines two methods to convert DocPolynom objects to other classes:

- double Converts to the double numeric type so functions can perform mathematical operations
 on the coefficients.
- char Converts to characters used to format output for display in the Command Window.

The Double Converter

The double converter method for the DocPolynom class returns the coefficient vector:

```
function c = double(obj)
    c = obj.coef;
end
```

For the DocPolynom object p, double returns a vector of class double.

```
p = DocPolynom([1 0 -2 -5]);
c = double(p)
c =
```

The Character Converter

The char method returns a char vector that represents the polynomial displayed as powers of x. The char vector returned is a syntactically correct MATLAB expression.

The char method uses a cell array to collect the char vector components that make up the displayed polynomial. The disp method uses the char method to format the DocPolynom object for display. Users of DocPolynom objects are not likely to call the char or disp methods directly, but these methods enable the DocPolynom class to behave like other data classes in MATLAB.

Overload disp for DocPolynom

To provide a more useful display of DocPolynom objects, this class overloads disp in the class definition. This disp method relies on the char method to produce a text representation of the polynomial, which it then displays.

The char method returns a cell array or the character '0' if the coefficients are all zero.

```
function disp(obj)
  c = char(obj);
  if iscell(c)
      disp([' ' c{:}])
  else
      disp(c)
  end
end
```

When MATLAB Calls the disp Method

This statement creates a DocPolynom object. Because the statement is not terminated with a semicolon, the resulting output is displayed on the command line using the overloaded disp method.

Display Evaluated Expression

The dispPoly method evaluates the polynomial for one or more values of x. The method loops through the input values of x and uses the polyval function with the coef property to evaluate the polynomial.

```
function dispPoly(obj,x)
  p = char(obj);
  y = zeros(length(x));
  disp(['f(x) = ',p,])
  for k = 1:length(x)
      y(k) = polyval(obj.coef,x(k));
      disp([' f(',num2str(x(k)),') = ',num2str(y(k))])
  end
end

Create a DocPolynom object p:
p = DocPolynom([1 0 -2 -5])
p =
      x^3 - 2*x - 5
```

Evaluate the polynomial at three values of x, [3 5 9]. Instead of returning a vector of values, the method uses function notation to present the results in an organized list.

```
dispPoly(p,[3 5 9])

f(x) = x^3 - 2*x - 5

f(3) = 16
```

```
f(5) = 110
f(9) = 706
```

Define Arithmetic Operators

The DocPolynom class implements methods for three arithmetic operations.

Method and Syntax	Operation
plus(a,b)	Addition
minus(a,b)	Subtraction
<pre>mtimes(a,b)</pre>	Matrix multiplication

The overloaded plus, minus, and mtimes methods accept argument pairs that include at least one DocPolynom object.

Define the + Operator

If either p or q is a DocPolynom object, this expression generates a call to the plus method overload defined by DocPolynom unless the other object is of higher precedence.

```
p + q
```

This method overloads the plus (+) operator for the DocPolynom class.

```
function r = plus(obj1,obj2)
  obj1 = DocPolynom(obj1);
  obj2 = DocPolynom(obj2);
  k = length(obj2.coef) - length(obj1.coef);
  zp = zeros(1,k);
  zm = zeros(1,-k);
  r = DocPolynom([zp,obj1.coef] + [zm,obj2.coef]);
end
```

The plus method performs these actions:

- Ensure that both input arguments are DocPolynom objects so that expressions that involve a DocPolynom and a double work correctly.
- Access the two coefficient vectors and, if necessary, pad one of them with zeros to make both the same length. The actual addition is simply the vector sum of the two coefficient vectors.
- Call the DocPolynom constructor to create a properly typed object that is the result of adding the
 polynomials.

Define the - Operator

The minus operator (-) uses the same approach as the plus (+) operator. The minus method computes p - q. The dominant argument must be a DocPolynom object.

```
function r = minus(obj1,obj2)
  obj1 = DocPolynom(obj1);
  obj2 = DocPolynom(obj2);
  k = length(obj2.coef) - length(obj1.coef);
  zp = zeros(1,k);
  zm = zeros(1,-k);
  r = DocPolynom([zp,obj1.coef] - [zm,obj2.coef]);
end
```

Define the * Operator

The mtimes method computes the product p*q. The mtimes method implements matrix multiplication because the multiplication of two polynomials is the convolution (conv) of their coefficient vectors:

```
methods
  function r = mtimes(obj1,obj2)
    obj1 = DocPolynom(obj1);
    obj2 = DocPolynom(obj2);
    r = DocPolynom(conv(obj1.coef,obj2.coef));
  end
end
```

Using the Arithmetic Operators

Create a DocPolynom object.

```
p = DocPolynom([1 0 -2 -5]);
```

These two arithmetic operations call the DocPolynom plus and mtimes methods.

Redefine Parentheses Indexing

The DocPolynom class inherits from matlab.mixin.Scalar, which in turn inherits from the modular indexing class matlab.mixin.indexing.RedefinesParen. Overloading the parenReference method of RedefinesParen enables users to evaluate a polynomial represented by a DocPolynom object using parentheses indexing syntax.

For example, create a DocPolynom object p.

The overloaded parenReference method evaluates the value of the polynomial at x = 3 and at x = 4 using this command.

```
p([3 4])
ans =
16 51
```

Modular Indexing Implementation Details

The parenReference method handles expressions of the form p(x), where p is a DocPolynom object and x contains numeric inputs. Instead of a traditional MATLAB indexing operation, however,

parenReference uses polyval to evaluate the polynomial using the coefficients stored in the coef property.

```
methods (Access = protected)
   function f = parenReference(obj,index0p)
    n = cell2mat(index0p(1).Indices);
   if numel(index0p) == 1
        f = polyval(obj.coef,n);
   else
        f = polyval(obj.coef,n).(index0p(2:end));
   end
end
```

The method performs these steps:

- 1 Extract the indexing values from index0p, which is an instance of the matlab.indexing.IndexingOperation class. The index0p object stores them as a cell array, and the method converts them to a numeric array and stores them in n.
- **2** Calculate the number of indexing operations in the expression.
- **3** Evaluate the polynomial at the values in n. The intended use of this syntax includes one parentheses indexing operation.
- 4 If the method finds more than one indexing operation, it uses polyval to evaluate the polynomial and then forwards the rest of the indexing operations to MATLAB using the forwarding syntax, .(index0p(2:end)). The class does not support any additional customized indexing operations, so MATLAB returns an error.

For example, attempting to evaluate a polynomial object while also using dot indexing to try to access its coef property at the same time errors.

```
p(5).coef(1)
Dot indexing is not supported for variables of this type.
```

For more information on forwarding operations with modular indexing, see "Forward Indexing Operations" on page 17-30.

Using the modular indexing class in this way means that only parentheses reference operations are customized. Dot access to properties and methods are unaffected and are handled by MATLAB as expected.

Note The matlab.mixin.Scalar and matlab.mixin.indexing.RedefinesParen functionality was introduced in R2021b.

Designing Related Classes

A Class Hierarchy for Heterogeneous Arrays

In this section...

"Interfaces Based on Heterogeneous Arrays" on page 20-2

"Define Heterogeneous Hierarchy" on page 20-2

"Assets Class" on page 20-4

"Stocks Class" on page 20-5

"Bonds Class" on page 20-6

"Cash Class" on page 20-8

"Default Object" on page 20-9

"Operating on an Assets Array" on page 20-11

Interfaces Based on Heterogeneous Arrays

A heterogeneous class hierarchy lets you create arrays containing objects of different classes that are related though inheritance. You can define class methods that operate on these heterogeneous arrays as a whole.

A class design based on heterogeneous arrays provides a more convenient interface than, for example, extracting elements from a cell array and operating on these elements individually. For more information on the design of class hierarchies that support heterogeneous arrays, see "Designing Heterogeneous Class Hierarchies" on page 10-19.

All heterogeneous hierarchies derive from matlab.mixin.Heterogeneous.

Define Heterogeneous Hierarchy

Note This example does not use valid terminology or techniques for managing financial assets. The purpose of this example is only to illustrate techniques for defining heterogeneous class hierarchies.

This example implements a system of classes to represent financial assets, such as stocks, bonds, and cash. Classes to represent categories of assets have certain common requirements. Each instance has one of the following:


- Textual description
- Type (stock, bond, or cash)
- Means to determine the current value of the asset

Heterogeneous arrays of these objects need methods that can operate on the whole array. These operations include:

- Creating a table of information about all assets contained in the array
- Graphing the relative contribution of each asset type contained in the array

These requirements are factored into the class that is the root of the hierarchy. The root class derives from matlab.mixin.Heterogeneous. In the following diagram, the Assets class is the root of the

hierarchy. The Stocks, Bonds, and Cash classes provide the specialization required for each type of asset.



Assets Class

The Assets class:

- Derives directly from matlab.mixin.Heterogeneous
- Is the root of the heterogeneous hierarchy
- Is abstract
- Is the class of heterogeneous arrays composed of any mixture of Stock, Bond, and Cash objects

Properties

The Assets class defines two properties:

- Description A general description of the individual asset constrained to be of class char.
- Type The type of asset defined as an abstract property that each subclass implements.

Methods

The Assets class defines these methods:

- pie A sealed method that creates a pie chart showing the relative mix of asset types.
- makeReport A sealed method that creates a report listing the assets.
- getCurrentValue An abstract method that each concrete subclass must implement to return the current value of the asset.
- getDefaultScalarElement matlab.mixin.Heterogeneous class method overridden in the Assets class to specify a default object. The Assets class is abstract so it cannot be used as the default object. For more information, see "Default Object" on page 20-9.

Methods in Heterogeneous Hierarchies

Methods defined by the Assets class are either:

- Concrete methods (fully implemented) that subclasses do not override
- Abstract methods (signatures only) that subclasses implement

Concrete methods defined by superclasses in a heterogeneous hierarchy must specify the Sealed attribute. Sealing these methods prevents subclasses from overriding methods implemented by the superclass. When calling methods on a heterogeneous array, MATLAB calls the methods defined by the class of the array (Assets in this example).

The pie and makeReport methods are examples of sealed methods that operate on heterogeneous arrays composed of Stock, Bond, and Cash objects.

Abstract methods defined by the superclasses in a heterogeneous hierarchy must specify the Abstract attribute. Defining an abstract method in a superclass ensures that concrete subclasses have an implementation for that exact method name. Use these methods element-wise so that each object calls its own method.

The getCurrentValue method is an example of an abstract method that is implemented by each subclass to get the current value of each asset.

Each type of subclass object calculates its current value in a different way. If you add another category of asset by adding another subclass to the hierarchy, this class must implement its own

version of a getCurrentValue method. Because all subclasses implement a getCurrentValue method, the pie and makeReport methods work with newly added subclasses.

For more information on the Sealed and Abstract method attributes, see "Method Attributes" on page 9-4.

Assets Class Code

The Assets class and other classes in the hierarchy are contained in a namespace called financial.

```
classdef Assets < matlab.mixin.Heterogeneous</pre>
   % file: +financial/@Assets/Assets.m
   properties
      Description char = 'Assets'
   properties (Abstract, SetAccess = private)
      Type
   end
   methods (Abstract)
      % Not implemented by Assets class
      value = getCurrentValue(obj)
   end
   methods (Static, Sealed, Access = protected)
      function defaultObject = getDefaultScalarElement
         defaultObject = financial.DefaultAsset;
   end
   methods (Sealed)
      % Implemented in separate files
      % +financial/@Assets/pie.m
      % +financial/@Assets/makeReport.m
      pie(assetArray)
      makeReport(assetArray)
   end
end
```

For code listings for pie and makeReport, see "Operating on an Assets Array" on page 20-11.

Stocks Class

The Stocks class represents a specific type of financial asset. It is a concrete class that implements the abstract members defined by the Assets class, and defines class properties and methods specific to this type of asset.

Properties

The Stocks class defines these properties:

- NumShares The number of shares held for this asset.
- Symbol The ticker symbol corresponding to this stock.
- Type Stocks class implementation of the abstract property defined by the Assets class. This
 concrete property must use the same attributes as the abstract version (that is, SetAccess
 private).

• SharePrice — Dependent property for the price per share. The get.SharePrice method obtains the current share price from web services when this property is queried.

Methods

The Stocks class defines these methods:

- Stocks The constructor assigns property values and supports a default constructor called with no input arguments.
- getCurrentValue This method is the Stocks class implementation of the abstract method defined by the Assets class. It returns the current value of this asset.
- get.SharePrice The property get method for the dependent SharePrice property returns the current share price of this stock. For information on how to access web services from MATLAB, see the webread function.

Stocks Class Code

```
classdef Stocks < financial.Assets</pre>
   properties
      NumShares double = 0
      Symbol string
   properties (SetAccess = private)
      Type = "Stocks"
   properties (Dependent)
      SharePrice double
   methods
      function sk = Stocks(description, numshares, symbol)
         if nargin == 0
            description = '';
            numshares = 0;
            symbol = '';
         end
         sk.Description = description;
         sk.NumShares = numshares;
         sk.Symbol = symbol;
      function value = getCurrentValue(sk)
         value = sk.NumShares*sk.SharePrice;
      end
      function pps = get.SharePrice(sk)
         % Implement web access to obtain
         % Current price per share
         % Returning dummy value
         pps = 1;
      end
   end
end
```

Bonds Class

The Bonds class represents a specific type of financial asset. It is a concrete class that implements the abstract members defined by the Assets class and defines class properties and methods specific to this type of asset.

Properties

The Bonds class defines these properties:

- FaceValue Face value of the bond.
- Yield Annual interest rate of the bond.
- Type Bonds class implementation of the abstract property defined by the Assets class. This
 concrete property must use the same attributes as the abstract version (that is, SetAccess
 private).
- CurrentYield Dependent property for the current yield, The get.CurrentYield property get method obtains the value from web services.

Methods

The Bonds class defines these methods:

- Bonds The constructor assigns property values and supports a default constructor called with no input arguments.
- getCurrentVlaue This method is the Bonds class implementation of the abstract method defined by the Assets class. It returns the current value of this asset.
- get.CurrentYield The property get method for the dependent CurrentYield property returns the current yield on this bond. For information on how to access web serviced from MATLAB, see the webread function.

Bonds Class Code

```
classdef Bonds < financial.Assets</pre>
   properties
      FaceValue double = 0
      Yield\ double = 0
   properties (SetAccess = private)
      Type = "Bonds"
   end
   properties (Dependent)
      CurrentYield double
   end
   methods
      function b = Bonds(description, facevalue, yield)
         if nargin == 0
            description = '';
            facevalue = 0;
            yield = 0;
         end
         b.Description = description;
         b.FaceValue = facevalue;
         b.Yield = yield;
      end
      function mv = getCurrentValue(b)
         y = b.Yield;
         cy = b.CurrentYield;
         if cy <= 0 || y <= 0
            mv = b.FaceValue;
         else
            mv = b.FaceValue*y/cy;
```

```
end
end
function r = get.CurrentYield(b)
% Implement web access to obtain
% Current yield for this bond
% Returning dummy value
    r = 0.24;
end
end
end
```

Cash Class

The Cash class represents a specific type of financial asset. It is a concrete class that implements the abstract members defined by the Assets class and defines class properties and methods specific to this type of asset.

Properties

The Cash class defines these properties:

- Amount The amount of cash held in this asset.
- Type Cash class implementation of the abstract property defined by the Assets class. This
 concrete property must use the same attributes as the abstract version (that is, SetAccess
 private).

Methods

The Cash class defines these methods:

- Cash The constructor assigns property values and supports a default constructor called with no input arguments.
- getCurrentValue This method is the Cash class implementation of the abstract method defined by the Assets class. It returns the current value of this asset.
- save This method adds the specified amount of cash to the existing amount and returns a new Cash object with the current amount.
- spend This method deducts the specified amount from the current amount and returns a new Cash object with the current amount.

Cash Class Code

```
classdef Cash < financial.Assets
  properties
    Amount double = 0
  end
  properties (SetAccess = private)
    Type = "Cash"
  end
  methods
    function c = Cash(description,amount)
    if nargin == 0
        description = '';
        amount = 0;
  end</pre>
```

```
c.Description = description;
         c.Amount = amount;
      end
      function value = getCurrentValue(c)
         value = c.Amount;
      end
      function c = save(c,amount)
         newValue = c.Amount + amount;
         c.Amount = newValue;
      function c = spend(c,amount)
         newValue = c.Amount - amount;
         if newValue < 0</pre>
            c.Amount = 0;
            disp('Your balance is $0.00')
            c.Amount = newValue;
         end
      end
   end
end
```

Default Object


The design of this class hierarchy uses an abstract root class (Assets). Therefore, the Assets class must specify a concrete class to use as a default object by overriding getDefaultScalarElement. In this case, options include:

- Use one of the existing concrete classes for the default object.
- Define a concrete class in the hierarchy to use for the default object.

This implementation adds the **DefaultAsset** class to the hierarchy as a subclass of the **Assets** class. MATLAB creates objects of this class when:

- Creating arrays using indexed assignment with gaps in index numbers
- Loading heterogeneous arrays from MAT-files when MATLAB cannot find the class of an array element.

This diagram shows the addition of the DefaultAsset class:



DefaultAsset Class Code

```
end
methods
   function obj = DefaultAsset
     obj.Description = 'Place holder';
   end
   function value = getCurrentValue(~)
     value = 0;
   end
end
end
```

Operating on an Assets Array

The Assets class defines these methods to operate on heterogeneous arrays of asset objects:

- pie Creates a pie chart showing the mix of asset types in the array.
- makeReport Uses the MATLAB table object to display a table of asset information.

To operate on a heterogeneous array, a method must be defined for the class of the heterogeneous array and must be sealed. In this case, the class of heterogeneous arrays is always the Assets class. MATLAB does not use the class of the individual elements of the heterogeneous array when dispatching to methods.

makeReport Method Code

The Assets class makeReport method builds a table using the common properties and getCurrentValue method for each object in the array.

```
function makeReport(obj)
   numMembers = length(obj);
   descs = cell(1,numMembers);
   types(numMembers) = "";
   values(numMembers) = 0;
   for k = 1:numMembers
      descs{k} = obj(k).Description;
      types(k) = obj(k).Type;
      values(k) = obj(k).getCurrentValue;
   end
   t = table;
   t.Description = descs';
   t.Type = types';
   t.Value = values';
   disp(t)
end
```

The Assets class pie method calls the getCurrentValue method element-wise on objects in the array to obtain the data for the pie chart.

pie Method Code

```
function pie(assetArray)
  stockAmt = 0; bondAmt = 0; cashAmt = 0;
  for k=1:length(assetArray)
    if isa(assetArray(k), 'financial.Stocks')
        stockAmt = stockAmt + assetArray(k).getCurrentValue;
    elseif isa(assetArray(k), 'financial.Bonds')
```

```
bondAmt = bondAmt + assetArray(k).getCurrentValue;
      elseif isa(assetArray(k), 'financial.Cash')
         cashAmt = cashAmt + assetArray(k).getCurrentValue;
      end
   end
   k = 1;
   if stockAmt ~= 0
      label(k) = {'Stocks'};
      pieVector(k) = stockAmt;
      k = k + 1:
   if bondAmt ~= 0
      label(k) = {'Bonds'};
      pieVector(k) = bondAmt;
      k = k + 1;
   end
   if cashAmt ~= 0
      label(k) = {'Cash'};
      pieVector(k) = cashAmt;
   pie(pieVector, label)
   tv = stockAmt + bondAmt + cashAmt;
   stg = {['Total Value of Assets: $',num2str(tv,'%0.2f')]};
   title(stg,'FontSize',10)
end
Folders and Files
Asset class:
+financial/@Assets/Assets.m
+financial/@Assets/makeReport.m
+financial/@Assets/pie.m
Stocks class:
+financial/@Stocks/Stocks.m
Bonds class:
+financial/@Bonds/Bonds.m
Cash class:
+financial/@Cash/Cash.m
DefaultAsset class:
+financial/@DefaultAsset/DefaultAsset.m
```


Create an Assets Array

These statements create a heterogeneous array by concatenating the Stocks, Bonds, and Cash objects. Calling the makeReport and pie methods creates the output shown.

```
s = financial.Stocks('Acme Motor Company',100,string('A'));
b = financial.Bonds('3 Month T',700,0.3);
c(1) = financial.Cash('Bank Account',500);
c(2) = financial.Cash('Gold',500);
```

assetArray = [s,b,c];
makeReport(assetArray)
pie(assetArray)

Description		Туре	Value
{'Acme Motor Company {'3 Month T' {'Bank Account' {'Gold'	' } } }	"Stock" "Bonds" "Cash" "Cash"	1232.5 875 500 500
(,		



See Also

Related Examples

- "Designing Heterogeneous Class Hierarchies" on page 10-19
- "Validate Property Values" on page 8-19
- "Get and Set Methods for Dependent Properties" on page 8-43