

GIÁM SÁT WINDOWS

- Thực hiện trên Graylog Server
- Chỉnh port allow port trên OS của graylog nếu cần
- Các Event phổ biến và ý nghĩa
 - Liên quan đến Remote Desktop

Event	Mục đích
4624	Login thành công
4625	Login thất bại
4634 / 4647	Đăng xuất hoặc ngắt kết nối (Logoff)
4778	Kết nối lại vào phiên RDP cũ (Session Reconnected)

- Các Event phổ biến khác và ý nghĩa

Event	Mục đích
4624	Login thành công
4625	Login thất bại
4672	Admin privilege
4740	Account bị lock
4720	Tạo user
4726	Xóa user
4732	Thêm user vào local group
4728	Thêm vào domain group
4738	User account changed
5136	AD object modified
5140	Network share access
1102	Clear Security Log (dấu hiệu xóa log)
4688	Process Creation (chạy file/process)

1. Khởi tạo Input

```
System
→ Inputs
→ Select input
→ Beats
```

- Launch new input
- Đặt tên
- Port: 5044
- bind_address: 0.0.0.0

Đảm bảo input vừa tạo **RUNNING**.

graylog Search Streams Alerts Dashboards Enterprise Security

1 System / Inputs 2

Inputs

Graylog nodes accept data via inputs. Launch or terminate as many inputs as you want here.

Beats 3 Launch new input 4 and more inputs

Launch new Beats input

5 ☒ Global

Should this input start on all nodes

Title

vck_Windows-DC-Beats

Bind address

0.0.0.0

Address to listen on. For example 0.0.0.0 or 127.0.0.1.

Port

5044

Port to listen on.

Receive Buffer Size (optional)

1048576

6

vck_Windows-DC-Beats Beats (6a3f4c91b0e1b8458205b9d5) 1 RUNNING 7

bind_address: 0.0.0.0
charset_name: UTF-8
no_beats_prefix: false
number_worker_threads: 8
override_source: <empty>
port: 5044

1.1 Sửa docker-compose.yml

- Thêm dòng - "5044:5044/tcp" vào file bên dưới ports:

```
cd /opt/graylog-stack
sudo nano docker-compose.yml
```

```
GRAYLOG_LOG_DIR: /usr/share/graylog/data/log
GRAYLOG_TELEMETRY_ENABLED: "false"
ports:
  - "${GRAYLOG_HTTP_PORT}:9000"
  - "${GRAYLOG_SYSLOG_UDP_PORT}:1514/udp"
  - "${GRAYLOG_SYSLOG_UDP_PORT}:1514/tcp"
  - "${GRAYLOG_GELF_UDP_PORT}:12201/udp"
  - "${GRAYLOG_GELF_UDP_PORT}:12201/tcp"
  - "# Windows Sidecar Beats"
  - "5044:5044/tcp"
```

- Restart stack & kiểm tra

```
sudo docker compose down
sudo docker compose up -d

sudo docker ps
```

```
sadmin@graylog-pro:/opt/graylog-stack$
sadmin@graylog-pro:/opt/graylog-stack$ sudo docker compose down
[+] down 4/4
✓ Container graylog Removed
✓ Container graylog-opensearch Removed
✓ Container graylog-mongodb Removed
✓ Network graylog-stack_graylog-net Removed
sadmin@graylog-pro:/opt/graylog-stack$ sudo docker compose up -d
[+] up 4/4
✓ Network graylog-stack_graylog-net Created
✓ Container graylog-opensearch Healthy
✓ Container graylog-mongodb Healthy
✓ Container graylog Started
sadmin@graylog-pro:/opt/graylog-stack$
```

Port MobaXterm by subscribing to the professional edition here: <https://mobaxterm.mobatek.net>

1.2 Kiểm tra port 5044

```
tnc -ComputerName 192.168.0.111 -Port 5044
```

```
PS C:\Windows\system32> tnc -ComputerName 192.168.0.111 -Port 5044
```

```
ComputerName      : 192.168.0.111
RemoteAddress     : 192.168.0.111
RemotePort        : 5044
InterfaceAlias    : Ethernet 3
SourceAddress     : 192.168.0.46
TcpTestSucceeded  : True
```

Chú ý:

- Đảm bảo port 5044 phải được mở mới làm tiếp các bước khác

2. Generate API key

System
→ Sidecars
→ Configuration
→ Create or reuse a token for the graylog-sidecar user

→ Đặt tên → Copy

Chú ý:

- Lấy token này qua điền vào file sidecar.yml bên máy Sender

3. Tạo Collector Configuration

The screenshot shows the 'Collector Configuration' page in Graylog. It has a navigation bar with 'Overview', 'Administration', 'Configuration' (highlighted with a red box and a red circle with the number 1), and 'Error Tracking'. The main title is 'Collector Configuration' with a subtitle 'Some words about collector configurations.' Below this, there are several sections: 'Name' (with a text input field containing 'vck_FS_DC-SERVER-FILEBEAT-CONFIG' and a red circle with the number 2), 'Configuration color' (with a blue color picker and a 'Change color' button), 'Configuration Assignment Tags' (with a 'Choose tags...' button), 'Collector' (with a dropdown menu showing 'winlogbeat on Windows'), and 'Configuration' (with a text area containing a YAML configuration file, highlighted with a red box and a red circle with the number 3). A yellow dashed arrow points from the 'Configuration' section to the text 'Nội dung file cấu hình' (Content of the configuration file).

Overview Administration **Configuration** Error Tracking

Collector Configuration

Some words about collector configurations.

Name

vck_FS_DC-SERVER-FILEBEAT-CONFIG

Required. Name for this configuration

Configuration color

Change color

Choose a color to use for this configuration.

Configuration Assignment Tags

Choose tags...

Sidecars which are configured with a matching tag will automatically receive this configuration.

Collector

winlogbeat on Windows

Note: Log Collector cannot change while the Configuration is in use. the Configuration to test it using another Collector.

Configuration

```
1 # Needed for Graylog
2 fields_under_root: true
3 fields_collector_node_id: ${sidecar.nodeName}
4 fields_gli_source_collector: ${sidecar.nodeId}
5
6
7 output.logstash:
8   hosts: ["${user.graylog_host}:5044"]
9
10 path:
11   data: ${sidecar.spoolDir! "C:\\Program Files\\Graylog\\sidecar\\cache\\winlogbeat"}\\data
12   logs: ${sidecar.spoolDir! "C:\\Program Files\\Graylog\\sidecar"}\\logs
13
14 tags:
15   - windows
16   - domain-controller
```

- Nội dung config tham khảo file [Sample-Config.YAML](#)

Chú ý (Sample-Config.YAML):

- Event ID trong file YAML là bộ lọc tối cao. Trên máy Windows có mở bao nhiêu log đi nữa thì cũng chỉ lưu cục bộ ở Event Viewer, còn Graylog chỉ nhận đúng những ID nào được list ra trong file cấu hình thôi.

Collector Configuration Reference

Runtime **1** Variables Reference

Use variables to share text snippets across multiple configurations.
If your configuration format needs to use literals like `${foo}`, which shall not act as a variable, you will have to write it as ``${'S'}{foo}`.

Create Variable

Name	Description	Actions
<code>\${user.graylog_host}</code>	Graylog Host.	2 Delete Edit

Edit Variable `${user.graylog_host}`

Name
graylog_host
Type a name for this variable

Description (Optional)
Graylog Host.
Type a description for this variable

3 Content
192.168.0.111
Write your variable content

Cancel Save

Kiểm tra
đúng IP Graylog
Server chưa

- Quay qua Sender **khởi động lại Graylog Sider**
- Gán Beat-Config cho sender

```
System
→ Sidecars
→ Administration
→ Winlogbeat
→ Assign configurations
→ Chọn Beat config thích hợp và -> Save
```

Collectors Administration

The Graylog collectors can reliably forward contents of log files or Windows EventLog from your servers.

Find sidecars ? Show 10 Rows

1 selected

DC-99.10 a8830bb6-217c-4335-b568-93d35451f59c

☐ filebeat

☒ winlogbeat

☐ nxlog

Edit winlogbeat Configurations
1 sidecar: DC-99.10

Enter search query...

Collector configurations that have a lock icon have been assigned using tags and cannot be changed here

☒ vck_DC-SERVER-FILEBEAT-CONFIG DC-99.10	winlogbeat on Windows
☐ vck_Member_DC-SERVER-FILEBEAT-CO...	winlogbeat on Windows
☐ winlogbeat-default	winlogbeat on Windows

[+ Add a new configuration](#)

Reset Cancel Save

- Done! vào Search để xem

Token

- DC 13e6ga1r0ketbtjn7vdvsjt7ei6s4cv1gvg24bqohamfv2100q65
- vck_Hansoll-Server 1nsf7l0fka61us46c2jb8khrbm4jnd1m2ii1h1pqeubdlc29v1kf