General Optimization



Optimized C++

Ed Keenan

27 October 2019

13.0.6.4.19 Mayan Long Count

Copyright 2019, Ed Keenan, all rights reserved.

DePaul University

Goals

- Everyone is connected
- Easy Way
  - Compilers
  - Money
- Source of inefficiency
- Techniques
  - Loops
  - Logic
  - Strings

General observations



- Everything is interconnected
  - Optimizing on one section, affects others
  - You might shuffle the whole system and make is slower
- Existing architecture might be the biggest challenge.
  - It’s hard to optimized when system isn’t modular or encapsulated
  - Might need to Refactor to make the system clearer

More observations



- Class design
  - Sometime the internal structure of classes and it layout dictate performance
  - Can you swap out routines easy?
  - Is their in-lining opportunities?
  - What is opaque versus observable?

Compilers



- Compilers
  - Huge difference in code performance
  - Intel creates optimal code for Intel processors.
    - How is that possible?
  - Compiler settings
    - Need to be understood and tweaked
- Compilers are smarter than you…
  - Almost, but generally better return for the dollar

Throw Money at it?



- Buy faster and better hardware
  - Is that enough?
- Why isn't my code going twice as fast?
  - I/O, Disc, Networking might be a bottleneck
  - Algorithms don't scale
  - Many processors, code only uses one.
- New systems have more but slower procs
  - Cost savings to manufacture
  - IBM servers…

Line Count?



- Reducing the lines of code, improves speed
  - Many things are happening under the hood.
  - Which is faster?

```
for( i=0; i < 10; i ++)
{
    a[i]=i;
}
```

```
a[0]=0;
a[1]=1;
a[2]=2;
...
a[9]=9;
```

Understand functions



- All operations are not created equally
  - Operating system calls, like copy, read, sort take a very long time.
  - Copy constructors, passing by value are deceiving
- Optimize everything
  - You have limited time and money to work
  - Spend them where it counts
  - Resist premature optimization
  - Later we'll talk about Performance Solution Engineering (PSE) in Week 9

Premature Victory



- Fast program is good enough
  - My program is:
    - 90% or almost working.
    - Practically done
  - Wrong, if it’s not working it’s not optimized.
    - Its generally the edge conditions that hurt clean streamlined code.

Source of Inefficiency



- Input / Output operations
  - Biggest and most evil
    - You have to deal with it.
  - Being clever can reduce it's effects.
    - Only use it if you have to.
  - Ways to improve it
    - Cache copies
    - Stream
    - Layout all help
    - Learn the hardware

Source of Inefficiency



- Memory
  - Yes it comes up everywhere
    - Very slow, we can do better
  - Custom schemes
    - Writing for our use cases
  - Virtual memory manager
    - Transparent but cost time
- Thread and process switching
  - Other heavy system calls
  - They hurt ☹

Source of Inefficiency



- Language choices
  - Compiler vs interpreted
    - Interpreted is roughly 20 times slower
    - There is a place and time for them
    - Not in the most call systems or loops
    - Remember the 80/20 rule
  - Maintenance vs speed
    - Support and readability sometimes get sacrificed for optimization

Source of Inefficiency



- Errors
  - Leaving debug information
  - Not freeing memory
  - Redundantly initializing memory
  - Unnecessary initializations
  - Bugs
  - Do you know what the code is really doing?
  - Many people do not step code or know how

Metrics

- Don’t be a Cowboy or Cowgirl
  - Your spidey sense isn’t that good.
  - Measure everything!
  - Assume nothing!
  - Story about Mips processor

Heisenberg Uncertainty Principle



- By observing the system you affect the results of the system
  - Mexico Story
- Optimizations
  - If you alter one system,
  - The next system might be negatively altered.

Break

- What time is it?
  - I’m Thirsty!!!

Techniques

- Reference:
  - Chapters 25 & 26 of Code Complete 2nd Edition
- Good News – Safari free for DePaul
  - http://proquestcombo.safaribooksonline.com/book/software-engineering-and-development/0735619670



Logic



- Conditionals
  - Early out
  - Reworking conditionals to use
- Does every know their Binary Logic?
  - And, Or, Xor, Not, Xnor,
  - Associative, Commutative, Distributive
  - DeMorgan?
    - !(x+y) = !x & !y
    - Why is this important?

DeMorgan



- Conditionals
  - Evaluation happens from left to right.
- If (x && y)
  - If x if false, no need to evaluate y
  - Early out.
- If (x||y) then …
  - If you can rework the logic to be negative
  - If !(x||y) then …Can use DeMorgan
- If (!x && !y) then …
  - You get the early out ☺

Switching / exiting



- Understand how switch() work!
  - They are implemented under the hood as
  - Many if else…
- Invariants
  - Do not have invariant states inside the loop
  - Only keep statements that change in the loop.
- Sentinals
  - What are they?
    - One time flags inside of loops
  - Evil, check is done every time
    - Move out of loop

Loops



- Combining work inside with same loops
  - Sometimes this is counter intuitive
  - Need to test, caching becomes a big issue
- Unrolling
  - Sometimes helps,
  - some times confuses compilers
- Busiest loop in the inner most loop
  - Multi-nested loops
  - Less loop-context switching

Floats



- Floats vs Integers
  - Floats are good for math
    - Not for indices or conditional testing
  - Integers are great of conditionals and indexing
    - Well kind of?
    - Should not be passed to floating point parameters
- Multi-dimensional arrays are slow
  - Indication of poor design
  - Refactor

Strings



- Strings
  - Very slow to compare and use
  - Get creative, do you really need them?
  - In industry, cause of many slowdowns
  - Often, too embedded in the existing architecture to remove ☹
- MD4 or MD5 quick alternative to strings
  - Allows integer compares
  - Fixed length strings… sound weird?
    - Making all your strings the same length has advantages in processing them.

System Calls



- Understand your system calls
  - Many take doubles, when you need floats.
    - Sqrt() is big offender.
  - Why do people need 64-bit floats when we went to the moon on 16 bit fix point?
- Bit shifts and tricks don’t work anymore.
  - Look at timing and metrics
  - They are implement with slow legacy and often with slow your project down.

Assembler



- Assembler
  - Just like Copernicus
  - You can’t practically do this for the N-stage pipeline in processors, with look ahead and in order executions, cache misses, hyper-threaded context switching, and vectorize embedded coprocessors.
  - We will learn intrinsics operators
    - Like mini micro assembler functions

Thank You!

- Easy?

Memory Overloading



Optimized C++

Ed Keenan

Copyright 2019, Ed Keenan, all rights reserved.

DePaul University

Goals

- Overloading Memory
  - C Functions
    - Malloc / Calloc / Realloc / Free
  - C++
    - New / Delete
  - STL
    - Allocators
- Useful at C++ and OO conventions
  - 1st conversation of the night

C Functions



- Overload standard C Functions
  - Malloc
    - Memory Allocations
  - Calloc
    - Clears the memory it returns for an allocation
  - Realloc
    - Resize allocations
    - Swiss Army Knife of allocations
  - Free
    - Deallocates previous allocations

Know **your Definitions**



- If you overload any function
  - You must know the function's spec inside and out.
  - Users assume same behavior
- Many programmers uses functions that they don't understand
  - ***VERY BAD!*** ☹
  - Take 1 minute and read the Online manual
  - Good References
    - http://www.cplusplus.com/reference/clibrary/cstdlib/
    - http://msdn.microsoft.com/en-us/library/dtefa218%28v=vs.110%29.aspx

Malloc



- Allocate Memory Block
  - void * **malloc** (size_t **size**);
- Definition
  - Allocates a block of size bytes of memory, returning a pointer to the beginning of the block.
  - The content of the newly allocated block of memory is not initialized, remaining with indeterminate values.
- Parameters
  - Size
    - Size in bytes of the allocations
- Return Value
  - On success, a pointer to the memory block allocated by the function.
    - The type of this pointer is always void*, which can be cast to the desired type of data pointer in order to be dereferenceable.
    - If the function failed to allocate the requested block of memory, a ***NULL*** pointer is returned.

Calloc



- Calloc
  - Clears the memory it returns for an allocation
  - What does ***C*** – stands for?
    - ***C****lear* – clears the memory
    - ***C****ount* – uses count in its arguments
    - ***C****ontiguous*, ***C****ore*, ***C****ommit*, ***C****hunk*, and ***C****haracter?*
  - *Early K & R?*
    - **Kernighan & Ritchie – the C Programming Language**
    - *Calloc – "C" language free*
    - *Cfree – "C" language free*

Calloc



- Allocate space for array in memory
  - void * **calloc** (size_t **num**, size_t **size**);
- Definition
  - Allocates a block of memory for an array of *num* elements, each of them *size* bytes long, and initializes all its bits to zero.
  - The effective result is the allocation of an zero-initialized memory block of (*num* * *size*) bytes.
- Parameters
  - num
    - Number of elements to be allocated.
  - size
    - Size of elements.
- Return Value
  - On success, a pointer to the memory block allocated by the function.
    - The type of this pointer is always void*, which can be cast to the desired type of data pointer in order to be dereferenceable.
    - If the function failed to allocate the requested block of memory, a ***NULL*** pointer is returned.

Realloc



- Reallocate memory block
  - void * **realloc** (void * **ptr**, size_t **size**);
- Definition
  - The size of the memory block pointed to by the *ptr* parameter is changed to the *size* bytes, expanding or reducing the amount of memory available in the block.
  - The function *may move* the memory block to a new location, in which case the new location is returned.
  - The content of the memory block is preserved up to the lesser of the new and old sizes, even if the block is moved. If the new *size* is larger, the value of the newly allocated portion is indeterminate.
  - In case that *ptr* is NULL, the function behaves exactly as malloc assigning a new block of *size* bytes and returning a pointer to the beginning of it.
  - In case that the *size* is 0, the memory previously allocated in *ptr* is deallocated as if a call to free was made, and a NULL pointer is returned.

Realloc



- Parameters
  - ptr
    - Pointer to a memory block previously allocated with malloc, calloc or realloc to be reallocated.
    - If this is NULL, a new block is allocated and a pointer to it is returned by the function.
  - size
    - New size for the memory block, in bytes.
    - If it is 0 and *ptr* points to an existing block of memory, the memory block pointed by *ptr* is deallocated and a NULL pointer is returned.
- Return Value
  - A pointer to the reallocated memory block, which may be either the same as the ptr argument or a new location.
  - The type of this pointer is void*, which can be cast to the desired type of data pointer in order to be dereferenceable.
  - If the function failed to allocate the requested block of memory, a NULL pointer is returned.

Free



- Deallocate space in memory
  - void **free** (void * **ptr**);
- Definition
  - A block of memory previously allocated using a call to malloc, calloc or realloc is deallocated, making it available again for further allocations.
  - Notice that this function leaves the value of ptr unchanged, hence it still points to the same (now invalid) location, and not to the null pointer.
- Parameters
  - ptr
    - Pointer to a memory block previously allocated with malloc, calloc or realloc to be deallocated.
    - If a null pointer is passed as argument, no action occurs.
- Return Value
  - (none)

Overloading C Libs



- Process

1. Create macros for your functions
   - #define **memMalloc**(size) **myMallocStdC**(size)
   - Implement macros in terms of your standard C library functions, *malloc(), calloc(), realloc(), free()*
2. Test the function replacement
   - Make sure for every malloc, calloc(), realloc() there is a corresponding free()
   - Look for every pair, If you miss one, bad stuff.
     - A mis-match will occur -> crash ☹

Cont.



3. Replace the Functions with your code
   - #define **memMalloc**(size) **myMalloc**(size)
4. Add file name and line number tracking
   - #define **memMalloc**(size) **myMalloc**(size, __FILE__, __LINE__)
5. Maintain the ability to switch back to std C
   - Useful for debug mode
     - Track performance difference
     - Track behavior or bug difference

Testbed: class Dog

```
class Dog
{
public:
   Dog()
      :a(1),b(2),c(3),d(4)
   {
      printf("Dog(%p): constructor   \n", this );
   };

   ~Dog()
   {
      printf("Dog(%p): destructor\n",this);
   };

public:
   float a;
   float b;
   float c;
   float d;
};
```

- Simple class
  - Has a few variables
  - Print statements in constructor and destructor

Dog Class
How original

Test calls



- ***fido***
  - Creation
    - Instantiated on stack
    - Constructor is called
  - Destruction
    - Leaves scope
    - Destructor is called
- ***p*** – dynamic object
  - Creation
    - Call global new
    - Constructor is called
  - Destruction
    - Call global delete
    - Destructor is called

Code:

```
{
// instatiate on stack
Dog fido;

// create dynamic object
Dog *p = new Dog();

// delete dynamic object
delete p;

// destroy fido (leaving scope)
}
```

Output:

```
// fido()
Dog(0012FF4C): constructor

// *p = new Dog();
Dog(00342950): constructor

// delete p;
Dog(00342950): destructor

// ~fido()
Dog(0012FF4C): destructor
```

Overload in Class

- class Dog
  - Overload new operator
  - Overload delete operator
- operator **new**()
  - Need allocation
  - Allocate memory: malloc(), ***CUSTOM*** function, global new()
  - Constructor is fired off after new operator
  - Calling function doesn't change
- operator **delete**()
  - Destructor is called before this operator
    - Automagic!
  - Release memory: free(), ***CUSTOM*** function, global delete()

```
class Dog
{
public:

   void * operator new( size_t size )
   {
     // create memory space
     void *p = malloc(size);
     // tracking print
     printf(" Overloaded new( %p) \n",p);
     // return the pointer, constructor is called after this operator
     return p;
   };

   void operator delete( void *p )
   {
     // destructor is called first, then enter this operator
     printf(" Overloaded delete(%p) \n",p );
     // release memory
     free(p);
   };
```

Sample



- Transparent
  - Calling function doesn't change
    - Use new the same way as before
    - Instead it calls the overloaded new of the class
  - Only overloads for that specific class
  - Make sure that allocation and deallocation match

Code:

```
{
// instatiate on stack
Dog fido;

// create dynamic object
Dog *p = new Dog();

// delete dynamic object
delete p;

// destroy fido (leaving scope
}
```

Output:

```
// fido()
Dog(0012FF4C): constructor

// *p = new Dog();
Overloaded new( 00342950)
Dog(00342950): constructor

// delete p;
Dog(00342950): destructor
Overloaded delete(00342950)

// ~fido()
Dog(0012FF4C): destructor
```

Same for [ ] operators

```
class Dog
{
public:

   void * operator new[]( size_t size )
   {
     // create memory space
     void *p = malloc(size);
     // tracking print
     printf(" Overloaded new[]( %p) \n",p);
     // return the pointer,
     //constructor is called after this operator
     return p;
   };

   void operator delete[]( void *p )
   {
     // destructor is called first, then enter this operator
     printf(" Overloaded delete[](%p) \n",p );
     // release memory
     free(p);
   };
```

Code:

```
// create dynamic object
Dog *p = new Dog[3]();

// delete dynamic object
delete[] p;
```

Output:

```
// *p = new Dog[3]()

// create memory
Overloaded new[]( 00342950)
// p[0] - constuctor
Dog(00342954): constructor
 // p[1] - constuctor
Dog(00342964): constructor
 // p[2] - constuctor
Dog(00342974): constructor

// delete[] p

// p[2] - destructor
Dog(00342974): destructor
 // p[2] - destructor
Dog(00342964): destructor
// p[2] - destructor
Dog(00342954): destructor
// overload delete[]
Overloaded delete[](00342950)
```

Extra info

- Useful for tracking allocations
  - Can call global new and delete in functions
    - void *p = (void *)::operator **new**(size);
    - ::operator **delete**(p);
  - Add tracking information
  - Behavior doesn't change
- Use custom memory systems
  - This is an easy way to hook up your custom memory systems

Hazards



- Overloading global new
  - issues
- Which new is used?
  - Custom or Libraries?
    - Link order issues
    - Dynamic memory before main() is called
      - Yes it happens…

Hazards



- Fun, fun, fun… ***NOT!***
  - Get very familiar with the linker
    - Up it's verbose warning dialog mode
  - Multiple functions defined
    - Common warnings thrown by linker
  - Control function overloading by controlling link order
    - Easy on some compilers
    - Ridiculously hard on others

Alternatives to Global New



- Create a macro
  - Include in all class declarations
  - Easy to #if out if desired
- Create a memory class
  - Contains overloaded new & delete
  - Publicly inherit to all class declarations

Alternatives to Global New



- Change the calling convention
  - Create your own version of new
    - #define **memNew**(heap) **new**(heap)
  - Add parameters and overload new
    - To extend and change the signature of the function.
    - To avoid collision with global new

STL allocators

- Did you know that STL uses memory?
  - I hope so…
  - You can overload the allocator
- Why is this useful?
  - Use your custom allocator
  - Track memory allocations
  - Be a coolest power programmer in the room
    - Be a code ninja!

Example 1: default allocator

```
//**********************************
// default allocator
//**********************************

cout<<"---- Default allocator ---"<<endl;

std::vector<int> v1;

for( int i=0; i<10; i++)
{
   cout<<" inserting "<<i<<endl;
   // add element to vector
   v1.push_back(i);
}

cout<<"---- DONE ---\n"<<endl;
```

Output

```
---- Default allocator ---
 inserting 0
 inserting 1
 inserting 2
 inserting 3
 inserting 4
 inserting 5
 inserting 6
 inserting 7
 inserting 8
 inserting 9
---- DONE ---
```

- Calls global new/delete for allocation
- What's happening?
  - How many allocations and deletions are there?
  - How many times are the data structures copied?

Example 2: custom allocator



Console

```
---- Custom ---
inserting 0
inserting 1
inserting 2
inserting 3
inserting 4
inserting 5
inserting 6
inserting 7
inserting 8
inserting 9
---- DONE ---
```

```
//*************************************
// custom allocator
//*************************************
{
cout<<"---- Custom allocator ---"<<endl;

std::vector< int, logging_allocator<int> > v2;

for( int i=0; i<10; i++)
{
   cout<<" inserting "<<i<<endl;
   v2.push_back(i);
}

cout<<"\n---- DONE ---\n"<<endl;
}
```

Output

```
1.  allocate() addr: 0x003B8328  num: 1  totalSize: 4
2.  allocate() addr: 0x003B95B0  num: 2  totalSize: 8
3.  dealloc() addr: 0x003B8328
4.  allocate() addr: 0x003B8328  num: 3  totalSize: 12
5.  dealloc() addr: 0x003B95B0
6.  allocate() addr: 0x003B95B0  num: 4  totalSize: 16
7.  dealloc() addr: 0x003B8328
8.  allocate() addr: 0x003B8328  num: 6  totalSize: 24
9.  dealloca() addr: 0x003B95B0
10. allocate() addr: 0x003B95B0  num: 9  totalSize: 36
11. dealloc() addr: 0x003B8328
12. allocate() addr: 0x003B9610  num: 13  totalSize: 52
13. dealloc() addr: 0x003B95B0
14. // leaving scope
15. dealloc() addr: 0x003B9610
```

- 7 allocations and deletions
- 6 separate copies of elements

Example 3: with Reserve



```
//*****************************************
// custom allocator with reserve()
//*****************************************
{
cout<<"---- Reserve Custom allocator ---"<<endl;

std::vector< int, logging_allocator<int> > v3;
v3.reserve(10);
for( int i=0; i<10; i++)
{
   cout<<" inserting "<<i<<endl;
   v3.push_back(i);
}

cout<<"---- DONE ---\n"<<endl;
}
```

Output

1. allocate() addr: 0x003B95B0 num: 10 totalSize: 40
2. dealloc() addr: 0x003B95B0

- Using Reserve saved 6 allocations and deletions
- Easy to track and monitor

Use Allocators:
To Understand STL containers



```
std::vector< data, logging_allocator<data> > v2;

for( int i=0; i<30; i++)
{
        fprintf(io::getHandle(), "inserting by push back: %d\n", i);
        v2.push_back(i);
}
```

```
inserting by push back: 0
  allocate() addr 0x003B9270  num: 1
inserting by push back: 1
  allocate() addr 0x003B92B0  num: 2
  deallocate() addr 0x003B9270
inserting by push back: 2
  allocate() addr 0x003B92F8  num: 3
  deallocate() addr 0x003B92B0
inserting by push back: 3
  allocate() addr 0x003B9270  num: 4
  deallocate() addr 0x003B92F8
inserting by push back: 4
  allocate() addr 0x003B92C0  num: 6
  deallocate() addr 0x003B9270
inserting by push back: 5
inserting by push back: 6
  allocate() addr 0x003B9318  num: 9
  deallocate() addr 0x003B92C0
inserting by push back: 7
inserting by push back: 8
inserting by push back: 9
  allocate() addr 0x003B9270  num: 13
  deallocate() addr 0x003B9318
inserting by push back: 10
inserting by push back: 11
inserting by push back: 12
inserting by push back: 13
  allocate() addr 0x003B92E0  num: 19
  deallocate() addr 0x003B9270
inserting by push back: 14
inserting by push back: 15
inserting by push back: 16
inserting by push back: 17
inserting by push back: 18
inserting by push back: 19
  allocate() addr 0x003B9368  num: 28
  deallocate() addr 0x003B92E0
inserting by push back: 20
inserting by push back: 21
```

v2.size(): 22

v2.capacity(): 28

STL Methods



Starting with a 10 element vector:

// understanding -> v.clear()

v2.size(): 10
v2.capacity(): 13
v2.clear()

~data(02D62C90) - destructor
~data(02D62C94) - destructor
~data(02D62C98) - destructor
~data(02D62C9C) - destructor
~data(02D62CA0) - destructor
~data(02D62CA4) - destructor
~data(02D62CA8) - destructor
~data(02D62CAC) - destructor
~data(02D62CB0) - destructor
~data(02D62CB4) - destructor
dealloc(0x0013F54C) addr 0x02D62C90 num: 13

v2.size(): 0
v2.capacity(): 0 now its in 13 C++11 spec…

Starting with a 10 element vector:

// understanding -> v.erase()

v2.size(): 10
v2.capacity(): 13
v2.erase()

~data(02D62C90) - destructor
~data(02D62C94) - destructor
~data(02D62C98) - destructor
~data(02D62C9C) - destructor
~data(02D62CA0) - destructor
~data(02D62CA4) - destructor
~data(02D62CA8) - destructor
~data(02D62CAC) - destructor
~data(02D62CB0) - destructor
~data(02D62CB4) – destructor

v2.size(): 0
v2.capacity(): 13

Start Trek 2: Wrath of Khan



- The gold standard (10/10)
  - All movies are compared to this movie
    - Gone with the Wind
    - Lawrence of Arabia

Star Wars: Empire Strikes back

- 6/10 on Khan scale.

Matrix:

- 7/10 on the Khan scale

Wizard of Oz

- 7/10 (flying blue monkeys)

Allocator



- Uses _Allocate() function to allocate memory.
  - This function calls new
  - Can be replace with your custom allocation
- STL allocation overloading is 9/10 on the Geek scale
  - Very few people have done it.
  - Ask around.

STL Allocator – Wrath of Khan



```
using namespace std;

template< typename T, typename Allocator = allocator<T> >
class logging_allocator
{
private:
        Allocator alloc;

public:
    typedef typename Allocator::size_type          size_type;
    typedef typename Allocator::difference_type    difference_type;
    typedef typename Allocator::pointer            pointer;
    typedef typename Allocator::const_pointer      const_pointer;
    typedef typename Allocator::reference          reference;
    typedef typename Allocator::const_reference    const_reference;
    typedef typename Allocator::value_type         value_type;

    // magic - you need the rebind....
    template <typename U> struct rebind
    {
        typedef logging_allocator<U, typename Allocator::template rebind<U>::other > other;
    };
```

Khan part 2/3

```
// default
logging_allocator()
{           };

// copy constructor
logging_allocator( const logging_allocator &x)
            : alloc(x.alloc)
{           };

// overloaded constructor
template <typename U>
            logging_allocator( const logging_allocator<U,
typename Allocator::template rebind<U>::other> &x)
            :alloc(x.alloc) {};

// destructor
~logging_allocator(){};

// return the address of the allocation
pointer address( reference x ) const
{
            return alloc.address(x);
};

// return the constant address to the allocation
const_pointer address(const_reference x) const
{
            return alloc.address(x);
};
```

```
// return the max size
size_type max_size() const
{
            return alloc.max_size();
}

// effectively operator new
void construct( pointer p, const value_type &val)
{
            alloc.construct(p, val);
}

// effectively destructor with deletion of allocation
void destroy(pointer p)
{
            alloc.destroy(p);
}

// malloc
pointer allocate(size_type n, const void *hint = 0 )
{
            pointer result = alloc.allocate(n,hint);
            stl_mem_track tmp;
            fprintf(io::getHandle()," allocate() addr 0x%p  num:
%d  \n",result, n);
            return result;
};
```

Khan 3/3

```
        // free
        void deallocate(pointer p, size_type n)
        {
                stl_mem_track tmp;
                fprintf(io::getHandle(),"deallocate() addr 0x%p  \n",p );
                alloc.deallocate(p,n);
        };
};

        template < typename T, typename Allocator1, typename U, typename Allocator2 >
        bool operator == ( const logging_allocator<T, Allocator1>& x, const logging_allocator<U, Allocator2>& y)
                {
                        return x.alloc == y.alloc;
                };

        template <typename T, typename Allocator1, typename U, typename Allocator2>
        bool operator != ( const logging_allocator<T, Allocator1> &x, const logging_allocator<U, Allocator2> &y)
                {
                        return x.alloc != y.alloc;
                };
```

Great book to learn STL

- This is my main reference for STL
  - STL Tutorial and Reference Guide.
- From scratch to overloading
  - Khan's memory overloading came from this book



Great book to master STL

- Another good reference
  - Effective STL
    - Scott Meyers
      - (He has good hair)
- Many interview questions are STL related
  - You will use STL a lot, master it



The Bible of Templates

- Template book
  - Hard core templates material
  - A lot there to master
  - Take a look



Thank You!

- Questions?

Particle Review

Optimized C++

Ed Keenan

16 May 2018

13.0.5.8.12 Mayan Long Count

DePaul University

Goals

- Particle system review
  - What it does
  - How to Use it
- Explain areas of interest
- Optimization ideas
- Project Deliverables
  - Competition times
  - Logs
- Contest
  - Compare on the same machine.

Who will win?

Keep a log



- Logs are Good!
  - Keep a work log of the tasks your are doing.
  - It's easy to track your progress
  - Leaves you notes on what you did and how much it helped
  - Leaves bread crumbs for partial credit. ☺
- Logs are Easy to do!
  - Open up a text file or word doc and go.
    - Changelist anyone???
  - Updates take 1-3 minutes
  - Do them after each major refactor
  - Do them at the end of the day

Keep a log



- Changelist: 90863 (Saturday Nov 5) *date stored in changelist automatically*
  - Added const to Vect4D
    - Saved 0.25 ms in release
  - Reworked Matrix to use references instead of pointer
    - Saved 0.05 ms in release
  - Added += operator in Vect4D
    - Reworked code to use this everywhere
    - Save 0.1 ms in release

- Changelist: 90872 (Monday Nov 12)
  - Added SIMD to Vect4D
    - Saved 2.5 ms
  - Cursed Keenan's Name out loud
    - His comments in code were wrong
      - Chased a red herring for 4 hours
      - I'll get him
  - I love Linker errors
    - Sutter come-on give a little more help.

General Ideas…



- Make constant
  - Add ***const*** everywhere
    - Function parameters
    - Constant methods
- Convert pointers to ***references***
  - Gives compiler more options
  - Removes pointer safety checks
- Remove Temporaries
  - Use **+=, -=, *=, /=** operators
  - Remember they remove temps

Things to look for…



- Look for invariants
  - Stuff that doesn’t change from loop to loop
    - Remove it
- Look for useless work
  - Remove it
- Dynamic memory timings
  - Is it worth replacing

Containers and Operators



- STL containers
  - Vector
    - Is that the best container
    - Do you need containers
    - Are they being used correctly
- Must overload operators
  - Default constructor
  - Copy Constructor
  - Assignment operator
  - Destructor

Time large sections



- Time groups and parts of the program
  - Leave Timers in while you develop
- Use #if to enable multiple metrics at a time
  - Control groups of timers with a switch
- Everything changes when you refactor a section.
  - There are side effects.
- Let the data drive you
  - Not your gut feeling or what you read.
  - Timers are KING

Guidelines



- Level Warning ALL
  - Compiles cleanly in Debug and Release
- Timing
  - Need timing metrics for both configurations
  - Need original timing before any modifications
    - Turn off all extra programs on your PC when timing.
- Back up often with notes
  - Use version control
- Logs
  - Turn in Logs every week

Refactoring

- What is it?
- Who has experience with it?
- Do you really understand the principles?



Refactoring



- Definition:
  - *Process of changing a software system in such a way that it does not alter the external behavior of the code yet improves its internal structure*.
- Improving a design after it's written

What do you Refactor



- For Maintenance reasons
  - Support
  - Development
  - Enhancements
- Architecture Improvements
- Optimizations

Why should you Refactor



- Improves the design of software
- Makes software easier to understand
- Helps you find bugs
- Help you program faster

Rules of the road



- Refactoring changes the programs in small steps.
  - If you make a mistake, its easy to find the bug.
- When you add a feature,
  - Refactor program to make it easier to add the feature.
- Testing is key
  - Make sure the system is understood and well tested, BEFORE you refactor

Important

- Any fool can write code….
  - Good programmers write code that humans understand.

Rule of three



- Three strikes and you refactor
  - Refactor when you add function
  - Refactor when you need to fix a bug
  - Refactor as you do a code review

Bad Smells in Code



- If it stinks, Change it.
  - - Grandma Beck,
    - Discussing child-rearing philosophy

Common Smells

- Duplicated Code
- Long Method
- Large Class
- Long Parameter List
- Divergent Change
- Shotgun Surgery
- Feature Envy
- Data Clumps
- Primitive Obsession
- Switch Statements
- Parallel Inheritance Hierarchies
- Lazy Class
- Speculative Generality

More smells

- Temporary Field
- Message Chains
- Middle Man
- Inappropriate Intimacy
- Alt classes with different interfaces
- Incomplete library class
- Data class
- Refused Bequest
- Comments

Tests



- Yes
- Have some…

Thank You!

- Questions?