JEUS SNMP 안내서



Copyright Notice

Copyright©2005 Tmax Soft Co., Ltd. All Rights Reserved.

Tmax Soft Co., Ltd

대한민국 서울시 강남구 대치동 946-1 글라스타워 18층 우)135-708

Restricted Rights Legend

This software and documents are made available only under the terms of the Tmax Soft License Agreement and may be used or copied only in accordance with the terms of this agreement. No part of this document may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, or optical, without the prior written permission of Tmax Soft Co., Ltd.

소프트웨어 및 문서는 오직 TmaxSoft Co., Ltd.와의 사용권 계약 하에서만 이용이 가능하며, 사용권 계약에 따라서 사용하거나 복사 할 수 있습니다. 또한 이 매뉴얼에서 언급하지 않은 정보에 대해서는 보증 및 책임을 지지 않습니다.

이 매뉴얼에 대한 권리는 저작권에 보호되므로 발행자의 허가 없이 전체 또는 일부를 어떤 형식이나, 사진 녹화, 기록, 정보 저장 및 검색 시스템과 같은 그래픽이나 전자적, 기계적 수단으로 복제하거나 사용할 수 없습니다.

Trademarks

Tmax, WebtoB, WebT, and JEUS are registered trademarks of Tmax Soft Co., Ltd.

All other product names may be trademarks of the respective companies with which they are associated.

Tmax, WebtoB, WebT, JEUS 는 TmaxSoft Co., Ltd 의 등록 상표입니다.

기타 모든 제품들과 회사 이름은 각각 해당 소유주의 상표로서 참조용으로만 사용됩니다.

Document info

Document name: JEUS SNMP 안내서

Document date: 2005-06-06 Manual release version: 3 Software Version: JEUS 5

차 례

1	소개		. 13
2	따라	하기	. 15
3	JEUS	SNMP Agent 의 개요	. 21
	3.1	소개	21
	3.2	JEUS SNMP Agent 특성	21
	3.3	JEUS SNMP Agent 컴포넌트	22
	3.4	JEUS SNMP Agent 아키텍처	23
	3.5	SNMP Agent	. 23
	3.6	SNMP Manager 애플리케이션	24
	3.7	결론	24
4	SNM	P Agent 의 설정	25
5		S SNMP 프로그래밍	
	5.1	소개	
	5.2	간단한 SNMP 클라이언트 프로그램	27
	5.3	결론	32
6	JEUS	S SNMP MIB	33
	6.1	소개	
	6.2	MIB 브라우징	33
	6.3	객체 식별(OID)	33
	6.4	JEUS SNMP OID 접미어	34
7	결론		37
A	JEUS	SNMP MIB 참조	39
	A.1	소개	
	A.2	목적	39
	A.3	OID 와 속성값의 매핑	39
	A.4	TMAX-JEUS5.0-MIB.mib	. 60

JEUS SNMP 안내서

В	JEUSMain.xml 의 XML 환경 설정 레퍼런스		215
	B.1	소개	215
	B.2	XML Schema/XML Tree	216
	B.3	Element Reference	216
색 약	ો		219

그림목차

그림 1.	JEUS SNMP Agent 아키텍처	.3
그림 2	JEUS MIB 의 OID3	4

매뉴얼에 대해서

매뉴얼의 대상

본 매뉴얼은 JEUS 시스템 관리자와 SNMP 를 사용하여 JEUS 를 모니터링 하려는 네트웍 관리자 및 개발자를 대상으로 한다.

매뉴얼의 전제 조건

- 이 매뉴얼을 읽기 전에 두 가지 전제 조건이 있다.
 - 1. 첫째, JEUS Server 안내서를 읽고 이해해야 한다.
 - 2. 둘째, 일반적인 SNMP 애플리케이션을 개발에 대해 알고 있어야 한다. 그렇지 못하다면 우선 SNMP 스펙에 대한 자료(http:// java.sun.com 또는 http://www.ietf.org/rfc.html 참조)나 관련 서적을 참조하기 바라다.

참조: 본 매뉴얼은 J2EE 나 SNMP 에 대한 기본적인 내용에 대해서는 설명하지 않는다.

문서 구조

이 매뉴얼은 다음과 같이 7 장의 본문과 2 장의 부록으로 구성되어있다.

본문:

- 1. **소개**: 인사말과 개요
- 2. 따라하기: 예제를 가지고 단계별로 시작하기
- 3. **JEUS SNMP Agent 의 개요**: **JEUS SNMP** agent 의 기본적인 개념과 구성
- 4. SNMP Agent 의 설정: SNMP Agent 구성

JEUS SNMP 안내서

- 5. **JEUS SNMP 프로그래밍**: SNMP manager 애플리케이션의 개발
- 6. **JEUS SNMP MIB**: JEUS 에서 사용하는 SNMP MIB 소개.
- 7. 결론

부록:

A JEUS SNMP MIB 참조: MIB 파일에 대한 설명.

B JEUSMain.xml 의 XML 환경 설정 레퍼런스: JEUSMain.xml 의 환경파일을 참조하여 완성.

관련 문서들

관련 문서들:

- 2EE 1.4 스펙.
- J2EE management 1.0 스펙.
- SNMP 스펙.
- JEUS JMX 안내서.

일러두기

표기 예	내 용
텍스트	본문, 12 포인트, 바탕체 Times New Roman
텍스트	본문 강조
CTRL+C	Ctrl 와 동시에 C 를 누름
<pre>public class myClass { }</pre>	_ _ Java 코드

표기 예		내용
	<system-config></system-config>	XML 문서
참조:/주의:		참조 사항과 주의할 사항
Configuratio	n 메뉴를 연다	GUI 의 버튼 같은 컴포넌트
JEUS_HOME	3	JEUS 가 실제로 설치된 디렉토리
		예) c:\jeus5
jeusadmin n	nodename	콘솔 명령어와 문법
[command a	argument]	옵션 파라미터
< xyz >		'<'와 '>' 사이의 내용이 실제 값으로 변경됨
		선택 사항. 예) A B: A 나 B 중 하나
•••		파라미터 등이 반복되어서 나옴
?, +, *		보통 XML 문서에 각각 "없거나, 한 번", "한 번 이상", "없거나, 여러 번" 을 나타낸다.
		XML 이나 코드등의 생략
	< <filename.ext>></filename.ext>	코드의 파일명
Figure 1.		그림 이름 또는 표 이름

OS에 대해서

본 문서는 모든 예제와 환경 구성을 Microsoft Windows™의 스타일을 따랐다. 유닉스와 같은 다른 환경에서 작업하는 사람은 몇가지 사항만 고려하면 별 무리없이 사용할 수 있다. 대표적인 것이 디렉토리 구분자인데, Windows 스타일인 "\"를 유닉스 스타일인 "/"로 바꿔서 사용하면 무리가 없다. 이외에 환경 변수도 유닉스 스타일로 변경해서 사용하면 된다.

그러나 Java 표준을 고려해서 문서를 작성했기 때문에, 대부분의 내용은 동일하게 적용된다.

용어 설명

용어

다음에 소개되는 용어는 본 문서 전체에 걸쳐서 사용되는 용어이다. 용어가 이해하기 어렵거나 명확하지 않을 때는 아래 정의를 참조하기 바란다.

정의

MIB	Management Information Base 의 약어.
OID	MIB 에 의해서 정의된 대상 식별자
SNMP	Simple Network Management Protocol 의 약어.
SNMP agent	SNMP manager 로부터 메시지를 받고 그것의 OID에 대한 정보를 보내는 서버.
SNMP manager	SNMP 로 시스템을 관리하는 애플리케이션.

연락처

Korea

Tmax Soft Co., Ltd

18F Glass Tower, 946-1, Daechi-Dong, Kangnam-Gu, Seoul 135-708

South Korea

Tel: 82-2-6288-2114
Fax: 82-2-6288-2115
Email: info@tmax.co.kr

Web (Korean): http://www.tmax.co.kr

USA

Tmax Soft, Inc.

560 Sylvan Ave, Englewood Cliffs NJ 07632

USA

Tel: 1-201-567-8266 FAX: 1-201-567-7339 Email: info@tmaxsoft.com

Web (English): http://www.tmaxsoft.com

Japan

Tmax Soft Japan Co., Ltd.

6-7 Sanbancho, Chiyoda-ku, Tokyo 102-0075

Japan

Tel: 81-3-5210-9270 FAX: 81-3-5210-9277

Email: info@tmaxsoft.co.jp

Web (Japanese): http://www.tmaxsoft.co.jp

China

Beijing Silver Tower, RM 1507, 2# North Rd Dong San Huan,

Chaoyang District, Beijing, China, 100027

Tel: 86-10-6410-6148 Fax: 86-10-6410-6144

E-mail: info@tmaxchina.com.cn

Web (Chinese): http://www.tmaxchina.com.cn

1 소개

Sun Microsystems J2EE 1. 4 의 JMX 1.2 스펙은, SNMP 를 지원하는 프로토콜 어댑터를 제공한다. 그리고 J2EE management 1.0 스펙은 인터넷 통신에 있어 네트워크나 시스템 관리 프로토콜을 사용하기 위한 Management Information Base(MIB) 를 정의하고 있다.

Tmax Soft 의 JEUS 제품군 중에서 JEUS SNMP agent 는 WAS 의 관리 프토토콜로 SNMP를 사용하기 위해서 JEUS JMX mbean 서버와 통신하며 SNMP 관리 애플리케이션을 지원한다. JEUS SNMP agent 는 SNMPv1, SNMPv2 및 SNMPv3 프로토콜을 제공한다.

이 메뉴얼은 JEUS SNMP agent 모듈을 사용하기 위한 모든 것에 대해서 설명한다. 우선은 전체적인 모듈에 대한 간략한 설명부터 시작한다(2 장따라하기). 다음으로 각각의 서브모듈을 면밀히 살펴보고, 모듈의 설정과관리를 어떻게 하는지(3 장 JEUS SNMP agent 의 개요), 그리고 JEUS 를모니터링하는 Java 애플리케이션을 어떻게 개발 하는지 (5 장 JEUS SNMP 프로그래밍)에 대해서 설명한다.

2 따라하기

이 장은 JEUS SNMP Agent 를 시작하고 중지하는 것과, 예제를 실행하는 기본적인 내용에 대해서 설명한다.

JEUS WAS 제품을 설치한 후에 다음의 과정을 따라 실행한다. 만일 JEUS 를 아직 설치하지 않았다면 JEUS 설치 안내서를 참조해서 제우스를 설치한다.

1. 'java' 명령을 실행하려면 'JAVA_HOME' 이 세팅되어야 한다. 만일 Windows 플랫폼에서 java.exe 가 C:\lang\j2sdk1.4.0\bin 에 존재한다면, JAVA_HOME 은 다음과 같이 'C:\lang\j2sdk1.4.0' 으로 세팅한다.

C: \>set JAVA_HOME=C: \I ang\j 2sdk1. 4. 0

2. 'jeus' 명령을 실행하려면 'JEUS_HOME' 이 세팅되어야 한다. 만일 Windows 플랫폼에서 c:\jeus5\bin 에 jeus.bat 가 있다면, JEUS_HOME 은 다음과 같이 'C:\jeus5' 로 세팅한다.

C: \>set JEUS_HOME=C: \j eus5

3. 'JEUS_BASEPORT', 'EJB_HOME', 'CLIENT_HOME', 'WEBTODIR' 같은 환경변수는 위에서 설명한 방법과 같이 세팅 한다.

참조: JEUS 를 정상적으로 설치했다면, JEUS_HOME\bin 디렉토리에 있는 jeus.properties 에 위 내용이 모두 적용되어 있다. 그러므로 위단계를 실행하지 않아도 무방하다.

4. 'JEUSMain.xml' 내의 'jmx-manager' 태그에 다음과 같이 "snmp-adaptor-port" 태그를 포함시킨다.

<<*JEUSMain.xml*>>

참조: 'JEUSMain.xml' 파일은 'JEUS_HOME\config\<node name>'라는 디렉토리에 위치한다. JEUS Sever 안내서의 JEUS Server 디렉토리 구조를 참조한다.

5. JEUS_HOME\bin 디렉토리에서 'jeus' 명령 스크립트를 실행한다.

C: \j eus5\bi n>j eus

```
[2005.01.11 16:21:39][0] [johan -10] [MGR-0411] virtual host name of this manager : johan
```

[2005.01.11 16:21:46][0] [johan -10] [SNMP-0004] SNMP AGENT is ready on port: 9999

[2005.01.11 16:21:46][0] [johan -10] [MGR-0241] JeusServer is Ready

6. 터미널/콘솔 창을 열고서 'jeusadmin'을 입력하고 그 뒤에 컴퓨터 이름을 입력한다(예 'jeusadmin johan'). 원도우즈에서는 'hostname' 명령, 유닉스에서는 'uname –a' 명령을 통해서 컴퓨터 이름을 확인할 수 있다.

C: \j eus5\bi n>hostname

j ohan

C: \j eus5\bi n>j eusadmi n j ohan

Login name>

주의: 이 매뉴얼에서는 JEUS 노드 이름을 'johan'으로 가정한다. 실제로는 사용자의 컴퓨터 이름을 사용한다.

- 7. 프롬프트에 JEUS 사용자 이름과 패스워드를 입력한다.
- 8. jeusadmin 프롬프트가 나타나면 boot 를 입력하고 엔터키를 친다. 다음의 예제를 참조한다:

C: \j eus5\bi n>j eusadmi n j ohan

Login name>jeus

Password>

JEUS 5.0 Jeus Manager Controller

j ohan>boot

johan boot done

j ohan_contai ner1

j ohan>

9. 잠시 후 콘솔 창에 다시 프롬프트가 나타난다. 이것은 현재 JEUS 서버가 부트가 되어서 다른 명령을 받아들일 준비가 되어 있다는 것을 의미한다. 아래와 같이 'allenglist' 명령을 실행해서 엔진이 부트가 되었는지를 확인한다.

JEUS 5.0 Jeus Manager Controller

j ohan>boot

johan boot done

j ohan_contai ner1

j ohan>al l engl i st

10. 터미널/콘솔 창을 열고서 'compile'을 실행 한 후에 'snmpclient.bat'을 실행한다. 이 명령을 실행할때 시스템 패스에 'JEUS_HOME\samples\manual_examples\snmp\bin' 이 포함되어 있다고 가정한다. 이것은 클라이언트 프로그램이 JEUS 로 부터 모니터링 정보를 얻기 위해서 필요하다. 다음같이 터미널 /콘솔 창을 실행한다:

C: \j eus5\sampl es\ manual _exampl es\snmp\bi n>snmpcl i ent
1. 3. 6. 1. 4. 1. 14586. 100. 77. 1

```
PORT: 9999

IP: 127.0.0.1

OID: 1.3.6.1.4.1.14586.100.77.1

Sending...

Reply:

PDU type: GET_RSP_MSG

error status: 0

error index: 0

1.3.6.1.4.1.14586.100.77.1.0: [JEUS
4.2:JMXManager=eghost, j 2eeType=JeusService, j

eusType=JeusManager, name=eghost]
```

참조: 'JEUS_HOME\samples\ manual_examples\snmp\classes' 디렉토리에 'snmpclient.bat' 에 필요한 모든 필요한 클래스들을 포함하고 있다. 만일 정상적으로 실행되지 않는다면, 필요한 클래스들이 그 디렉토리에 존재하는지 확인한다. 애플리케이션의 소스는 'JEUS_HOME\samples\ manual_examples\snmp\src' 디렉토리에 있으며, snmp 클라이언트 파라미터는 JEUS SNMP OID 이다 (예: 1.3.6.1.4.1.14586.100.77.1)

이 장에서는 JEUS SNMP agent 를 기동시키는 방법과 SNMP 클라이언트 애플리케이션이 JEUS 로부터 모니터링 정보를 어떻게 가져오는지에 대해서 간략하게 설명을 하였다.

다음 장은 JEUS SNMP agent 의 개요에 대해서 설명한다.

3 JEUS SNMP Agent 의 개요

3.1 소개

SNMP는 Simple Network Management Protocol의 약자로, 네트웍 상의 여러 하드웨어 및 소프트웨어를 모니터링 하기 위한 표준 프로토콜이다. JEUS SNMP agent 모듈은 SNMP 를 통해 JEUS 시스템을 관리할 때 유용한 컴포넌트이다.

JEUS SNMP agent 는 JEUS JMX 와 완전히 통합된다. JEUS SNMP agent 가 검색할 수 있는 모든 정보는 JEUS JMX API 를 통해서 가능하다. 예를들어, JMX mbean 은 EJB 엔진에 디플로이된 모든 모듈에 대한 정보를 관리하고, SNMP manager 는 이 정보를 EJB 엔진에 해당하는 JEUS SNMP OID(Object ID) 를 SNMP agent 에 보냄으로써 디플로이된 모듈을 알 수 있다.

다음 절은 JEUS SNMP agent 의 기술적인 세부 사항을 살펴보기 전에 JEUS SNMP agent 에 대한 간략한 소개를 한다.

- JEUS SNMP Agent 특성.
- JEUS SNMP Agent 컴포넌트.
- JEUS SNMP Agent 아키텍처.
- JEUS SNMP Agent.
- SNMP Manager 애플리케이션.

참조: 본 매뉴얼에서는 J2EE 나 J2EE management 1.0 의 기본적인 기술지식이 필요하지만 내용을 설명하지 않는다. 이 매뉴얼을 보기 전에 이와 관련된 내용의 책이나 스펙을 우선 읽어 보길 권한다.

3.2 JEUS SNMP Agent 특성

현재 JEUS SNMP agent 는 J2EE 의 컴포넌트 뿐만 아니라 엔터프라이즈 메시지 미들웨어의 특징을 가지고 있다. 주목할 만한 특성은 다음과 같다:

- JMX management 1.0 스펙 완전 제공
- NMS 프로토콜로 일반적으로 사용되는 SNMPv1 와 SNMPv2 를 제공. SNMPv1 와 SNMPv2 를 사용하는 모든 SNMP manager 들은 agent 를 통해서 JEUS 내부 정보들을 알아 올 수 있다.
- SNMP agent 와 보안 통신을 하기 위한 SNMPv3 제공. 안정적으로 SNMP agent 와 통신하기 위해서 SNMP manager 가 필요하다. SNMPv3 를 사용하는 모든 SNMP manager 들은 안전하게 정보를 가져올 수 있다.
- JEUS SNMP agent 들은 각각의 JEUS JVM (JEUS manager 와 모든 Engine Container)에서 실행할 수 있다.

3.3 JEUS SNMP Agent 컴포넌트

이 절에서는 JEUS SNMP agent 가 동작하는데 필요한 컴포넌트에 대해서 설명한다.

Main 컴포넌트

1. JEUS SNMP agent 는 JMX mbean 서버와 통신을 하며, 논리적으로 JEUS 서버의 manager 또는 엔진 컨테이너 내에 위치한다.

참조: JEUS 서버와 세부적인 엔진 컨테이너 구조에 대해서는 JEUS Server 안내서를 참조한다.

- 2. MIB(Management Information Base)는 JEUS management 정보 구조를 제공한다. MIB 파일의 이름은 TMAX-JEUS5.0-MIB.mib 이다.
- 3. SNMP manager 는 메시지를 주고 받는다.

JEUS SNMP agent 는 JEUS 를 관리하기 위한 기반 구조를 제공하며, J2EE 1.4 와 J2EE management 1.0 을 구현했다.

SNMP manager 애플리케이션이 SNMP 메시지를 보낼때, SNMP agent 는 설정한 포트를 listen 하고 있다. 해당 포트로 요청이 들어오면 먼저 MIB-tree 에서 OID 를 찾고, 그것의 PDU 타입을 알아내서 JEUS JMX mbean 서버를 호출한다. 정보를 찾아내면 SNMP manager 애플리케이션에 그 값을 리턴해 준다.

3.4 JEUS SNMP Agent 아키텍처

[그림 1]은 JEUS SNMP Agent 와 관련 아키텍처를 표현하였다. 동작 방식은 앞 절에서 설명하였다.




그림 1. JEUS SNMP Agent 아키텍처

3.5 SNMP Agent

SNMP agent 는 JEUS management system 의 Second-Level 서비스 컴포넌트로 JEUS JMX API 를 사용한다. 각각의 JEUS SNMP Agent 는 JEUS system 의 JEUS Manager 와 Engine Container 같은 JVM 들 중의 하나와 연관되어 있다.

SNMP Agent 인스턴스는 JEUS JMX 의 프로토콜 어댑터로서 운영되며, SNMP manager 애플리케이션으로부터 SNMP 패킷을 받아 처리한다. 이것은 특정 포트를 계속 리슨하고 있으면서 SNMP manager 의 요청을 기다리고 있다. 이 리슨 포트는 JEUSMain.xml 파일에서 세팅된다. 세팅을 하지 않으면, 동작하지 않는다.

모든 agent 인스턴스들은 같은 방법으로 작용한다. 그러므로, 각각의 Agent 는 JEUS management system 의 모든 정보를 얻을 수 있다. 만일 하나 이상의 agent 인스턴스가 한 머신에서 부트가 되려면, 포트 넘버가 달라야 한다.

참조: JEUS SNMP Agent 를 운영하려면, SNMP 어댑터 포트를 반드시설정해야만 한다.

3.6 SNMP Manager 애플리케이션

일반적으로, "SNMP manager"는 시스템, 특히 통신 장비를 관리하는 애플리케이션를 나타낸다. J2EE 에서 "SNMP manager"는 엔터프라이즈 애플리케이션, 특히 Web Application Server(WAS)와 같은 미들웨어를 관리한다.

SNMP manager 애플리케이션은 MIB 를 참조하여 SNMP agent 에서 관리 정보를 요청한다. 애플리케이션은 MIB 파일을 파싱해서 정보의 구조를 알아야 한다. 그리고, 관리자가 읽고 관리하기 쉽도록 관리한다.

3.7 결론

JEUS SNMP의 아키텍처에 대한 소개를 마친다.

이 장에서 JEUS SNMP Agent 가 JEUS 시스템 전체와 어떻게 관계되며, JEUS JMX 와는 어떤 관계인지, 그리고 J2EE management system 을 구현하기 위해서 어떻게 동작하는지에 대해서 보았다. 그리고, SNMP agent 에 메시지를 보내고 받는 SNMP Manager 애플리케이션에 대해서 간단하게 살펴 보았다.

다음 장에서는 JEUS SNMP Agent 의 설정에 대해서 살펴 본다.

4 SNMP Agent 의 설정

SNMP Agent 설정은 JEUSMain.xml 의 <jmx-manager> 태그 아래에서 이루어 진다. 다음과 같은 설정 항목이 있다.

- Snmp adaptor port 설정은 snmp 서버가 listen 하고 있는 포트를 설정한다. Snmp manager는 이 port를 통해 management 정보를 요청할 수 있다.
- **Snmp version** 은 agent 가 사용할 SNMP 버전을 명시한다. 1, 2, 3 의 정수 값을 쓴다.
- Snmp max packet size 설정은 SNMP 패킷에 대한 최대값을 설정하며 최소 256 바이트부터 설정 할 수 있다.
- Snmp security 설정은 보안을 적용시킬 것 인지를 설정한다. 보안은 SNMP 버전 3 에서만 지정이 가능 하다.
- Trap daemon 설정은 장애 상황 발생시 TRAP 메세지를 보낼 서버를 설정한다. 여러 개 설정이 가능하며 설정된 모든 ip, address 로 메세지를 보낸다. 현재는 JEUS의 TRAP 정보가 등록되지 않아서 설정해도 아무런 메시지가 가지 않으며 이는 향후 5.1 버전에서 지원될 예정이다.
- Pooling: SNMP agent 로 많은 요청이 동시에 들어오는 경우, Thread Pool을 사용하여 처리하도록 할 수 있다. min, max 는 Worker Thread 의 최소, 최대 개수이고 period는 thread 체크 주기이다. 이는 JEUS의 여러 다른 컴포넌트에서 공유하는 설정이므로 Thread Pool의 동작에 대해서는 자세히 설명하지 않는다.

다음은 JEUSMain.xml 의 snmp adaptor 를 설정한 예제이다.

<<*JEUSMain.xml*>>

```
<node>
 <engine-container>
 </engine-container>
 <jmx-manager>
      <html-adaptor-port>7070</html-adaptor-port>
      <jmx-connector>
       <jmxmp-connector>
         <jmxmp-connector-port>5001</jmxmp-connector-port>
       </jmxmp-connector>
      </jmx-connector>
      <snmp-adaptor>
         <snmp-adaptor-port>9999</snmp-adaptor-port>
         <snmp-version>2</snmp-version>
         <snmp-max-packet-size>4096</snmp-max-packet-size>
         <snmp-security>false</snmp-security>
         <pooling>
           <min>1</min>
           <max>10</max>
           <period>30000</period>
         </pooling>
      </snmp-adaptor>
 </jmx-manager>
 </node>
```

SNMP agent 의 설정은 JMX 설정의 한 부분므로 스키마에 관련된 것은 JEUS JMX 안내서의 환경 설정을 참조하기 바란다.

5 JEUS SNMP 프로그래밍

5.1 소개

이번 장에서는 JEUS SNMP manager 애플리케이션을 개발하는 방법과 설정하는 방법에 대해서 설명한다. 앞서도 언급했듯이 SNMP 와 MIB 에 대한 배경 지식을 가지고 있다고 가정한다. SNMP (SNMPv1, SNMPv2, SNMPv3) 표준을 준수하는 SNMP manager 들은 JEUS SNMP 와 함께 동작할 수 있다. JEUS SNMP 만의 프로그래밍 모델과 추천 사항이 존재한다.

다음 절에서 SNMP manager 애플리케이션에 좀 더 정확하게 이해하기 위해서 간단한 SNMP 클라이언트 프로그램을 살펴보겠다.

참조: 위에서 언급한 SNMP 에 대해서 자세한 설명은 SNMP Management Framework 관련 스펙을 참조하기 바란다 (J2EE management 1.0 스펙 참조). MIB 에 대한 자세한 설명은 다음 6장 "JEUS SNMP MIB "와 부록 A JEUS SNMP MIB 참조"를 살펴보길 바란다.

5.2 간단한 SNMP 클라이언트 프로그램

어플리케이션의 형태는 필요에 따라 다양한 형태를 가지지만, 이 절에서는 JEUS SNMP 클라이언트의 일반적인 형태를 제시한다.

SNMP 클라이언트 애플리케이션은 다음 단계를 수행해야 한다.

- 단계 1: SNMP 메시지 객체를 생성한다.
- 단계 2 : Protocol Data Unit 을 세팅한다.
- 단계 3 : 메시지를 전송한다.
- 단계 4 : 응답을 수신한다.

위 단계를 밟기 전에 우선 접속하려는 SNMP agent 의 IP 주소와 Port 번호를 지정하고, 데이터를 가져올 OID 를 정해야 한다.

단계 1, 2 는 특정 OID 와 SNMP 버전을 위한 SNMP 메시지를 만드는 단계이고, 단계 3, 4 는 메시지를 보내고 받는 단계이다. 단계 4 이후부터 응답 메시지를 처리해서 모니터링하거나 통계 처리를 하는 단계이다.

<< SnmpClientSample1.java>>

```
import java.io.*;
  import java.net.*;
  import java.util.*;
  import jeus.management.snmp.core.*;
  public class SnmpClientSample {
      static SnmpMessage snmpMessage;
      static SnmpGetSetPdu getSetPdu;
      static int defaultPort = 161;
      static String defaultIP = "127.0.0.1";
      static String defaultOID = "1.3.6.1.4.1.14586.100.77.1";
      static void testGet(String oid) throws java.io.IOException
          // Step 1. Create SNMP message object. It may contain
one of the following
          // protocol data unit : GET, SET, TRAP, GET-NEXT.
          snmpMessage = new SnmpMessage ();
          // Step 2. Create a Set Protocol Data Unit.
          getSetPdu = new SnmpGetSetPdu ();
          getSetPdu.setMsgType (AsnObject.GET_REQ_MSG );
          getSetPdu.setRegId (2);
          snmpMessage.setPdu (getSetPdu);
          snmpMessage.setSnmpVersion (2);
          getSetPdu.addNameValuePair (new AsnNameValuePair (oid,
new AsnNull());
          // Step 3. Send message
          System.out.println ("Sending ... ");
          SnmpClient client = new SnmpClient ();
          client.sendSnmpMessage (defaultIP, defaultPort,
snmpMessage);
```

```
// Step 4. Receive reply
          System.out.println ("Reply : ");
          SnmpGetSetPdu reply = (SnmpGetSetPdu)
snmpMessage.getPdu ();
          System.out.println(" PDU type : " +
reply.getMsgTypeName());
          System.out.println(" error status : " +
reply.getErrorStatus());
          System.out.println(" error index : " +
reply.getErrorIndex());
          for (int i=0; i<reply.getValueSize(); i++) {</pre>
  System.out.println(reply.getNameValuePair(i).toString());
      }
      public static void main(String[] args) throws
java.io.IOException {
          // get the SNMP port number
          if (args.length > 0) {
             defaultPort = Integer.parseInt (args[0]);
          System.out.println ("PORT : " + defaultPort);
          // get the ip address of the machine that the SNMP
agent runs on
          if (args.length > 1) {
              defaultIP = args[1];
          System.out.println ("IP : " + defaultIP);
          // get the OID number that you want to get the value of
          if (args.length > 2) {
              defaultOID = args[2];
          System.out.println ("OID : " + defaultOID);
          try {
                  testGet(defaultOID);
```

```
catch (Exception ex) {
        System.out.println ("ex *** : " + ex);
        ex.printStackTrace ();
    }
}
```

JEUS SNMP 어댑터는 SNMPv3(보안)를 제공한다. 만일 JEUS 를 안전하게 모니터링 하려면, SNMP security 를 true 로 세팅한다. 이런 경우에는 SNMP 클라이언트 프로그램은 SNMP 메시지 객체에 대해서 User Name 과 Password 을 세팅해야 한다. SnmpClientSample2.java 의 단계 2 에서 설명하고 있다.

<< SnmpClientSample2.java>>

```
import java.io.*;
  import java.net.*;
  import java.util.*;
  import jeus.management.snmp.core.*;
 public class SnmpClientSample {
      static SnmpMessage snmpMessage;
      static SnmpGetSetPdu getSetPdu;
      static int defaultPort = 161;
      static String defaultIP = "127.0.0.1";
      static String defaultOID = "1.3.6.1.4.1.14586.100.77.1";
      static void testGet(String oid) throws java.io.IOException
          // Step 1. Create SNMP message object. It may contain
one of the following
          // protocol data unit : GET, SET, TRAP, GET-NEXT.
          snmpMessage = new SnmpMessage ();
          // Step 2. Create a Set Protocol Data Unit.
          getSetPdu = new SnmpGetSetPdu ();
          getSetPdu.setMsgType (AsnObject.GET_REQ_MSG );
          getSetPdu.setReqId (1);
          snmpMessage.setPdu (getSetPdu);
          snmpMessage.setSnmpVersion (3);
```

```
snmpMessage.setUserName ("administrator".getBytes());
          snmpMessage.setAuthMode (true);
          snmpMessage.setAuthAlgorithm (SecurityInterface.SHA);
          snmpMessage.setAuthPassword ("jeusadmin".getBytes ());
getSetPdu.addNameValuePair (new AsnNameValuePair (oid, new
AsnNull());
          // Step 3. Send message
          System.out.println ("Sending ... ");
          SnmpClient client = new SnmpClient ();
          client.sendSnmpMessage (defaultIP, defaultPort,
snmpMessage);
          // Step 4. Receive reply
          System.out.println ("Reply : ");
          SnmpGetSetPdu reply = (SnmpGetSetPdu)
snmpMessage.getPdu ();
          System.out.println(" PDU type : " +
reply.getMsgTypeName());
          System.out.println(" error status : " +
reply.getErrorStatus());
          System.out.println(" error index : " +
reply.getErrorIndex());
          for (int i=0; i<reply.getValueSize(); i++) {</pre>
System.out.println(reply.getNameValuePair(i).toString());
      }
      public static void main(String[] args) throws
java.io.IOException {
          // get the SNMP port number
          if (args.length > 0) {
             defaultPort = Integer.parseInt (args[0]);
          System.out.println ("PORT : " + defaultPort);
```

```
// get the ip address of the machine that the SNMP
agent runs on
          if (args.length > 1) {
              defaultIP = args[1];
          System.out.println ("IP : " + defaultIP);
          // get the OID number that you want to get the value of
          if (args.length > 2) {
              defaultOID = args[2];
          }
          System.out.println ("OID : " + defaultOID);
          try {
                  testGet(defaultOID);
          catch (Exception ex) {
              System.out.println ("ex *** : " + ex);
              ex.printStackTrace ();
          }
      }
```

이 예제에서, 리소스의 어떤 부분이든 초기화가 실패하면 어플리케이션이 멈추게 된다. 실제 애플리케이션은 예외 처리를 하고 실패 상황에 대해서 관리해줘야 한다.

참조: SNMP API 는 JEUS SNMP agent 만을 위한 것이 아니라, SNMPv1, SNMPv2, SNMPv3 를 제공하는 모든 SNMP agent 를 위한 것이다. 그리고 사용자가 JEUS SNMP agent 로부터 정보를 얻기 위해서 SNMP 라이브러리를 사용할 수도 있다.

5.3 결론

이상으로 JEUS SNMP manager 어플리케이션 개발에 대한 설명을 마친다.

6 JEUS SNMP MIB

6.1 소개

사용자는 모든 JEUS 서버의 속성에 접근할 수 있는데, 이것들은 JEUS MIB 에 정의되어 있다. MIB 는 표준 SNMP 의 한부분이다. MIB 에 대한 내용은 www.ietf.org 사이트를 참조한다.

다음과 같은 순서로 JEUS MIB 를 소개한다.

- MIB 브라우징
- Object Identifiers(OID)
- JEUS SNMP 의 OID 접미어

6.2 MIB 브라우징

JEUS MIB 파일은 TMAX-JEUS5.0-MIB.mib 라는 파일에 정의되어 있으며, %JEUS_HOME%\lib\system 디렉토리에 존재한다. 직접적으로 MIB 파일을 볼 수 있으며, 부록 A JEUS SNMP MIB 참조 에서는 oid 속성값의 매핑을 볼수 있다. 그리고 3rd-Party MIB browser 를 사용할 수 있다. JEUS 에서는 MIB browser 는 제공하지는 않지만, SNMP 유틸리티 벤더 대부분에서 MIB browser 를 제공한다.

6.3 객체 식별(OID)

OID 는 관리되는 객체를 구별하기 위한 정수를 나열한 것으로, OID 트리 구조를 사용해서 객체의 경로를 정의한다. OID 는 MIB 파일에서 정의된다.

각 OID 는 JEUS mbean 의 각 속성과 매핑 된다. JEUS SNMP agent 로 특정한 OID 값을 가진 SNMP packet 을 보내면 OID 와 일치하는 정보를 얻을 수 있다.




그림 2. JEUS MIB 의 OID

위의 [그림 2] 는 JEUS MIB 의 OID 트리를 나타낸다. Tmax Soft 의 enterprise OID 는 1.3.6.1.4.1.14586 이다. 모든 JEUS 속성값의 접두어는 1.3.6.1.4.1.14586.100 이 된다. 예를 들어, JEUSManager 의 서버 버전 속성값의 OID 는 1.3.6.1.4.1.14586.100.77.2 이다.

6.4 JEUS SNMP OID 접미어

객체열을 가져오는 표준 접미어가 있다. 모든 객체를 가져오는 접미어는 "0"이다. "1"을 접미어로 사용하면 전체 객체 중에서 첫번째 객체만 가져온다. 예를 들어, 1.3.6.1.4.1.14586.100.9.1 은 EJBModule 의 객체이름의 속성을 의미하고, 1.3.6.1.4.1.14586.100.9.1.1 은 첫번째 EJBModule 의 객체 이름을 의미한다.

게다가 JEUS SNMP agent 는 객체들의 개수를 알아오는 틀벽한 OID 접미어인 "9999" 를 제공한다. 예를 들어, GET 1.3.6.1.4.1.14586.100.9.1.9999 라고 했을 때, JEUS 에 10 개의 EJB 가 deploy 되어 있다면 10 을 리턴한다.

참조: 모든 접미어가 OID 트리에 있는 것이 아니므로, 실제 OID 만 탐색할수 있다. 그러므로 GET_NEXT 1.3.6.1.4.1.14586.100.9.1 을 사용하면 1.3.6.1.4.1.14586.100.9.1.1 의 결과가 아닌 1.3.6.1.4.1.14586.100.9.2 의 값이리턴된다.

7 결론

지금까지 SNMP Manager 애플리케이션을 개발하기 위해서 모든 필요한 내용을 설명하였다. JEUS SNMP agent 에 대한 설명을 하였고, 설정 방법과 SNMP Manager 애플리케이션 개발에 대한 것을 알아보았다.

A JEUS SNMP MIB 참조

A.1 소개

이 부록에서는 JEUS SNMP MIB 를 세부적으로 살펴본다.

A.2 목적

SNMP manager 개발자는 개발하면서 참조할 MIB 파일이 필요하다. JEUS 의 MIB 파일인 TMAX-JEUS5.0-MIB.MIB 파일은 %JEUS_HOME%\lib\system 디렉토리에 있다. 이 파일을 보면 JEUS SNMP MIB 파일의 내부적인 부분과 그것들의 속성값 그리고 OID 의 매핑을 살펴볼 수 있다.

A.3 OID 와 속성값의 매핑

TMAX-JEUS-MIB 를 더 쉽게 이해할 수 있도록 하기 위해서 간단한 OID 와 속성값의 테이블을 제공한다. MIB 는 다음 절에 소개되어 있으며 이 매핑을 보면 각 OID 에 대해서 세부적인 설명을 살펴볼 수 있다.

Tmax Soft 의 엔터프라이즈 넘버는 14586 이고 JEUS 제품의 넘버는 100 이다. 그리고 매핑의 포멧은 다음과 같다. JEUS 4.X 버전과 달라진 점은 속성이름의 앞에 그룹 이름이 들어간다는 것이다. 이는 Mib 파일에서 중복되는 mib object 이름이 생기는 것을 방지하기 위함이다.

포멧은 [OID] [속성] 이고 모든 OID 의 공통적인 prefix 로 들어가는 "1.3.6.1.4.1.14586.100."은 생략하였다.

- 2.1 j2EEDomainobjectName
- 2.2 j2EEDomainservers
- 2.3 j2EEDomaintroubles
- 2.4 j2EEDomainownTroubles
- 3.1 j2EEServerobjectName
- 3.2 j2EEServerserverVersion
- 3.3 j2EEServerserverVendor

- 3.4 j2EEServerjavaVMs
- 3.5 j2EEServerdeployedObjects
- 3.6 j2EEServerresources
- 3.8 j2EEServerjeusServices
- 3.9 j2EEServerengines
- 3.10 j2EEServerenginesFromDescriptor
- 3.15 j2EEServerdistributedModules
- 3.17 j2EEServernodeName
- 3.18 j2EEServerappPaths
- 3.19 j2EEServertroubles
- 3.20 j2EEServerownTroubles
- 4.1 jVMobjectName
- 4.2 jVMjavaVersion
- 4.3 jVMjavaVendor
- 4.4 jVMnode
- 4.6 jVMoSName
- 4.7 jVMoSVersion
- 4.8 jVMallProperties
- 4.9 jVMtroubles
- 4.10 jVMownTroubles
- 4.101 jVMheapSize-upperBound
- 4.102 jVMheapSize-lowerBound
- 4.103 jVMheapSize-highWaterMark
- 4.104 jVMheapSize-lowWaterMark
- 4.105 jVMheapSize-current
- 4.111 jVMupTime-count
- 4.121 jVMtotalSize-highWaterMark
- 4.122 jVMtotalSize-lowWaterMark
- 4.123 jVMtotalSize-current
- 6.1 j2EEApplicationobjectName
- 6.2 j2EEApplicationdeploymentDescriptor
- 6.3 j2EEApplicationserver
- 6.4 j2EEApplicationmodules
- 6.5 j2EEApplicationmoduleType
- 6.6 j2EEApplicationapplicationType
- 6.7 j2EEApplicationjeusDeploymentPlan
- 6.8 j2EEApplicationtargetModuleID
- 6.9 j2EEApplicationtroubles
- 6.10 j2EEApplicationownTroubles

- 8.1 appClientModuleobjectName
- 8.2 appClientModuledeploymentDescriptor
- 8.3 appClientModuleserver
- 8.4 appClientModulejavaVMs
- 8.5 appClientModuleapplicationType
- 8.6 appClientModulemoduleType
- 8.7 appClientModulejeusDeploymentPlan
- 8.8 appClientModuletargetModuleID
- 8.9 appClientModuletroubles
- 8.10 appClientModuleownTroubles
- 9.1 eJBModuleobjectName
- 9.2 eJBModuledeploymentDescriptor
- 9.3 eJBModuleserver
- 9.4 eJBModulejavaVMs
- 9.5 eJBModuleejbs
- 9.6 eJBModuleejbCount
- 9.7 eJBModuleclientViewPath
- 9.8 eJBModulejeusDeploymentPlan
- 9.9 eJBModuletargetModuleID
- 9.10 eJBModulemoduleType
- 9.11 eJBModuleapplicationType
- 9.12 eJBModuletroubles
- 9.13 eJBModuleownTroubles
- 11.1 messageDrivenBeanobjectName
- 11.2 messageDrivenBeantroubles
- 11.3 messageDrivenBeanownTroubles
- 11.101 messageDrivenBeancreateCount-count
- 11.111 messageDrivenBeanremoveCount-count
- 11.121 messageDrivenBeanrequestCount-count
- 11.131 messageDrivenBeancommittedCount-count
- 11.141 messageDrivenBeanrolledbackCount-count
- 11.151 messageDrivenBeantimeoutRolledbackCount-count
- 11.161 messageDrivenBeanmessageCount-count
- 11.171 messageDrivenBeanactiveEJBBeanCount-highWaterMark
- 11.172 messageDrivenBeanactiveEJBBeanCount-lowWaterMark
- 11.173 messageDrivenBeanactiveEJBBeanCount-current
- 11.181 messageDrivenBeantotalEJBBeanCount-highWaterMark
- 11.182 messageDrivenBeantotalEJBBeanCount-lowWaterMark
- 11.183 messageDrivenBeantotalEJBBeanCount-current

12.1 entityBeanobjectName 12.2 entityBeantroubles 12.3 entityBeanownTroubles 12.101 entityBeancreateCount-count 12.111 entityBeanremoveCount-count 12.121 entityBeanrequestCount-count 12.131 entityBeancommittedCount-count 12.141 entityBeanrolledbackCount-count 12.151 entityBeantimeoutRolledbackCount-count 12.161 entityBeanreadyCount-highWaterMark 12.162 entityBeanreadyCount-lowWaterMark 12.163 entityBeanreadyCount-current 12.171 entityBeanpooledCount-highWaterMark 12.172 entityBeanpooledCount-lowWaterMark 12.173 entityBeanpooledCount-current 12.181 entityBeanautoRemovedEJBObjectCount-count 12.191 entityBeantotalEJBBeanCount-highWaterMark 12.192 entityBeantotalEJBBeanCount-lowWaterMark 12.193 entityBeantotalEJBBeanCount-current 12.201 entityBeanactiveEJBBeanCount-highWaterMark 12.202 entityBeanactiveEJBBeanCount-lowWaterMark 12.203 entityBeanactiveEJBBeanCount-current 12.211 entityBeantotalThreadCount-highWaterMark 12.212 entityBeantotalThreadCount-lowWaterMark 12.213 entityBeantotalThreadCount-current 12.221 entityBeanactiveThreadCount-highWaterMark 12.222 entityBeanactiveThreadCount-lowWaterMark 12.223 entityBeanactiveThreadCount-current 12.231 entityBeantotalEJBObjectCount-highWaterMark 12.232 entityBeantotalEJBObjectCount-lowWaterMark 12.233 entityBeantotalEJBObjectCount-current 12.241 entityBeanactiveEJBObjectCount-highWaterMark 12.242 entityBeanactiveEJBObjectCount-lowWaterMark 12.243 entityBeanactiveEJBObjectCount-current 12.251 entityBeanpassiveCount-highWaterMark 12.252 entityBeanpassiveCount-lowWaterMark 12.253 entityBeanpassiveCount-current 14.1 statefulSessionBeanobjectName 14.2 statefulSessionBeantroubles

```
14.3 statefulSessionBeanownTroubles
14.101 statefulSessionBeancreateCount-count
14.111 statefulSessionBeanremoveCount-count
14.121 statefulSessionBeanrequestCount-count
14.131 statefulSessionBeancommittedCount-count
14.141 statefulSessionBeanrolledbackCount-count
14.151 statefulSessionBeantimeoutRolledbackCount-count
14.161 statefulSessionBeanmethodReadyCount-highWaterMark
14.162 statefulSessionBeanmethodReadyCount-lowWaterMark
14.163 statefulSessionBeanmethodReadyCount-current
14.171 statefulSessionBeanpassiveCount-highWaterMark
14.172 statefulSessionBeanpassiveCount-lowWaterMark
14.173 statefulSessionBeanpassiveCount-current
14.181 statefulSessionBeanautoRemovedEJBObjectCount-count
14.191 statefulSessionBeantotalEJBBeanCount-highWaterMark
14.192 statefulSessionBeantotalEJBBeanCount-lowWaterMark
14.193 statefulSessionBeantotalEJBBeanCount-current
14.201 statefulSessionBeanactiveEJBBeanCount-highWaterMark
14.202 statefulSessionBeanactiveEJBBeanCount-lowWaterMark
14.203 statefulSessionBeanactiveEJBBeanCount-current
14.211 statefulSessionBeantotalThreadCount-highWaterMark
14.212 statefulSessionBeantotalThreadCount-lowWaterMark
14.213 statefulSessionBeantotalThreadCount-current
14.221 statefulSessionBeanactiveThreadCount-highWaterMark
14.222 statefulSessionBeanactiveThreadCount-lowWaterMark
14.223 statefulSessionBeanactiveThreadCount-current
14.231 statefulSessionBeantotalEJBObjectCount-highWaterMark
14.232 statefulSessionBeantotalEJBObjectCount-lowWaterMark
14.233 statefulSessionBeantotalEJBObjectCount-current
14.241 statefulSessionBeanactiveEJBObjectCount-highWaterMark
14.242 statefulSessionBeanactiveEJBObjectCount-lowWaterMark
14.243 statefulSessionBeanactiveEJBObjectCount-current
14.251 statefulSessionBeanfileDBSizeCount-highWaterMark
14.252 statefulSessionBeanfileDBSizeCount-lowWaterMark
14.253 statefulSessionBeanfileDBSizeCount-current
15.1 statelessSessionBeanobjectName
15.2 statelessSessionBeantroubles
15.3 statelessSessionBeanownTroubles
15.101 statelessSessionBeancreateCount-count
```

15.111 statelessSessionBeanremoveCount-count 15.121 statelessSessionBeanrequestCount-count 15.131 statelessSessionBeancommittedCount-count 15.141 statelessSessionBeanrolledbackCount-count 15.151 statelessSessionBeantimeoutRolledbackCount-count 15.161 statelessSessionBeanmethodReadyCount-highWaterMark 15.162 statelessSessionBeanmethodReadyCount-lowWaterMark 15.163 statelessSessionBeanmethodReadyCount-current 15.171 statelessSessionBeantotalEJBBeanCount-highWaterMark 15.172 statelessSessionBeantotalEJBBeanCount-lowWaterMark 15.173 statelessSessionBeantotalEJBBeanCount-current 15.181 statelessSessionBeanactiveEJBBeanCount-highWaterMark 15.182 statelessSessionBeanactiveEJBBeanCount-lowWaterMark 15.183 statelessSessionBeanactiveEJBBeanCount-current 15.191 statelessSessionBeantotalThreadCount-highWaterMark 15.192 statelessSessionBeantotalThreadCount-lowWaterMark 15.193 statelessSessionBeantotalThreadCount-current 15.201 statelessSessionBeanactiveThreadCount-highWaterMark 15.202 statelessSessionBeanactiveThreadCount-lowWaterMark 15.203 statelessSessionBeanactiveThreadCount-current 16.1 webModuleobjectName 16.2 webModuledeploymentDescriptor 16.3 webModuleserver 16.4 webModulejavaVMs 16.5 webModuleservlets 16.6 webModulecontextGroupObjectName 16.7 webModulecontextGroup 16.8 webModulerealDocBase 16.9 webModulejeusDeploymentPlan 16.10 webModuletargetModuleID 16.11 webModulemoduleType 16.12 webModuleapplicationType 16.13 webModuleautoReload 16.14 webModuletroubles 16.15 webModuleownTroubles 16.101 webModulerequestCount-count 16.111 webModuleallSessionsSize-count 16.121 webModuleactiveSessionsSize-count

16.131 webModulepassivateSessionsSize-count

- 16.141 webModulelocalSessionsSize-count
- 16.151 webModuleprocessingTime-count
- 17.1 servletobjectName
- 17.2 servletservletInfo
- 17.3 servletaverageExecutionTime
- 17.4 servlettroubles
- 17.5 servletownTroubles
- 17.101 servletserviceTime-count
- 17.102 servletserviceTime-maxTime
- 17.103 servletserviceTime-minTime
- 17.104 servletserviceTime-totalTime
- 18.1 resourceAdapterModuleobjectName
- 18.2 resourceAdapterModuledeploymentDescriptor
- 18.3 resourceAdapterModuleserver
- 18.4 resourceAdapterModulejavaVMs
- 18.6 resourceAdapterModulemoduleType
- 18.7 resourceAdapterModuleapplicationType
- 18.8 resourceAdapterModulejeusDeploymentPlan
- 18.9 resourceAdapterModuletargetModuleID
- 18.10 resourceAdapterModulemin
- 18.11 resourceAdapterModulemax
- 18.12 resourceAdapterModulestep
- 18.13 resourceAdapterModulekeepAliveTime
- 18.14 resourceAdapterModulereleaseTimeout
- 18.15 resourceAdapterModulerejectTimeout
- 18.16 resourceAdapterModuletroubles
- 18.17 resourceAdapterModuleownTroubles
- 19.1 resourceAdapterobjectName
- 19.2 resourceAdaptertroubles
- 19.3 resourceAdapterownTroubles
- 21.1 javaMailResourceobjectName
- 21.2 javaMailResourceproperty
- 21.3 javaMailResourcetroubles
- 21.4 javaMailResourceownTroubles
- 22.1 jCAResourceobjectName
- 22.4 jCAResourcecMInfo
- 22.5 jCAResourcetroubles
- 22.6 jCAResourceownTroubles
- 23.1 jCAConnectionFactoryobjectName

23.2 jCAConnectionFactorycMInfo 23.3 jCAConnectionFactorymin 23.4 jCAConnectionFactorymax 23.5 jCAConnectionFactorymaxWaiter 23.6 jCAConnectionFactorymaxDisposableCount 23.7 jCAConnectionFactorywaitTrial 23.8 jCAConnectionFactorywaitingTime 23.9 jCAConnectionFactorypooledTimeout 23.10 jCAConnectionFactorydissociationtimeout 23.11 jCAConnectionFactoryinvalidationtimeout 23.13 jCAConnectionFactoryskipMatching 23.14 jCAConnectionFactoryuseWrapper 23.15 jCAConnectionFactorytroubles 23.16 jCAConnectionFactoryownTroubles 24.1 jCAManagedConnectionFactoryobjectName 24.2 jCAManagedConnectionFactorytroubles 24.3 jCAManagedConnectionFactoryownTroubles 25.1 jDBCResourceobjectName 25.2 jDBCResourcejdbcDataSources 25.3 jDBCResourcecPInfo 25.4 jDBCResourcetroubles 25.5 jDBCResourceownTroubles 25.101 jDBCResourceconnectionPools-createCount-count 25.111 jDBCResourceconnectionPools-closeCount-count 25.121 jDBCResourceconnectionPools-poolSize-upperBound 25.122 jDBCResourceconnectionPools-poolSize-lowerBound 25.123 jDBCResourceconnectionPools-poolSize-highWaterMark 25.124 jDBCResourceconnectionPools-poolSize-lowWaterMark 25.125 jDBCResourceconnectionPools-poolSize-current 25.131 jDBCResourceconnectionPools-freePoolSize-upperBound 25.132 jDBCResourceconnectionPools-freePoolSize-lowerBound 25.133 jDBCResourceconnectionPools-freePoolSize-highWaterMark 25.134 jDBCResourceconnectionPools-freePoolSize-lowWaterMark 25.135 jDBCResourceconnectionPools-freePoolSize-current 25.141 jDBCResourceconnectionPools-waitingThreadCounthighWaterMark 25.142 jDBCResourceconnectionPools-waitingThreadCountlowWaterMark

25.143 jDBCResourceconnectionPools-waitingThreadCount-current

```
25.161 jDBCResourceconnectionPools-waitTime-count
25.162 jDBCResourceconnectionPools-waitTime-maxTime
25.163 jDBCResourceconnectionPools-waitTime-minTime
25.164 jDBCResourceconnectionPools-waitTime-totalTime
25.171 jDBCResourceconnectionPools-useTime-count
25.172 jDBCResourceconnectionPools-useTime-maxTime
25.173 jDBCResourceconnectionPools-useTime-minTime
25.174 jDBCResourceconnectionPools-useTime-totalTime
25.181 jDBCResourceconnectionPools-jdbcDataSource
26.1 jDBCDataSourceobjectName
26.2 jDBCDataSourcejdbcDriver
26.3 jDBCDataSourceconfig
26.4 jDBCDataSourcecPInfo
26.6 jDBCDataSourcetroubles
26.7 jDBCDataSourceownTroubles
26.101 jDBCDataSourcecreateCount-count
26.111 jDBCDataSourcecloseCount-count
26.121 jDBCDataSourcepoolSize-upperBound
26.122 jDBCDataSourcepoolSize-lowerBound
26.123 jDBCDataSourcepoolSize-highWaterMark
26.124 jDBCDataSourcepoolSize-lowWaterMark
26.125 jDBCDataSourcepoolSize-current
26.131 jDBCDataSourcefreePoolSize-upperBound
26.132 jDBCDataSourcefreePoolSize-lowerBound
26.133 jDBCDataSourcefreePoolSize-highWaterMark
26.134 jDBCDataSourcefreePoolSize-lowWaterMark
26.135 jDBCDataSourcefreePoolSize-current
26.141 jDBCDataSourcewaitingThreadCount-highWaterMark
26.142 jDBCDataSourcewaitingThreadCount-lowWaterMark
26.143 jDBCDataSourcewaitingThreadCount-current
26.151 jDBCDataSourcereConnectCount-count
26.161 jDBCDataSourcewaitTime-count
26.162 jDBCDataSourcewaitTime-maxTime
26.163 jDBCDataSourcewaitTime-minTime
26.164 jDBCDataSourcewaitTime-totalTime
26.171 jDBCDataSourceuseTime-count
26.172 jDBCDataSourceuseTime-maxTime
26.173 jDBCDataSourceuseTime-minTime
26.174 jDBCDataSourceuseTime-totalTime
```

- 27.1 jDBCDriverobjectName
- 27.2 jDBCDrivertroubles
- 27.3 jDBCDriverownTroubles
- 28.1 jMSResourceobjectName
- 28.3 jMSResourceclusterInfo
- 28.5 jMSResourcejMSConnectionFactoryResourceNames
- 28.6 jMSResourcejMSDestinationResourceNames
- 28.7 jMSResourcejMSClientResourceNames
- 28.9 jMSResourcefreeMemory
- 28.10 jMSResourcetotalMemory
- 28.11 jMSResourcejMSConnectionFactoryResources
- 28.12 jMSResourcetroubles
- 28.13 jMSResourceownTroubles
- 28.101 jMSResourceconnections-sessions-messageCount-count
- 28.111 jMSResourceconnections-sessions-pendingMessageCount-count
- ${\tt 28.121 \ jMSResource connections-sessions-expired Message Count-count}$
- 28.131 jMSResourceconnections-sessions-messageWaitTime-count
- 28.132 jMSResourceconnections-sessions-messageWaitTime-maxTime
- 28.133 jMSResourceconnections-sessions-messageWaitTime-minTime
- 28.134 jMSResourceconnections-sessions-messageWaitTime-totalTime
- 28.141 jMSResourceconnections-sessions-durableSubscriptionCount-count
- 28.151 jMSResourceconnections-sessions-producers-destination
- 28.161 jMSResourceconnections-sessions-producers-messageCount-count
- 28.171 jMSResourceconnections-sessions-producers-

pendingMessageCount-count

28.181 jMSResourceconnections-sessions-producers-

expiredMessageCount-count

- 28.191 jMSResourceconnections-sessions-producers-messageWaitTime-count
- 28.192 jMSResourceconnections-sessions-producers-messageWaitTime-maxTime
- 28.193 jMSResourceconnections-sessions-producers-messageWaitTime-minTime
- 28.194 jMSResourceconnections-sessions-producers-messageWaitTime-totalTime
- 28.201 jMSResourceconnections-sessions-consumers-origin

- 28.211 jMSResourceconnections-sessions-consumers-messageCount-count
- 28.221 jMSResourceconnections-sessions-consumers-

pendingMessageCount-count

- 28.231 jMSResourceconnections-sessions-consumers-
- expiredMessageCount-count
- 28.241 jMSResourceconnections-sessions-consumers-messageWaitTime-count
- ${\tt 28.242~jMSResource} connections-{\tt sessions-consumers-messageWaitTime-maxTime}$
- 28.243 jMSResourceconnections-sessions-consumers-messageWaitTime-minTime
- 28.244 jMSResourceconnections-sessions-consumers-messageWaitTime-totalTime
- 29.1 jNDIResourceobjectName
- 29.2 jNDIResourcetroubles
- 29.3 jNDIResourceownTroubles
- 30.1 jTAResourceobjectName
- 30.2 jTAResourceaverageExecutionTime
- 30.3 jTAResourceactiveTimeout
- 30.4 jTAResourceprepareTimeout
- 30.5 jTAResourcepreparedTimeout
- 30.6 jTAResourcecommitTimeout
- 30.7 jTAResourcerecoveryTimeout
- 30.8 jTAResourceuncompletedTimeout
- 30.9 jTAResourceheuristicRollback
- 30.10 jTAResourceresolution
- 30.11 jTAResourcethreadPool
- 30.12 jTAResourcetroubles
- 30.13 jTAResourceownTroubles
- 30.101 jTAResourceactiveCount-count
- 30.111 jTAResourcecommittedCount-count
- 30.121 jTAResourcerolledbackCount-count
- 30.131 jTAResourcetimeoutCount-count
- 30.141 jTAResourcetimeoutRolledbackCount-count
- 30.151 jTAResourceactiveTimeoutCount-count
- 30.161 jTAResourceprepareTimeoutCount-count
- 30.171 jTAResourcepreparedTimeoutCount-count
- 30.181 jTAResourcecommitTimeoutCount-count

30.191 jTAResourceheuristicRolledbackCount-count 30.201 jTAResourceexecutionTime-count 30.202 jTAResourceexecutionTime-maxTime 30.203 jTAResourceexecutionTime-minTime 30.204 jTAResourceexecutionTime-totalTime 32.1 uRLResourceobjectName 32.2 uRLResourceuRLInfo 32.3 uRLResourcetroubles 32.4 uRLResourceownTroubles 33.1 jMSConnectionResourceobjectName 33.2 jMSConnectionResourcejMSSessionResourceNames 33.3 jMSConnectionResourcetroubles 33.4 jMSConnectionResourceownTroubles 33.101 jMSConnectionResourcesessions-messageCount-count 33.111 jMSConnectionResourcesessions-pendingMessageCount-count 33.121 jMSConnectionResourcesessions-expiredMessageCount-count 33.131 jMSConnectionResourcesessions-messageWaitTime-count 33.132 jMSConnectionResourcesessions-messageWaitTime-maxTime 33.133 jMSConnectionResourcesessions-messageWaitTime-minTime 33.134 jMSConnectionResourcesessions-messageWaitTime-totalTime 33.141 jMSConnectionResourcesessions-durableSubscriptionCountcount 33.151 jMSConnectionResourcesessions-producers-destination 33.161 jMSConnectionResourcesessions-producers-messageCount-count 33.171 jMSConnectionResourcesessions-producerspendingMessageCount-count 33.181 jMSConnectionResourcesessions-producersexpiredMessageCount-count 33.191 jMSConnectionResourcesessions-producers-messageWaitTime-33.192 jMSConnectionResourcesessions-producers-messageWaitTimemaxTime 33.193 jMSConnectionResourcesessions-producers-messageWaitTimeminTime 33.194 jMSConnectionResourcesessions-producers-messageWaitTimetotalTime 33.201 jMSConnectionResourcesessions-consumers-origin 33.211 jMSConnectionResourcesessions-consumers-messageCount-count

- 33.221 jMSConnectionResourcesessions-consumerspendingMessageCount-count
- 33.231 jMSConnectionResourcesessions-consumersexpiredMessageCount-count
- 33.241 jMSConnectionResourcesessions-consumers-messageWaitTimecount
- 33.242 jMSConnectionResourcesessions-consumers-messageWaitTimemaxTime
- 33.243 jMSConnectionResourcesessions-consumers-messageWaitTime-
- 33.244 jMSConnectionResourcesessions-consumers-messageWaitTimetotalTime
- 33.251 jMSConnectionResourcesessionCount-count
- 33.261 jMSConnectionResourceconnectionConsumerCount-count
- 33.271 jMSConnectionResourceconnectionConsumers-origin
- 33.281 jMSConnectionResourceconnectionConsumers-messageCountcount
- 33.291 jMSConnectionResourceconnectionConsumerspendingMessageCount-count
- 33.301 jMSConnectionResourceconnectionConsumersexpiredMessageCount-count
- 33.401 jMSConnectionResourceconnectionConsumers-messageWaitTimecount
- 33.402 jMSConnectionResourceconnectionConsumers-messageWaitTimemaxTime
- 33.403 jMSConnectionResourceconnectionConsumers-messageWaitTimeminTime
- 33.404 jMSConnectionResourceconnectionConsumers-messageWaitTimetotalTime
- 34.1 jMSConsumerResourceobjectName
- 34.2 jMSConsumerResourcedestination
- 34.3 jMSConsumerResourcedestinationResourceObjectName
- 34.4 jMSConsumerResourcedurableSubscriberResourceObjectName
- 34.5 jMSConsumerResourcesendTimeAvg
- 34.6 jMSConsumerResourcetroubles
- 34.7 jMSConsumerResourceownTroubles
- 34.101 jMSConsumerResourceorigin
- 34.111 jMSConsumerResourcemessageCount-count
- 34.121 jMSConsumerResourcependingMessageCount-count

34.131 jMSConsumerResourceexpiredMessageCount-count
34.141 jMSConsumerResourcemessageWaitTime-count
34.142 jMSConsumerResourcemessageWaitTime-maxTime
34.143 jMSConsumerResourcemessageWaitTime-minTime
34.144 jMSConsumerResourcemessageWaitTime-totalTime
34.151 jMSConsumerResourcesendTime-count
34.152 jMSConsumerResourcesendTime-maxTime
34.153 jMSConsumerResourcesendTime-minTime
34.154 jMSConsumerResourcesendTime-totalTime
35.1 jMSProducerResourceobjectName
35.3 jMSProducerResourcedestinationResourceObjectName
35.4 jMSProducerResourcedurableSubscriberResourceObjectName
35.5 jMSProducerResourcesendTimeAvg
35.6 jMSProducerResourcedestination
35.7 jMSProducerResourcetroubles
35.8 jMSProducerResourceownTroubles
35.111 jMSProducerResourcemessageCount-count
35.121 jMSProducerResourcependingMessageCount-count
35.131 jMSProducerResourceexpiredMessageCount-count
35.141 jMSProducerResourcemessageWaitTime-count
35.142 jMSProducerResourcemessageWaitTime-maxTime
35.143 jMSProducerResourcemessageWaitTime-minTime
35.144 jMSProducerResourcemessageWaitTime-totalTime
35.151 jMSProducerResourcesendTime-count
35.152 jMSProducerResourcesendTime-maxTime
35.153 jMSProducerResourcesendTime-minTime
35.154 jMSProducerResourcesendTime-totalTime
36.1 jMSSessionResourceobjectName
36.2 jMSSessionResourcejMSEndPointConsumerNames
36.3 jMSSessionResourcetroubles
36.4 jMSSessionResourceownTroubles
36.101 jMSSessionResourcemessageCount-count
36.111 jMSSessionResourcependingMessageCount-count
36.121 jMSSessionResourceexpiredMessageCount-count
36.131 jMSSessionResourcemessageWaitTime-count
36.132 jMSSessionResourcemessageWaitTime-maxTime
36.133 jMSSessionResourcemessageWaitTime-minTime
36.134 jMSSessionResourcemessageWaitTime-totalTime
36.141 jMSSessionResourcedurableSubscriptionCount-count

36.151 jMSSessionResourceproducers-destination 36.161 jMSSessionResourceproducers-messageCount-count 36.171 jMSSessionResourceproducers-pendingMessageCount-count 36.181 jMSSessionResourceproducers-expiredMessageCount-count 36.191 jMSSessionResourceproducers-messageWaitTime-count 36.192 jMSSessionResourceproducers-messageWaitTime-maxTime 36.193 jMSSessionResourceproducers-messageWaitTime-minTime 36.194 jMSSessionResourceproducers-messageWaitTime-totalTime 36.201 jMSSessionResourceconsumers-origin 36.211 jMSSessionResourceconsumers-messageCount-count 36.221 jMSSessionResourceconsumers-pendingMessageCount-count 36.231 jMSSessionResourceconsumers-expiredMessageCount-count 36.241 jMSSessionResourceconsumers-messageWaitTime-count 36.242 jMSSessionResourceconsumers-messageWaitTime-maxTime 36.243 jMSSessionResourceconsumers-messageWaitTime-minTime 36.244 jMSSessionResourceconsumers-messageWaitTime-totalTime 36.251 jMSSessionResourcesendTime-count 36.252 jMSSessionResourcesendTime-maxTime 36.253 jMSSessionResourcesendTime-minTime 36.254 jMSSessionResourcesendTime-totalTime 36.261 jMSSessionResourcecommitCount-count 36.271 jMSSessionResourcerollbackCount-count 36.281 jMSSessionResourcetransactionCount-count 41.1 eJBEngineMoobjectName 41.2 eJBEngineMoblockThreadCount 41.3 eJBEngineMostats 41.4 eJBEngineMotroubles 41.5 eJBEngineMoownTroubles 51.1 contextGroupMoobjectName 51.2 contextGroupMowebModules 51.3 contextGroupMowebListeners 51.4 contextGroupMosessionContainer 51.5 contextGroupMosessionTimeout 51.6 contextGroupMotroubles 51.7 contextGroupMoownTroubles 52.1 dBConnectionPoolMoobjectName 52.2 dBConnectionPoolMoblockDuration

52.3 dBConnectionPoolModBConnectionPoolInfo-dBConnectionInfo 52.4 dBConnectionPoolModBConnectionPoolInfo-currentPoolSize

- 52.5 dBConnectionPoolModBConnectionPoolInfo-freeConnectionNum
- 52.6 dBConnectionPoolModBConnectionPoolInfo-activeConnectionNum
- 52.7 dBConnectionPoolModBConnectionPoolInfo-connectionPoolID
- 52.8 dBConnectionPoolModBConnectionPoolInfo-connectionPoolingRule
- 52.9 dBConnectionPoolModBConnectionPoolInfo-connectionUrl
- 52.10 dBConnectionPoolModBConnectionPoolInfo-driverClassName
- $52.11 \ dB Connection {\tt PoolModBConnectionPoolInfo-connectionArgs}$
- 52.12 dBConnectionPoolModBConnectionPoolInfo-initCapacity
- 52.13 dBConnectionPoolModBConnectionPoolInfo-maxCapacity
- 52.14 dBConnectionPoolModBConnectionPoolInfo-incrementRate
- 52.15 dBConnectionPoolModBConnectionPoolInfo-maxIdleTime
- 52.17 dBConnectionPoolModBConnectionPoolInfo-dynamicIncrement
- 52.18 dBConnectionPoolModBConnectionPoolInfo-connectionTimeOut
- 52.19 dBConnectionPoolModBConnectionPoolInfo-loginDelay
- 52.20 dBConnectionPoolModBConnectionPoolInfo-closeDelay
- 52.21 dBConnectionPoolModBConnectionPoolInfo-

closeLongActiveConnection

- 52.22 dBConnectionPoolModBConnectionPoolInfo-maxActiveTime
- 52.23 dBConnectionPoolModBConnectionPoolInfo-maxUseCount
- 52.24 dBConnectionPoolModBConnectionPoolInfo-checkQuery
- 52.26 dBConnectionPoolMomin
- 52.28 dBConnectionPoolMomax
- 52.30 dBConnectionPoolMostep
- 52.31 dBConnectionPoolModBConnectionPoolInfo-maxAliveTime
- 52.33 dBConnectionPoolMomaxIdleTime
- 52.35 dBConnectionPoolMomaxAliveTime
- 52.37 dBConnectionPoolModynamicIncrement
- 52.38 dBConnectionPoolMogetConnectionTimeout
- 52.39 dBConnectionPoolMocloseLongActiveConnection
- 52.40 dBConnectionPoolMomaxActiveTime
- 52.42 dBConnectionPoolMomaxUseCount
- 52.43 dBConnectionPoolMotroubles
- 52.44 dBConnectionPoolMoownTroubles
- 52.101 dBConnectionPoolMoactiveThreadCount-count
- 52.111 dBConnectionPoolMoblockThreadCount-count
- 52.121 dBConnectionPoolMoallThreadCount-count
- 53.1 threadPoolMoobjectName
- 53.3 threadPoolMomin
- 53.5 threadPoolMomax

- 53.7 threadPoolMostep
- 53.9 threadPoolMomaxIdleTime
- 53.11 threadPoolMomaxQueue
- 53.13 threadPoolMomaxWaitQueue
- 53.14 threadPoolMomaxThreadActiveTime
- 53.15 threadPoolMonotifyThreshold
- 53.16 threadPoolMorestartThreshold
- 53.17 threadPoolMotroubles
- 53.18 threadPoolMoownTroubles
- 53.101 threadPoolMoactiveThreadCount-count
- 53.111 threadPoolMoblockThreadCount-count
- 53.121 threadPoolMoallThreadCount-count
- 53.131 threadPoolMomaxThreadCount-count
- 53.141 threadPoolMowaitQueueCount-count
- 54.1 webEngineMoobjectName
- 54.2 webEngineMocontextGroups
- 54.3 webEngineMoconfigInfo
- 54.4 webEngineMoserverStatus
- 54.5 webEngineModBConnectionPool
- 54.6 webEngineMocontextGroupNames
- 54.7 webEngineMosessionContainer
- 54.8 webEngineMowebtConnectionGroup
- 54.9 webEngineMoconfiguration
- 54.11 webEngineMocheckThreadPool
- 54.13 webEngineMocheckClassReload
- 54.15 webEngineMocheckSession
- 54.17 webEngineMocheckDbConnectionPool
- 54.18 webEngineMotroubles
- 54.19 webEngineMoownTroubles
- 54.101 webEngineMofreeMemory-count
- 54.111 webEngineMototalMemory-count
- 55.1 webListenerMoobjectName
- 55.2 webListenerMothreadPools
- 55.3 webListenerMotype
- 55.4 webListenerMoport
- 55.6 webListenerMoreadTimeout
- 55.8 webListenerMoreconnectTimeout
- 55.10 webListenerMopostdataReadTimeout
- 55.11 webListenerMotroubles

- 55.12 webListenerMoownTroubles
- 56.1 webtConnectionGroupMoobjectName
- 56.2 webtConnectionGroupMotroubles
- 56.3 webtConnectionGroupMoownTroubles
- 56.101 webtConnectionGroupMototalConnectionCount-count
- 56.111 webtConnectionGroupMofreeConnectionCount-count
- 56.121 webtConnectionGroupMousedConnectionCount-count
- 61.1 jMSClientResourceobjectName
- 61.2 jMSClientResourcehostAddress
- 61.3 jMSClientResourceport
- 61.4 jMSClientResourcejMSConnectionResourceNames
- 61.6 jMSClientResourcenamePartString
- 61.7 jMSClientResourcetroubles
- 61.8 jMSClientResourceownTroubles
- 61.101 jMSClientResourceconnectionCount-count
- 62.1 jMSQueueConnectionFactoryResourceobjectName
- 62.3 jMSQueueConnectionFactoryResourcename
- 62.4 jMSQueueConnectionFactoryResourcetroubles
- 62.5 jMSQueueConnectionFactoryResourceownTroubles
- 63.1 jMSQueueDestinationResourceobjectName
- 63.2 jMSQueueDestinationResourcename
- 63.3 jMSQueueDestinationResourceexportName
- 63.4 jMSQueueDestinationResourcetype
- 63.8 jMSQueueDestinationResourcedestination
- 63.9 jMSQueueDestinationResourcejMSConsumerResourceNames
- 63.10 jMSQueueDestinationResourceremainingMessages
- 63.11 jMSQueueDestinationResourcetroubles
- 63.12 jMSQueueDestinationResourceownTroubles
- 63.101 jMSQueueDestinationResourcemessageCount-count
- 63.111 jMSQueueDestinationResourcependingMessageCount-count
- 63.121 jMSQueueDestinationResourceexpiredMessageCount-count
- 63.122 jMSQueueDestinationResourcemessageWaitTime-count
- 63.123 jMSQueueDestinationResourcemessageWaitTime-maxTime
- 63.124 jMSQueueDestinationResourcemessageWaitTime-minTime
- 63.125 jMSQueueDestinationResourcemessageWaitTime-totalTime
- 63.131 jMSQueueDestinationResourcesendTime-count
- 63.132 jMSQueueDestinationResourcesendTime-maxTime
- 63.133 jMSQueueDestinationResourcesendTime-minTime
- 63.134 jMSQueueDestinationResourcesendTime-totalTime

- 64.1 jMSDurableSubscriberResourceobjectName
- 64.2 jMSDurableSubscriberResourcename
- 64.3 jMSDurableSubscriberResourceclientID
- 64.5 jMSDurableSubscriberResourceremainingMessages
- 64.6 jMSDurableSubscriberResourceselector
- 64.7 jMSDurableSubscriberResourcejMSConsumerResourceName
- 64.8 jMSDurableSubscriberResourcetroubles
- 64.9 jMSDurableSubscriberResourceownTroubles
- 65.1 jMSTopicConnectionFactoryResourceobjectName
- 65.3 jMSTopicConnectionFactoryResourcename
- 65.4 jMSTopicConnectionFactoryResourcetroubles
- 65.5 jMSTopicConnectionFactoryResourceownTroubles
- 66.1 jMSTopicDestinationResourceobjectName
- 66.2 jMSTopicDestinationResourcename
- 66.3 jMSTopicDestinationResourceexportName
- 66.4 jMSTopicDestinationResourcetype
- 66.6 jMSTopicDestinationResourcejMSDurableSubscriberResourceNames
- 66.8 jMSTopicDestinationResourcedestination
- 66.9 jMSTopicDestinationResourcejMSConsumerResourceNames
- 66.10 jMSTopicDestinationResourcetroubles
- 66.11 jMSTopicDestinationResourceownTroubles
- 66.101 jMSTopicDestinationResourcemessageCount-count
- 66.111 jMSTopicDestinationResourcependingMessageCount-count
- 66.121 jMSTopicDestinationResourceexpiredMessageCount-count
- 66.122 jMSTopicDestinationResourcemessageWaitTime-count
- 66.123 jMSTopicDestinationResourcemessageWaitTime-maxTime
- 66.124 jMSTopicDestinationResourcemessageWaitTime-minTime
- 66.125 jMSTopicDestinationResourcemessageWaitTime-totalTime
- 66.131 jMSTopicDestinationResourcesendTime-count
- 66.132 jMSTopicDestinationResourcesendTime-maxTime
- 66.133 jMSTopicDestinationResourcesendTime-minTime
- 66.134 jMSTopicDestinationResourcesendTime-totalTime
- 71.1 threadPoolobjectName
- 71.2 threadPoolthreadOperationInfo
- 71.4 threadPoolmax
- 71.6 threadPoolperiod
- 71.7 threadPooltroubles
- 71.8 threadPoolownTroubles
- 77.1 jEUSManagerobjectName

- 77.2 jEUSManagerserverVersion
- 77.3 jEUSManagerserverVendor
- 77.4 jEUSManagerjavaVMs
- 77.5 jEUSManagerjeusServices
- 77.6 jEUSManagerj2eeServers
- 77.9 jEUSManagernodesFromDescriptor
- 77.10 jEUSManageraliveNodeNames
- 77.11 jEUSManagerjeusHome
- 77.12 jEUSManagerpID
- 77.13 jEUSManagertroubles
- 77.14 jEUSManagerownTroubles
- 77.15 jEUSManagerj2eeServerNames
- 81.1 webServerInfoobjectName
- 81.2 webServerInfonodeInfo
- 81.3 webServerInfosvrAllInfo
- 81.4 webServerInfotroubles
- 81.5 webServerInfoownTroubles
- 81.101 webServerInfosvrCount-count
- 81.111 webServerInfoexecCount-count
- 81.121 webServerInfoavgTime-count
- 81.122 webServerInfoavgTime-maxTime
- 81.123 webServerInfoavqTime-minTime
- 81.124 webServerInfoavgTime-totalTime
- 92.1 externalWebtDataSourceobjectName
- 92.2 externalWebtDataSourcetype
- 92.3 externalWebtDataSourceport
- 92.4 externalWebtDataSourcewebtProperties
- 92.5 externalWebtDataSourceexportName
- 92.6 externalWebtDataSourcehostAddr
- 92.8 externalWebtDataSourcelevel
- 92.9 externalWebtDataSourcetroubles
- 92.10 externalWebtDataSourceownTroubles
- 92.101 externalWebtDataSourcecreateCount-count
- 92.111 externalWebtDataSourcecloseCount-count
- 92.121 externalWebtDataSourcepoolSize-upperBound
- 92.122 externalWebtDataSourcepoolSize-lowerBound
- 92.123 externalWebtDataSourcepoolSize-highWaterMark
- 92.124 externalWebtDataSourcepoolSize-lowWaterMark
- 92.125 externalWebtDataSourcepoolSize-current

92.131 externalWebtDataSourcefreePoolSize-upperBound 92.132 externalWebtDataSourcefreePoolSize-lowerBound 92.133 externalWebtDataSourcefreePoolSize-highWaterMark 92.134 externalWebtDataSourcefreePoolSize-lowWaterMark 92.135 externalWebtDataSourcefreePoolSize-current 92.141 externalWebtDataSourcewaitingThreadCount-highWaterMark 92.142 externalWebtDataSourcewaitingThreadCount-lowWaterMark 92.143 externalWebtDataSourcewaitingThreadCount-current 92.151 externalWebtDataSourcereConnectCount-count 92.161 externalWebtDataSourcetotalConnectionCount-count 92.171 externalWebtDataSourcefreeConnectionCount-count 92.181 externalWebtDataSourceactiveConnectionCount-count 101.1 subjectMoobjectName 101.2 subjectMosubjectNames 101.3 subjectMotroubles 101.4 subjectMoownTroubles 102.1 securityDomainMoobjectName 102.2 securityDomainModomainName 102.3 securityDomainMopolicys 102.4 securityDomainMosubjects 102.5 securityDomainMotroubles 102.6 securityDomainMoownTroubles 102.7 securityDomainModescription 103.1 policyMoobjectName 103.2 policyMopolicyIds 103.3 policyMotroubles 103.4 policyMoownTroubles 104.1 securityMoobjectName 104.2 securityMocurrentDomain 104.3 securityMosecurityDomains 104.4 securityMotroubles 104.5 securityMoownTroubles 105.1 jMSEngineMojMSResource 105.2 jMSEngineMoengineName 105.3 jMSEngineMoobjectName

105.4 jMSEngineMotroubles 105.5 jMSEngineMoownTroubles

A.4 TMAX-JEUS5.0-MIB.mib

```
TMAX-JEUS-MIB DEFINITIONS ::= BEGIN
IMPORTS
     enterprises, Counter
           FROM RFC1155-SMI
     OBJECT-TYPE
           FROM RFC-1212
     DisplayString
           FROM RFC1213-MIB
     TRAP-TYPE
           FROM RFC-1215;
tmax OBJECT IDENTIFIER ::= { enterprises 14586 }
jeus OBJECT IDENTIFIER ::= { tmax 100 }
-- SNMP moniroting objects in each MBeans
-- j2EEDomain
j2EEDomain OBJECT IDENTIFIER
   ::= { jeus 2 }
j2EEDomainobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { j2EEDomain 1 }
j2EEDomainservers OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of the J2EE Servers that this
domain includes"
   ::= { j2EEDomain 2 }
j2EEDomaintroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { j2EEDomain 3 }
j2EEDomainownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { j2EEDomain 4 }
_____
-- j2EEServer
_____
j2EEServer OBJECT IDENTIFIER
   ::= { jeus 3 }
j2EEServerobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { j2EEServer 1 }
j2EEServerserverVersion OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the version of JEUS that is being used"
    j2EEServerserverVendor OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the J2EE platform vendor of this J2EE Server"
   ::= { j2EEServer 3 }
j2EEServerjavaVMs OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of the JVMs on which J2EE
Server is running"
   ::= { j2EEServer 4 }
j2EEServerdeployedObjects OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard object names of the J2EE Modules that are
deployed on this J2EE Server"
   ::= { j2EEServer 5 }
j2EEServerresources OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of the J2EE Resources that can
be used in this J2EE Server"
   ::= { j2EEServer 6 }
j2EEServerjeusServices OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { j2EEServer 8 }
j2EEServerengines OBJECT-TYPE
  SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { j2EEServer 9 }
j2EEServerenginesFromDescriptor OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { j2EEServer 10 }
j2EEServerdistributedModules OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { j2EEServer 15 }
j2EEServernodeName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { j2EEServer 17 }
j2EEServerappPaths OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { j2EEServer 18 }
j2EEServertroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       11 11
   ::= { j2EEServer 19 }
j2EEServerownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { j2EEServer 20 }
_____
-- jVM
jVM OBJECT IDENTIFIER
  ::= { jeus 4 }
jVMobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jVM 1 }
jVMjavaVersion OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the system property value of java.version"
   ::= { jVM 2 }
jVMjavaVendor OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      "the system property value of java.vendor"
```

```
::= { jVM 3 }
jVMnode
         OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the host name and ip address of the machine on which
this JVM is running"
   ::= { jVM 4 }
jVMoSName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the system property value of os.name"
   ::= { jVM 6 }
jVMoSVersion OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the system property value of os.version"
   ::= { jVM 7 }
jVMallProperties OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the all system property values"
   ::= { jVM 8 }
jVMtroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jVM 9 }
jVMownTroubles OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jVM 10 }
jVMheapSize-upperBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jVM 101 }
jVMheapSize-lowerBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jVM 102 }
jVMheapSize-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jVM 103 }
jVMheapSize-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jVM 104 }
jVMheapSize-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { jVM 105 }
jVMupTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jVM 111 }
jVMtotalSize-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jVM 121 }
jVMtotalSize-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jVM 122 }
jVMtotalSize-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jVM 123 }
-- j2EEApplication
j2EEApplication OBJECT IDENTIFIER
   ::= { jeus 6 }
j2EEApplicationobjectName OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { j2EEApplication 1 }
j2EEApplicationdeploymentDescriptor OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { j2EEApplication 2 }
j2EEApplicationserver OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { j2EEApplication 3 }
j2EEApplicationmodules OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { j2EEApplication 4 }
j2EEApplicationmoduleType OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { j2EEApplication 5 }
j2EEApplicationapplicationType OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { j2EEApplication 6 }
j2EEApplicationjeusDeploymentPlan OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { j2EEApplication 7 }
j2EEApplicationtargetModuleID OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { j2EEApplication 8 }
j2EEApplicationtroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { j2EEApplication 9 }
j2EEApplicationownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { j2EEApplication 10 }
-- appClientModule
appClientModule OBJECT IDENTIFIER
   ::= { jeus 8 }
appClientModuleobjectName OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { appClientModule 1 }
appClientModuledeploymentDescriptor OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { appClientModule 2 }
appClientModuleserver OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { appClientModule 3 }
appClientModulejavaVMs OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { appClientModule 4 }
appClientModuleapplicationType OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { appClientModule 5 }
appClientModulemoduleType OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { appClientModule 6 }
appClientModulejeusDeploymentPlan OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { appClientModule 7 }
appClientModuletargetModuleID OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { appClientModule 8 }
appClientModuletroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { appClientModule 9 }
appClientModuleownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { appClientModule 10 }
-- eJBModule
eJBModule OBJECT IDENTIFIER
   ::= { jeus 9 }
eJBModuleobjectName OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard MBean object name"
    ::= { eJBModule 1 }
eJBModuledeploymentDescriptor OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "XML deployment descriptor of this module"
    ::= { eJBModule 2 }
eJBModuleserver OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the name of the J2EE Server(JEUS container) on which
this module is deployed"
    ::= { eJBModule 3 }
eJBModulejavaVMs OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard object names of the JVMs on which this
module is running"
    ::= { eJBModule 4 }
eJBModuleejbs OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard object names of the ejb
components(EntityBean, StatefullSessionBean, or
StatelessSessionBean) that this EJB Module includes"
   ::= { eJBModule 5 }
eJBModuleejbCount OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { eJBModule 6 }
eJBModuleclientViewPath OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { eJBModule 7 }
eJBModulejeusDeploymentPlan OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { eJBModule 8 }
eJBModuletargetModuleID OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { eJBModule 9 }
eJBModulemoduleType OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { eJBModule 10 }
eJBModuleapplicationType OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { eJBModule 11 }
eJBModuletroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { eJBModule 12 }
eJBModuleownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { eJBModule 13 }
-- messageDrivenBean
______
messageDrivenBean OBJECT IDENTIFIER
   ::= { jeus 11 }
messageDrivenBeanobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { messageDrivenBean 1 }
messageDrivenBeantroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { messageDrivenBean 2 }
messageDrivenBeanownTroubles OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { messageDrivenBean 3 }
messageDrivenBeancreateCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { messageDrivenBean 101 }
messageDrivenBeanremoveCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { messageDrivenBean 111 }
messageDrivenBeanrequestCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { messageDrivenBean 121 }
messageDrivenBeancommittedCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { messageDrivenBean 131 }
messageDrivenBeanrolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { messageDrivenBean 141 }
messageDrivenBeantimeoutRolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       п п
   ::= { messageDrivenBean 151 }
messageDrivenBeanmessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { messageDrivenBean 161 }
messageDrivenBeanactiveEJBBeanCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { messageDrivenBean 171 }
messageDrivenBeanactiveEJBBeanCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
    ::= { messageDrivenBean 172 }
messageDrivenBeanactiveEJBBeanCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { messageDrivenBean 173 }
messageDrivenBeantotalEJBBeanCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       11 11
   ::= { messageDrivenBean 181 }
messageDrivenBeantotalEJBBeanCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { messageDrivenBean 182 }
messageDrivenBeantotalEJBBeanCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { messageDrivenBean 183 }
_____
-- entityBean
_____
entityBean OBJECT IDENTIFIER
   ::= { jeus 12 }
entityBeanobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { entityBean 1 }
entityBeantroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { entityBean 2 }
entityBeanownTroubles
                     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { entityBean 3 }
entityBeancreateCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the beans that is created by create()
method"
   entityBeanremoveCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the beans that is removed by remove()
method"
   ::= { entityBean 111 }
entityBeanrequestCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the requests on this bean"
   ::= { entityBean 121 }
entityBeancommittedCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that is committed"
   entityBeanrolledbackCount-count OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that is rollbacked"
   entityBeantimeoutRolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that is rollbacked by
timeout"
   ::= { entityBean 151 }
entityBeanreadyCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the highest number of the bean instances that are READY
state"
   ::= { entityBean 161 }
entityBeanreadyCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the lowest number of the bean instances that are READY
state"
   ::= { entityBean 162 }
entityBeanreadyCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the current number of the bean instances that are READY
state"
   ::= { entityBean 163 }
entityBeanpooledCount-highWaterMark OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the bean instances that are POOLED
state"
    ::= { entityBean 171 }
entityBeanpooledCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the bean instances that are POOLED
state"
    ::= { entityBean 172 }
entityBeanpooledCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the bean instances that are POOLED
state"
    ::= { entityBean 173 }
entityBeanautoRemovedEJBObjectCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the bean instances that are removed
automatically when they are passivated"
    ::= { entityBean 181 }
entityBeantotalEJBBeanCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the bean instances that are in the
bean pool of this bean"
   ::= { entityBean 191
```

```
entityBeantotalEJBBeanCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the bean instances that are in the
bean pool of this bean"
    ::= { entityBean 192 }
entityBeantotalEJBBeanCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the bean instances that are in the
bean pool of this bean"
    ::= { entityBean 193 }
entityBeanactiveEJBBeanCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the bean instances that are ACTIVE
state"
    ::= { entityBean 201 }
entityBeanactiveEJBBeanCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the bean instances that are ACTIVE
state"
    ::= { entityBean 202 }
entityBeanactiveEJBBeanCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the bean instances that are ACTIVE
state"
```

```
::= { entityBean 203 }
entityBeantotalThreadCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the threads that are in thread
pool of this bean"
   ::= { entityBean 211 }
entityBeantotalThreadCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the threads that are in thread pool
of this bean"
   ::= { entityBean 212 }
entityBeantotalThreadCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the threads that are in thread
pool of this bean"
   ::= { entityBean 213 }
entityBeanactiveThreadCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the highest number of the threads that are being used in
thread pool of this bean"
   ::= { entityBean 221 }
entityBeanactiveThreadCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the lowest number of the threads that are being used in
thread pool of this bean"
    ::= { entityBean 222 }
entityBeanactiveThreadCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the current number of the threads that are being used in
thread pool of this bean"
    ::= { entityBean 223 }
entityBeantotalEJBObjectCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the objects that are in connection
pool of this bean"
   ::= { entityBean 231 }
entityBeantotalEJBObjectCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the objects that are in connection
pool of this bean"
   ::= { entityBean 232 }
entityBeantotalEJBObjectCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the objects that are in connection
pool of this bean"
    ::= { entityBean 233 }
entityBeanactiveEJBObjectCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
       "the highest number of the objects that are being useed
in connection pool of this bean"
    entityBeanactiveEJBObjectCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the lowest number of the objects that are being useed in
connection pool of this bean"
    ::= { entityBean 242 }
entityBeanactiveEJBObjectCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the current number of the objects that are being useed
in connection pool of this bean"
    ::= { entityBean 243 }
entityBeanpassiveCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the highest number of the bean instances that are
passivated"
    ::= { entityBean 251 }
entityBeanpassiveCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the lowest number of the bean instances that are
passivated"
   ::= { entityBean 252 }
entityBeanpassiveCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       "the current number of the bean instances that are
passivated"
   ::= { entityBean 253 }
_____
-- statefulSessionBean
_____
statefulSessionBean OBJECT IDENTIFIER
   ::= { jeus 14 }
statefulSessionBeanobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { statefulSessionBean 1 }
statefulSessionBeantroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { statefulSessionBean 2 }
statefulSessionBeanownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { statefulSessionBean 3 }
statefulSessionBeancreateCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the number of the beans that is created by create()
method"
    ::= { statefulSessionBean 101 }
statefulSessionBeanremoveCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the beans that is removed by remove()
method"
    ::= { statefulSessionBean 111 }
statefulSessionBeanrequestCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the requests on this bean"
   ::= { statefulSessionBean 121 }
statefulSessionBeancommittedCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the transactions that is committed"
    ::= { statefulSessionBean 131 }
statefulSessionBeanrolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that is rollbacked"
    ::= { statefulSessionBean 141 }
statefulSessionBeantimeoutRolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that is rollbacked by
timeout"
```

```
::= { statefulSessionBean 151 }
statefulSessionBeanmethodReadyCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the higest number of the beans that are METHOD-READY
state"
   ::= { statefulSessionBean 161 }
statefulSessionBeanmethodReadyCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the beans that are METHOD-READY
state"
   ::= { statefulSessionBean 162 }
statefulSessionBeanmethodReadyCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the beans that are METHOD-READY
state"
    ::= { statefulSessionBean 163 }
statefulSessionBeanpassiveCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the bean instances that are
passivated"
    ::= { statefulSessionBean 171 }
statefulSessionBeanpassiveCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the lowest number of the bean instances that are
passivated"
    ::= { statefulSessionBean 172 }
statefulSessionBeanpassiveCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the current number of the bean instances that are
passivated"
    ::= { statefulSessionBean 173 }
statefulSessionBeanautoRemovedEJBObjectCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the bean instances that are removed
automatically when they are passivated"
    ::= { statefulSessionBean 181 }
statefulSessionBeantotalEJBBeanCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the bean instances that are in the
bean pool of this bean"
    ::= { statefulSessionBean 191 }
statefulSessionBeantotalEJBBeanCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the bean instances that are in the
bean pool of this bean"
   ::= { statefulSessionBean 192 }
statefulSessionBeantotalEJBBeanCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
        "the current number of the bean instances that are in the
bean pool of this bean"
   ::= { statefulSessionBean 193 }
statefulSessionBeanactiveEJBBeanCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the highest number of the bean instances that are ACTIVE
state"
    ::= { statefulSessionBean 201 }
statefulSessionBeanactiveEJBBeanCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the lowest number of the bean instances that are ACTIVE
state"
    ::= { statefulSessionBean 202 }
statefulSessionBeanactiveEJBBeanCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the current number of the bean instances that are ACTIVE
state"
    ::= { statefulSessionBean 203 }
statefulSessionBeantotalThreadCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the highest number of the threads that are in thread
pool of this bean"
    ::= { statefulSessionBean 211 }
statefulSessionBeantotalThreadCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
        "the lowest number of the threads that are in thread pool
of this bean"
   ::= { statefulSessionBean 212 }
statefulSessionBeantotalThreadCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the threads that are in thread
pool of this bean"
   ::= { statefulSessionBean 213 }
statefulSessionBeanactiveThreadCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the threads that are being used in
thread pool of this bean"
   ::= { statefulSessionBean 221 }
statefulSessionBeanactiveThreadCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the threads that are being used in
thread pool of this bean"
    ::= { statefulSessionBean 222 }
statefulSessionBeanactiveThreadCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the threads that are being used in
thread pool of this bean"
   ::= { statefulSessionBean 223 }
statefulSessionBeantotalEJBObjectCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the objects that are in connection
pool of this bean"
    ::= { statefulSessionBean 231 }
statefulSessionBeantotalEJBObjectCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the objects that are in connection
pool of this bean"
   ::= { statefulSessionBean 232 }
statefulSessionBeantotalEJBObjectCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the objects that are in connection
pool of this bean"
    ::= { statefulSessionBean 233 }
statefulSessionBeanactiveEJBObjectCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the objects that are being useed
in connection pool of this bean"
    ::= { statefulSessionBean 241 }
statefulSessionBeanactiveEJBObjectCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the objects that are being useed in
connection pool of this bean"
   ::= { statefulSessionBean 242 }
statefulSessionBeanactiveEJBObjectCount-current OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the current number of the objects that are being useed
in connection pool of this bean"
   ::= { statefulSessionBean 243 }
statefulSessionBeanfileDBSizeCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the biggest size of the file that contains the beans
that is passivated"
   ::= { statefulSessionBean 251 }
statefulSessionBeanfileDBSizeCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the smallest size of the file that contains the beans
that is passivated"
   ::= { statefulSessionBean 252 }
statefulSessionBeanfileDBSizeCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the current size of the file that contains the beans
that is passivated"
   ::= { statefulSessionBean 253 }
-- statelessSessionBean
statelessSessionBean OBJECT IDENTIFIER
   ::= { jeus 15 }
```

```
statelessSessionBeanobjectName
                                  OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { statelessSessionBean 1 }
statelessSessionBeantroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { statelessSessionBean 2 }
statelessSessionBeanownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { statelessSessionBean 3 }
statelessSessionBeancreateCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the beans that is created by create()
method"
    ::= { statelessSessionBean 101 }
statelessSessionBeanremoveCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the beans that is removed by remove()
method"
    ::= { statelessSessionBean 111 }
statelessSessionBeanrequestCount-count OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the requests on this bean"
    ::= { statelessSessionBean 121 }
statelessSessionBeancommittedCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that is committed"
   ::= { statelessSessionBean 131 }
statelessSessionBeanrolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that is rollbacked"
   ::= { statelessSessionBean 141 }
statelessSessionBeantimeoutRolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that is rollbacked by
timeout"
    ::= { statelessSessionBean 151 }
statelessSessionBeanmethodReadyCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the higest number of the beans that are METHOD-READY
state"
   ::= { statelessSessionBean 161 }
statelessSessionBeanmethodReadyCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
        "the lowest number of the beans that are METHOD-READY
state"
    ::= { statelessSessionBean 162 }
statelessSessionBeanmethodReadyCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the current number of the beans that are METHOD-READY
state"
    ::= { statelessSessionBean 163 }
statelessSessionBeantotalEJBBeanCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the highest number of the bean instances that are in the
bean pool of this bean"
    ::= { statelessSessionBean 171 }
statelessSessionBeantotalEJBBeanCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the lowest number of the bean instances that are in the
bean pool of this bean"
    ::= { statelessSessionBean 172 }
statelessSessionBeantotalEJBBeanCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the current number of the bean instances that are in the
bean pool of this bean"
    ::= { statelessSessionBean 173 }
statelessSessionBeanactiveEJBBeanCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
        "the highest number of the bean instances that are ACTIVE
state"
   ::= { statelessSessionBean 181 }
statelessSessionBeanactiveEJBBeanCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the lowest number of the bean instances that are ACTIVE
state"
   ::= { statelessSessionBean 182 }
statelessSessionBeanactiveEJBBeanCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the bean instances that are ACTIVE
state"
   ::= { statelessSessionBean 183 }
statelessSessionBeantotalThreadCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the threads that are in thread
pool of this bean"
    ::= { statelessSessionBean 191 }
statelessSessionBeantotalThreadCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the threads that are in thread pool
of this bean"
   ::= { statelessSessionBean 192 }
statelessSessionBeantotalThreadCount-current OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the threads that are in thread
pool of this bean"
   ::= { statelessSessionBean 193 }
statelessSessionBeanactiveThreadCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the threads that are being used in
thread pool of this bean"
   ::= { statelessSessionBean 201 }
statelessSessionBeanactiveThreadCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the threads that are being used in
thread pool of this bean"
   ::= { statelessSessionBean 202 }
statelessSessionBeanactiveThreadCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the threads that are being used in
thread pool of this bean"
    ::= { statelessSessionBean 203 }
-- webModule
webModule OBJECT IDENTIFIER
   ::= { jeus 16 }
webModuleobjectName OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { webModule 1 }
webModuledeploymentDescriptor OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "XML deployment descriptor of this module"
   ::= { webModule 2 }
webModuleserver OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the name of the J2EE Server(JEUS container) on which
this module is deployed"
   ::= { webModule 3 }
webModulejavaVMs OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard object names of the JVMs on which this
module is running"
    ::= { webModule 4 }
webModuleservlets OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard object names of the Servlets that this Web
Module includes"
   ::= { webModule 5 }
webModulecontextGroupObjectName OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard object names of the context group on which
this Web Module is deployed"
   ::= { webModule 6 }
webModulecontextGroup OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the names of the context group on which this Web Module
is deployed"
   ::= { webModule 7 }
webModulerealDocBase
                      OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webModule 8 }
webModulejeusDeploymentPlan OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
    ::= { webModule 9 }
webModuletargetModuleID OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webModule 10 }
webModulemoduleType
                    OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
      11 11
   ::= { webModule 11 }
webModuleapplicationType OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webModule 12 }
webModuleautoReload OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { webModule 13 }
webModuletroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { webModule 14 }
webModuleownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { webModule 15 }
webModulerequestCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the requests on this web module"
    ::= { webModule 101 }
webModuleallSessionsSize-count OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the all sessions that is registered on the
session server that this Web Module is using"
    ::= { webModule 111 }
webModuleactiveSessionsSize-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the active sessions that is registered on
the session server that this Web Module is using"
    ::= { webModule 121 }
webModulepassivateSessionsSize-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the passivated sessions that is registered
on the session server that this Web Module is using"
    ::= { webModule 131 }
webModulelocalSessionsSize-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the local sessions that is not related to
the session server that this Web Module is using"
    ::= { webModule 141 }
webModuleprocessingTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
    ::= { webModule 151 }
```

```
_____
-- servlet
_____
servlet OBJECT IDENTIFIER
   ::= { jeus 17 }
servletobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { servlet 1 }
servletservletInfo OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the general information of the servlets that is
deployed"
   ::= { servlet 2 }
servletaverageExecutionTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the average execution time of the servlets that is
deplyed in milliseconds"
   ::= { servlet 3 }
servlettroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { servlet 4 }
servletownTroubles OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { servlet 5 }
servletserviceTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of times that Servelt serves"
   ::= { servlet 101 }
servletserviceTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the longest time that Servlet serves"
   ::= { servlet 102 }
servletserviceTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the shortest time that Servlet serves"
   ::= { servlet 103 }
servletserviceTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total time that Servlet serves"
   ::= { servlet 104 }
-- resourceAdapterModule
______
resourceAdapterModule OBJECT IDENTIFIER
```

```
::= { jeus 18 }
resourceAdapterModuleobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { resourceAdapterModule 1 }
resourceAdapterModuledeploymentDescriptor OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { resourceAdapterModule 2 }
resourceAdapterModuleserver OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { resourceAdapterModule 3 }
resourceAdapterModulejavaVMs OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { resourceAdapterModule 4 }
resourceAdapterModulemoduleType OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { resourceAdapterModule 6 }
resourceAdapterModuleapplicationType OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { resourceAdapterModule 7 }
resourceAdapterModulejeusDeploymentPlan OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { resourceAdapterModule 8 }
resourceAdapterModuletargetModuleID OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { resourceAdapterModule 9 }
resourceAdapterModulemin OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { resourceAdapterModule 10 }
resourceAdapterModulemax
                           OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { resourceAdapterModule 11 }
resourceAdapterModulestep OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
```

```
::= { resourceAdapterModule 12 }
resourceAdapterModulekeepAliveTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { resourceAdapterModule 13 }
resourceAdapterModulereleaseTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { resourceAdapterModule 14 }
resourceAdapterModulerejectTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { resourceAdapterModule 15 }
resourceAdapterModuletroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { resourceAdapterModule 16 }
resourceAdapterModuleownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { resourceAdapterModule 17 }
_____
-- resourceAdapter
```

```
_____
resourceAdapter OBJECT IDENTIFIER
   ::= { jeus 19 }
resourceAdapterobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { resourceAdapter 1 }
resourceAdaptertroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { resourceAdapter 2 }
resourceAdapterownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { resourceAdapter 3 }
-- javaMailResource
______
javaMailResource OBJECT IDENTIFIER
   ::= { jeus 21 }
javaMailResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { javaMailResource 1 }
javaMailResourceproperty OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { javaMailResource 2 }
javaMailResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
     11 11
   ::= { javaMailResource 3 }
javaMailResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { javaMailResource 4 }
._____
-- jCAResource
______
jCAResource OBJECT IDENTIFIER
   ::= { jeus 22 }
jCAResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jCAResource 1 }
jCAResourcecMInfo OBJECT-TYPE
```

```
SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jCAResource 4 }
jCAResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jCAResource 5 }
jCAResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jCAResource 6 }
_____
-- jCAConnectionFactory
______
jCAConnectionFactory OBJECT IDENTIFIER
   ::= { jeus 23 }
jCAConnectionFactoryobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jCAConnectionFactory 1 }
jCAConnectionFactorycMInfo OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
      11 11
   ::= { jCAConnectionFactory 2 }
jCAConnectionFactorymin OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { jCAConnectionFactory 3 }
jCAConnectionFactorymax OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { jCAConnectionFactory 4 }
jCAConnectionFactorymaxWaiter OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jCAConnectionFactory 5 }
jCAConnectionFactorymaxDisposableCount OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { jCAConnectionFactory 6 }
jCAConnectionFactorywaitTrial OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { jCAConnectionFactory 7 }
jCAConnectionFactorywaitingTime OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       п п
   ::= { jCAConnectionFactory 8 }
jCAConnectionFactorypooledTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jCAConnectionFactory 9 }
jCAConnectionFactorydissociationtimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jCAConnectionFactory 10 }
jCAConnectionFactoryinvalidationtimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { jCAConnectionFactory 11 }
jCAConnectionFactoryskipMatching OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jCAConnectionFactory 13 }
jCAConnectionFactoryuseWrapper OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
```

```
::= { jCAConnectionFactory 14 }
jCAConnectionFactorytroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jCAConnectionFactory 15 }
jCAConnectionFactoryownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jCAConnectionFactory 16 }
-- jCAManagedConnectionFactory
jCAManagedConnectionFactory OBJECT IDENTIFIER
   ::= { jeus 24 }
jCAManagedConnectionFactoryobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jCAManagedConnectionFactory 1 }
jCAManagedConnectionFactorytroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jCAManagedConnectionFactory 2 }
jCAManagedConnectionFactoryownTroubles OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jCAManagedConnectionFactory 3 }
_____
-- jDBCResource
_____
jDBCResource OBJECT IDENTIFIER
   ::= { jeus 25 }
jDBCResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jDBCResource 1 }
jDBCResourcejdbcDataSources OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of JDBC Data Sources that is
related to this JDBC Resource"
   ::= { jDBCResource 2 }
jDBCResourcecPInfo OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jDBCResource 3 }
jDBCResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jDBCResource 4 }
jDBCResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jDBCResource 5 }
jDBCResourceconnectionPools-createCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the connected connections in the
connection pool of each JDBC Data Sources that is related to this
JDBC Resource"
    ::= { jDBCResource 101 }
jDBCResourceconnectionPools-closeCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the disconnected connections in the
connection pool of each JDBC Data Sources that is related to this
JDBC Resource"
   ::= { jDBCResource 111 }
jDBCResourceconnectionPools-poolSize-upperBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the max value that is configured to be upper bound of
the pool size of the connection pool of each JDBC Data Sources
that is related to this JDBC Resource"
   ::= { jDBCResource 121 }
jDBCResourceconnectionPools-poolSize-lowerBound OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the min value that is configured to be lower bound of
the pool size of the connection pool of each JDBC Data Sources
that is related to this JDBC Resource"
   ::= { jDBCResource 122 }
jDBCResourceconnectionPools-poolSize-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest value of the pool size of the connection
pool of each JDBC Data Sources that is related to this JDBC
Resource"
   ::= { jDBCResource 123 }
jDBCResourceconnectionPools-poolSize-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest value of the pool size of the connection pool
of each JDBC Data Sources that is related to this JDBC Resource"
    ::= { jDBCResource 124 }
jDBCResourceconnectionPools-poolSize-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current value of the pool size of the connection
pool of each JDBC Data Sources that is related to this JDBC
Resource"
   ::= { jDBCResource 125 }
jDBCResourceconnectionPools-freePoolSize-upperBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the upper bound of the free connections in the
connection pool of each JDBC Data Sources that is related to this
JDBC Resource (It is equal to the connectionPools-PoolSize-
UpperBound)"
   ::= { jDBCResource 131 }
jDBCResourceconnectionPools-freePoolSize-lowerBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lower bound of the free connections in the
connection pool of each JDBC Data Sources that is related to this
JDBC Resource (It is set to be 0)"
   ::= { jDBCResource 132 }
jDBCResourceconnectionPools-freePoolSize-highWaterMark
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the free connections in the
connection pool of each JDBC Data Source that is related to this
JDBC Resource"
    ::= { jDBCResource 133 }
jDBCResourceconnectionPools-freePoolSize-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the free connections in the
connection pool of each JDBC Data Source that is related to this
JDBC Resource"
   ::= { jDBCResource 134 }
jDBCResourceconnectionPools-freePoolSize-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the current number of the free connections in the
connection pool of each JDBC Data Source that is related to this
JDBC Resource"
    ::= { jDBCResource 135 }
jDBCResourceconnectionPools-waitingThreadCount-highWaterMark
     OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the highest number of the threads, which are waiting to
get connections from the connection pool of each JDBC Data
Sources that is related to this JDBC Resource"
    ::= { jDBCResource 141 }
\verb|jdbCResourceconnectionPools-waitingThreadCount-lowWaterMark| \\
     OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the lowest number of the threads, which are waiting to
get connections from the connection pool of each JDBC Data
Sources that is related to this JDBC Resource"
    ::= { jDBCResource 142 }
jDBCResourceconnectionPools-waitingThreadCount-current
      OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the current number of the threads, which are waiting to
get connections from the connection pool of each JDBC Data
Sources that is related to this JDBC Resource"
    ::= { jDBCResource 143 }
jDBCResourceconnectionPools-waitTime-count OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
```

```
"the waiting time to get connection available in
connection pool"
   ::= { jDBCResource 161 }
jDBCResourceconnectionPools-waitTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the maximum waiting time to get connection available in
connection pool"
   ::= { jDBCResource 162 }
jDBCResourceconnectionPools-waitTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the minimum waiting time to get connection available in
connection pool"
   ::= { jDBCResource 163 }
jDBCResourceconnectionPools-waitTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total waiting time to get connection available in
connection pool"
   ::= { jDBCResource 164 }
jDBCResourceconnectionPools-useTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the time to use connection"
   ::= { jDBCResource 171 }
jDBCResourceconnectionPools-useTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the maximum time to use connection"
   ::= { jDBCResource 172 }
jDBCResourceconnectionPools-useTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the minimum time to use connection"
   ::= { jDBCResource 173 }
jDBCResourceconnectionPools-useTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total time to use connection"
   ::= { jDBCResource 174 }
jDBCResourceconnectionPools-jdbcDataSource OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object name of JDBC datasource of each
connectios in this connection pool"
   ::= { jDBCResource 181 }
-- jDBCDataSource
jDBCDataSource OBJECT IDENTIFIER
   ::= { jeus 26 }
jDBCDataSourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jDBCDataSource 1 }
```

```
jDBCDataSourcejdbcDriver OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object name of the JDBC Driver that is
related to this JDBC Data Source"
   ::= { jDBCDataSource 2 }
jDBCDataSourceconfig OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the config information about this JDBC Data Source"
   ::= { jDBCDataSource 3 }
jDBCDataSourcecPInfo OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jDBCDataSource 4 }
jDBCDataSourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jDBCDataSource 6 }
jDBCDataSourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jDBCDataSource 7 }
jDBCDataSourcecreateCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
        "the number of the connected connections to this JDBC
Data Source"
   ::= { jDBCDataSource 101 }
jDBCDataSourcecloseCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the disconnected connections to this JDBC
Data Source"
   ::= { jDBCDataSource 111 }
jDBCDataSourcepoolSize-upperBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the max value that is configured to be upper bound of
the pool size of the connection pool of this JDBC Data Source"
   ::= { jDBCDataSource 121 }
jDBCDataSourcepoolSize-lowerBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the min value that is configured to be lower bound of
the pool size of the connection pool of this JDBC Data Source"
    ::= { jDBCDataSource 122 }
jDBCDataSourcepoolSize-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest value of the pool size of the connection
pool of this JDBC Data Source"
   ::= { jDBCDataSource 123 }
jDBCDataSourcepoolSize-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the lowest value of the pool size of the connection pool
of this JDBC Data Source"
   ::= { jDBCDataSource 124 }
jDBCDataSourcepoolSize-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current value of the pool size of the connection
pool of this JDBC Data Source"
   ::= { jDBCDataSource 125 }
jDBCDataSourcefreePoolSize-upperBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the upper bound of the free connections in the
connection pool of this JDBC Data Source (It is equal to the
poolSize-UpperBound)"
    ::= { jDBCDataSource 131 }
jDBCDataSourcefreePoolSize-lowerBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lower bound of the free connections in the
connection pool of this JDBC Data Source (It is set to be 0)"
    ::= { jDBCDataSource 132 }
jDBCDataSourcefreePoolSize-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the free connections in the
connection pool of this JDBC Data Source"
    ::= { jDBCDataSource 133 }
```

```
jDBCDataSourcefreePoolSize-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the free connections in the
connection pool of this JDBC Data Source"
    ::= { jDBCDataSource 134 }
jDBCDataSourcefreePoolSize-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the current number of the free connections in the
connection pool of this JDBC Data Source"
    ::= { jDBCDataSource 135 }
jDBCDataSourcewaitingThreadCount-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the highest number of the threads, which are waiting to
get connections from the connection pool of this JDBC Data
Source"
    ::= { jDBCDataSource 141 }
jDBCDataSourcewaitingThreadCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the lowest number of the threads, which are waiting to
get connections from the connection pool of this JDBC Data
Source"
   ::= { jDBCDataSource 142 }
jDBCDataSourcewaitingThreadCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the current number of the threads, which are waiting to
get connections from the connection pool of this JDBC Data
Source"
   ::= { jDBCDataSource 143 }
jDBCDataSourcereConnectCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the reconnections to this JDBC Data
Source"
    ::= { jDBCDataSource 151 }
jDBCDataSourcewaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total number of requests that are waiting to get
connections from the connection pool of this JDBC Data Source"
    ::= { jDBCDataSource 161 }
jDBCDataSourcewaitTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the longest time for waiting to get connections from the
connection pool of this JDBC Data Source"
    ::= { jDBCDataSource 162 }
jDBCDataSourcewaitTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the shortest time for waiting to get connections from
the connection pool of this JDBC Data Source"
    ::= { jDBCDataSource 163 }
jDBCDataSourcewaitTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
        "the total time for waiting to get connections from the
connection pool of this JDBC Data Source"
   ::= { jDBCDataSource 164 }
jDBCDataSourceuseTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the total number of requests that use connections from
the connection pool of this JDBC Data Source"
   ::= { jDBCDataSource 171 }
jDBCDataSourceuseTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the longest time for using connections from the
connection pool of this JDBC Data Source"
   ::= { jDBCDataSource 172 }
jDBCDataSourceuseTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the shortest time for using connections from the
connection pool of this JDBC Data Source"
    ::= { jDBCDataSource 173 }
jDBCDataSourceuseTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the total time for using connections from the connection
pool of this JDBC Data Source"
   ::= { jDBCDataSource 174 }
______
```

```
-- jDBCDriver
_____
jDBCDriver OBJECT IDENTIFIER
   ::= { jeus 27 }
jDBCDriverobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jDBCDriver 1 }
jDBCDrivertroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jDBCDriver 2 }
jDBCDriverownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jDBCDriver 3 }
-- jMSResource
jMSResource OBJECT IDENTIFIER
   ::= { jeus 28 }
jMSResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
        "JMX-standard MBean object name"
    ::= { jMSResource 1 }
jMSResourceclusterInfo OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the information about the cluster of JMS server"
   ::= { jMSResource 3 }
jMSResourcejMSConnectionFactoryResourceNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the list of the names of JMS connection factory
resources that are belong to this JMS Resource"
    ::= { jMSResource 5 }
jMSResourcejMSDestinationResourceNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the list of the names of JMS destination resources that
are belong to this JMS Resource"
   ::= { jMSResource 6 }
jMSResourcejMSClientResourceNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the list of the names of JMS client resources that are
belong to this JMS Resource"
   ::= { jMSResource 7 }
jMSResourcefreeMemory OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { jMSResource 9 }
jMSResourcetotalMemory OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSResource 10 }
jMSResourcejMSConnectionFactoryResources OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jMSResource 11 }
jMSResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSResource 12 }
jMSResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
    ::= { jMSResource 13 }
jMSResourceconnections-sessions-messageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the messages that are processed in each
sessions"
   ::= { jMSResource 101 }
```

```
jMSResourceconnections-sessions-pendingMessageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that reside in each sessions
without acknoledgement"
   ::= { jMSResource 111
                            }
jMSResourceconnections-sessions-expiredMessageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are expired in each
sessions"
   ::= { jMSResource 121 }
jMSResourceconnections-sessions-messageWaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
    ::= { jMSResource 131 }
jMSResourceconnections-sessions-messageWaitTime-maxTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
   ::= { jMSResource 132 }
jMSResourceconnections-sessions-messageWaitTime-minTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
    DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
   ::= { jMSResource 133 }
jMSResourceconnections-sessions-messageWaitTime-totalTime
     OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the total period of time between when it creates message
and when it delivers message"
    ::= { jMSResource 134 }
\verb|jMSResourceconnections-sessions-durableSubscriptionCount-count|\\
     OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the number of the durable subscribers that are created
in each sessions"
    ::= { jMSResource 141 }
jMSResourceconnections-sessions-producers-destination OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "name of the destination to which each producers send
messages"
    ::= { jMSResource 151 }
jMSResourceconnections-sessions-producers-messageCount-count
     OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the number of the messages that are processed in each
producers"
```

```
::= { jMSResource 161 }
jMSResourceconnections-sessions-producers-pendingMessageCount-
count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that reside in each producers
without acknoledgement"
    ::= { jMSResource 171 }
jMSResourceconnections-sessions-producers-expiredMessageCount-
count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are expired in each
producers"
    ::= { jMSResource 181 }
jMSResourceconnections-sessions-producers-messageWaitTime-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
    ::= { jMSResource 191 }
jMSResourceconnections-sessions-producers-messageWaitTime-maxTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
   ::= { jMSResource 192 }
jMSResourceconnections-sessions-producers-messageWaitTime-minTime
     OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
   ::= { jMSResource 193 }
jMSResourceconnections-sessions-producers-messageWaitTime-
totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total period of time between when it creates message
and when it delivers message"
    ::= { jMSResource 194 }
jMSResourceconnections-sessions-consumers-origin OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "name of the destination that each consumers connect to"
   ::= { jMSResource 201 }
jMSResourceconnections-sessions-consumers-messageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the messages that are processed in each
consumers"
    ::= { jMSResource 211 }
jMSResourceconnections-sessions-consumers-pendingMessageCount-
count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the number of the messages that reside in each consumers
without acknoledgement"
    ::= { jMSResource 221 }
jMSResourceconnections-sessions-consumers-expiredMessageCount-
count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are expired in each
consumers"
    ::= { jMSResource 231 }
jMSResourceconnections-sessions-consumers-messageWaitTime-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
   ::= { jMSResource 241
                            }
jMSResourceconnections-sessions-consumers-messageWaitTime-maxTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
    ::= { jMSResource 242 }
jMSResourceconnections-sessions-consumers-messageWaitTime-minTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
    ::= { jMSResource 243
```

```
jMSResourceconnections-sessions-consumers-messageWaitTime-
totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total period of time between when it creates message
and when it delivers message"
   ::= { jMSResource 244 }
______
-- jNDIResource
_____
jNDIResource OBJECT IDENTIFIER
   ::= { jeus 29 }
jNDIResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jNDIResource 1 }
jNDIResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jNDIResource 2 }
jNDIResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { jNDIResource 3 }
```

```
_____
-- jTAResource
_____
jTAResource OBJECT IDENTIFIER
   ::= { jeus 30 }
jTAResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jTAResource 1 }
jTAResourceaverageExecutionTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "average processing time of the transactions that are
processed on J2EE Server"
    ::= { jTAResource 2 }
jTAResourceactiveTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jTAResource 3 }
jTAResourceprepareTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jTAResource 4 }
jTAResourcepreparedTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
```

```
STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jTAResource 5 }
jTAResourcecommitTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jTAResource 6 }
jTAResourcerecoveryTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jTAResource 7 }
jTAResourceuncompletedTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { jTAResource 8 }
jTAResourceheuristicRollback OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS write-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jTAResource 9 }
jTAResourceresolution OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { jTAResource 10 }
```

```
jTAResourcethreadPool OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jTAResource 11 }
jTAResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jTAResource 12 }
jTAResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jTAResource 13 }
jTAResourceactiveCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that are active"
   ::= { jTAResource 101 }
jTAResourcecommittedCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that are committed"
   ::= { jTAResource 111 }
jTAResourcerolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
       "the number of the transactions that are rollbacked"
    ::= { jTAResource 121 }
jTAResourcetimeoutCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that cause time-out"
   ::= { jTAResource 131 }
jTAResourcetimeoutRolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the transactions that is rollbacked by
timeout"
   ::= { jTAResource 141 }
jTAResourceactiveTimeoutCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the transactions that cause active time-
out"
   ::= { jTAResource 151 }
jTAResourceprepareTimeoutCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the transactions that cause time-out for
prepare message"
   ::= { jTAResource 161 }
jTAResourcepreparedTimeoutCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the number of the transactions that cause time-out for
the global desion message originated from the root coordinator"
    ::= { jTAResource 171 }
jTAResourcecommitTimeoutCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the transactions that cause time-out for
the root coordinator to receive the response from the sub-
coordinator"
    ::= { jTAResource 181 }
jTAResourceheuristicRolledbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the transactions that cause huristic
rolled-back"
    ::= { jTAResource 191 }
jTAResourceexecutionTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the requests that execute transactions"
    ::= { jTAResource 201 }
jTAResourceexecutionTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the longest execution time for all transactions"
    ::= { jTAResource 202 }
jTAResourceexecutionTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the shortest execution time for all transactions"
   ::= { jTAResource 203 }
jTAResourceexecutionTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total execution time for all transactions"
   ::= { jTAResource 204 }
______
-- uRLResource
_____
uRLResource OBJECT IDENTIFIER
   ::= { jeus 32 }
uRLResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { uRLResource 1 }
uRLResourceuRLInfo OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { uRLResource 2 }
uRLResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { uRLResource 3 }
uRLResourceownTroubles OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { uRLResource 4 }
_____
-- jMSConnectionResource
_____
jMSConnectionResource OBJECT IDENTIFIER
   ::= { jeus 33 }
jMSConnectionResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSConnectionResource 1 }
jMSConnectionResourcejMSSessionResourceNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of the session resource that
is created by this connection"
   ::= { jMSConnectionResource 2 }
jMSConnectionResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSConnectionResource 3 }
jMSConnectionResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
        11 11
    ::= { jMSConnectionResource 4 }
jMSConnectionResourcesessions-messageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are processed in each
sessions"
    ::= { jMSConnectionResource 101 }
jMSConnectionResourcesessions-pendingMessageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that reside in this session
without acknoledgement"
   ::= { jMSConnectionResource 111 }
jMSConnectionResourcesessions-expiredMessageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are expired in each
sessions"
   ::= { jMSConnectionResource 121 }
jMSConnectionResourcesessions-messageWaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
   ::= { jMSConnectionResource 131 }
jMSConnectionResourcesessions-messageWaitTime-maxTime OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
    ::= { jMSConnectionResource 132 }
jMSConnectionResourcesessions-messageWaitTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
    ::= { jMSConnectionResource 133 }
jMSConnectionResourcesessions-messageWaitTime-totalTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the total period of time between when it creates message
and when it delivers message"
    ::= { jMSConnectionResource 134 }
jMSConnectionResourcesessions-durableSubscriptionCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the durable subscribers that are created
in each sessions"
    ::= { jMSConnectionResource 141 }
jMSConnectionResourcesessions-producers-destination OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"name of the destination to which each producers send
messages"
    ::= { jMSConnectionResource 151 }
jMSConnectionResourcesessions-producers-messageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are processed in each
producers"
    ::= { jMSConnectionResource 161 }
jMSConnectionResourcesessions-producers-pendingMessageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that reside in each producers
without acknoledgement"
   ::= { jMSConnectionResource 171 }
jMSConnectionResourcesessions-producers-expiredMessageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are expired in each
producers"
   ::= { jMSConnectionResource 181 }
jMSConnectionResourcesessions-producers-messageWaitTime-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
    ::= { jMSConnectionResource 191
```

```
jMSConnectionResourcesessions-producers-messageWaitTime-maxTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
   ::= { jMSConnectionResource 192
jMSConnectionResourcesessions-producers-messageWaitTime-minTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
   ::= { jMSConnectionResource 193 }
jMSConnectionResourcesessions-producers-messageWaitTime-totalTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the total period of time between when it creates message
and when it delivers message"
    ::= { jMSConnectionResource 194 }
jMSConnectionResourcesessions-consumers-origin OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "name of the destination that each consumers connect to"
    ::= { jMSConnectionResource 201 }
jMSConnectionResourcesessions-consumers-messageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
    STATUS mandatory
```

```
DESCRIPTION
        "the number of the messages that are processed in each
consumers"
    ::= { jMSConnectionResource 211 }
jMSConnectionResourcesessions-consumers-pendingMessageCount-count
     OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the number of the messages that reside in each consumers
without acknoledgement"
   ::= { jMSConnectionResource 221 }
jMSConnectionResourcesessions-consumers-expiredMessageCount-count
     OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the number of the messages that are expired in each
consumers"
    ::= { jMSConnectionResource 231 }
jMSConnectionResourcesessions-consumers-messageWaitTime-count
     OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
    ::= { jMSConnectionResource 241 }
\verb|jMSC| on nection Resources essions-consumers-message Wait Time-max Time|
     OBJECT-TYPE
    SYNTAX DisplayString
    ACCESS read-only
    STATUS mandatory
    DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
```

```
::= { jMSConnectionResource 242 }
jMSConnectionResourcesessions-consumers-messageWaitTime-minTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
   ::= { jMSConnectionResource 243 }
jMSConnectionResourcesessions-consumers-messageWaitTime-totalTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the total period of time between when it creates message
and when it delivers message"
    ::= { jMSConnectionResource 244 }
jMSConnectionResourcesessionCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the sessions that are created by this
connection"
    ::= { jMSConnectionResource 251 }
jMSConnectionResourceconnectionConsumerCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
    ::= { jMSConnectionResource 261 }
jMSConnectionResourceconnectionConsumers-origin OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { jMSConnectionResource 271 }
jMSConnectionResourceconnectionConsumers-messageCount-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSConnectionResource 281 }
jMSConnectionResourceconnectionConsumers-pendingMessageCount-
count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSConnectionResource 291 }
jMSConnectionResourceconnectionConsumers-expiredMessageCount-
count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSConnectionResource 301 }
jMSConnectionResourceconnectionConsumers-messageWaitTime-count
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSConnectionResource 401 }
jMSConnectionResourceconnectionConsumers-messageWaitTime-maxTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
      11 11
   ::= { jMSConnectionResource 402 }
jMSConnectionResourceconnectionConsumers-messageWaitTime-minTime
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSConnectionResource 403 }
jMSConnectionResourceconnectionConsumers-messageWaitTime-
totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jMSConnectionResource 404 }
_____
-- jMSConsumerResource
_____
jMSConsumerResource OBJECT IDENTIFIER
   ::= { jeus 34 }
jMSConsumerResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSConsumerResource 1 }
jMSConsumerResourcedestination OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the reference of the QueueImpl object to which this
consumer connects"
    ::= { jMSConsumerResource 2 }
jMSConsumerResourcedestinationResourceObjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object name of destination to which this
consumer connects"
    ::= { jMSConsumerResource 3 }
jMSConsumerResourcedurableSubscriberResourceObjectName
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object name of durable subscriber to which
this consumer connects"
    ::= { jMSConsumerResource 4 }
jMSConsumerResourcesendTimeAvg OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "average time to send messages to this JMS client"
   ::= { jMSConsumerResource 5 }
jMSConsumerResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSConsumerResource 6 }
jMSConsumerResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { jMSConsumerResource 7 }
jMSConsumerResourceorigin OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "name of the destination that consumer connects to"
   ::= { jMSConsumerResource 101 }
jMSConsumerResourcemessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are processed in this
consumer"
   ::= { jMSConsumerResource 111 }
jMSConsumerResourcependingMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that reside in this consumer
without acknoledgement"
    ::= { jMSConsumerResource 121 }
jMSConsumerResourceexpiredMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the messages that are expired in this
consumer"
    ::= { jMSConsumerResource 131 }
jMSConsumerResourcemessageWaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the period of time between when it creates message and
when it delivers message"
   ::= { jMSConsumerResource 141 }
jMSConsumerResourcemessageWaitTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the maximum period of time between when it creates
message and when it delivers message"
    ::= { jMSConsumerResource 142 }
jMSConsumerResourcemessageWaitTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
   ::= { jMSConsumerResource 143 }
jMSConsumerResourcemessageWaitTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the total period of time between when it creates message
and when it delivers message"
    ::= { jMSConsumerResource 144 }
jMSConsumerResourcesendTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the period of time to delivers messages"
    ::= { jMSConsumerResource 151 }
jMSConsumerResourcesendTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the maximum period of time to delivers messages"
   ::= { jMSConsumerResource 152 }
jMSConsumerResourcesendTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the minimum period of time to delivers messages"
   ::= { jMSConsumerResource 153 }
jMSConsumerResourcesendTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total period of time to delivers messages"
   ::= { jMSConsumerResource 154 }
-- jMSProducerResource
jMSProducerResource OBJECT IDENTIFIER
   ::= { jeus 35 }
jMSProducerResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSProducerResource 1 }
jMSProducerResourcedestinationResourceObjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object name of destination to which this
consumer connects"
   ::= { jMSProducerResource 3
```

```
jMSProducerResourcedurableSubscriberResourceObjectName
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object name of durable subscriber to which
this consumer connects"
   ::= { jMSProducerResource 4 }
jMSProducerResourcesendTimeAvg OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "average time to send messages to this JMS client"
   ::= { jMSProducerResource 5 }
jMSProducerResourcedestination OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       "name of the destination to which this producer sends
messages"
    ::= { jMSProducerResource 6 }
jMSProducerResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSProducerResource 7 }
jMSProducerResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { jMSProducerResource 8 }
jMSProducerResourcemessageCount-count OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are processed in this
producer"
    ::= { jMSProducerResource 111 }
jMSProducerResourcependingMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that reside in this producer
without acknoledgement"
    ::= { jMSProducerResource 121 }
jMSProducerResourceexpiredMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are expired in this
producer"
    ::= { jMSProducerResource 131 }
jMSProducerResourcemessageWaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
    ::= { jMSProducerResource 141 }
jMSProducerResourcemessageWaitTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
    ::= { jMSProducerResource 142 }
```

```
jMSProducerResourcemessageWaitTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
    ::= { jMSProducerResource 143 }
jMSProducerResourcemessageWaitTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total period of time between when it creates message
and when it delivers message"
    ::= { jMSProducerResource 144 }
jMSProducerResourcesendTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the period of time to delivers messages"
    ::= { jMSProducerResource 151 }
jMSProducerResourcesendTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the maximum period of time to delivers messages"
    ::= { jMSProducerResource 152 }
jMSProducerResourcesendTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the minimum period of time to delivers messages"
    ::= { jMSProducerResource 153 }
jMSProducerResourcesendTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total period of time to delivers messages"
    ::= { jMSProducerResource 154 }
______
-- jMSSessionResource
_____
jMSSessionResource OBJECT IDENTIFIER
   ::= { jeus 36 }
jMSSessionResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSSessionResource 1 }
jMSSessionResourcejMSEndPointConsumerNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of comsumers that are created
by this session"
    ::= { jMSSessionResource 2 }
jMSSessionResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSSessionResource 3 }
jMSSessionResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
      11 11
    ::= { jMSSessionResource 4 }
jMSSessionResourcemessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the messages that are processed in this
session"
    ::= { jMSSessionResource 101 }
jMSSessionResourcependingMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that resides in this session
without acknoledgement"
    ::= { jMSSessionResource 111 }
jMSSessionResourceexpiredMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are expired in this
session"
    ::= { jMSSessionResource 121 }
jMSSessionResourcemessageWaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
    ::= { jMSSessionResource 131 }
jMSSessionResourcemessageWaitTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
    ::= { jMSSessionResource 132 }
jMSSessionResourcemessageWaitTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
    ::= { jMSSessionResource 133 }
jMSSessionResourcemessageWaitTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the total period of time between when it creates message
and when it delivers message"
    ::= { jMSSessionResource 134 }
jMSSessionResourcedurableSubscriptionCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the durable subscribers that are created
in this sessions"
    ::= { jMSSessionResource 141 }
jMSSessionResourceproducers-destination OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "name of the destination to which each producers send
messages"
    ::= { jMSSessionResource 151 }
jMSSessionResourceproducers-messageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
        "the number of the messages that are processed in this
producer"
   ::= { jMSSessionResource 161 }
jMSSessionResourceproducers-pendingMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that reside in each producers
without acknoledgement"
   ::= { jMSSessionResource 171 }
jMSSessionResourceproducers-expiredMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are expired in each
producers"
   ::= { jMSSessionResource 181 }
jMSSessionResourceproducers-messageWaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
    ::= { jMSSessionResource 191 }
jMSSessionResourceproducers-messageWaitTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
    ::= { jMSSessionResource 192 }
jMSSessionResourceproducers-messageWaitTime-minTime OBJECT-TYPE
    SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
    ::= { jMSSessionResource 193 }
jMSSessionResourceproducers-messageWaitTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the total period of time between when it creates message
and when it delivers message"
    ::= { jMSSessionResource 194 }
jMSSessionResourceconsumers-origin OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "name of the destination that each consumers connect to"
    ::= { jMSSessionResource 201 }
jMSSessionResourceconsumers-messageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are processed in each
consumer"
    ::= { jMSSessionResource 211 }
jMSSessionResourceconsumers-pendingMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that reside in each consumers
without acknoledgement"
    ::= { jMSSessionResource 221 }
jMSSessionResourceconsumers-expiredMessageCount-count OBJECT-TYPE
    SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of the messages that are expired in each
consumers"
   ::= { jMSSessionResource 231 }
jMSSessionResourceconsumers-messageWaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the period of time between when it creates message and
when it delivers message"
    ::= { jMSSessionResource 241 }
jMSSessionResourceconsumers-messageWaitTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the maximum period of time between when it creates
message and when it delivers message"
    ::= { jMSSessionResource 242 }
jMSSessionResourceconsumers-messageWaitTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the minimum period of time between when it creates
message and when it delivers message"
    ::= { jMSSessionResource 243 }
jMSSessionResourceconsumers-messageWaitTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the total period of time between when it creates message
and when it delivers message"
   ::= { jMSSessionResource 244 }
jMSSessionResourcesendTime-count OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the period of time to delivers messages"
   ::= { jMSSessionResource 251 }
jMSSessionResourcesendTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the maximum period of time to delivers messages"
   ::= { jMSSessionResource 252 }
jMSSessionResourcesendTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the minimum period of time to delivers messages"
   ::= { jMSSessionResource 253 }
jMSSessionResourcesendTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the total period of time to delivers messages"
   ::= { jMSSessionResource 254 }
jMSSessionResourcecommitCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { jMSSessionResource 261 }
jMSSessionResourcerollbackCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { jMSSessionResource 271 }
jMSSessionResourcetransactionCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSSessionResource 281 }
______
-- eJBEngineMo
_____
eJBEngineMo OBJECT IDENTIFIER
   ::= { jeus 41 }
eJBEngineMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { eJBEngineMo 1 }
eJBEngineMoblockThreadCount OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the blocked threads of this EJB Engine"
   ::= { eJBEngineMo 2 }
eJBEngineMostats OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { eJBEngineMo 3 }
eJBEngineMotroubles OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { eJBEngineMo 4 }
eJBEngineMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { eJBEngineMo 5 }
-- contextGroupMo
contextGroupMo OBJECT IDENTIFIER
   ::= { jeus 51 }
contextGroupMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { contextGroupMo 1 }
contextGroupMowebModules OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of the Web Modules that is
deployed on this Context Group"
   ::= { contextGroupMo 2 }
contextGroupMowebListeners OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of the Listeners that is
registered on this Context Group"
   ::= { contextGroupMo 3 }
contextGroupMosessionContainer OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
     11 11
   ::= { contextGroupMo 4 }
contextGroupMosessionTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { contextGroupMo 5 }
contextGroupMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { contextGroupMo 6 }
contextGroupMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ....
   ::= { contextGroupMo 7 }
-- dBConnectionPoolMo
dBConnectionPoolMo OBJECT IDENTIFIER
```

```
::= { jeus 52 }
dBConnectionPoolMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard MBean object name"
   ::= { dBConnectionPoolMo 1 }
dBConnectionPoolMoblockDuration OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
        "the value of the interval which Web Engine considers as
BLOCK when the db connection of this DB Connection Pool executes
a SQL query"
   ::= { dBConnectionPoolMo 2 }
\tt dBConnectionPoolModBConnectionPoolInfo-dBConnectionInfo
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { dBConnectionPoolMo 3 }
dBConnectionPoolModBConnectionPoolInfo-currentPoolSize
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
    ::= { dBConnectionPoolMo 4 }
\tt dBConnectionPoolModBConnectionPoolInfo-freeConnectionNum
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
      11 11
   ::= { dBConnectionPoolMo 5 }
\tt dBConnectionPoolModBConnectionPoolInfo-activeConnectionNum
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { dBConnectionPoolMo 6 }
dBConnectionPoolModBConnectionPoolInfo-connectionPoolID
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { dBConnectionPoolMo 7 }
\tt dBConnectionPoolModBConnectionPoolInfo-connectionPoolingRule
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { dBConnectionPoolMo 8 }
dBConnectionPoolModBConnectionPoolInfo-connectionUrl OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { dBConnectionPoolMo 9 }
dBConnectionPoolModBConnectionPoolInfo-driverClassName
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
     11 11
   ::= { dBConnectionPoolMo 10 }
dBConnectionPoolModBConnectionPoolInfo-connectionArgs OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 11 }
SYNTAX DisplayString
  ACCESS read-only
   STATUS mandatory
  DESCRIPTION
     ....
   ::= { dBConnectionPoolMo 12 }
dBConnectionPoolModBConnectionPoolInfo-maxCapacity OBJECT-TYPE
   SYNTAX DisplayString
  ACCESS read-only
   STATUS mandatory
   DESCRIPTION
     11 11
   ::= { dBConnectionPoolMo 13 }
SYNTAX DisplayString
  ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 14 }
SYNTAX DisplayString
  ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 15 }
```

```
dBConnectionPoolModBConnectionPoolInfo-dynamicIncrement
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       п п
   ::= { dBConnectionPoolMo 17 }
dBConnectionPoolModBConnectionPoolInfo-connectionTimeOut
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { dBConnectionPoolMo 18 }
dBConnectionPoolModBConnectionPoolInfo-loginDelay OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 19 }
dBConnectionPoolModBConnectionPoolInfo-closeDelay OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 20 }
dBConnectionPoolModBConnectionPoolInfo-closeLongActiveConnection
    OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 21 }
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { dBConnectionPoolMo 22 }
dBConnectionPoolModBConnectionPoolInfo-maxUseCount OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { dBConnectionPoolMo 23 }
dBConnectionPoolModBConnectionPoolInfo-checkQuery OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { dBConnectionPoolMo 24 }
dBConnectionPoolMomin OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 26 }
dBConnectionPoolMomax OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 28 }
dBConnectionPoolMostep OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
```

```
::= { dBConnectionPoolMo 30 }
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 31 }
dBConnectionPoolMomaxIdleTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { dBConnectionPoolMo 33 }
dBConnectionPoolMomaxAliveTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 35 }
dBConnectionPoolModynamicIncrement OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { dBConnectionPoolMo 37 }
dBConnectionPoolMogetConnectionTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { dBConnectionPoolMo 38 }
dBConnectionPoolMocloseLongActiveConnection OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-write
   STATUS mandatory
   DESCRIPTION
    ::= { dBConnectionPoolMo 39 }
dBConnectionPoolMomaxActiveTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { dBConnectionPoolMo 40 }
dBConnectionPoolMomaxUseCount OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { dBConnectionPoolMo 42 }
dBConnectionPoolMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { dBConnectionPoolMo 43 }
dBConnectionPoolMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { dBConnectionPoolMo 44 }
dBConnectionPoolMoactiveThreadCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the number of the threads that are being used in thread
pool of this DB Connection Pool"
   ::= { dBConnectionPoolMo 101 }
dBConnectionPoolMoblockThreadCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the threads that are blocked in thread
pool of this DB Connection Pool"
   ::= { dBConnectionPoolMo 111 }
dBConnectionPoolMoallThreadCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of all threads that are in thread pool of
this DB Connection Pool"
   ::= { dBConnectionPoolMo 121 }
______
-- threadPoolMo
_____
threadPoolMo OBJECT IDENTIFIER
   ::= { jeus 53 }
threadPoolMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { threadPoolMo 1 }
threadPoolMomin OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
```

```
::= { threadPoolMo 3 }
threadPoolMomax OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { threadPoolMo 5 }
threadPoolMostep OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPoolMo 7 }
threadPoolMomaxIdleTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPoolMo 9 }
threadPoolMomaxQueue OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPoolMo 11 }
threadPoolMomaxWaitQueue OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPoolMo 13 }
threadPoolMomaxThreadActiveTime OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { threadPoolMo 14 }
threadPoolMonotifyThreshold OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPoolMo 15 }
threadPoolMorestartThreshold OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPoolMo 16 }
threadPoolMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { threadPoolMo 17 }
threadPoolMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPoolMo 18 }
threadPoolMoactiveThreadCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"the number of the threads that are being used in thread
pool of this Thread Pool"
   ::= { threadPoolMo 101 }
threadPoolMoblockThreadCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the threads that are blocked in thread
pool of this Thread Pool"
   ::= { threadPoolMo 111 }
threadPoolMoallThreadCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the number of all threads that are in thread pool of
this Thread Pool"
   ::= { threadPoolMo 121 }
threadPoolMomaxThreadCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { threadPoolMo 131 }
threadPoolMowaitQueueCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPoolMo 141 }
-- webEngineMo
webEngineMo OBJECT IDENTIFIER
```

```
::= { jeus 54 }
webEngineMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { webEngineMo 1 }
webEngineMocontextGroups
                            OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard object names of Context Groups that are
deployed on this Web Engine"
   ::= { webEngineMo 2 }
webEngineMoconfigInfo OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the contents of the configuration file(WEBMain.xml) of
this Web Engine"
   ::= { webEngineMo 3 }
webEngineMoserverStatus OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the status of the session server that is configured in
this Web Engine"
   ::= { webEngineMo 4 }
webEngineModBConnectionPool OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
"JMX-standard object names of db connection pools in this
Web Engine"
    ::= { webEngineMo 5 }
webEngineMocontextGroupNames OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webEngineMo 6 }
webEngineMosessionContainer OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { webEngineMo 7 }
webEngineMowebtConnectionGroup OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { webEngineMo 8 }
webEngineMoconfiguration OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webEngineMo 9 }
webEngineMocheckThreadPool OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
    ::= { webEngineMo 11 }
webEngineMocheckClassReload OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webEngineMo 13 }
webEngineMocheckSession OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webEngineMo 15 }
webEngineMocheckDbConnectionPool OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { webEngineMo 17 }
webEngineMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webEngineMo 18 }
webEngineMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webEngineMo 19 }
webEngineMofreeMemory-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { webEngineMo 101 }
webEngineMototalMemory-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webEngineMo 111 }
______
-- webListenerMo
______
webListenerMo OBJECT IDENTIFIER
   ::= { jeus 55 }
webListenerMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { webListenerMo 1 }
webListenerMothreadPools OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of the Thread Pools that is
registered on this Web Listener"
    ::= { webListenerMo 2 }
webListenerMotype OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the type of this Web Listener"
   ::= { webListenerMo 3 }
```

```
webListenerMoport OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webListenerMo 4 }
webListenerMoreadTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { webListenerMo 6 }
webListenerMoreconnectTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webListenerMo 8 }
webListenerMopostdataReadTimeout OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
    ::= { webListenerMo 10 }
webListenerMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { webListenerMo 11 }
webListenerMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
    11 11
   ::= { webListenerMo 12 }
_____
-- webtConnectionGroupMo
_____
webtConnectionGroupMo OBJECT IDENTIFIER
   ::= { jeus 56 }
webtConnectionGroupMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webtConnectionGroupMo 1 }
webtConnectionGroupMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webtConnectionGroupMo 2 }
webtConnectionGroupMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
    ::= { webtConnectionGroupMo 3 }
webt {\tt Connection Group Mototal Connection Count-count} \ {\tt OBJECT-TYPE}
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webtConnectionGroupMo 101 }
```

```
webtConnectionGroupMofreeConnectionCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { webtConnectionGroupMo 111 }
webtConnectionGroupMousedConnectionCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webtConnectionGroupMo 121 }
-- jMSClientResource
jMSClientResource OBJECT IDENTIFIER
   ::= { jeus 61 }
jMSClientResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSClientResource 1 }
jMSClientResourcehostAddress OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "remote address of the socket to which clients are
connected"
   ::= { jMSClientResource 2 }
jMSClientResourceport OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "remote port of the socket to which clients are
connected"
   ::= { jMSClientResource 3 }
jMSClientResourcejMSConnectionResourceNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard object names of the connections that are
created by JMS clients"
   ::= { jMSClientResource 4 }
jMSClientResourcenamePartString OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSClientResource 6 }
jMSClientResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { jMSClientResource 7 }
jMSClientResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { jMSClientResource 8 }
jMSClientResourceconnectionCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
       "the number of the connections that are created by JMS
clients"
   ::= { jMSClientResource 101 }
-----
-- jMSQueueConnectionFactoryResource
_____
jMSQueueConnectionFactoryResource OBJECT IDENTIFIER
   ::= { jeus 62 }
jMSQueueConnectionFactoryResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSQueueConnectionFactoryResource 1 }
jMSQueueConnectionFactoryResourcename OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { jMSQueueConnectionFactoryResource 3 }
jMSQueueConnectionFactoryResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSQueueConnectionFactoryResource 4 }
jMSQueueConnectionFactoryResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { jMSQueueConnectionFactoryResource 5 }
_____
-- jMSQueueDestinationResource
jMSQueueDestinationResource OBJECT IDENTIFIER
   ::= { jeus 63 }
jMSQueueDestinationResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSQueueDestinationResource 1 }
jMSQueueDestinationResourcename OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the name of this JMS Destination"
   ::= { jMSQueueDestinationResource 2 }
jMSQueueDestinationResourceexportName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the JNDI export name of this JMS Destination"
   ::= { jMSQueueDestinationResource 3 }
jMSQueueDestinationResourcetype OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the type of this JMS Destination"
   ::= { jMSQueueDestinationResource 4 }
jMSQueueDestinationResourcedestination OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the reference of the DestinationImpl object, which has
destination information"
    ::= { jMSQueueDestinationResource 8 }
jMSQueueDestinationResourcejMSConsumerResourceNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "names of JMS clients that belong to JMS Destination"
   ::= { jMSQueueDestinationResource 9 }
jMSQueueDestinationResourceremainingMessages OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
    ::= { jMSQueueDestinationResource 10 }
jMSQueueDestinationResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { jMSQueueDestinationResource 11 }
jMSQueueDestinationResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
    ::= { jMSQueueDestinationResource 12 }
jMSQueueDestinationResourcemessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { jMSQueueDestinationResource 101 }
jMSQueueDestinationResourcependingMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSQueueDestinationResource 111 }
jMSQueueDestinationResourceexpiredMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { jMSQueueDestinationResource 121 }
jMSQueueDestinationResourcemessageWaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSQueueDestinationResource 122 }
jMSQueueDestinationResourcemessageWaitTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSQueueDestinationResource 123 }
jMSQueueDestinationResourcemessageWaitTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSQueueDestinationResource 124 }
jMSQueueDestinationResourcemessageWaitTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
```

```
ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSQueueDestinationResource 125 }
jMSQueueDestinationResourcesendTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jMSQueueDestinationResource 131 }
jMSQueueDestinationResourcesendTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jMSQueueDestinationResource 132 }
jMSQueueDestinationResourcesendTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSQueueDestinationResource 133 }
jMSQueueDestinationResourcesendTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jMSQueueDestinationResource 134 }
-- jMSDurableSubscriberResource
jMSDurableSubscriberResource OBJECT IDENTIFIER
```

```
::= { jeus 64 }
jMSDurableSubscriberResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSDurableSubscriberResource 1 }
jMSDurableSubscriberResourcename OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the name of JMS Durable Subscriber"
   ::= { jMSDurableSubscriberResource 2 }
jMSDurableSubscriberResourceclientID OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the client ID of JMS Durable Subscriber"
   ::= { jMSDurableSubscriberResource 3 }
jMSDurableSubscriberResourceremainingMessages OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the number of the messages which are alive in durable
subscriber"
   ::= { jMSDurableSubscriberResource 5 }
jMSDurableSubscriberResourceselector OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "selector value which is configured in durable
subscriber"
   ::= { jMSDurableSubscriberResource 6
```

```
jMSDurableSubscriberResourcejMSConsumerResourceName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSDurableSubscriberResource 7 }
jMSDurableSubscriberResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSDurableSubscriberResource 8 }
jMSDurableSubscriberResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jMSDurableSubscriberResource 9 }
_____
-- jMSTopicConnectionFactoryResource
jMSTopicConnectionFactoryResource OBJECT IDENTIFIER
   ::= { jeus 65 }
jMSTopicConnectionFactoryResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSTopicConnectionFactoryResource 1 }
jMSTopicConnectionFactoryResourcename OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSTopicConnectionFactoryResource 3 }
jMSTopicConnectionFactoryResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSTopicConnectionFactoryResource 4 }
jMSTopicConnectionFactoryResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSTopicConnectionFactoryResource 5 }
-- jMSTopicDestinationResource
_____
jMSTopicDestinationResource OBJECT IDENTIFIER
   ::= { jeus 66 }
jMSTopicDestinationResourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jMSTopicDestinationResource 1 }
jMSTopicDestinationResourcename OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the name of this JMS Destination"
```

```
::= { jMSTopicDestinationResource 2 }
jMSTopicDestinationResourceexportName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the JNDI export name of this JMS Destination"
    ::= { jMSTopicDestinationResource 3 }
jMSTopicDestinationResourcetype OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the type of this JMS Destination"
   ::= { jMSTopicDestinationResource 4 }
jMSTopicDestinationResourcejMSDurableSubscriberResourceNames
     OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the names of JMS Durable Subscribers that belong to JMS
Destination"
    ::= { jMSTopicDestinationResource 6 }
jMSTopicDestinationResourcedestination OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the reference of the DestinationImpl object, which has
destination information"
    ::= { jMSTopicDestinationResource 8 }
jMSTopicDestinationResourcejMSConsumerResourceNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "names of JMS clients that belong to JMS Destination"
   ::= { jMSTopicDestinationResource 9 }
```

```
jMSTopicDestinationResourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSTopicDestinationResource 10 }
jMSTopicDestinationResourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSTopicDestinationResource 11 }
jMSTopicDestinationResourcemessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSTopicDestinationResource 101 }
jMSTopicDestinationResourcependingMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSTopicDestinationResource 111 }
jMSTopicDestinationResourceexpiredMessageCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSTopicDestinationResource 121 }
jMSTopicDestinationResourcemessageWaitTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
      11 11
   ::= { jMSTopicDestinationResource 122 }
jMSTopicDestinationResourcemessageWaitTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSTopicDestinationResource 123 }
jMSTopicDestinationResourcemessageWaitTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { jMSTopicDestinationResource 124 }
jMSTopicDestinationResourcemessageWaitTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSTopicDestinationResource 125 }
jMSTopicDestinationResourcesendTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSTopicDestinationResource 131 }
jMSTopicDestinationResourcesendTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSTopicDestinationResource 132 }
jMSTopicDestinationResourcesendTime-minTime OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSTopicDestinationResource 133 }
jMSTopicDestinationResourcesendTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jMSTopicDestinationResource 134 }
-- threadPool
threadPool OBJECT IDENTIFIER
   ::= { jeus 71 }
threadPoolobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPool 1 }
threadPoolthreadOperationInfo OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPool 2 }
threadPoolmax OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
```

```
DESCRIPTION
     11 11
   ::= { threadPool 4 }
threadPoolperiod OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
   ::= { threadPool 6 }
threadPooltroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { threadPool 7 }
threadPoolownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { threadPool 8 }
-- jEUSManager
jEUSManager OBJECT IDENTIFIER
   ::= { jeus 77 }
jEUSManagerobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "JMX-standard MBean object name"
   ::= { jEUSManager 1 }
```

```
OBJECT-TYPE
jEUSManagerserverVersion
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       "the version of JEUS that is being used"
   ::= { jEUSManager 2 }
jEUSManagerserverVendor OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "the J2EE platform vendor of this JEUS Manager"
    ::= { jEUSManager 3 }
jEUSManagerjavaVMs
                  OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
        "JMX-standard object names of the JVMs on which JEUS
Manager is running"
   ::= { jEUSManager 4 }
jEUSManagerjeusServices OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
    ::= { jEUSManager 5 }
jEUSManagerj2eeServers OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { jEUSManager 6 }
jEUSManagernodesFromDescriptor OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jEUSManager 9 }
jEUSManageraliveNodeNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jEUSManager 10 }
jEUSManagerjeusHome OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { jEUSManager 11 }
jEUSManagerpID OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jEUSManager 12 }
jEUSManagertroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jEUSManager 13 }
jEUSManagerownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jEUSManager 14 }
```

```
jEUSManagerj2eeServerNames OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jEUSManager 15 }
-----
-- webServerInfo
_____
webServerInfo OBJECT IDENTIFIER
   ::= { jeus 81 }
webServerInfoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webServerInfo 1 }
webServerInfonodeInfo OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { webServerInfo 2 }
webServerInfosvrAllInfo OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webServerInfo 3 }
webServerInfotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webServerInfo 4 }
webServerInfoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { webServerInfo 5 }
webServerInfosvrCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { webServerInfo 101 }
webServerInfoexecCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webServerInfo 111 }
webServerInfoavgTime-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { webServerInfo 121 }
webServerInfoavgTime-maxTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webServerInfo 122 }
```

```
webServerInfoavgTime-minTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { webServerInfo 123 }
webServerInfoavgTime-totalTime OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { webServerInfo 124 }
-- externalWebtDataSource
externalWebtDataSource OBJECT IDENTIFIER
   ::= { jeus 92 }
externalWebtDataSourceobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { externalWebtDataSource 1 }
externalWebtDataSourcetype OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 2 }
externalWebtDataSourceport OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
      11 11
   ::= { externalWebtDataSource 3 }
externalWebtDataSourcewebtProperties OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { externalWebtDataSource 4 }
externalWebtDataSourceexportName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { externalWebtDataSource 5 }
externalWebtDataSourcehostAddr OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 6 }
externalWebtDataSourcelevel OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-write
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { externalWebtDataSource 8 }
externalWebtDataSourcetroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 9 }
```

```
externalWebtDataSourceownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 10 }
externalWebtDataSourcecreateCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { externalWebtDataSource 101 }
externalWebtDataSourcecloseCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { externalWebtDataSource 111 }
externalWebtDataSourcepoolSize-upperBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
    ::= { externalWebtDataSource 121 }
externalWebtDataSourcepoolSize-lowerBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { externalWebtDataSource 122 }
externalWebtDataSourcepoolSize-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
      11 11
   ::= { externalWebtDataSource 123 }
externalWebtDataSourcepoolSize-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 124 }
externalWebtDataSourcepoolSize-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       ....
   ::= { externalWebtDataSource 125 }
externalWebtDataSourcefreePoolSize-upperBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { externalWebtDataSource 131 }
externalWebtDataSourcefreePoolSize-lowerBound OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 132 }
externalWebtDataSourcefreePoolSize-highWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 133 }
externalWebtDataSourcefreePoolSize-lowWaterMark OBJECT-TYPE
```

```
SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       п п
   ::= { externalWebtDataSource 134 }
externalWebtDataSourcefreePoolSize-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 135 }
externalWebtDataSourcewaitingThreadCount-highWaterMark
     OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { externalWebtDataSource 141 }
externalWebtDataSourcewaitingThreadCount-lowWaterMark OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
    ::= { externalWebtDataSource 142 }
externalWebtDataSourcewaitingThreadCount-current OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { externalWebtDataSource 143 }
externalWebtDataSourcereConnectCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
```

```
DESCRIPTION
      11 11
   ::= { externalWebtDataSource 151 }
externalWebtDataSourcetotalConnectionCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 161 }
externalWebtDataSourcefreeConnectionCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      ....
   ::= { externalWebtDataSource 171 }
externalWebtDataSourceactiveConnectionCount-count OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { externalWebtDataSource 181 }
-- subjectMo
subjectMo OBJECT IDENTIFIER
   ::= { jeus 101 }
subjectMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
subjectMosubjectNames OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { subjectMo 2 }
subjectMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { subjectMo 3 }
subjectMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { subjectMo 4 }
______
-- securityDomainMo
securityDomainMo OBJECT IDENTIFIER
   ::= { jeus 102 }
securityDomainMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { securityDomainMo 1 }
securityDomainModomainName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
```

```
STATUS mandatory
   DESCRIPTION
       11 11
   ::= { securityDomainMo 2 }
securityDomainMopolicys OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { securityDomainMo 3 }
securityDomainMosubjects OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
       11 11
   ::= { securityDomainMo 4 }
securityDomainMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { securityDomainMo 5 }
securityDomainMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { securityDomainMo 6 }
securityDomainModescription OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { securityDomainMo 7 }
```

```
-- policyMo
policyMo OBJECT IDENTIFIER
   ::= { jeus 103 }
policyMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { policyMo 1 }
policyMopolicyIds OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { policyMo 2 }
policyMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { policyMo 3 }
policyMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { policyMo 4 }
-- securityMo
```

```
securityMo OBJECT IDENTIFIER
   ::= { jeus 104 }
securityMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { securityMo 1 }
securityMocurrentDomain OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { securityMo 2 }
securityMosecurityDomains OBJECT-TYPE
   SYNTAX SEQUENCE OF DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { securityMo 3 }
securityMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { securityMo 4 }
securityMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
```

```
::= { securityMo 5 }
_____
-- jMSEngineMo
jMSEngineMo OBJECT IDENTIFIER
   ::= { jeus 105 }
jMSEngineMojMSResource OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jMSEngineMo 1 }
jMSEngineMoengineName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
   ::= { jMSEngineMo 2 }
jMSEngineMoobjectName OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jMSEngineMo 3 }
jMSEngineMotroubles OBJECT-TYPE
   SYNTAX DisplayString
   ACCESS read-only
   STATUS mandatory
   DESCRIPTION
      11 11
   ::= { jMSEngineMo 4 }
jMSEngineMoownTroubles OBJECT-TYPE
   SYNTAX DisplayString
```

JEUS SNMP 안내서

```
ACCESS read-only
STATUS mandatory
DESCRIPTION
""
::= { jMSEngineMo 5 }
```

B JEUSMain.xml 의 XML 환경 설정 레퍼런스

B.1 소개

본 부록의 레퍼런스는 JEUS 의 주 설정 파일인 JEUSMain.xml 중에서 JMX 관련 태그에 대해서 설명하고 있다. 이 파일의 xsd 파일은 "JEUS_HOME\config\xsds" 디렉토리의 "jeus-main.xsd" 파일이다

본 레퍼런스는 3 부분으로 나뉘어져 있다

- 1. **XML Schema/XML 트리**: XML 설정 파일의 모든 태그 리스트를 정리했다. 각 노드의 형식은 다음과 갈다.
 - a. 태그 레퍼런스로 빨리 찾아보기 위해서 각 태그마다 인덱스 번호(예:(11))를 붙여놓았다. 태그 레퍼런스 에서는 이 번호 순서로 설명한다.
 - b. XML Schema 에서 정의한 XML 태그명을 <tag name> 형식으로 표시한다.
 - c. XML Schema 에서 정의한 Cardinality 를 표시한다. "?" = 0 개나 1 개의 element, "+" = 1 개 이상의 element, "*" = 0 개 이상의 element, (기호가 없음) = 정확히 1 개의 element.
 - d. 몇몇 태그에는 "P" 문자를 붙여 놓았는데, 해당 태그는 성능에 관계되는 태그라는 것을 뜻한다. 이 태그는 설정을 튜닝할 때 사용된다.
- 2. **태그 레퍼런스**: 트리에 있는 각 XML 태그를 설명한다. 이런 테이블은 다음 하위-항목들을 포함하고 있다.
 - a. Description: 태그에 대한 간단한 설명
 - b. Value Description: 입력하는 값과 타입
 - c. Value Type: 값의 데이터 타입. 예) String

- d. **Default Value**: 해당 XML을 사용하지 않았을 때 기본적으로 사용되는 값
- e. Defined values: 이미 정해져 있는 값
- f. Example: 해당 XML 태그에 대한 예
- g. **Performance Recommendation**: 성능 향상을 위해서 추천하는 값
- h. Child Elements: 자신의 태그 안에 사용하는 태그
- 3. 샘플 XML 파일: "JEUSMain.xml"에 대한 완전한 예제

B.2 XML Schema/XML Tree

```
(226) <snmp-adaptor>?
  (227) <snmp-adaptor-port>
  (228) <snmp-version>? P
  (229) <snmp-max-packet-size>? P
  (230) <snmp-security>? P
  (231) <trap-demon>*
        (232) <ip-address>
        (233) <port>
  (234) <pooling>?
        (235) <min>? P
        (236) <max>? P
  (237) <period>? P
```

B.3 Element Reference

```
(226) <jeus-system> <node> <engine-container> <jmx-manager> <snmp-adaptor>

Description

JMX 의 adapter 중 하나인 SNMP adapter 를 설정한다.

(227) snmp-adaptor-port
(228) snmp-version?
(229) snmp-max-packet-size?
(230) snmp-security?
(231) trap-demon*
(234) pooling?
```

adaptor> <snmp-adaptor-port>

Description SNMP 어댑터의 리스너 포트

Value Type snmp-adaptor-portType

(228) <jeus-system> <node> <engine-container> <jmx-manager> <snmpadaptor> <snmp-version>

Description SNMP 버전을 지정하며 1, 2 또는 3 을 지정할 수 있다

Value Type snmp-versionType

Default Value 3

Defined Value 1

2

3

(229) (229) <jeus-system> <node> <engine-container> <jmx-manager> <snmpadaptor> <snmp-max-packet-size>

Description SNMP 패킷에 대한 최대값을 설정하며 최소 256 바이트부터 설정 할

수 있다.

Value Type snmp-max-packet-sizeType

Default Value 4096

(230) <jeus-system> <node> <engine-container> <jmx-manager> <snmp-adaptor> <snmp-security>

Description 보안을 적용시킬 것 인지를 설정한다. 보안은 SNMP 버전 3 에서만

지정이 가능 하다.

Value Type boolean

Default Value false

(231) <jeus-system> <node> <engine-container> <jmx-manager> <snmpadaptor> <trap-demon>

Description 장애 상황 발생시 TRAP 메세지를 보낼 서버를 설정한다. 여러 개

설정이 가능하며 설정된 모든 ip, address 로 메세지를 보낸다.

Child Elements (232)ip-address

(233)port

(232) <jeus-system> <node> <engine-container> <jmx-manager> <snmpadaptor> <trap-demon> <ip-address>

Description Demon □ IP address

Value Description a valid IP address

Value Type token

JEUS SNMP 안내서

Example <host-name>111.111.111.1

(233) <jeus-system> <node> <engine-container> <jmx-manager> <snmpadaptor> <trap-demon> <port>

Description Demon □ port

Value Description a port number

Value Type int

Example <port>8888</port>

(234) <jeus-system> <node> <engine-container> <jmx-manager> <snmpadaptor> <pooling>

Description SNMP Server 에서 요청을 처리하는 쓰레드로 구성되어 있다. 아래

element 는 이 쓰레드를 관리하는 pool 을 설정한다.

Child Elements (235)min?

(236)max? (237)period?

(235) <jeus-system> <node> <engine-container> <jmx-manager> <snmpadaptor> <pooling> <min>

Description pooling 되는 객체의 최소값을 지정한다.

Value Type nonNegativeIntType

Value Type Description 0 이상의 int type 이다. 즉, int 범위에서 0 이상의 값들을 포함한다.

Default Value 2

(236) <jeus-system> <node> <engine-container> <jmx-manager> <snmpadaptor> <pooling> <max>

Description pooling 되는 객체의 최대값을 지정한다.

Value Type nonNegativeIntType

Value Type Description 0 이상의 int type 이다. 즉, int 범위에서 0 이상의 값들을 포함한다.

Default Value 30

(237) <jeus-system> <node> <engine-container> <jmx-manager> <snmpadaptor> <pooling> <period>

Description pooling 되는 객체를 정리하는 시간을 지정한다.

Value Type long

Default Value 3600000

Performance 이 값이 클수록 정리하는 주기가 길어져 server 운영에는 부하가 적게

Recommendation 가해지나 그만큼 메모리가 누수될 수 있으므로 적당한 값으로

지정한다.

색 인

J	N	
JEUS SNMP agent. 7, 13, 19, 21, 22, 32, 33, 35, 37	NMS 프로토콜	22
jeus.properties	S	
jmx-manager 15, 16, 26	session snmp-adaptor-port 1	
M	SNMPv113, 2	2, 27, 32
Management Information Base	SNMPv2	
MIR 8 10 13 22 24 27 33 34 39 60	DI (1/11 / J 15, 22, 2	,, 50, 52