Memory Virtualization: Paging


OSTEP Chapter 18:

http://pages.cs.wisc.edu/~remzi/OSTEP/vm-paging.pdf

Jan Reineke Universität des Saarlandes

Review: Segmentation

Assumption: 14-bit virtual addresses, 2 most-significant bits determine segment



Where does the segment table live?

- → Registers in MMU for active process
- → PCB otherwise

| Segment | Base | Bounds |
|---------|--------|--------|
| 0 | 0x4000 | Oxfff |
| 1 | 0x5800 | Oxfff |
| 2 | 0x6800 | 0x7ff |

Review: Memory accesses

0x0010: movl 0x1100, %edi
0x0013: addl \$0x3, %edi

0x0019: movl %edi, 0x1100

| Seg | Base | Bounds |
|-----|--------|--------|
| 0 | 0x4000 | Oxfff |
| 1 | 0x5800 | Oxfff |
| 2 | 0x6800 | 0x7ff |

Physical Memory Accesses?

- 1) Instruction Fetch, virtual address 0x0010
 - Physical addr.: 0x4010

Load from virtual address 0x1100

- Physical addr.: 0x5900
- 2) Instruction Fetch from virtual address 0x0013
 - Physical addr.: 0x4013
- 3) Instruction Fetch from virtual address 0x0019
 - Physical addr.: 0x4019

Store to virtual address 0x1100

- Physical addr.: 0x5900

Total of 5 memory accesses (3 instruction fetches, 2 load/stores).


Problem: External fragmentation

Definition (Fragmentation): Free memory that cannot be usefully allocated Why?

- Free memory (hole) is too small and scattered
- Rules for allocating memory prohibit using this free space

Types of fragmentation:

- External: visible to OS
- Internal: visible to application (e.g. if must allocate at some granularity)




Paging

Goal: Eliminate requirement that address space is contiguous


- Eliminate external fragmentation
- Grow segments as needed

Idea: Divide address spaces into fixed-size pages and physical memory into fixed-size page frames of the same size

• Size 2ⁿ, Example: 4 KB




(Virtual) address spaces




Address translation

- How to translate virtual addresses into physical addresses?
 - Most-significant bits determine page number
 - Least-signifiant bits determine offset within page



How does format of address space determine number of pages and size of pages?


Address translation



How should OS translate VPN to PPN? What data structure is good?

Big array: page table

Quiz: Page table



Memory Virtualization: Paging

Where are page tables stored?

How big is a typical page table?

- 32-bit address space
- 4 KB pages
- 32 Bit = 4 byte entries

Solution: $2 \wedge (32 - \log_2 (4*1024))*4$ Byte = 4 MB

- Size of page table = Number of entries * Size of individual entries
- Number of entries = Number of pages = 2^(bits for page number)
- Bits for page number = 32 bits for offset = 32 $\log_2(4096)$ = 32-12 = 20
- Thus, 2²⁰ 4-byte entries

Where are page tables stored?

Implication:

Store page table in memory, not in registers.

Hardware finds page table with page table base register.

What happens on a context switch:

- Save old page table base register in PCB of descheduled process
- Change contents of page table base register to newly scheduled process

Other page table info

What other info is in page table entries besides translation?

- valid bit = is the page allocated?
- protection bits, encode access rights
- present bit
- reference bit
- dirty bit

discussed later on

Memory accesses with paging

```
0x0010: movl 0x1100, %edi
```

0x0013: addl \$0x3, %edi

0x0019: movl %edi, 0x1100

Page table is at phys. addr. 0x5000 Every entry is 4 bytes 4KB pages, i.e., 12 bits for offset

First 4 entries of the page table

Physical memory accesses with paging?

- 1) Instruction Fetch at virtual address 0x0010:
 - VPN = 0, so access entry 0 of page table
 - Access 1: 0x5000 to learn: PPN = 2
 - Access 2: Instruction fetch at phys. addr. 0x2010

Load at virtual address 0x1100:

- VPN = 1, so access entry 1 of page table
- Access 3: 0x5004 to learn: PPN = 0
- Access 4: Load at phys. addr. 0x0100

Doubling number of memory accesses!

Advantages of paging

No external fragmentation:

Any page can be placed in any frame in physical memory

Fast to allocate and free:

Linked list of free pages

Simple to swap-out portions of memory to disk (later lecture)

- Page size = disk block size
- Can run process when some pages are on disk
 - Add present bit to page table entries

Disadvantages of paging

Internal fragmentation:

Wasted memory grows with larger pages

Additional memory access to page table upon every memory access

→ extremely inefficient

- Page table must be stored in memory
- MMU stores only base address of page table
- Solution: TLB = "page table cache"

Substantial storage for page tables

• Simple page table: one entry for each page in address space, even if not allocated

