

Conduit Control Center

Product Roadmap

Document:	CCC_Product_Roadmap_v1
Version:	1.1
Date:	2026-06-10
Status:	Draft for Review
Includes:	R1 Capability Audit · D1 UX/UI Design Milestone

Open Source · Not for Distribution

Table of Contents

- 1. Overview
- 2. Guiding Principles
- 3. R1 — Capability Audit (Research Milestone)
 - 3.1 Audit Scope
 - 3.2 Conduit Linux CLI Capability Matrix
 - 3.3 Confirmed Findings Summary
- 4. v0.1.1 — Maintenance Release
- 5. D1 — UX/UI Design Milestone (Gate for v0.2.0)
 - 5.1 Design Principles
 - 5.2 Information Architecture
 - 5.3 First-Screen Requirements
 - 5.4 Navigation Model
 - 5.5 Visual Hierarchy Rules
 - 5.6 Human-Readable Values
 - 5.7 Settings UX
 - 5.8 Warnings, Confirmations, and Errors
 - 5.9 Mobile Behaviour
 - 5.10 Theme Support
 - 5.11 Pre-Implementation Deliverables
- 6. v0.2.0 — Smart Conduit Control
 - 6.1 Conduit Configuration
 - 6.2 Live Operations Panel
 - 6.3 Regional Analytics
 - 6.4 Smart Assistant
 - 6.5 Bandwidth Scheduling
 - 6.6 Broker Live Status
 - 6.7 Theme Support
- 7. v0.3.0 — Historical Analytics & Operations
- 8. v0.4.0 — Personal Mode & Ryve
- 9. Out of Scope
- 10. Revision History

1. Overview

Conduit Control Center (CCC) is an open-source web dashboard for managing Psiphon Conduit nodes on Linux servers and Raspberry Pi devices. Its goal is to give volunteer operators a secure, lightweight, user-friendly interface that eliminates the need for direct CLI access for day-to-day operations.

This roadmap documents the planned evolution of CCC from a monitoring dashboard (v0.1) to a full control centre capable of configuring Conduit, visualising live and historical traffic, intelligently assisting operators with resource decisions, and managing personal relay identities.

Target platform: Raspberry Pi 4 (4 GB), Ubuntu 22.04 ARM64, public IP, Cloudflare DNS, Nginx, FastAPI, Python 3.

2. Guiding Principles

Principle	Requirement
Open-source first	No proprietary dependencies. No telemetry without consent.
Security by default	Never store or expose private keys, pairing tokens, or API secrets. Principle of least privilege throughout.
Beginner-friendly	install.sh should work for a first-time Linux user.
Lightweight	Suitable for Raspberry Pi 4 (4 GB). Avoid heavy frameworks or background indexing.
Production-ready	Systemd integration, Nginx TLS, proper logging, graceful restarts.
Capability-driven	No feature is scoped until confirmed possible with the installed Conduit binary.

3. R1 — Capability Audit (Research Milestone)

Gate: No v0.2.0 implementation begins until R1 is complete and the capability matrix is approved.

3.1 Audit Scope

Five areas audited against Psiphon-Inc/conduit (2026-06-10):

#	Area
A	Personal Mode — Personal Links, Pairing URLs, QR generation, identities, invitations
B	Client Limits — max common, max personal, scopes, runtime configurability
C	Bandwidth Controls — global, per-direction, reduced/scheduling, runtime configurability
D	Metrics Inventory — complete conduit_* Prometheus gauge catalogue
E	Ryve — claim workflow, QR, rewards metadata, mobile integration

Sources: [cli/cmd/start.go](#), [cli/cmd/ryve.go](#), [cli/internal/config/config.go](#), [cli/internal/config/compartment.go](#), [cli/internal/metrics/metrics.go](#), [cli/README.md](#), [cli/GUIDE.md](#).

3.2 Conduit Linux CLI Capability Matrix

CCC Candidate column describes the proposed CCC surface for each capability.

#	Capability	Android	Linux CLI	CCC Now	CCC Candidate
A — Personal Mode					
A1	Enable personal clients	✓	✓ --max-personal-clients	✗	Read+Write (v0.4.0)
A2	Compartment ID generation	✓	✓ new-compartment-id	✗	Generate+persist (v0.4.0)
A3	Personal pairing token (v1)	✓	✓ BuildPersonalPairingToken	✗	Generate+display (v0.4.0)
A4	Personal pairing QR code	✓	✓ (token→QR)	✗	Display in UI (v0.4.0)
A5	--compartment-id: raw or token	—	✓ NormalizePersonalCompartmentInput	✗	Both formats (v0.4.0)
A6	Pairing name max 32 chars	32c	✓ enforced	✗	Validated input (v0.4.0)
A7	Compartment persisted to disk	—	✓ personal_compartment.json	✗	Read persisted (v0.4.0)
A8	Per-user invitation management	✓	✗ Not in CLI	✗	Out of scope
B — Client Limits					
B1	Max common clients (0–1000)	✓	✓ --max-common-clients (def 50)	✗ read	Read+Write (v0.2.0)
B2	Max personal clients (0–1000)	✓	✓ --max-personal-clients (def 0)	✗	Read (v0.2.0), Write (v0.4.0)
B3	At-least-one-client validation	—	✓ error if both=0	—	Enforce in UI (v0.2.0)
B4	Runtime client limit update	—	✓ SetConfig(c, p, bw)	✗	Service restart (v0.2.0)
B5	InproxyMaxCommonClients via --set	—	✓ in allowlist	—	Covered by B1
B6	InproxyMaxPersonalClients via --set	—	✗ NOT in allowlist	—	Use --max-personal-clients (v0.4.0)
C — Bandwidth Controls					
C1	Global bandwidth limit (Mbps)	✓	✓ --bandwidth (def 40, -1 unlim)	✗ read	Read+Write (v0.2.0)
C2	Bandwidth stored as bytes/sec	—	✓ Mbps×1,000,000/8	—	Display as Mbps (v0.2.0)
C3	Separate upstream/downstream	✓	✓ JSON config only	✗	Out of scope v0.2.0
C4	Unlimited bandwidth (-1)	✓	✓	✗	Unlimited toggle (v0.2.0)
C5	Runtime bandwidth update	—	✓ SetConfig(..., bw)	✗	Service restart (v0.2.0)
C6	Reduced-mode scheduling	—	✓ InproxyReduced* via --set	✗	Scheduling UI (v0.2.0)
C7	Reduced clients during schedule	—	✓ InproxyReducedMaxCommonClients	✗	Scheduling UI (v0.2.0)
C8	Min throttle (100GB/7d)	—	✓ conduit-monitor enforces	—	UI tooltip (v0.2.0)
D — Metrics					

#	Capability	Android	Linux CLI	CCC Now	CCC Candidate
D1	conduit_announcing	—	✓	✓	Already exposed
D2	conduit_connecting_clients	—	✓	✓	Already exposed
D3	conduit_connected_clients	—	✓	✓	Already exposed
D4	conduit_is_live (broker)	—	✓	✗	Live Ops badge (v0.2.0)
D5	conduit_max_common_clients	—	✓	✓	Already exposed
D6	conduit_max_personal_clients	—	✓	✗	Config panel (v0.2.0)
D7	conduit_bandwidth_limit_bytes_per_second	—	✓	✗	Config panel (v0.2.0)
D8	conduit_bytes_uploaded	—	✓	✗	Live Ops (v0.2.0)
D9	conduit_bytes_downloaded	—	✓	✗	Live Ops (v0.2.0)
D10	conduit_uptime_seconds (GaugeFunc)	—	✓	✗	Live Ops (v0.2.0)
D11	conduit_idle_seconds (GaugeFunc)	—	✓	✗	Live Ops (v0.2.0)
D12	conduit_region_bytes_uploaded{scope,region}	—	✓	✗	Regional Analytics (v0.2.0)
D13	conduit_region_bytes_downloaded{scope,region}	—	✓	✗	Regional Analytics (v0.2.0)
D14	conduit_region_connecting_clients{scope,region}	—	✓	✗	Regional Analytics (v0.2.0)
D15	conduit_region_connected_clients{scope,region}	—	✓	✗	Regional Analytics (v0.2.0)
D16	conduit_build_info{repo,rev,go,values}	—	✓	partial	Full build info (v0.2.0)
D17	Scope labels: common/personal	—	✓	✗	Scope filter in Regions (v0.2.0)
E — Ryve					
E1					
E2	Claim URI (network.ryve.app://...)	—	✓	✗	Display claim QR (v0.4.0)
E3	QR PNG → data/ryve-claim-qr.png	—	✓	✗	Serve PNG (v0.4.0)
E4	ProxyID (Curve25519 public key)	—	✓	✗	Display ProxyID (v0.4.0)
E5	Private key in claim	—	✓ requires confirm	✗	NEVER store/display private key
E6	Ryve rewards data	—	✗ not in CLI	✗	Out of scope until confirmed
E7	Station name/identity	—	✓ --name on ryve-claim	✗	Pre-fill hostname (v0.4.0)

3.3 Confirmed Findings Summary

Area	Finding
Personal Mode	Fully supported via --max-personal-clients and --compartment-id. Compartment ID required before enabling personal clients. Pairing tokens use v1 format (base64url JSON {v:"1", data:{id, name}}). Full workflow implementable in v0.4.0.
Client Limits	Runtime-configurable via SetConfig(). CCC's apply mechanism is a service restart, not in-process hot-reload.

Area	Finding
Bandwidth	Defaults to 40 Mbps (decimal). Combined limit only via --bandwidth flag. Reduced-mode scheduling (InproxyReduced* via --set) is the mechanism for time-based throttling.
conduit_is_live	Confirmed (1=broker connected, 0=disconnected). Not yet in CCC. Must be the topmost status signal in v0.2.0.
Ryve Security	conduit ryve-claim prints the private key to stdout. CCC must never store or display it. Use --output for PNG only; discard stdout private key field entirely.
InproxyMaxPersonaIClients	NOT in --set allowlist. v0.4.0 must use --max-personal-clients flag in the service unit drop-in, not --set.

4. v0.1.1 — Maintenance Release

v0.1.1 is a maintenance-only release. No new user-facing features.

Issue	Title	Priority
#3	Harden pair() subprocess PATH in adapter.py	High
#4	Restrict ccc.db file permissions (644 → 600)	High
#5	Remove duplicate DDNS cron entry from root crontab	Medium
#6	Update UFW firewall rules in pre-install.md	Low

Release criteria: all four issues resolved, tests green, CHANGELOG updated.

5. D1 — UX/UI Design Milestone (Gate for v0.2.0)

Gate: No v0.2.0 implementation begins until D1 design deliverables are approved. The dashboard must be designed to a professional frontend/UX standard before any implementation code is written.

The dashboard must not be a raw metrics dump. Every screen must be understandable and actionable by a non-technical volunteer operator without reading documentation.

5.1 Design Principles

Principle	Requirement
User-friendly	Operators must understand every value on screen without knowing Prometheus, systemd, or Go.
WYSIWYG	Configuration changes must preview their effect before being applied.
Non-technical clarity	No raw metric names, no internal identifiers, no backend jargon exposed to users.
Clean and modern	Visual design consistent with contemporary dashboards (Grafana, Vercel, Linear).
Mobile-friendly	Fully usable on a smartphone. Operators must check health and change limits from their phone.
Lightweight	No heavy JS frameworks. Must load acceptably on Raspberry Pi 4 over slow mobile. Max 300 KB initial payload.

5.2 Information Architecture

The dashboard is organised into eight named sections driving navigation and feature grouping across v0.2.0–v0.4.0:

#	Section	Contents
1	Overview	Station status, health indicator, key metrics summary — the home screen
2	Live Clients	Connected + connecting clients, broker status, uptime, idle time
3	Traffic	Total upload/download, bandwidth limit display
4	Regions	Top active countries with flags, client counts, traffic volumes
5	Configuration	Max common clients, max personal clients, bandwidth limit, apply workflow
6	Scheduling	Bandwidth schedule profiles (reduced-mode)
7	Smart Assistant	Manual / Assisted / Automatic mode selector and analysis panel
8	Personal & Ryve	Personal mode setup, pairing tokens, Ryve claim QR (v0.4.0)

Settings (theme, password, session) are accessible via a gear icon, separate from the eight operational sections.

5.3 First-Screen Requirements

The Overview screen must answer three questions in under three seconds: (1) Is my station working? (2) Is anyone using it? (3) How much have I served?

The following elements must appear above the fold on a standard desktop browser:

Element	Value Shown	Notes
Station status badge	Live / Starting / Offline / Disconnected	Green/yellow/grey/red
Health indicator	Good / Warning / Critical	Derived from status + idle + clients
Connected clients	Integer	Large metric card
Connecting clients	Integer	Secondary metric card
Bandwidth limit	X Mbps or Unlimited	Secondary metric card
Upload total	KiB/MiB/GiB/TiB	Secondary metric card
Download total	KiB/MiB/GiB/TiB	Secondary metric card
Top active countries	Top 3–5 names + client counts	Compact summary; links to Regions
Uptime	Xd Xh Xm	Secondary detail

5.4 Navigation Model

Viewport	Navigation Pattern
Desktop	Persistent left sidebar with section icons and labels. Collapses to icon-only at narrower widths. No horizontal top navigation.
Mobile	Bottom navigation bar for 5 primary sections (Overview, Live Clients, Traffic, Regions, Configuration) + More. No hamburger menu.

- Current section title is always visible in the page header.

- Sections are flat — no breadcrumbs required.
- Destructive actions (apply config, restart service) are never reachable in one tap. They require entering Configuration first.
- Deep-linking to sections is supported (/dashboard#regions, /dashboard#config).

5.5 Visual Hierarchy Rules

Rule	Detail
Large metric cards	3–4 most critical values per section. Number font size $\geq 32\text{px}$.
Secondary cards	Supporting values (connecting clients, uptime). Same component, smaller.
Tables	Only when a list of comparable rows is genuinely the clearest format. Never for single values.
Charts	Only when the shape of data over time improves a decision (v0.3.0+). Not in v0.2.0 except where called out.
No raw metric names	Never display conduit_bytes_uploaded, conduit_is_live, or any Prometheus identifier.
No raw ISO codes alone	Always show flag emoji + country name + ISO code in parentheses.
Colour semantics	Green=live/good. Yellow=warning/transitioning. Red=error/offline. Grey=unknown/stopped. Blue=informational.
Empty states	Every section with potential zero data must display a friendly explanation of what will appear once data is available.

5.6 Human-Readable Values

Value Type	Display Format	Example
Byte counts (transfer totals)	Binary: KiB, MiB, GiB, TiB	14.3 GiB
Bandwidth limit	Decimal Mbps (matches CLI) or Unlimited	40 Mbps / Unlimited
Duration (uptime, idle)	Xd Xh Xm Xs — omit leading zero units	2d 4h / 37m 12s
Client counts	Plain integer	127
Country identifiers	Flag + full name + ISO code in parentheses	Myanmar (MM)
Conduit version	Semantic version from build info	v2.0.0
Timestamps	Local time YYYY-MM-DD HH:mm	2026-06-10 14:23
Bandwidth rates (v0.3.0+)	Binary + /s	1.2 MiB/s

Never mix decimal and binary byte prefixes on the same panel. Mbps (decimal) is used exclusively for the configured bandwidth limit. All other byte quantities use binary prefixes.

5.7 Settings UX

The Configuration section manages all parameters that affect Conduit's behaviour. Because changes cause a service restart, every interaction must be deliberate and reversible.

Layout: single form with logically grouped sub-sections (Client Limits, Bandwidth, Scheduling). A persistent Apply Changes button disabled until the operator changes at least one value.

Field	Input Type	Constraints
Max common clients	Number input + slider	0–1000. Warning if both common and personal would be 0.
Max personal clients	Read-only in v0.2.0	"Personal mode not yet configured" placeholder.
Global bandwidth limit	Number input (Mbps) + Unlimited toggle	Minimum 1 Mbps.
Smart Assistant mode	Three-way toggle: Manual/Assisted/Automatic	Automatic requires a separate confirmation dialog.

Save/apply workflow: (1) Operator changes a value — changed fields highlighted. (2) Diff summary appears: "You are changing: Max common clients 50 → 75". (3) Operator clicks Apply Changes. (4) Confirmation modal with diff and restart warning. (5) Operator confirms — CCC writes drop-in, restarts service, shows progress. (6) Success: green toast. Failure: red toast, no changes retained.

Bandwidth schedule layout: visual 24h timeline bar with reduced window highlighted. Fields: start time, end time, reduced bandwidth (Mbps), reduced max clients (optional), schedule type (Weekdays / Weekends / Every day / Custom). Tooltip explains 100 GB / 7 day minimum. Same diff+confirm+restart flow.

5.8 Warnings, Confirmations, and Errors

Level	Trigger	Presentation
Toast	Success actions, non-critical state changes	Bottom-right, auto-dismiss 4s. Green or red.
Banner	Station offline, broker disconnected, health degraded	Top of section, persists until resolved. Yellow or red. Dismissible.
Modal	Restarts Conduit, enables Automatic mode, Ryve claim	Blocking. Shows exact change and consequence. Cancel always present.

Required warning messages:

Context	Message Text
Before applying config	Applying these changes will briefly restart Conduit. Clients currently connected will be disconnected for a few seconds. Do you want to continue?
Before Automatic mode	Automatic mode will adjust your client limits without asking for confirmation. You can set minimum and maximum bounds. Are you sure?
Before Ryve claim (v0.4.0)	Generating the Ryve claim QR code requires accessing your station's private key. The key will not be stored or transmitted — only the QR image will be displayed. This should only be done in a private location. Continue?
Station offline banner	Your Conduit station is not running. Check the service status or review the logs.
Broker disconnected	Conduit is running but not connected to the Psiphon broker. No clients can be served until the connection is restored.
New station empty state	No clients connected yet. New stations can take several hours to receive traffic while building reputation with the Psiphon network.

5.9 Mobile Behaviour

The dashboard must be fully functional on a 375px-wide smartphone screen.

Component	Mobile Behaviour
Sidebar navigation	Hidden. Replaced by bottom navigation bar (5 primary sections + More).
Metric cards	Stack vertically, full width.
Configuration form	Single-column layout. Sliders replaced by number inputs with +/- buttons.
Regions table	Simplified: flag, country name, clients only. Traffic columns hidden (expand per row).
Modals	Full-screen on small viewports.
Charts (v0.3.0+)	Horizontally scrollable within their container.
Toast notifications	Bottom-centre, full width.
Touch targets	All interactive elements: minimum 44×44px touch target.

5.10 Theme Support

Three modes: **Light**, **Dark**, **System** (follows OS preference).

Requirement	Detail
Implementation	CSS custom properties (--color-bg, --color-surface, --color-text, etc.). No JS required to switch.
Persistence	Server-side cookie (theme=light dark system) via settings endpoint. Not localStorage.
System fallback	@media (prefers-color-scheme: dark) as CSS fallback for System mode.
Toggle placement	Small icon in header or sidebar footer, accessible from all screens.
Contrast	All status colours must meet WCAG AA contrast in both light and dark themes.
Charts & tables	Theme-aware colour palettes — no hardcoded colours.

5.11 Pre-Implementation Deliverables

The following design artefacts must be produced and approved before any v0.2.0 implementation code is written:

Deliverable	Description
Dashboard layout proposal	Annotated wireframe or mockup of each section on desktop and mobile. Must show navigation model, card hierarchy, and Configuration form layout.
Section hierarchy document	Written description of each section's content, information priority, and relationship to adjacent sections.
Card/table structure specification	For each metric card and table: data source, display format, empty state, and error state.
Navigation model diagram	Diagram showing movement between sections, what is reachable from Overview, and what requires deliberate navigation.
Mobile wireframe	Wireframe of bottom navigation bar and at least three sections in mobile layout.
UX rule document	All warning messages, confirmation dialogs, and error states from Section 5.8 plus any additional cases identified during design.

6. v0.2.0 — Smart Conduit Control

Gate: D1 design deliverables must be approved before implementation begins.

v0.2.0 transforms CCC from a read-only monitoring dashboard into an interactive control centre. Central theme: *display everything Conduit exposes and give operators control over the parameters they need most.*

6.1 Conduit Configuration

Parameter	Source Metric	Range	Notes
Max common clients	conduit_max_common_clients	0–1000	At-least-one-client enforced
Max personal clients	conduit_max_personal_clients	0–1000	Read-only v0.2.0; write in v0.4.0
Global bandwidth limit	conduit_bandwidth_limit_bytes_per_second	1–∞ Mbps / unlimited	Display/input as Mbps. 0=unlimited

Apply mechanism: write new flags to systemd service unit drop-in (/etc/systemd/system/conduit.service.d/ccc.conf), run systemctl daemon-reload && systemctl restart conduit. Follow the confirm+restart workflow defined in Section 5.7.

Note: conduit_bandwidth_limit_bytes_per_second uses decimal megabits (1 Mbps = 125,000 bytes/sec). Display and input must use decimal Mbps.

6.2 Live Operations Panel

Metric	Source	Display Format
Broker status	conduit_is_live	Live/Starting/Offline/Disconnected badge
Connected clients	conduit_connected_clients	Large metric card
Connecting clients	conduit_connecting_clients	Secondary metric card
Uptime	conduit_uptime_seconds	Xd Xh Xm
Idle time	conduit_idle_seconds	Xd Xh Xm or Active
Bytes uploaded	conduit_bytes_uploaded	KiB/MiB/GiB/TiB
Bytes downloaded	conduit_bytes_downloaded	KiB/MiB/GiB/TiB
Build revision	conduit_build_info	v2.0.0 · short-rev

State	Condition	Indicator
Not running	No metrics endpoint reachable	Grey
Starting	announcing=1, is_live=0	Yellow
Live	is_live=1	Green
Disconnected	is_live=0, not announcing	Red

Idle assistant trigger: if idle > 12h and clients == 0, Smart Assistant shows: "Your station hasn't served any clients recently. New stations can take 24–48 hours to build reputation."

6.3 Regional Analytics

Top 15 active regions displayed as a table with flag emoji + country name + ISO code. Regions with zero clients AND zero bytes are hidden. Scope filter (All/Common/Personal) visible only when personal clients > 0.

6.4 Smart Assistant

Manual and Assisted modes ship in v0.2.0. Automatic mode deferred to v0.3.0 (risk: restart cascades on Raspberry Pi during peak traffic; requires audit log infrastructure that ships in v0.3.0).

Assisted mode analysis inputs: CPU (psutil), RAM, connected clients, bandwidth limit, bytes up/down, idle seconds. Baseline: ~150–350 users per CPU/2 GB RAM (GUIDE.md).

6.5 Bandwidth Scheduling

Time-based profiles using InproxyReduced* via --set, presented as a visual 24h timeline (Section 5.7). Fields written: InproxyReducedStartTime, InproxyReducedEndTime, InproxyReducedLimitUpstreamBytesPerSecond, InproxyReducedLimitDownstreamBytesPerSecond, InproxyReducedMaxCommonClients (optional). Same confirm+restart flow as Configuration.

Implementation note: Section 6.5 is blocked on Section 6.1 being shipped and stable. Both share the same systemd drop-in write path.

6.6 Broker Live Status

conduit_is_live is the topmost element on the Overview screen and also present in Live Clients. Four-state logic defined in Section 6.2. Broker disconnected banner per Section 5.8.

6.7 Theme Support

Light / Dark / System themes per Section 5.10. Preference persisted via server-side cookie.

7. v0.3.0 — Historical Analytics & Operations

Feature	Description
Historical charts	Time-series for connected clients, bytes transferred, bandwidth. SQLite, 30-day default retention.
Health score	Composite: uptime %, broker live %, avg client count, bandwidth headroom. Shown on Overview.
Smart Assistant — Automatic mode	Adjusts max_common_clients within operator bounds. Requires audit log infrastructure from this release.
Backup & restore	Export CCC config (not Conduit key) to encrypted archive. Restore from archive.
Update centre	Check GitHub releases API. Display release notes. One-click update (update.sh). No auto-update.
Per-direction bandwidth display	Show upstream/downstream limits separately if set in psiphon_config.json. Read-only.

8. v0.4.0 — Personal Mode & Ryve

Feature	Description
Personal mode setup	Generate compartment ID, persist to personal_compartment.json, display in Config panel.
Pairing token generation	Build v1 pairing tokens. Display as QR + copyable string. Max name: 32 chars.

Feature	Description
Personal client limit control	--max-personal-clients write path (requires compartment ID). Uses flag, not --set.
Scope filter in Regions	Show common/personal breakdown when personal clients > 0.
Ryve claim QR	Subprocess after full-screen modal (Section 5.8). Serve QR PNG. Delete after display. NEVER store private key.
ProxyID display	Show Curve25519-derived ProxyID. Display-only.
Ryve rewards	Out of scope until rewards data exposed via metrics or documented API.

Security (Ryve): conduit ryve-claim prints the private key to stdout. Capture only the PNG path and ProxyID. Discard the private key before any logging or storage. Full-screen modal warning required before invocation.

9. Out of Scope

Item	Reason
Ryve rewards / points data	Not in Conduit binary. Requires documented Ryve API.
Per-user invitation management	Android only. No Linux CLI mechanism confirmed.
Separate upstream/downstream write	Requires psiphon_config.json changes, not --set. Deferred.
Auto-update	Update centre is one-click only. No unattended upgrade.
Multi-node management	CCC manages one Conduit instance per installation.
Psiphon config file editing	psiphon_config.json is provided externally.

10. Revision History

Version	Date	Notes
1.0	2026-06-10	Initial draft. R1 capability audit complete.
1.1	2026-06-10	Added Section 5: D1 UX/UI Design Milestone gate for v0.2.0. Sections renumbered 6-10. Smart Assistant Automatic mode deferred to v0.3.0. Theme persistence changed from localStorage to server-side cookie.

For questions or contributions, open an issue at the CCC GitHub repository.