Solaris Accounts

Account default settings file: /etc/login.defs Default user shell init files: /etc/skel ****** Local Accounts: ****** Create a new group: # groupadd -g <gid> <groupname> Delete a group: # groupdel <groupname> Modify a group definition: # groupmod -g <gid> <groupname> To create a new account, you will need a username and a UID. If a UID isn't available, the system will assign the next available UID. Create a user account: # /usrsbin/useradd -d <path-to-home-directory>/userid -m -s /bin/ <shell> -c "User's Full Name" <userid> Note: -d may be omitted if you are using the system default "home" directory path -m makes the home directory and copies the default init files from /etc/skel Assign a default password: # passwd <userid> Change ownership of a home directory: # chown -R <userid>:<primary_group> <directory_name> Change the UID (note: user cannot be logged in) # usermod -u <newuid> <olduid> Change user's shell: # passwd -e Delete a user account: # /usr/sbin/userdel -r <userid> Change userid and home directory: # usermod -d <path to home directory> -m -l <new userid> <old userid> ****** NIS+ Accounts: ****** NIS+ Tables that need to be updated for accounts: 1. shadow; 2. passwd; 3. cred; 4. scoscntl NIS+ Required Processes: /usr/sbin/rpc.nisd /usr/sbin/nis cachemgr /usr/sbin/rpc.nispasswdd

Change User's Shell

nispasswd -s <userid>
Prompt: New Shell: <type_in_full_path_and_shell_executable>
i.e. /bin/bash

Change a user's DES Key

chkey -p note: requires user's original or "old" password Note: If a user receives the error: "The Secure RPC credential information for <userid> will not be changed" or "Secure RPC key will not decrypt secret." Fix using the "chkey -p" tool to re-encrypt the DES credentials.

Display password history file objects: % niscat —o passhist