Ref: 30023/1.10/1.9/SD

User Guide

Product Name Borrower Portal User Guide

Notice

The information contained in this document is confidential, and is intended only for use internally by the company to which it is delivered by Company Name Limited. Any reproduction of this document, in whole or in part, or the disclosure of any of its contents, without the prior written consent of Company Name Limited is prohibited.

Note that in no event shall Company Name Limited be liable for any loss of profits, loss of business, or loss of data, or for indirect, incidental or consequential damages of any kind, arising from any error in this document.

Copyright © 2025 Company Name Limited.

All Rights Reserved.

2, Example Street, London, UK

Tel: +44 +44 (0)123 456 7890

Email: info@companyname.com

Company Name Limited recognises that all product names mentioned in this document are trademarks or registered trademarks of their respective owners.

Revision History

Version	Date	Reason	Who
1.0	26/03/2024	New Borrower Portal User Guide, based on content from original Portal user guide that contained elements of both Borrower and Lender Portals.	Peter Kingston
1.1	17/04/2024	Updated version based on release 1.1.11 of Product Name Borrower Portal.	Peter Kingston
1.2	23/05/2024	Updated version based on release 1.2 of Product Name Borrower Portal.	Peter Kingston
1.3	25/06/2024	Updated version based on release 1.3 of Product Name Borrower Portal. Added descriptions of hide and lock column functionality. Removed a number of columns from Availability tab. Added new Smart Bucket fields to tabs. Added description of improved column selection. Added new Central Counterparty fields to tabs. Updated formatting of Ready to Book download file. Added Expiry dropdown to Borrow Request Tab. Updated descriptions in line with counter-offer improvements.	Peter Kingston
1.4	15/07/2024	Updated version based on release 1.4 of Product Name Borrower Portal. Added description of incorrect login entry lockout. Updated “To create and send a new request” to cover ability to upload requests from an Excel spreadsheet. Documented new ability to accept/reject Lender modifications to firm borrow request responses in the Firm Request List Grid. Updates to “Availability Tab” to cover splitting out of two new sub-tabs.	Peter Kingston
1.5	07/08/2024	Updated version based on release 1.4.11 of Product Name. Added	Peter Kingston

© 2025 by Company Name Ltd.

Version	Date	Reason	Who
		description of the new Trades Grid in the Borrow Requests Tab.	
1.6	12/09/2024	Updated version based on release 1.5 of Product Name. Added description of applying Values to Multiple Cells. Updates covering changes to Callable checkbox. Added description of Profile default 'Callable' options. Added description of new grid download functionality.	Peter Kingston
1.7	09/10/2024	Updated version based on release 1.6 of Product Name. Added description of the new End of Day Tab. Clarified how TA uses the term 'LEI'. Updates covering new password reset and management. Added two new fields to various tabs, *Our Settlement Account* and *Cpty Settlement Account* to support identification of source/target DTC accounts.	Peter Kingston
1.8	12/12/2024	Added description of how to restore columns to default layout. Added description of notifications on tab headers when something changes within a grid.	Peter Kingston
1.9	03/01/2025	Added description of new *Availability Search* Sub-Tab from the *Availability* Tab. In the *Lender Posted Availability* Sub-Tab of the *Availability* Tab, the existing field *Price* has been renamed to *Price Without Margin*. In the *Borrow Enquiries* Sub-Tab of the *Availability* Tab, the existing field *Price* has been renamed to *Price Without Margin*. In the *Borrow Requests / Ready to Book / End of Day* Tabs::	Peter Kingston

© 2025 by Company Name Ltd.

Version	Date	Reason	Who
		The existing field *Price* is now the price with margin. The existing field *Billing Price* is now the billing price with margin. Two new fields, *Price without Margin* and *Billing Price without Margin* have been added to each tab.	
1.10	03/02/2025	Added details of how to reset password. Previously, in the *Lender Posted Availability sub-tab*, if a user borrowed directly from a line of availability from a Lender, it always disappeared from the tab. Now, the user can borrow as many times as they like, and the lend list entry will remain in the *Lender Posted Availability sub-tab*, with separate entries appearing in the *Borrow Request Tab* for each borrow. Documented the new *Outcomes* dropdown in the *Negotiations sub-tab*. Added new *Price Unit* and *Value without Margin* fields to various tabs.	Peter Kingston

© 2025 by Company Name Ltd.

Table of Contents

INTRODUCTION 7

Purpose of document 7

Who should read this document 7

Structure of this document 7

OVERVIEW 8

What is Product Name? 8

Getting Connected 8

LOGGING IN 9

To change your password 9

To reset your password 9

To log out 9

Using the Grids and Tabs 10

Managing Profiles 14

Switching Between Borrower and Lender Roles 15

Switching Between Legal Entities 15

BORROW WORKBOOK TAB 16

AVAILABILITY TAB 20

Borrow Enquiries Sub-Tab 20

Lender Posted Availability Sub-Tab 26

Availability Search Sub-Tab 31

Example of Negotiation Using Counter-Offers 32

BORROW REQUESTS TAB 33

Lists Grid 33

Firm Request List Grid 34

Trades Grid 38

READY TO BOOK TAB 39

END OF DAY TAB 41

All Trades Sub-Tab 41

Negotiations Sub-Tab 41

© 2025 by Company Name Ltd.

Introduction

Purpose of document

This document provides user-level instructions on how to get the most out of the Product Name Borrower Portal.

Who should read this document

This document is aimed at traders looking to understand how to use the Product Name Borrower Portal.

Structure of this document

The remainder of this document contains the following sections:

- *Overview*: A high-level description of Product Name and its associated GUI.
- *Logging In*: How to access and manage the system.
- *Borrow Workbook Tab*: Features of the tab used to create and manage a list of borrow requests, before sending to a Lender.
- *Availability Tab*: Features of the tab used to view Lender responses to your availability requests, or unsolicited availability messages from a Lender (Push Lists).
- *Borrow Requests Tab*: Features of the tab used to view active lists you've sent in, or availability lists that you've received from Lenders.
- *Ready to Book Tab*: Features of the tab used to view requests that have been sent successfully, have been accepted and are now ready to book.
- *End of Day Tab*: Features of the tab used to review and download a file of accepted trades for the current day, and generate an Audit Report of pre-trade conversations.

© 2025 by Company Name Ltd.

Overview

What is Product Name?

Product Name is a global bilateral messaging service provided by Company Name. It presents a novel trading alternative, designed to offer market participants a secure, dependable, and cost-effective trading solution. This platform will effectively enable and support pre-trade negotiation and post-trade lifecycle events, encompassing actions such as trade execution, rerating, recall, and return processes. Notably, it encompasses the capability to send and receive targeted availability notifications, availability requests, requests to borrow, counter offers, and completed trade confirmations, thus enhancing the overall trading experience.

Getting Connected

The process of establishing a connection is straightforward and, in certain instances, plug-and-play, contingent upon the specific system configuration. A graphical user interface (GUI) is accessible to participants (the use of which is described in this document) or our Application Programming Interface (API) can be utilised (which is described in the separate *Product Name API Getting Started document*).

Product Name is delivered as a cloud-based Software-as-a-Service (SaaS) subscription service, accessible through standard Web service API calls, rendering it readily available to the market. Furthermore, it incorporates built-in disaster recovery capabilities, thus obviating the need for Message Queues (MQ) or leased line expenses.

© 2025 by Company Name Ltd.

Logging In

To access the application, do the following:

1. In your Web browser, enter the URL for the Product Name Borrower Portal.

   Staging:
   https://pname-staging.tradingapps.com/productname/portal/borrower

   Production:
   https://pname-prod.tradingapps.com/productname/portal/borrower

   The Login screen appears:



2. If this is your first log in, you will have been sent a link and a PIN in two separate emails. Click the link, and you will be prompted to enter the PIN. Then you will be prompted to provide a password that you will then use for future logins. New passwords must meet the following minimum criteria:
   - ◊ 16 characters long
   - ◊ Contains two uppercase, and two lowercase letters
   - ◊ Contains two numbers, and one special character

   Also, if you have had previous passwords for Product Name, the new password cannot be one of the five previous you have used.
3. When you log in to the Product Name Access Management Portal, your *Main Screen* will be displayed.

To change your password

If you need to change your password, then click the button and select *Change Password*. New passwords must meet the minimum criteria listed above.

To reset your password

If you forget your password, click *Forgot your Password?* Then enter your Product Name Portal User ID and click *Request Password Reset Email*. If your email is registered, you should shortly receive a reset email with a link to update your password. If not, contact your user administrator as your account may be locked.

To log out

To log out, click the button and select *Logout*. You return to the Login dialog box.

© 2025 by Company Name Ltd.

Using the Grids and Tabs



The *Main Screen* of the Product Name Borrower Portal consists of five main tabs:

- *Borrow Workbook*: This is the default initial tab that is displayed when you log in. Here you can create and manage a list of borrow requests, or requests for availability, before sending to a Lender.
- *Availability*: Contains two further sub-tabs, the *Borrow Enquiries* Sub-Tab and the *Lender Posted Availability* Sub-Tab. Where you view Lender responses to your availability requests, or unsolicited availability messages from a Lender (Push Lists).
- *Borrow Requests*: Where you can view and manage your active firm borrow requests.
- *Ready to Book*: Where you can view and generate downloads of firm borrow requests that have been accepted by the Lender and are now ready to book.
- *End of Day*: Where you can review and download a file of accepted trades for the current day, and generate an Audit Report of pre-trade conversations.

You can also click *Logout* to leave the Portal.

If there are new messages in the *Borrow Enquiries* or *Borrow Requests* tabs and those tabs are not currently active, a red exclamation mark will appear next to the tab name to indicate new messages. The mark will disappear once the tab is clicked and loaded.

Filtering Items

If a grid has data in columns and rows, you use *Filters* to quickly and simply filter data across one or more of them. From the box under the column heading, you select an operator then type a value. The data in the grid will then automatically be filtered accordingly as follows:

Op.	Name	Action
=	Is equal	Displays data that exactly matches the filter value.
≠	Not equal	Displays data that does not exactly match the filter value.
~	Like	Displays data that is similar to the filter value.
>	Greater Than	In numeric columns, displays data that is greater than the filter value. In date/time columns, displays data that is later the specified date/time.

© 2025 by Company Name Ltd.

Op.	Name	Action
>=	Greater Than or Equal To	In numeric columns, displays data that is greater than or equal to the filter value. In date/time columns, displays data that is equal to or later than the specified date/time.
<	Less Than	In numeric columns, displays data that is less than the filter value. In date/time columns, displays data that is before the specified date/time.
<=	Less Than or Equal To	In numeric columns, displays data that is less than or equal to the filter value. In date/time columns, displays data that is equal to or before the specified date/time.
∅	Empty	In text columns, displays data where the value in this column is empty.
∃	Not Empty	In text columns, displays data where the value in this column is not empty.

In date columns, you can also filter by date by clicking on the calendar icon and selecting a date using the date selection tool. You can quickly remove a filter by clicking the **X** icon to the left.

Tip: You can copy and paste multiple security identifiers from a Bloomberg chat, text file or Excel file and paste them into the quick filters. This makes it much easier for you to search for a list of securities you are interested in rather than having to search for them one at a time.

Applying Values to Multiple Cells

If you, for example, are borrowing from multiple lines of availability, it can be time-consuming to fill in the same details on multiple rows. Therefore, when right-clicking on a value in an editable field in a grid, you have these menu options to help:

- To apply the value to all otherwise empty cells in the corresponding grid column. This will not change the values in fields that already contain a value.
- To force the value to all cells in the corresponding grid column. Following a confirmation prompt, this will overwrite the values in fields that already contain a value.
- To clear the values in all editable cells in the corresponding grid column.

Note that this feature does not apply to:

- Action column options (i.e., Accept, Counter, Reject)
- Read-only tabs (Ready To Book Tab, etc.)

Tip: You can quickly populate fields in specific rows by first applying a filter to display only those rows. Then, use the functionality above, which will affect only the visible rows.

© 2025 by Company Name Ltd.

Configuring Columns

When you first log in to the Product Name Borrower Portal, the grids will display a default set of columns considered to be the most useful. You can, however, hide any of these, or even select from an extensive set of alternative columns.

Selecting Columns

To select which columns to display in a grid, hover over any column header and click the down arrow next to the column title to display a list of all available columns (see right).



From here you can select or deselect checkboxes, indicating which columns to display. When you select a new column, this is inserted to the right of the column from which you accessed the column selector.

Changing Column Order

When you have selected the columns you want, you can change the order of displayed columns within the grid itself by clicking and holding the column title and dragging and dropping it to the required location.

Hiding Columns

To quickly hide a column from display without having to navigate through the column list and deselecting it, you can click the down arrow on the column and just select *Hide Column*. To un-hide the column, click the down arrow on any visible column, and then select the hidden column from the column list.

Locking Columns

Locked columns enable you to display specific columns at all times while you scroll the grid horizontally. To lock a column, click the down arrow above a column, and select *Lock*. The column is then shifted to the left of the grid. To unlock, click the down arrow again, and select Unlock.

Restoring Columns to Default Layout

If you have made changes to the default column layout using the actions above, and you want to restore the columns back to the original default layout, click the down arrow above a column, and select *Default Layout*.

Sorting Items

To sort the data, you can click on the column header to alternate between a descending and an ascending sort. Another way is to hover over the column header and click the triangle next to the column title. A menu will open with options to sort in ascending or descending order. When the column is sorted, an arrow will be displayed in the column header, indicating the direction of the sort.

© 2025 by Company Name Ltd.

Downloading Grid Data

It's sometimes useful to be able to download the content of grids as a file so that you can use the data elsewhere (e.g., perform calculations, or use in reports).

To do this, click the *Download* button in a grid header bar, and then select a format to export (.xslx, or . csv). The file is then saved to your default downloads location with a filename that includes the time and date downloaded. All rows in your grid are downloaded (subject to the Excel-imposed restriction of 1,048,576 rows) - however only those columns that you have selected for display (see page 12) are included.

© 2025 by Company Name Ltd.

Managing Profiles

Product Name allows you to create profiles to define default values that will then automatically populate specified fields when you add securities to the *Borrow Workbook*, with that Profile selected. You can create multiple Profiles for different scenarios and even share the Profiles, so they are available to your colleagues. If you have no Profile selected, then no defaulting occurs.

To select an existing Profile

If you have previously created a Profile you want to apply, you just open the *Profile* dropdown at the top right of the *Main Screen*:



Then select the Profile you require.

To create a new Profile

Initially, when you first log in to the *Borrow Workbook Tab*, you will not have a Profile ('No Profile' is displayed), and you will have to create one:

1. From the *Profile* dropdown at the top of the *Main Screen*, click the down arrow.
2. Now select *Create New Profile* to open the *Create New Profile* dialog box.
3. Complete the fields as follows:

Field	Description
Name	Unique identifier for your Profile.
Description	Brief textual description of your Profile.
Shared	Whether or not you want your Profile to be viewed, used and amended by other users.
Collateral Type	Default collateral type requested for your Profile. Select from *Cash*, *Non-Cash*, or *Cash Pool*.
Collateral Currency	Default collateral currency for your Profile.
Collateral Group	If the *Collateral Type* is *Non-Cash*, the default collateral group for your Profile.
Settlement Type	Default settlement type for your Profile. Select from *DVP*: Delivery Versus Payment or *FOP*: Free Of Payment.
Div Req Type	Default dividend requirement type. Select from: *Maximum*: Any dividend requirement up to and including the value in the *Div Req* field. *Absolute*: Dividend requirement must be equal to the value in the *Div Req* field.
Div Req	Default dividend requirement. See *Div Req Type*.
Billing Currency	Default billing currency.
Trading Increment	Default trading increment (only positive quantities in increments of this are accepted).

© 2025 by Company Name Ltd.

Field	Description
Callable	Default callable indicator (*YES*, *NO* or unspecified (blank)).
Expiry	Default expiry time, indicating how long borrow requests will be valid for after being sent. Choose from a pre-defined list of time periods.

Once you have completed the fields, click *Save* to store the new Profile, and return to the previous screen. The Profile you have just created will be applied.

To delete a Profile

If you have previously created a Profile you want to permanently remove:

1. From the *Profile* dropdown at top right of the *Main Screen*, click the down arrow.
2. Now click the delete icon to the right of the Profile you want to remove.
3. You are prompted to confirm the deletion.

To edit a Profile

If you have previously created a Profile and want to change it:

1. From the *Profile* dropdown at top right of the *Main Screen*, click the down arrow.
2. Now click the edit icon to the right of the Profile you want to amend to display the *Edit Profile* dialog box.
3. Edit the fields as described under *To create a new Profile* on page 14.
4. Click *Save* to store the edited Profile, and return to the previous screen. The Profile you have just edited will be applied.

Switching Between Borrower and Lender Roles

If your institution uses Product Name in both a Borrower and Lender mode (e.g., as a broker), then you may have access to both the Product Name Borrower and the Product Name Lender Portals. In which case, to switch simply between these Portals, click the appropriate *Lender* or *Borrower* button at the top right of the *Main Screen*. For more on the Product Name Lender Portal, refer to the separate *Product Name Lender Portal User Guide*.

Switching Between Legal Entities

Organisations may have more than one legal entity. If you sit within multiple legal entities, then you can switch between them by clicking the dropdown at the top right of the *Main Screen* and selecting the appropriate Legal Entity Identifier (LEI). At Company Name, an LEI is a single child subsidiary that sits under the parent Organisation. The *LEI Name* does not need to conform to the ISO 17442 standard used to identify financial organisations. It just needs to be a unique identifier within Product Name, e.g.: 'BANK-ABC-LENDER-ENTITY2'.

© 2025 by Company Name Ltd.

Borrow Workbook Tab

When you log in, the default view is of the *Borrow Workbook Tab* (see the example on page 10). You use this tab to create and manage a list of availability requests or firm borrow requests before sending to a Lender.

To create and send a new request

To create and send a request, you do the following:

1. Ensure that, from the *Counterparty* dropdown, you have selected the Lender to whom to send the request. If the counterparty has configured their side it is here where you would see their DTC account (or LEI ID). Once you select a *Counterparty*, the grid below is unlocked.
2. In the *Settlement Account* dropdown, you can choose your DTC account so that the recipient knows exactly who is making the enquiry/request.
3. In the *List Name* field, type a unique name for a new list to contain the request, or leave blank to accept the automatically generated name.
4. The *Firm Request* checkbox is selected by default, indicating to the Lender that you are good to trade. However, if you simply want to make an availability request, unselect this checkbox. If required fields have not been entered, the row will be highlighted red, along with a tooltip describing the issue.
5. The *Allow Partials* checkbox is selected by default, indicating to the Lender that you are willing to accept a partial fill. If this is not the case, unselect this checkbox.
6. The *Allow Counter Offer* checkbox is also selected by default, indicating to the Lender that you are willing to accept counter offers. If this is not the case, unselect this checkbox.
7. If you want to limit how long your borrow requests are valid for, select a period of time from the *Expiry* dropdown. It is also possible to specify a default expiry time in your profile, and this expiry time will then be populated in the *Expiry* box.
8. You can then enter requests in one of two ways:
   - ◊ Type/copy/paste details directly into the grid (go to step 9).
   - ◊ Upload from a Microsoft Excel spreadsheet (go to step 8).
9. If you prefer to upload from an Excel spreadsheet, you can use a template to assist you by clicking on *Download Template*. This will open a drop-down menu, allowing you to choose one of two templates (*Availability Request* or *Firm Request*), which will download to your default Downloads folder. These templates contain three tabs:
   - ◊ A blank sheet for entering details of your availability requests or firm requests to be uploaded.
   - ◊ A sheet containing a description of all the available fields, including the expected column headers, data format and minimum columns to be supplied. Note that columns are subject to change between versions.

© 2025 by Company Name Ltd.

◊ A sheet containing an example upload.

Format the template to include the fields you would like and save for future use. Now you will not have to do this again.

To upload requests, ensure all the details are added to the file and save it. Now return to the *Borrow Workbook* Tab and click *Upload Requests*. You will have to choose which type of file you want to upload (*Availability Requests* or *Firm Requests*) and then you will be presented with a dialog box to search for the file you just created. Browse for the file and click *OK* to begin the upload. You will see the requests from the template replicated in the *Workbook* grid.

10. When you start to enter details in a row, initially, it may be highlighted red, indicating that further details are required. This will also be indicated by the text 'INVALID' in the *Transport Status* column. Hover your mouse over the row to see what further fields are required to complete the request correctly.

    If you are simply making an availability request, the minimum information you need to provide is a security identifier (CUSIP, Ticker, etc.)

11. When the row is no longer highlighted red, the request is ready to send. The *Transport Status* column will change to 'New' and the *Send* button will become available. Click *Send* to send the firm/availability request. You will be prompted to confirm the message. You can also click *Clear* to remove your content and start again.

12. Now, the following happens:

    ◊ If this is an availability request (i.e., you unselected select Firm Request), and if the request is sent successfully, it will be removed from the *Workbook* grid, and will be displayed in the *Availability Tab* (see page 20).

    ◊ If this is a firm request, and if the request is sent successfully, it will be removed from the *Workbook* grid, and will be displayed in the *Borrow Requests* tab (see page 33).

    If there has been an issue, it will carry on being displayed with the *Transport Status* of 'SEND' or 'FAILED'. To delete the unsent request, you can right-click on it and select *Delete*.

© 2025 by Company Name Ltd.

The table below lists all available columns in the *Workbook* grid (see *Configuring Columns* on page 12 for more on adding and removing columns):

Column	Description
All-In Rate	All-In dividend rate.
Allow Counter Offer	Indicates whether or not the Borrower will accept counter offers.
Allow Partial	Indicate whether or not the Borrower will accept partial fills.
Billing Ccy	Requested Billing Currency.
Callable	Indicates whether or not the Borrower will accept recalls for this request. Blank means unspecified.
Cash Start Date	Cashflow start date.
Central Counterparty	Code representing the central counterparty. A Borrower can request to borrow through the specified central counterparty. For example, 'OCC' indicates any subsequent trades would be done under the OCC Stock Loan/Hedge Program.
Coll. Ccy	If the requested collateral type is *Cash*, the requested collateral currency can be specified.
Coll. Group	If the requested collateral type is *Non-Cash*, a collateral group can also be specified. This should be a code recognised by both parties.
Coll. Method	Requested Collateral method to use when booking. Can be *Pledge* or *Title Transfer*.
Coll. Type	Requested Collateral Type. Can be *Cash*, *Non-Cash* or *Cash Pool*.
CUSIP	CUSIP security identifier (Committee on Uniform Securities Identification Procedures) for the requested security.
Div Req	Requested dividend requirement.
Div Req Type	Determines what is meant by the *Div Req* value: *Maximum*: Borrower will accept any dividend requirement up to the *Div Req* value. *Absolute*: Borrower will only accept a dividend requirement equal to the *Div Req* value.
End Date	Requested end date.
Firm Request	Indicates whether or not this a firm request (i.e., good to trade). If it is not a firm request then it is a request for availability.
Increment	Borrower will only accept a quantity in increments of this value, e.g., 1,000.

© 2025 by Company Name Ltd.

Column	Description
ISIN	ISIN security identifier (International Securities Identification Number) for the requested security.
Lender	Borrower can specify which underlying fund/beneficial owner they wish to borrow from.
Lender Override	If Borrower specifies a Fund/Beneficial Owner (*Lender* field above), this field allows them to indicate whether or not the Lender can override that preference.
Max. Shapes	Maximum number of shapes/lots the Borrower is willing to accept to fulfil the Borrower request.
Min. Quantity	Minimum quantity that the Borrower will accept, if they have indicated that partial fills are allowed.
Quantity	Quantity of securities requested.
QUICK	QUICK security identifier for requested security.
Rate	Requested rate for the security, quoted as a percentage. Can be a rebate or a fee, depending on the requested *Coll. Type*.
Ref. Index	If the requested collateral type is *Cash*, the requested rate may be quoted as a Reference index + Spread. This is the Reference Index and should be a code recognised by both parties.
Sec. Ctry	Country of the requested security.
SEDOL	SEDOL security identifier (UK Stock Exchange Daily Official List) for the requested security.
Settlement Location	Requested Settlement location.
Settlement Type	Requested Settlement Type. May be *DVP* or *FOP*. Firm requests must have a valid Settlement Type.
Spread	If the requested collateral type is *Cash*, the requested rate may be quoted as a Reference index + Spread. This is the Spread and should be quoted as a percentage.
Start Date	Requested Settlement/Start Date.
Trade Date	Requested Trade Date.
Trade Type	Requested trade type, e.g., stock borrow loan or repurchase agreement (repo).
Transport Status	Transport status of the request (NEW, SEND, SENT, FAILED, INVALID).
Transport Status Detail	Textual description for the *Transport Status*.

© 2025 by Company Name Ltd.

Availability Tab

You use the *Availability Tab* to view Lender responses to your availability requests, or unsolicited availability messages from a Lender (Push Lists). The *Availability Tab* contains three further sub-tabs, the *Lender Posted Availability* Sub-Tab, the *Borrow Enquiries* Sub-Tab, and the *Availability Search* Sub-Tab, as shown in the example below:



Borrow Enquiries Sub-Tab

This sub-tab contains details of your availability requests and the subsequent responses from Lenders.

Enquiries Grid

In the *Enquiries* grid, for each availability request list, there are the following available columns:

Column	Description
Counterparty	Name of the associated counterparty.
Counterparty ID	LEI of the associated counterparty.
Creation Date/Time	Date and time the list was created.
Last Update Date/Time	Date and time the list was last updated.
List Name	Unique name for the Availability request list.
Sender List Group	A group identifier typically supplied by the Lender on the availability to indicate that it should be grouped in a different list on the Borrower side. More likely to be populated on Lender posted availability (push lists) rather than on a response to a Borrower's availability request.
User	User who created the availability enquiry.

To view details contained within an availability request list, select it to populate the *Enquiry Details* grid below.

© 2025 by Company Name Ltd.

Enquiry Details Grid

You can use the *Enquiry Details* grid to borrow directly from Lender availability. For the list selected in the *Enquiries* grid above, there are the following available columns showing the associated enquiry list entries:

Column	Description
Action	For each received availability message from a Lender, you can do one of the following: • Click ✔ to borrow all the availability on the Lender's terms. • Type a new amount in the *Quantity* field (this must be lower than the *Offered Qty*). • Counter the offer. You can *EITHER*: ➢ Click ↩ and type a *Rate* or *Spread*. *OR* ➢ Simply type a new *Rate* or *Spread*. In both cases, the *Status* field changes to *Counter Pending* and the row is highlighted blue. You can click the eraser to reverse any changes. You will be prompted to complete other fields as necessary. When the response is ready to send, the *Send* button will be enabled. Click *Send* to send your response(s) to the Lender. When you receive a response from the Lender, the associated rows will be transferred to the *Borrow Requests Tab* (see page 33), Then, one of the following will happen: • If the Lender has accepted your counter-offer in full, then you can proceed to the *Ready to Book Tab* to generate a file of trade details for upload into your books and records system (see page 39). • If the Lender has responded to your counter-offer with a counter-offer of their own, then the rows will have a Status of *Lender Countered*. You can then either accept ✔ or reject ✖ their counter-offer, or even make another counter-offer of your own using ↩ as above. You can negotiate counter-offers in this way as many times as you wish.

© 2025 by Company Name Ltd.

Column	Description
	If you finally accept the Lender's offer, then click *Send* to send the accept message. The Lender can now proceed to book.
All-In Rate	All-In dividend rate requested by the Borrower or provided by the Lender.
Allow Counter Offer	Indicates whether or not the Borrower will accept counter offers.
Billing Ccy	Billing Currency specified by the Lender.
Central Counterparty	Code representing the central counterparty. A Borrower can enquire about availability that is eligible to be borrowed through the specified central counterparty. For example, 'OCC' indicates any subsequent trades would be done under the OCC Stock Loan/Hedge Program.
Coll. Ccy	Collateral currency requested by the Borrower, or specified by the Lender, if not requested, when the collateral type is *Cash*.
Coll. Group	Collateral group requested by the Borrower, or specified by the Lender, if not requested, when the collateral type is *Non-Cash.* This should be a code recognised by both parties.
Coll. Method	Collateral method requested by the Borrower, or specified by the Lender, if not requested. Can be *Pledge* or *Title-Transfer*.
Coll. Type	Collateral type requested by the Borrower, or specified by the Lender, if not requested. Can be *Cash*, *Non-Cash* or *Cash Pool*.
Counterparty	Name of the associated counterparty.
Counterparty ID	LEI of the associated counterparty.
Cpty Settlement Account	The target Counterparty DTC Account that you sent the enquiry to.
CUSIP	CUSIP security identifier (Committee on Uniform Securities Identification Procedures) for the requested security.
Div Req	Dividend Requirement requested by the Borrower, or specified by the Lender, if not requested.
Div Req Type	Determines what is meant by the *Div Req* value when requested by the Borrower. Can be: *Maximum*: Will accept any dividend requirement up to the *Div Req* value.

© 2025 by Company Name Ltd.

Column	Description
	Absolute: Will only accept a dividend requirement equal to the *Div Req* value.
End Date	End date requested by the Borrower, or specified by the Lender, if not requested.
Expiry Date/Time	Date and time at which availability request (enquiry) from the Borrower will expire and no longer be required.
ISIN	ISIN security identifier (International Securities Identification Number) for the requested security.
Last Update Date/Time	Time and date the enquiry was last updated.
Our LEI	LEI that you are using for this trade.
Lender	If the Lender operates on a disclosed basis, this is the underlying fund/beneficial owner the Borrower has requested to borrow from.
Lender Availability ID	ID supplied by the Lender to identify an availability line. If the Borrower requests to borrow from that availability line, this ID will be returned to the Lender.
Lender Availability Type	Indicates the type of availability posted by the Lender. For availability arising from a Borrower enquiry, this will always be *REQUEST*.
List ID	Unique Product Name ID representing the Enquiry List to which this List entry is associated.
Max. Shapes	Maximum number of shapes/lots allowed to fulfil a Borrower request.
Message Date/Time	Date/time stamp for the message.
Offered Qty	Quantity of securities offered by the Lender.
Offered Rate	Rate offered by the Lender. Can be a rebate or fee, depending on the *Coll. Type*, and is quoted as a percentage.
Offered Ref. Index	Reference Index offered by the Lender.
Offered Settlement Type	Settlement type offered by the Lender.
Offered Spread	Spread offered by the Lender.
Ordinal	Represents the position in the list for borrow enquiries sent by the Borrower.
Our Settlement Account	Your DTC account as you specified while making the enquiry (which is optional).
Price Without Margin	Security price quoted by the Lender.

© 2025 by Company Name Ltd.

Column	Description
Price Ccy	Currency in which *Price* is expressed.
Price Unit	Value by which the price should be divided, to calculate the value of a trade (for example, 100 for bonds, 1 for equities).
Quantity	Borrower enters the quantity they would like to borrow here if they would like to send a firm borrow request directly from the availability line.
QUICK	QUICK identifier for the requested security.
Rate	Borrower enters the rate at which they would like to borrow the security, if they send a firm borrow request directly from the availability line. Can be a rebate or fee, depending on the *Coll. Type*, and is quoted as a percentage.
Reason	Shows the reason why a borrow request has been rejected, e.g., "No availability".
Ref. Index	Reference index used for quoting rates vs cash collateral. For availability posts, it is the reference index used to quote the Lender's offered rate. For availability requests, it is the reference index used to quote the Borrower's requested rate.
Requested Qty	Quantity of securities requested.
Requested Rate	Rate requested by the Borrower on availability requests. Can be a rebate or fee, depending on the *Coll. Type*, and is quoted as a percentage.
Requested Ref. Index	Reference index used by the Borrower on availability requests when the requested rate is quoted as a reference index + spread.
Requested Spread	Spread requested by the Borrower on availability requests when the requested rate is quoted as a reference index + spread.
Sec. Ctry	Country of the requested security.
SEDOL	SEDOL security identifier (UK Stock Exchange Daily Official List) for the requested security.
Sender List Group	A group identifier typically supplied by the Lender on the availability to indicate that it should be grouped in a different list on the Borrower side. More likely to be populated on Lender posted availability (push lists) rather than on a response to a Borrower's availability request.
Settlement Location	Settlement location for the availability. Should be a code recognised by both parties.

© 2025 by Company Name Ltd.

Column	Description
Settlement Type	Settlement type specified by Lender on availability posts. Can be *DVP* or *FOP*.
Smart Bucket	Smart Bucket unique identifier. Smart Buckets allow Lenders to group funds based on RWA ratings, and so on. Then, Borrowers can request to borrow from one of these Smart Buckets. If the Lender accepts, the trade will only be allocated from funds in that Smart Bucket.
Spread	When the Borrower sends a firm borrow request directly from the availability line, and the requested rate is quoted against a reference index, they can enter the spread here. Quoted as a %.
Start Date	Expected Settlement/Start Date requested by the Borrower, or specified by the Lender, if not requested.
TICKER	Ticker security identifier for the requested security.
Trade Date	Trade Date.
Trade Type	Type of trade, e.g., stock borrow loan or repurchase agreement (repo).
Transport Status	Transport status of the request (NEW, SEND, SENT, FAILED, INVALID).
Value	Total value of the securities offered/accepted by the Lender.

Where multiple lines of availability are returned for a single request, use the *Group by Original Request* checkbox to view the availability in one of two ways:

- Unselect, to view all lines of availability in the grid, ungrouped.
- Select, to view availability grouped per request. This makes it easy to see which lines of availability were returned by the Lender for a specific request. You can expand or collapse the requests as necessary to show or hide detail, and request to borrow one or more of the lines within that request.

© 2025 by Company Name Ltd.

Lender Posted Availability Sub-Tab

This sub-tab contains unsolicited availability posted by lenders (Push Lists).

Posted Availability Grid

In the *Posted Availability* grid, for each availability list, there are the following available columns:

Column	Description
Counterparty	Name of the associated counterparty.
Counterparty ID	LEI of the associated counterparty.
Creation Date/Time	Date and time the list was created.
Last Update Date/Time	Date and time the list was last updated.
Sender List Group	A group identifier, supplied by the Lender, that is typically used to indicate that the availability should be grouped in a different list on the Borrower side.

To view details of the availability contained within an availability list, select it to populate the Availability Details grid below.

Availability Details Grid

You can use the Availability Details grid to borrow directly from Lender availability. For the availability lists selected in the *Enquiries* grid above, there are the following available columns showing associated availability list entries:

Column	Description
Action	For each list entry in a received availability message from a Lender, you can do one of the following: • Click ✔ to borrow all the availability on the Lender's terms. • Type a new amount in the *Quantity* field (this must be lower than the *Offered Qty*). • Counter the offer. You can *EITHER*: ➢ Click ↩ and type a *Rate* or *Spread*. *OR* ➢ Simply type a new *Rate* or *Spread*. In both cases, the *Status* field changes to *Counter Pending* and the row is highlighted

© 2025 by Company Name Ltd.

Column	Description
	blue. You can click the eraser to reverse any changes. You will be prompted to complete other fields as necessary. When the response is ready to send, the *Send* button will be enabled. Click *Send* to send your response(s) to the Lender. When you receive a response from the Lender, the associated rows will be transferred to the *Borrow Requests Tab* (see page 33), Then, one of the following will happen: • If the Lender has accepted your counter-offer in full, then you can proceed to the *Ready to Book Tab* to generate a file of trade details for upload into your books and records system (see page 39). • If the Lender has responded to your counter-offer with a counter-offer of their own, then the rows will have a Status of *Lender Countered*. You can then either accept or reject their counter-offer, or even make another counter-offer of your own using as above. You can negotiate counter-offers in this way as many times as you wish. If you finally accept the Lender's offer, then click *Send* to send the accept message. The Lender can now proceed to book.
All-In Rate	All-In dividend rate requested by the Borrower or provided by the Lender.
Allow Counter Offer	Indicates whether or not the Borrower will accept counter offers.
Billing Ccy	Billing Currency specified by the Lender.
Cash Start Date	Cashflow start date.
Central Counterparty	Code representing the central counterparty. A Lender can specify that the availability will be borrowed through a central counterparty. For example, 'OCC' indicates any subsequent trades would be done under the OCC Stock Loan/Hedge Program.
Coll. Ccy	Collateral currency specified by the Lender, or requested by the Borrower, if not specified, when the collateral type is *Cash*.

© 2025 by Company Name Ltd.

Column	Description
Coll. Group	Collateral group specified by the Lender, or requested by the Borrower, if not specified, when the collateral type is *Non-Cash.* This should be a code recognised by both parties.
Coll. Method	Collateral method specified by the Lender, or requested by the Borrower, if not specified. Can be *Pledge* or *Title-Transfer*.
Coll. Type	Collateral type specified by the Lender, or requested by the Borrower, if not specified. Can be *Cash*, *Non-Cash* or *Cash Pool*.
Counterparty	Name of the associated counterparty.
Counterparty ID	LEI of the associated counterparty.
Cpty Settlement Account	DTC Account of the Lender that sent your their inventory list.
CUSIP	CUSIP security identifier (Committee on Uniform Securities Identification Procedures) for the available security.
Div Req	Dividend Requirement specified by the Lender, or requested by the Borrower, if not specified.
End Date	End date specified by the Lender, or requested by the Borrower, if not specified.
Expiry Date/Time	Date and time at which the availability line supplied by the Lender will expire and no longer be available.
ISIN	ISIN security identifier (International Securities Identification Number) for the available security.
Last Update Date/Time	Time and date the availability post was last updated.
Lender	If the Lender operates on a disclosed basis, this is the underlying fund/beneficial owner supplying the availability.
Lender Availability ID	ID supplied by the Lender to identify an availability line. If the Borrower requests to borrow from that availability line, this ID will be returned to the Lender.
Lender Availability Type	Indicates the type of availability posted by the Lender. Can be *TARGETED* or *GENERAL.*
List ID	Unique Product Name ID representing the Availability List to which this List entry is associated.

© 2025 by Company Name Ltd.

Column	Description
Max. Shapes	Maximum number of shapes/lots allowed to fulfil a Borrower request.
Message Date/Time	Date/time stamp for the message.
Offered Qty	Quantity of securities offered by the Lender.
Offered Rate	Rate offered by the Lender. Can be a rebate or fee, depending on the *Coll. Type*, and is quoted as a percentage.
Offered Ref. Index	Reference Index offered by the Lender.
Offered Settlement Type	Settlement type offered by the Lender.
Offered Spread	Spread offered by the Lender.
Ordinal	Represents the position in the list for availability items supplied by the Lender.
Our LEI	LEI that you are using for this trade.
Our Settlement Account	Your DTC account as specified by the Lender when publishing their inventory.
Price Without Margin	Security price quoted by the Lender.
Price Ccy	Currency in which *Price* is expressed.
Price Unit	Value by which the price should be divided, to calculate the value of a trade (for example, 100 for bonds, 1 for equities).
Quantity	Borrower enters the quantity they would like to borrow here if they would like to send a firm borrow request directly from the availability line.
QUICK	QUICK identifier for the available security.
Rate	Borrower enters the rate at which they would like to borrow the security, if they send a firm borrow request directly from the availability line. Can be a rebate or fee, depending on the *Coll. Type*, and is quoted as a percentage.
Ref. Index	Reference index used for quoting rates vs cash collateral. For availability posts, it is the reference index used to quote the Lender's offered rate. For availability requests, it is the reference index used to quote the Borrower's requested rate.
Sec. Ctry	Country of the available/requested security.
SEDOL	SEDOL security identifier (UK Stock Exchange Daily Official List) for the available/requested security.

© 2025 by Company Name Ltd.

Column	Description
Sender List Group	A group identifier, supplied by the Lender, that is typically used to indicate that the availability should be grouped in a different list on the Borrower side.
Settlement Location	Settlement location for the availability. Should be a code recognised by both parties.
Settlement Type	Settlement type specified by Lender on availability posts. Can be *DVP* or *FOP*.
Smart Bucket	Smart Bucket unique identifier. Smart Buckets allow Lenders to group funds based on RWA ratings, and so on. Lenders can specify that the availability will be allocated from funds within one of these Smart Buckets.
Spread	When the Borrower sends a firm borrow request directly from the availability line, and the requested rate is quoted against a reference index, they can enter the spread here. Quoted as a %.
Start Date	Expected Settlement/Start Date specified on the availability from the Lender or the requested Settlement/Start Date from the Borrower.
Status	Current request status, e.g., the field is populated with NEW when you first create a request.
TICKER	Ticker security identifier for the available security.
Trade Date	Trade Date.
Trade Type	Type of trade, e.g., stock borrow loan or repurchase agreement (repo).
Transport Status	Transport status of the request (NEW, SEND, SENT, FAILED, INVALID).
Value	Total value of the securities offered/accepted by the Lender.

Availability posts from Lenders can be quite large but it is easy to find securities within the list by using the filters (see *Filtering Items* on page 10). It is also possible to paste a list of security identifiers into a filter. For an individual availability list entry, you can:

- Copy to the Workbook:
  - ◊ Right-click on any availability line and choose *Copy* to *Borrow Workbook*. This will add a line for that security in the Borrow Workbook Tab.
  - ◊ When you have copied all the securities you want to borrow, go to the *Borrow Workbook Tab* (see page 16), update any details such as *Quantity* and click *Send* to create and send a Firm Borrow Request list to the Lender.
- Borrow directly from the availability:
  - ◊ Click the arrow in the *Action* column to accept the Offered Rate and Offered Qty, OR,

© 2025 by Company Name Ltd.

◊ Enter your preferred *Quantity*. You can borrow as many times as you like and each borrow will create a separate entry in the Borrow Requests Tab.

- Counter the offer:

  ◊ Click and type a Rate or Spread, OR,

  ◊ Simply type a new Rate or Spread.

  In both cases, the *Status* field changes to *Counter Pending* and the row is highlighted blue.

  You can click the eraser to reverse any changes.

  Where the row is highlighted red, this indicates that further details are required. Hover the mouse over the row to see what further fields are required to complete the response correctly. This will also be indicated by the text 'INVALID' in the *Transport Status* column.

  Now you can click *Send* to create and send a Firm Borrow Request list back to the Lender.

  If you would like to remove all of your edits to all availability list entries content and start again, click *Clear All*.

Availability Search Sub-Tab

This sub-tab allows you to search for availability by security identifier across both the *Lender Posted Availability* and *Borrow Enquiries* Sub-Tabs described above.

Search Parameters Grid

In the *Search Parameters* grid, there are the following available columns by which you can search for availability in the other tabs. You can either type in details manually, or paste from another application:

Column	Description
Ticker	Ticker security identifier to match.
CUSIP	CUSIP security identifier (Committee on Uniform Securities Identification Procedures) to match.
ISIN	ISIN security identifier (International Securities Identification Number to match.
SEDOL	SEDOL security identifier (UK Stock Exchange Daily Official List) to match.
QUICK	QUICK security identifier to match.
Sec. Ctry	Security country to match.

Once you have finished populating the grid, click *Find Availability* to initiate a search or *Clear Security IDs* to start again. The *Availability Details* grid below displays list entries matching the security identifiers you provided.

© 2025 by Company Name Ltd.

Availability Details Grid

The *Availability Details* grid displays list entries matching the security identifiers you provided in the *Search Parameters* grid above, displaying the corresponding columns and actions from the *Lender Posted Availability* and *Borrow Enquiries* Sub-Tabs as appropriate (see earlier).

Example of Negotiation Using Counter-Offers

Product Name supports negotiation of availability using counter-offers. Typically, this is the workflow that will occur:

1. The Borrower sends a firm Borrow Request to the Lender using the *Borrow Workbook Tab* in the Borrower Portal, and the post moves to the *Borrow Requests Tab*.
2. The Lender receives the firm Borrow Request, reviews it, and then either accepts the whole requested quantity, rejects the request, or counters the offer with a new Rate or Spread. The Lender then sends a response.
3. The Borrower receives the Lender's response in the *Borrow Requests Tab* of the Borrower Portal, reviews it, and then either accepts the offer, rejects the offer, or counters the offer with a new Rate or Spread.
4. When the Borrower accepts an offer, and the Lender provides final acceptance, the request is then passed to the *Ready to Book Tab*, ready to be downloaded to a file).

© 2025 by Company Name Ltd.

Borrow Requests Tab

You use the *Borrow Requests Tab* to view the current status of your firm borrow requests. This tab contains three grids, labelled *Lists*, *Firm Request List*, and *Trades* (optional) as shown in the example below:



Lists Grid

In the *Lists* grid, for each list, there are the following available columns:

Column	Description
Availability Type	Indicates the type of availability. Can be *TARGETED* or *GENERAL*.
Counterparty	Name of the associated counterparty.
Counterparty ID	LEI of the associated counterparty.
Creation Date/Time	Date and time the list was created.
Last Update Date/Time	Date and time the list was last updated.
List ID	Unique identifier for the Borrower request list.
List Name	Unique name for the Borrower request list.
Sender List Group	A group identifier, supplied by the Lender, that is typically used to indicate that the availability should be grouped in a different list on the Borrower side.
User	User who created the Borrower request list.

To view details of list entries contained within the list, select it in the *Lists* grid to populate the *Firm Request List* grid below.

© 2025 by Company Name Ltd.

Firm Request List Grid

In the *Firm Request List* grid, for the list selected above, there are the following available columns (see *Configuring Columns* on page 12 for more on adding and removing columns):

Column	Description
Action	When you receive a response to a firm borrow request from the Lender, one of the following will happen: • If the Lender has accepted your request / counter-offer in full, then you can proceed to the *Ready to Book* tab to generate a file of trade details for upload into your books and records system (see page 39). • If the Lender has responded to your counter-offer with a counter-offer of their own, then the rows will have a *Status* of *Lender Countered*. You can then either accept ✔ or reject ✖ their counter-offer, or even make another counter-offer of your own using ↩ as above. You can negotiate counter-offers in this way as many times as you wish. • If the Lender has accepted your firm borrow request, but has made one or more changes in their response, then the Portal will highlight the associated row in yellow, and display a list of the differences in the Information Bar at the bottom of the grid. Now, you can do one of the following: ➢ Click 👍 to indicate that the changes are acceptable. A Borrow Acknowledge message is sent, and the status changed to ACCEPTED. ➢ Click 👎 to indicate that the changes are not acceptable. A Borrow Cancel message is sent, and the status changed to BORROWER CANCELLED. Note that if the Lender simply populated a field that was empty in your original request, then these icons will not be available. If you finally accept the Lender's offer, then click *Send* to send the accept message. The Lender will

© 2025 by Company Name Ltd.

Column	Description
	provide final acceptance and the trades can then be booked.
All-In Rate	All-In dividend rate requested by the Borrower or provided by the Lender.
Allow Counter Offer	Indicates whether or not the Borrower will accept counter offers.
Billing Ccy	Currency in which the *Billing Price* is expressed. Requested by the Borrower or provided by the Lender.
Billing Price	Billing price with margin provided by the Lender, expressed in the *Billing Ccy*.
Billing Price without Margin	Billing price without margin provided by the Lender, expressed in the *Billing Ccy*.
Callable	Indicates whether or not the Borrower was willing to be recalled, or can be provided by the Lender if not set. Can be left blank (i.e., unspecified).
Cash Start Date	Cashflow start date.
Central Counterparty	Code representing the central counterparty. A Borrower can request for the trade to be done through the specified central counterparty. For example, 'OCC' indicates any subsequent trades would be done under the OCC Stock Loan/Hedge Program.
Coll. Ccy	If the collateral type is *Cash*, the requested collateral currency can be specified. If not requested, can be set by the Lender.
Coll. Group	If the collateral type is *Non-Cash*, a collateral group can also be specified. This should be a code recognised by both parties. If not requested, can be set by the Lender.
Coll. Method	Collateral method requested by the Borrower or specified by the Lender. Can be *Pledge* or *Title-Transfer*.
Coll. Type	Collateral Type requested by the Borrower. Can be *Cash*, *Non-Cash* or *Cash Pool*.
Counterparty	Name of the associated counterparty.
Counterparty ID	LEI of the associated counterparty.
Cpty Settlement Account	The Counterparty's DTC Account where you want the fill to come from.
Div Req	Dividend Requirement requested by the Borrower.

© 2025 by Company Name Ltd.

Column	Description
Div Req Type	Determines what is meant by the *Div Req* value. Can be: *Maximum*: Will accept any dividend requirement up to the *Div Req* value. *Absolute*: Will only accept a dividend requirement equal to the *Div Req* value.
End Date	Requested end date.
Expiry Date/Time	An indication to the Lender of how long the borrow request will holds before it expires.
ID	Trade ID supplied by the Lender (to be deprecated).
Increment	Borrower will only accept a quantity in increments of this value, e.g., 1,000.
ISIN	ISIN security identifier (International Securities Identification Number) for the requested security.
Last Update Date/Time	Date and time the list was last updated.
Lender	Borrower can specify which underlying fund/beneficial owner they wish to borrow from. If not supplied, and the Lender lends on a disclosed basis, this will be the fund/beneficial owner from which the loan has been allocated.
Lender Availability Type	If the Borrower has requested to borrow from a line of availability the Lender previously posted, this is the Type of that availability. Can be: *TARGETED*: An unsolicited availability message from a Lender (Push List). REQUESTED: A response to an availability request from the Borrower, sent earlier. *GENERAL*: A general availability type.
Lender Override	If the Borrower specifies a Fund/Beneficial Owner (*Lender* field above), this field indicates whether or not the Lender is allowed to override that preference.
List ID	Unique Product Name ID representing the List to which this List entry is associated.
Margin	Required margin for the requested security.
Max. Shapes	Maximum number of shapes/lots the Borrower will accept to fulfil the request.
Message Date/Time	Date/time stamp for the message.
Min. Quantity	If the Borrower has indicated that partial fills are allowed, this is the minimum quantity that will be accepted.

© 2025 by Company Name Ltd.

Column	Description
Offered Qty	Quantity of securities offered by the Lender.
Offered Rate	Rate offered by the Lender. Can be a rebate or fee, depending on the *Coll. Type*, and is quoted as a percentage.
Offered Ref Index	Reference Index offered by the Lender.
Offered Spread	Spread offered by the Lender.
Ordinal	Represents the position in the list for the requests sent by the Borrower.
Original Request ID	Identifier from the original Borrower request.
Our LEI	LEI that you are using for this trade.
Our Settlement Account	Your DTC account as you specified (which is optional).
Price	Trade price with margin quoted by the Lender.
Price without Margin	Trade price without margin quoted by the Lender.
Price Ccy	Currency in which *Price* is expressed.
Price Unit	Value by which the price should be divided, to calculate the value of a trade (for example, 100 for bonds, 1 for equities).
Quantity	Quantity accepted by the Lender.
QUICK	QUICK security identifier.
Rate	Rate accepted by the Lender. Can be a rebate or fee, depending on the *Coll. Type*, and is quoted as a percentage.
Reason	Shows the reason why a borrow request has been rejected, e.g., “No availability”.
Ref. Index	Reference Index used to quote the Lender’s accepted Rate when the *Coll. Type* is *Cash* and the Rate is quoted as an Index + Spread.
Requested Qty	Quantity of securities requested.
Requested Rate	Rate requested by the Borrower. Can be a rebate or fee, depending on the *Coll. Type*, and is quoted as a percentage.
Requested Ref. Index	If the Borrower requests a rate on the borrow request as a reference index + spread, this is the reference index.
Requested Spread	Spread requested by the Borrower, for requested rates quoted as Index + Spread.
Sec. Ctry	Country of the requested security.
SEDOL	SEDOL security identifier (UK Stock Exchange Daily Official List) for the requested security.

© 2025 by Company Name Ltd.

Column	Description
Sender List Group	A group identifier, supplied by the Lender, that is typically used to indicate that availability should be grouped in a different list on Borrower side.
Settlement Location	Settlement Location requested by the Borrower, or specified by the Lender.
Settlement Type	Requested Settlement Type. Can be DVP or FOP. Firm requests must have a valid Settlement Type.
Smart Bucket	Smart Bucket unique identifier. Smart Buckets allow Lenders to group funds based on RWA ratings, and so on. Then, Borrowers can request to borrow from one of these Smart Buckets. If the Lender accepts, the trade will only be allocated from funds in that Smart Bucket.
Spread	If the *Coll. Type* is *Cash,* the Lender's accepted rate may be quoted as a Reference index + Spread. This is the Spread and should be quoted as a percentage.
Start Date	Settlement/Start Date requested by the Borrower, or supplied by the Lender.
Status	Current status of a request
TICKER	Ticker security identifier for requested security.
Trade Date	Trade Date requested by the Borrower, or supplied by the Lender.
Trade ID	Unique trade identifier, supplied by the Lender.
Trade Type	Type of trade, e.g., stock borrow loan or repurchase agreement (repo).
Transport Status	Transport status of the request (NEW, SEND, SENT, RECEIVED, INVALID).
UTI	Unique Transaction Identifier, supplied by Lender.
Value	Total value of the requested securities, including margin.
Value without Margin	Total value of the requested securities, excluding margin.

Once you have completed reviewing list entries in the grid, if required, you can select the *Show Lender Trades Grid* checkbox to display the read-only *Trades Grid* (see below).

Trades Grid

In the *Firm Request List Grid* (see above), select the *Show Lender Trades Grid* checkbox to display the read-only *Trades Grid*. Sometimes the lender will need to book multiple trades to fill one firm request. The availability may be held in multiple locations, or there may be size limitations. In the *Trades Grid*, for an entry selected in the *Firm Requests Entries Grid* above, the user can view details of all the trades booked by the Lender.

© 2025 by Company Name Ltd.

Ready to Book Tab

The *Ready to Book* tab shows firm borrow requests (as individual rows for all lend accept details) that have been accepted by the Lender, and are now ready to book, as in the example below:



With the exception of the *Action* field, this tab contains the same available columns as the *List Entries* grid in the *Borrow Requests Tab* (see page 33). From here, you can generate a file containing Ready to Book trades:

- To generate only specific trades, then select the associated checkboxes for each row and click the *Download Selected Trades* button.
- To generate all trades, click the *Download All Trades* button.

The file containing the trade details is then saved into your default downloads folder, and from there can be sent to and processed by your books and records system.

All entries that have been downloaded will be removed from the tab, so they are not downloaded twice. However, if it is necessary to download one or more items again, you can find the entry in the *Borrow Requests* tab, right-click, and select *Re-flag for Download*. The selected entries will reappear on the *Ready to Book* tab where they can be downloaded again.

Configuring the Download File Format

It is possible to define the format of the download file obtained from the *Ready to Book Tab* at the LEI level. To do this, click *Configure Download* in the *Ready to Book Tab* to open the *Configure Ready to Book Entries Download* panel. This panel consists of two grids:

- *Available Columns:* This is a list of all the columns in the *Ready to Book* tab that can be included in the download file.
- *Download Columns:* This is a list of all columns that have been selected for inclusion in the download file, including the *Name* of the included column, the *Title* that the column will be given in the download file, and the *Format* of the data within that column.

To select a column to appear in the download file, and its relative position in the file, simply drag and drop a column *Name* from the *Available Columns* grid to a position in the *Download Columns* grid. In the *Available Columns* grid, you can provide an alternative name for the column by clicking on *Title* in the appropriate row and typing a new column

© 2025 by Company Name Ltd.

title. This will replace the original column name as the header in the download file. Use the *Include Column Titles* checkbox to select whether or not to include a header row in the file.

You can also define the format of the data within the column by clicking on *Format* in the appropriate row as follows:

- For Text fields, a mapping dialog box is displayed that allows you to define mappings from Product Name values to values that are recognised in your own system. For example, Product Name might have 'N' for non-cash in the *Coll.Type* field, but it is known by the label 'NC' in your system. In this case, you would simply type 'N' in the *From* column and 'NC' in the *To* column. If no mapping has been defined for a value, then that value is passed to the download file “as is”.
- For Date fields, you can specify a date format to be used, for example, dd-mmm-yy.
- For Numeric fields, you can specify a number format to be used, for example, #,###.

Additionally, using the *Excel* and *Delimited Text* checkboxes, you can select the file format for your download file. If you select *Delimited Text*, you can further select the character used for the delimiter from the *Text Delimiter* dropdown.

You then click *Save* to update the new download file format. This will then be used for all future downloads.

© 2025 by Company Name Ltd.

End of Day Tab

You use the *End of Day Tab* to review and download a file of accepted trades for the current day, and generate an Audit Report of pre-trade conversations. The *End of Day Tab* contains two further sub-tabs, the *All Trades* Sub-Tab and the *Negotiations* Sub-Tab, as shown in the example below:



All Trades Sub-Tab

The *All Trades Sub-Tab* contains details of accepted trades for the current day. With the exception of the *Action* field, this sub-tab contains the same available columns as the *List Entries* grid in the *Borrow Requests Tab* (see page 33).

From here, you can generate a file containing all accepted trades by clicking the *Download Trades* button. The file containing the trade details is then saved into your default downloads folder, and from there can be sent to and processed by your books and records system.

Negotiations Sub-Tab

The *Negotiations Sub-Tab* contains details of pre-trade conversations for the current day. For each negotiation message, there are the following available columns:

Column	Description
All-In Rate	All-In dividend rate.
Allow Counter Offer	Indicates whether or not the Borrower will accept counter offers.
Allow Lender Override	Whether or not the Lender is allowed to override the Borrower's requested fund.
Availability ID	Unique availability post identifier.
Billing Ccy	Currency in which the *Billing Price* is expressed. Requested by the Borrower or provided by the Lender.
Billing Price	Billing price with margin provided by the Lender, expressed in the *Billing Ccy*.

© 2025 by Company Name Ltd.

Column	Description
Billing Price without Margin	Billing price without margin provided by the Lender, expressed in the *Billing Ccy*.
Borrower Settlement Account	Borrower-specified settlement account to be used.
Callable	Indicates whether or not any borrows from this availability would be callable.
Cash Start Date	Cashflow start date.
Central Counterparty	Code representing the central counterparty. A Borrower can request to borrow through the specified central counterparty. For example, 'OCC' indicates any subsequent trades would be done under the OCC Stock Loan/Hedge Program.
Coll. Ccy	If the requested collateral type is *Cash*, the requested collateral currency can be specified.
Coll. Group	If the requested collateral type is *Non-Cash*, a collateral group can also be specified. This should be a code recognised by both parties.
Coll. Method	Requested Collateral method to use when booking. Can be *Pledge* or *Title Transfer*.
Coll. Type	Requested Collateral Type. Can be *Cash*, *Non-Cash* or *Cash Pool*.
CUSIP	CUSIP security identifier (Committee on Uniform Securities Identification Procedures) for the requested security.
Destination	LEI to which the message was sent.
Div Req	Requested dividend requirement.
Div Req Type	Determines what is meant by the *Div Req* value. Can be: *Maximum*: Borrower will accept any dividend requirement up to the *Div Req* value. *Absolute*: Borrower will only accept a dividend requirement equal to the *Div Req* value.
End Date	Requested end date.
ID	Unique system identifier.
ISIN	ISIN security identifier (International Securities Identification Number) for the requested security.

© 2025 by Company Name Ltd.

Column	Description
Lender	Borrower can specify which underlying fund/beneficial owner they wish to borrow from.
Lender Settlement Account	Lender-specified settlement account to be used.
Margin	Required margin for the requested security.
Max. Shapes	Maximum number of shapes/lots the Borrower is willing to accept to fulfil the Borrower request.
Message Date/Time	Date/time stamp for the message.
Message Type	Negotiation message type, e.g., COUNTER.
Min. Quantity	Minimum quantity that the Borrower will accept, if they have indicated that partial fills are allowed.
Offered Qty	Quantity of securities offered by the Lender.
Offered Rate	Rate offered by the Lender. Can be a rebate or fee, depending on the collateral type, and is quoted as a percentage.
Offered Ref. Index	Reference Index offered by the Lender.
Offered Settlement Type	Settlement type offered by the Lender.
Offered Spread	Spread offered by the Lender.
Portal Trade ID	Unique portal identifier for the trade.
Price	Trade price with margin quoted by the Lender.
Price Unit	Value by which the price should be divided, to calculate the value of the trade (for example, 100 for bonds, 1 for equities).
Price without Margin	Trade price without margin quoted by the Lender.
Price Ccy	Currency in which *Price* is expressed.
QUICK	QUICK security identifier for the requested security.
Reject Reason	If the trade was rejected, the textual reason for this.
Requested Qty	Quantity of securities requested
Requested Rate	Rate requested by the Borrower on availability requests. Can be a rebate or fee, depending on the *Coll. Type*, and is quoted as a percentage.
Requested Ref. Index	If the requested collateral type is *Cash*, the requested rate may be quoted as a Reference index + Spread. This is the Reference Index and should be a code recognised by both parties.

© 2025 by Company Name Ltd.

Column	Description
Requested Spread	Spread requested by the Borrower on availability requests when the requested rate is quoted as a reference index + spread
Sec. Ctry	Country of the requested security.
SEDOL	SEDOL security identifier (UK Stock Exchange Daily Official List) for the requested security.
Sender	LEI from which the message was sent.
Settlement Location	Settlement location.
Settlement Type	Settlement Type. May be *DVP* or *FOP*. Firm requests must have a valid Settlement Type.
Smart Bucket	Smart Bucket unique identifier. Smart Buckets allow Lenders to group funds based on RWA ratings, and so on. Then, Borrowers can request to borrow from one of these Smart Buckets. If the Lender accepts, the trade will only be allocated from funds in that Smart Bucket.
Start Date	Requested Settlement/Start Date.
Sub Type	Requested trade sub type.
Ticker	Ticker security identifier for the requested security.
Trade Date	Requested Trade Date.
Trade ID	Trade ID supplied by the Lender.
Trade Type	Requested trade type, e.g., stock borrow loan or repurchase agreement (repo).
UTI	Unique Transaction Identifier, supplied by the Lender.
Value	Trade value, including margin.
Value without Margin	Trade value, excluding margin.

As there can be a large number of messages displayed, it is possible to select which messages to display according to the outcome of the last message received. From the *Outcomes* dropdown you can select from one or more of the following:

- Traded
- Rejected/Cancelled
- Incomplete

Now, from here, you can generate a file containing all negotiation messages by clicking the *Download All Negotiations* button. The file containing the message details is then saved into your default downloads folder.

© 2025 by Company Name Ltd.

Configuring the Download File Format

It is possible to define the format of the download file obtained from the *All Trades* and *Negotiations Sub-Tabs* at the LEI level. To do this, click *Configure Download* to open the *Configure All Trades / Negotiations Items Download* panel. This panel consists of two grids:

- *Available Columns:* This is a list of all the columns in the *All Trades / Negotiations Sub-Tab* that can be included in the download file.
- *Download Columns:* This is a list of all columns that have been selected for inclusion in the download file, including the *Name* of the included column, the *Title* that the column will be given in the download file, and the *Format* of the data within that column.

To select a column to appear in the download file, and its relative position in the file, simply drag and drop a column *Name* from the *Available Columns* grid to a position in the *Download Columns* grid. In the *Available Columns* grid, you can provide an alternative name for the column by clicking on *Title* in the appropriate row and typing a new column title. This will replace the original column name as the header in the download file. Use the *Include Column Titles* checkbox to select whether or not to include a header row in the file.

You can also define the format of the data within the column by clicking on *Format* in the appropriate row as follows:

- For Text fields, a mapping dialog box is displayed that allows you to define mappings from Product Name values to values that are recognised in your own system. For example, Product Name might have 'N' for non-cash in the *Coll.Type* field, but it is known by the label 'NC' in your system. In this case, you would simply type 'N' in the *From* column and 'NC' in the *To* column. If no mapping has been defined for a value, then that value is passed to the download file “as is”.
- For Date fields, you can specify a date format to be used, for example, dd-mmm-yy.
- For Numeric fields, you can specify a number format to be used, for example, #,###.

Additionally, using the *Excel* and *Delimited Text* checkboxes, you can select the file format for your download file. If you select *Delimited Text*, you can further select the character used for the delimiter from the *Text Delimiter* dropdown.

You then click *Save* to update the new download file format. This will then be used for all future downloads.

© 2025 by Company Name Ltd.

Send Us Your Comments

Product Name Borrower Portal User Guide
Ref: 30023/1.10/1.9/SD

Company Name welcomes your comments and suggestions on the quality and usefulness of this document. Your input is an important part of the information used for revision.

- Did you find any errors?
- Is the information clearly presented?
- Do you need more information? If so, where?
- Are the examples correct? Do you need more examples?
- What features did you like most?

If you find any errors or have any other suggestions for improvement, please indicate the document title and version number, and the part, section, and page number (if available). You can send comments to us by email to peter.kingston@tradingapps.com.

© 2025 by Company Name Ltd.

2, Example Street, London, UK
Tel: +44 (0)123 456 7890
Email: info@companyname.com