ПРИЛОЖЕНИЕ. Экспорт результатов вычисления в инженерный графопостроитель tecplot 360 для последующего анализа.

Передаваемая в tecplot 360 (https://www.tecplot.com/products/tecplot-360/) учебная область из четырёх треугольников представлена на нижеследующем рисунке 1.




Рисунок 1 – Переданная в tecplot 360 сетка из четырёх треугольников.

1. Описание данных для передачи графопостроителю tecplot 360.

```
1. int main()
2. {
3.
4.
       float* x = new float[6];
       float* y = new float[6];
5.
6.
       int nodi = 6;
7.
       int maglie = 4;
8.
       x[0] = -1.0f; y[0] = 0.0f;
9.
10.
       x[1] = 0.0f; y[1] = 0.0f;
11.
       x[2] = 1.0f; y[2] = 0.0f;
12.
       x[3] = -0.5f; y[3] = 0.8f;
13.
       x[4] = 0.5f; y[4] = 0.8f;
14.
       x[5] = 0.0f; y[5] = 1.6f;
15.
       int numvar = 2;
16.
17.
       int** n123 = new int* [3];
18.
19.
       for (int i = 0; i < 3; ++i) {
20.
            n123[i] = new int[maglie];
21.
       n123[0][0] = 1; \quad n123[1][0] = 2; \quad n123[2][0] = 4;
22.
23.
       n123[0][1] = 2;  n123[1][1] = 3;  n123[2][1] = 5;
24.
       n123[0][2] = 2; \quad n123[1][2] = 5; \quad n123[2][2] = 4;
25.
       n123[0][3] = 4; \quad n123[1][3] = 5; \quad n123[2][3] = 6;
26.
27.
       write_tecplot360_PLT0(nodi, x, y, maglie, numvar, n123);
28.
       // либо человеческий формат (текстовый).
29.
       write_tecplot360_DAT(nodi, x, y, maglie, numvar, n123);
30.
31.
       delete[] x;
32.
       delete[] y;
33.
```

```
34.    for (int i = 0; i < 3; ++i) {
35.         delete[] n123[i];
36.    }
37.    38.
39.    delete[] n123;
40.}</pre>
```

В следующем пункте рассмотрим понятный человеку вариант передачи данных в программу tecplot 360 в текстовом виде.

1. Человеческий (текстовый) формат записи данных для графопостроителя (.dat)

```
// создание файла для записи и передачи в программу tecplot 360 в текстовом виде.
void write_tecplot360_DAT(int nodi, float*& x, float*& y,
                              int maglie, int numvar, int**& n123) {
    FILE* fp;
    errno t err;
    if ((err = fopen_s(&fp, "example_text_export2tecplot.dat", "w")) != 0) {
        printf("Create File Error\n");
    else {
         // запись имён переменных
        fprintf(fp, "TITLE = \" Easy mesh\" \n");
fprintf(fp, "VARIABLES = \"x, m\", \"y, m\" \n");
fprintf(fp, "ZONE T=\"Rampant\", N=%d, E=%d,
               ET=TRIANGLE, F=FEBLOCK \n\n", nodi, maglie);
         for (int i = 0; i < nodi; ++i) {</pre>
             fprintf(fp, "%e ", x[i]);
             if ((i != 0) && (i % 10 == 0)) fprintf(fp, "\n");
         fprintf(fp, "\n");
        for (int i = 0; i < nodi; ++i) {</pre>
             fprintf(fp, "%e ", y[i]);
             if ((i != 0) && (i % 10 == 0)) fprintf(fp, "\n");
         fprintf(fp, "\n");
         for (int i = 0; i < maglie; ++i) {</pre>
             fprintf(fp, "%d %d %d \n", n123[0][i], n123[1][i], n123[2][i]);
        fclose(fp);
    }
```

Текстовый файл example_text_export2tecplot.dat с расширением .dat для tecplot 360 имеет следующий вид:

```
TITLE = " Easy mesh"
```

```
VARIABLES = "x, m", "y, m"

ZONE T="Rampant", N=6, E=4, ET=TRIANGLE, F=FEBLOCK

-1.000000e+00 0.000000e+00 1.000000e+00 -5.000000e-01 5.000000e-01
0.000000e+00 0.000000e+00 0.000000e+00 8.000000e-01 8.000000e-01
1.600000e+00
1 2 4
2 3 5
2 5 4
4 5 6
```

Это учебный пример, но если текстовый файл для tecplot большого размера более 10млн неизвестных, то открытие такого файла занимает целый рабочий день. Поэтому используется машинный двоичный формат файла.

2. Машинный двоичный формат файла (binary .PLT).

```
void write_tecplot360_PLT0(int nodi, float* &x, float* &y, int maglie, int numvar, int** &n123)
{
      int buttaINT, FileType, ZoneType, StrandID, VarLoc, * nodeCELLcenter, jmax;
      float dt. BUTTA:
      double t, DBLEmin, DBLEmax;
      float ** CSprint;
      char header[10];
      char aster:
      const char NULCHAR = '\0';
      CSprint = new float* [std::max(maglie, nodi) + 1];
      for (int i = 0; i < std::max(maglie, nodi) + 1; ++i) {
        CSprint[i] = new float[numvar+1];
      }
      nodeCELLcenter = new int[numvar+1];
      //allocate(CSprint(max(maglie, nodi), numvar), nodeCELLcenter(numvar))
       //write BINARY FILE FOR TECPLOT
```

```
FILE* fp;
   #ifdef MINGW_COMPILLER
      int err = 0;
      fp = fopen64("AliceFlow_v0_66.PLT", "wb");
   #else
      errno_t err;
      err = fopen_s(&fp, "AliceFlow_v0_66.PLT", "wb");
   #endif
      if ((err) != 0) {
        printf("Create binary File AliceFlow_v0_66.PLT Error in function
export_thermal_conductivity in tecplot_binary_writer.cpp\n");
        system("pause");
      }
      //int din = 0;
      //All character strings are null terminated(i.e.terminated by a zero value)
      //header = '#!TDV112'
      //header
      header[0] = '\#'; header[1] = '!'; header[2] = 'T';
      header[3] = 'D'; header[4] = 'V'; header[5] = '1';
      header[6] = '1'; header[7] = '1'; header[8] = '\0';
      header[9] = \n';
      for (int i = 0; i < 8; ++i) {
        aster = header[i];
        fwrite(&aster, sizeof(char), 1, fp);
      }
      buttaINT = 1;
```

```
fwrite(&buttaINT, sizeof(int), 1, fp);
      //iii.Title and variable names.
      FileType = 0; //Title and variable names. 0 = FULL, 1 = GRID, 2 = SOLUTION
      fwrite(&FileType, sizeof(int), 1, fp);
      aster = 'T';
      buttaINT = (int)aster;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      buttaINT = (int)NULCHAR;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      fwrite(&numvar, sizeof(int), 1, fp);
      //DOI = 1, NUMVAR
      //Variable names(INT32 * N).N = L[1] + L[2] + ....L[NumVar]where:L[i] = length of the ith
variable name + 1 (for the terminating 0 value).
      aster = 'x';
      buttaINT = (int)aster;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      buttaINT = (int)NULCHAR;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      aster = 'y';
      buttaINT = (int)aster;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      buttaINT = (int)NULCHAR;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      BUTTA = 299.0; //Zone marker.
      fwrite(&BUTTA, sizeof(float), 1, fp);
      //Zone name(INT32 * N).N = (length of zone name) + 1(for the terminating 0 value).
      aster = 'Z';
```

```
buttaINT = (int)aster;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      aster = 'O';
      buttaINT = (int)aster;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      aster = 'N';
      buttaINT = (int)aster;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      aster = 'E';
      buttaINT = (int)aster;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      aster = '1';
      buttaINT = (int)aster;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      buttaINT = (int)NULCHAR;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      buttaINT = -1;
      fwrite(&buttaINT, sizeof(int), 1, fp); //0 //ParentZone: 0 = indicates that this zone is not
associated with a parent zone. > 0 = A value greater than zero is considered this zone's parent.
      StrandID = 0;
      fwrite(&StrandID, sizeof(int), 1, fp); //IN REALTA IL MANUALE DICE StrandID = 0 = >
static zone StrandID: -2 = pending strand ID for assignment by Tecplot; -1 = static strand ID; 0 <=
N < 32700 valid strand ID
      t = 0.0;
      dt = 0.0:
      t = t + static_cast<double>(dt);
      fwrite(&t, sizeof(double), 1, fp);
      buttaINT = -1;
```

```
ZoneType = 2;
      fwrite(&ZoneType, sizeof(int), 1, fp); //ZoneType 0 = ORDERED, 1 = FELINESEG, 2 =
FETRIANGLE, 3 = FEQUADRILATERAL, 4 = FETETRAHEDRON, 5 = FEBRICK, 6 =
FEPOLYGON, 7 = FEPOLYHEDRON
        // DataPacking 0 = Block, 1 = Point
      buttaINT = 1;
      fwrite(&buttaINT, sizeof(int), 1, fp);
      VarLoc = 1;
      fwrite(&VarLoc, sizeof(int), 1, fp); //Specify Var Location. 0 = Don't specify, all data is
locatedat the nodes. 1 = Specify
      if (VarLoc == 1) {
        for (int i = 0; i < numvar; ++i) {
           nodeCELLcenter[i] = 0;
           buttaINT = nodeCELLcenter[i];
           fwrite(&buttaINT, sizeof(int), 1, fp); //0 = Node, 1 = Cell Centered(See note 5.)
        }
      }
      buttaINT = 0;
      fwrite(&buttaINT, sizeof(int), 1, fp); //Are raw local 1 - to - 1 face neighbors supplied? (0 =
FALSE 1 = TRUE).
      buttaINT = 0;
      fwrite(&buttaINT, sizeof(int), 1, fp); //Number of miscellaneous user - defined face neighbor
connections(value >= 0). This value is in addition to the face neighbors
      fwrite(&nodi, sizeof(int), 1, fp);
      fwrite(&maglie, sizeof(int), 1, fp);
```

fwrite(&buttaINT, sizeof(int), 1, fp);//Not used.

```
//ICellDim, JCellDim, KCellDim(for future use; set to zero)
buttaINT = 0;
fwrite(&buttaINT, sizeof(int), 1, fp);
buttaINT = 0;
fwrite(&buttaINT, sizeof(int), 1, fp);
buttaINT = 0;
fwrite(&buttaINT, sizeof(int), 1, fp);
//1 = Auxiliary name / value pair to follow; 0 = No more Auxiliary name / value pairs.
buttaINT = 0;
fwrite(&buttaINT, sizeof(int), 1, fp);
//v.Geometries
//write(36, rec = iwrite) 399.0e0 !Geometry marker.Value = 399.0
//iwrite = iwrite + 1
//vi.Text
//write(36, rec = iwrite) 499.0e0 !Text marker.Value = 499.0
//iwrite = iwrite + 1
//vii.CustomLabel
//write(36, rec = iwrite) 599.0e0 !CustomLabel Marker; F = 599
//iwrite = iwrite + 1
//viii.UserRec
//write(36, rec = iwrite) 699.0e0 !UserRec Marker; F = 699
//iwrite = iwrite + 1
//ix.Dataset Auxiliary data.
//write(36, rec = iwrite) 799.0e0 !DataSetAux Marker; F = 799.0
//iwrite = iwrite + 1
//x.Variable Auxiliary data.
//write(36, rec = iwrite) 999.0e0 !VarAux Marker; F = 899.0
```

```
//iwrite = iwrite + 1
      BUTTA = 357.0e0; //EOHMARKER, value = 357.0.
      fwrite(&BUTTA, sizeof(float), 1, fp);
      //II.DATA SECTION
      BUTTA = 299.0e0;
      fwrite(&BUTTA, sizeof(float), 1, fp); //Zone marker Value = 299.0
             //i.For both ordered and fe zones:
      for (int i_1 = 1; i_1 <= numvar; ++i_1) {
         buttaINT = 1; //Variable data format(INT32 * N), N = Total number of vars 1 = Float, 2 =
   Double, 3 = LongInt, 4 = ShortInt, 5 = Byte, 6 = Bit
        fwrite(&buttaINT, sizeof(int), 1, fp);
      }
      buttaINT = 0;
      fwrite(&buttaINT, sizeof(int), 1, fp); //Has passive variables : 0 = \text{no}, 1 = \text{yes}.
      buttaINT = 0;
      fwrite(&buttaINT, sizeof(int), 1, fp); //Has variable sharing 0 = \text{no}, 1 = \text{yes}.
      buttaINT = -1; //Zero based zone number to share connectivity list with(-1 = no
sharing).FEPOLYGON and FEPOLYHEDRON zones use this zone number to share face map data.
      fwrite(&buttaINT, sizeof(int), 1, fp);
      //Compressed list of min / max pairs for each non - shared and non - passive variables
      for (int i_1 = 1; i_1 \le nodi; ++i_1) {
        CSprint[i_1][1] = x[i_1-1];
        CSprint[i_1][2] = y[i_1-1];
      }
```

```
for (int i_1 = 1; i_1 <= numvar; ++i_1) {
  if (nodeCELLcenter[i_1 - 1] == 0) {
    jmax = nodi;
  }
  else if (nodeCELLcenter[i_1 - 1] == 1) {
    jmax = maglie;
  }
  DBLEmin = 1.0e36;
  // DBLEmin = DBLE(MINVAL(CSprint(1:jmax, i)))
  for (int i_2 = 1; i_2 <= jmax; ++i_2) {
    if (CSprint[i_2][i_1] < DBLEmin) {</pre>
      DBLEmin = CSprint[i_2][i_1];
    }
  }
  DBLEmax = -1.0e36;
  //DBLEmax = DBLE(MAXVAL(CSprint(1:jmax, i)))
  for (int i_2 = 1; i_2 <= jmax; ++i_2) {
    if (CSprint[i_2][i_1] > DBLEmax) {
      DBLEmax = CSprint[i_2][i_1];
    }
  }
  fwrite(&DBLEmin, sizeof(double), 1, fp);
  fwrite(&DBLEmax, sizeof(double), 1, fp);
  std::cout << DBLEmin << " " << DBLEmax << "\n";</pre>
}
  jmax = nodi;
```

```
for (int i_2 = 1; i_2 <= j_{max}; ++i_2) {
       BUTTA = CSprint[i_2][1];
       fwrite(&BUTTA, sizeof(float), 1, fp);
       BUTTA = CSprint[i_2][2];
       fwrite(&BUTTA, sizeof(float), 1, fp);
     }
  }
  //ii.specific to ordered zones
  //iii.specific to fe zones
  for (int i = 0; i < maglie; ++i) {
    for (int k = 0; k < 3; ++k)
     {
       buttaINT = n123[k][i]-1;
       fwrite(&buttaINT, sizeof(int), 1, fp);
     }
  }
  for (int i = 0; i < std::max(maglie, nodi) + 1; ++i) {
    delete[] CSprint[i];
  }
  delete[] CSprint;
  delete[] nodeCELLcenter;
  fclose(fp);
}
```

Приводимый программный код записи в бинарный файл с расширением .PLT тяжеловат для восприятия человеком. Модели записанные в бинарном виде для техплот (tecplot 360) и имеющие более 10млн узлов открываются теперь мгновенно в программе tecplot 360.

3. Быстрое открытие больших моделей в бинарном виде подтверждается в документации самого tecplot 360:

Tecplot Data File Types

- ASCII (.dat) Plain text
 - · Human readable and writeable data files
- Binary (.plt) Established Tecplot Binary format
 - · An industry standard exported from most CFD solvers
- Binary SZL (.szplt) New Tecplot Binary format
 - · Only loads regions of interest, using sub-zone load-on-demand




Рисунок 2 — Три вида файлов с которыми работает программа визуализатор tecplot 360

Prefer Binary over ASCII

Stanford Solar Car

- · 7.1 million elements
- · Single Slice

отает програм	ма визуал	іизатор і	ecpioi 360.
ДФ Перевести видео			
ы выйти из полноэкранного режима			-
			9

File Type	ASCII (.dat)	Binary (.plt)	Binary (.szplt)
File size	795 Mb	394 Mb	264 Mb
Load time	312 sec	2 sec	2 sec
RAM used	659 Mb	453 Mb	160 Mb

Рисунок 3 — Характеристики быстродействия и памяти для трёх форматов файлов, используемых программой tecplot 360.

Отличие во времени открытия файла 156 раз для текстового и двоичного форматов записи.

4. Преобразование из одного формата файла в другой формат средствами программы tecplot 360.

Можно вызвать утилиту tec360.exe поставляемую с программой техплот и выполнить конвертацию файла из одного формата файла в другой формат файла.

Только текстовый файл с расширением .dat при преобразовании будет считываться также долго, как и при открытии. А преобразование бинарного PLT в более сжатый и еще более быстрый szplt заслуживает внимания (и использования).