


Mounting an NFS File System (Windows)


1. On Windows, Install the NFS client.
 - a. Open the **Control Panel** and click **Programs**.
 - b. Click **Turn Windows features on or off**.





- c. Display **Services for NFS** list, select **Administrative Tools** and **Client for NFS**, and click OK.



2. Modify the NFS transfer protocol.
 - a. Go to **Control Panel > System and Security > Administrative Tools > Services for Network File System (NFS)**.




- b. Right-click **Client for NFS**, choose **Properties**, change the transport protocol to **TCP**, and select **Use hard mounts**, as shown in the figure.



3. Run the following command in the Command Prompt of Windows (X is the drive letter of the free disk).

`mount -o nolock -o casesensitive=yes IP address: /! X:`

You can find the IP address on the SFS console of Huawei Cloud.




< sfs-turbo-44d5

Basic Info Tags Authorizations

Name	sfs-turbo-44d5	Shared Path	15beea94-03c6-4c14-80d4-ce3df8b58803.sfsturbo.internal/
ID	15beea94-03c6-4c14-80d4-ce3df8b58803	Alternative Shared Path	192.168.0.14 192.168.0.43
Used Capacity (GB)	0.00	Status	Available
Total Capacity (GB)	500.00	File System Type	Standard
Created	2024/05/02 09:33:20 GMT-05:00	Region	LA-Santiago
AZ	AZ1	VPC	vpc-main1
Subnet	subnet-main1-1 (192.168.0.0/26)	Security Group	sg-filesystem
Enterprise Project	default	Encryption	No

4. After the file system is mounted successfully, you can view the mounted file system on the **This PC** window, as shown in the figure.




Mounting a File System Automatically

File system mounting information may be lost after an ECS is restarted. You can configure automatic mounting for the ECS to avoid the mounting information loss.

1. Before mounting the file system, create a script named **auto_mount.bat**, save the script to a local host, and **record the save path**. The script contains the following content:


```
mount -o nolock -o casesensitive=yes IP address:/! X:
```



NOTE: This .bat script cannot be stored in the same path of step 2, that stores the .vbs file. For example, the .bat script could be stored in C:\test\.

2. Create a .txt file whose name is **XXX.vbs** and save the file to the directory **C:\Users\User\AppData\Roaming\Microsoft\Windows\Start Menu\Programs\Startup**. The file contains the following content:

```
set ws=WScript.CreateObject("WScript.Shell")
ws.Run "Local path and script name of the auto_mount.bat script /start", 0
```



3. After the task is created, you can restart and check whether the configuration is successful. After the configuration is successful, the file system automatically appears in **This PC**.