Operating Systems [10. Virtual Memory]

Chung-Wei Lin

cwlin@csie.ntu.edu.tw

CSIE Department

National Taiwan University

Objectives

- Define virtual memory and describe its benefits
- Illustrate how pages are loaded into memory using demand paging
- ☐ Apply the FIFO, optimal, and LRU page-replacement algorithms
- Describe the working set of a process, and explain how it is related to program locality
- Describe how Linux, Windows 10, and Solaris manage virtual memory

Outline

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- Thrashing
- ☐ Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Background (1/2)


- ☐ Basic requirement
 - > The instructions being executed must be in physical memory
- One approach
 - > Place the entire logical address space in physical memory
 - Dynamic linking can help to ease this restriction, but it generally requires special precautions and extra work by the programmer
 - > Limit the size of a program to the size of physical memory
- In fact
 - In many cases, the entire program is not needed
 - Error handling code, large data structures, rarely-used options and features ©
 - > Even if the entire program is needed, it may not all be needed at the same time

Background (2/2)

- ☐ Benefits of executing a program only partially in memory
 - > A program is no longer constrained by the amount of physical memory
 - More programs can be run at the same time
 - Increase in CPU utilization and throughput
 - No decrease in response time or turnaround time
 - Less I/O is needed to load or swap portions of programs into memory
 - Each program would run faster


Virtual Memory

- Separation of logical memory as perceived by developers from physical memory
 - ➤ Allow an extremely large virtual memory to be provided for programmers when only a smaller physical memory is available
 - ➤ Make the task of programming much easier



Virtual Memory Space

- ☐ Logical (or virtual) view of how a process is stored in memory
 - A process begins at a certain logical address and exists in contiguous memory
 - ➤ The physical page frames assigned to the process may not be contiguous
 - > The MMU maps logical pages to physical page frames
- ☐ The blank space (or hole) between the heap and the stack is part of the virtual address space
 - ➤ It requires actual physical pages only if the heap or stack grows
 - Virtual address spaces with holes are known as sparse address spaces
 - Using a sparse address space is beneficial because the holes can be filled if the stack or heap grows or if we wish to dynamically link libraries



Shared Library Using Virtual Memory


☐ Virtual memory also allows files and memory to be shared by two or more processes through page sharing

Processes share system libraries through mapping the shared object into

a virtual address space

 The actual physical pages where the libraries (typically read-only) reside are shared

- Processes share memory
 - One process creates a region of memory and shares it with another process
 - Processes consider it part of their virtual address space, yet the actual physical pages are shared
- > Pages are shared with **fork()** system call
 - Speed up process creation



Outline

■ Background Demand Paging Basic Concepts, Free-Frame List, Performance of Demand Paging ■ Copy-on-Write ■ Page Replacement Allocation of Frames Thrashing ■ Memory Compression ■ Allocating Kernel Memory Other Considerations

Operating-System Examples

Demand Paging


- One approach
 - > Program starts with a list of available options that the user is to select
- ☐ Another approach: **demand paging**
 - > Pages are loaded only when they are demanded during execution
 - > Pages that are never accessed are never loaded into physical memory
 - > It is commonly used in virtual memory systems
 - ➤ Memory is used more efficiently


Outline


■ Background Demand Paging Basic Concepts, Free-Frame List, Performance of Demand Paging ■ Copy-on-Write ☐ Page Replacement Allocation of Frames Thrashing ■ Memory Compression ■ Allocating Kernel Memory Other Considerations Operating-System Examples


Basic Concepts (1/2)

- While a process is executing, some pages are in memory, and some pages are in secondary storage
 - > We need some form of hardware support to distinguish between them
 - > The valid-invalid bit scheme described before can be used












Basic Concepts (2/2)

- ☐ If the bit is **valid**, the associated page is legal and in memory
- ☐ If the bit is **invalid**, the page is either
 - ➤ Not valid, or
 - ➤ Valid but currently in secondary storage




Logical Memory






1


3




- ☐ Access to a page marked invalid causes a page fault
 - ➤ The paging hardware will notice that the invalid bit is set and cause a trap to the operating system
- Procedure for handling this page fault
 - ➤ 1. Check an internal (another) table (usually kept with the process control block) to determine whether the reference was valid or invalid




- ☐ Access to a page marked invalid causes a page fault
 - ➤ The paging hardware will notice that the invalid bit is set and cause a trap to the operating system
- ☐ Procedure for handling this page fault
 - > 2A. If the reference was invalid, terminate the process
 - > 2B. If the reference was valid but we have not yet brought in that page,




- ☐ Access to a page marked invalid causes a page fault
 - ➤ The paging hardware will notice that the invalid bit is set and cause a trap to the operating system
- Procedure for handling this page fault
 - > 3. Find a free frame (by taking one from the free-frame list, for example)
 - The free-frame list will be introduced later




- ☐ Access to a page marked invalid causes a page fault
 - ➤ The paging hardware will notice that the invalid bit is set and cause a trap to the operating system
- ☐ Procedure for handling this page fault
 - ➤ 4. Schedule a secondary storage operation to read the desired page into the newly allocated frame



- ☐ Access to a page marked invalid causes a page fault
 - ➤ The paging hardware will notice that the invalid bit is set and cause a trap to the operating system
- Procedure for handling this page fault
 - > 5. Modify the internal table kept with the process and the page table to indicate that the page is now in memory



- ☐ Access to a page marked invalid causes a page fault
 - ➤ The paging hardware will notice that the invalid bit is set and cause a trap to the operating system
- Procedure for handling this page fault
 - ➤ 6. Restart the instruction that was interrupted by the trap



Aspects of Demand Paging

☐ Pure demand paging

- Never bring a page into memory until it is required
- Start executing a process with no page in memory
- > Set the instruction pointer to the first instruction (fault immediately)

□ Locality of reference

- ➤ Theoretically, some programs access several new pages of memory with each instruction execution
 - Example: one page for the instruction and many for data
 - Unacceptable system performance
- Analysis of running processes shows that this behavior is exceedingly unlikely

☐ Hardware support (same as paging and swapping)


- Page table with a valid-invalid bit (or other protection bits)
- Secondary memory (swap device with <u>swap space</u>)

Instruction Restart (1/2)

- ☐ A page fault may occur at any memory reference
 - > Occur on the instruction fetch: fetch the instruction again
 - > Occur on the operand fetch: fetch the instruction again and then fetch the operand
- Example
 - > Fetch and decode the instruction (ADD)
 - > Fetch A
 - > Fetch B
 - > Add A and B
 - > Store the sum in C
 - If C is in a page not currently in memory, we will have to get the desired page, bring it in, correct the page table, and restart the instruction (all steps above)
- ☐ Performance is not a major concern
 - > There is not much repeated work (less than one complete instruction)

Instruction Restart (2/2)

- ☐ Major difficulty: one instruction modifies different locations
 - Example: an instruction moves some bytes from one location to another (possibly overlapping) location
 - If either block (source or destination) straddles a page boundary, a page fault may occur after the move is partially done
 - If the source and destination blocks overlap, the source block may have been modified, in which case we cannot simply restart the instruction
 - > Solutions
 - Microcode attempts to access both ends of both blocks and triggers page faults (if any) before anything is modified
 - Temporary registers hold the values of overwritten locations, and, if there is a page fault, all the old values are written back into memory before the trap




Outline

- BackgroundDemand Paging
 - > Basic Concepts, Free-Frame List, Performance of Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- Allocation of Frames
- ☐ Thrashing
- Memory Compression
- Allocating Kernel Memory
- Other Considerations
- ☐ Operating-System Examples

Free-Frame List

- ☐ When a page fault occurs, the operating system must bring the desired page from secondary storage into main memory
 - Most operating systems maintain a <u>free-frame list</u>
 - When a system starts up, all available memory is placed on the freeframe list



- Operating systems typically allocate free frames using <u>zero-fill-on-demand</u>
 - > Erase their previous contents
 - Consider the potential security implications of not clearing out the contents

Outline

Background Demand Paging > Basic Concepts, Free-Frame List, Performance of Demand Paging Copy-on-Write ☐ Page Replacement Allocation of Frames Thrashing ■ Memory Compression ■ Allocating Kernel Memory Other Considerations Operating-System Examples

Sequence of a Page Fault (1/2)

- 1. Trap to the operating system
- 2. Save the registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal, and determine the location of the page in secondary storage
- 5. Issue a read from the storage to a free frame
 - Wait in a queue until the read request is serviced
 - ➤ Wait for the device seek and/or latency time
 - Begin the transfer of the page to a free frame
- 6. While waiting, allocate the CPU core to some other process
- 7. Receive an interrupt from the storage I/O subsystem (I/O completed)

Sequence of a Page Fault (2/2)

- 8. Save the registers and process state for the other process
- 9. Determine that the interrupt was from the secondary storage device
- 10. Correct the page table and other tables to show that the desired page is now in memory
- 11. Wait for the CPU core to be allocated to this process again
- ☐ Not all of these steps are necessary in every case

Performance of Demand Paging (1/2)

- ☐ Three major task components of the page-fault service time
 - Service the page-fault interrupt
 - Can be reduced to several hundred instructions or 1--100 microseconds
 - > Read in the page
 - Probably close to 8 milliseconds with a typical hard disk
 - If a queue of processes is waiting for the device, we have to add queuing time
 - Restart the process
 - Can be reduced to several hundred instructions or 1--100 microseconds.

Performance of Demand Paging (2/2)

- ☐ Effective access time (EAT)
 - ➤ Memory-access time = 200 nanoseconds
 - Average page-fault service time = 8 milliseconds
 - Probably of a page fault = p
 - \triangleright EAT = $(1 p) \cdot 200 + p \cdot 8,000,000 = 200 + p \cdot 7,999,800 (nanoseconds)$
- ☐ If one access out of 1,000 causes a page fault
 - > EAT = 8.2 microseconds
 - Slow down by a factor of 40 because of demand paging
- ☐ If we want performance degradation to be less than 10%
 - > p < 0.0000025

Swap Space Handling (1/2)

- ☐ I/O to swap space is generally faster than that to the file system
 - > Swap space is allocated in much larger blocks
 - > File lookups and indirect allocation methods are not used (Chapter 11)
- ☐ For better paging throughput
 - > First option
 - Copy an entire file image into the swap space at process startup
 - Perform demand paging from the swap space
 - Second option
 - Demand-page from the file system initially
 - Write the pages to swap space as they are replaced

Swap Space Handling (2/2)


- ☐ Some systems attempt to limit the amount of swap space used through demand paging of binary executable files
 - ➤ When page replacement is called for
 - These frames can simply be overwritten (because they are never modified)
 - The pages can be read in from the file system again if needed
 - ➤ However, swap space must still be used for pages not associated with a file (known as **anonymous memory**)
 - These pages include the stack and heap for a process
- ☐ Mobile operating systems typically do not support swapping
 - Demand-page from the file system
 - Reclaim read-only pages (such as code) from applications if memory becomes constrained

Outline

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- ☐ Operating-System Examples

Copy-on-Write

- ☐ Allow the parent and child processes initially to share the same pages
 - > These shared pages are marked as copy-on-write pages
 - Only pages that can be modified need be marked as copy-on-write
 - ➤ If either process writes to a shared page, a copy of the shared page is created
 - When the copy-on-write technique is used, only the pages that are modified by either process are copied



33

Virtual Memory Fork


- □ vfork()
 - > The parent process is suspended
 - > The child process uses the address space of the parent
- □ vfork() does <u>not</u> use copy-on-write
 - > If the child process changes any pages of the parent's address space, the altered pages will be visible to the parent once it resumes
 - ➤ It is intended to be used when the child process calls **exec()** immediately after creation
 - It must be used with caution
 - It is an extremely efficient method to process creation
- ☐ Similar concepts with thread duplication of fork()?

Outline

- Background, Demand Paging, Copy-on-Write
- □ Page Replacement
 - ➤ Basic Page Replacement
 - > FIFO Page Replacement
 - Optimal Page Replacement
 - ➤ LRU Page Replacement
 - ➤ LRU-Approximation Page Replacement
 - Counting-Based Page Replacement
 - Page-Buffering Algorithms
 - ➤ Applications and Page Replacement
- ☐ Allocation of Frames, Thrashing, Memory Compression
- ☐ Allocating Kernel Memory, Other Considerations, Operating-System Examples

Page Replacement


- ☐ If we increase our degree of multiprogramming, we are <u>over-allocating</u> memory
 - > What if there is no free frame on the free-frame list?
 - Terminate the process (does not make sense)
 - Swap out a process (high overhead)
 - Combine swapping pages with page replacement



- ☐ Background, Demand Paging, Copy-on-Write
- Page Replacement
 - Basic Page Replacement
 - > FIFO Page Replacement
 - Optimal Page Replacement
 - ➤ LRU Page Replacement
 - ➤ LRU-Approximation Page Replacement
 - Counting-Based Page Replacement
 - Page-Buffering Algorithms
 - ➤ Applications and Page Replacement
- ☐ Allocation of Frames, Thrashing, Memory Compression
- ☐ Allocating Kernel Memory, Other Considerations, Operating-System Examples

Basic Page Replacement

- 1. Find the location of the desired page on secondary storage
- 2. Find a free frame
 - > If there is a free frame, use it
 - > If there is no free frame
 - Use a page-replacement algorithm to select a <u>victim frame</u>
 - Write the victim frame to secondary storage (if necessary) and change the page and frame tables accordingly
- 3. Read the desired page into the newly freed frame and change the page and frame tables
- 4. Continue the process from where the page fault occurred



Page Replacement Overhead

- ☐ If no frame is free, two page transfers (one for the page-out and one for the page-in) are required
 - Double the page-fault service time
 - > Increase the effective access time
- ☐ Reduce this overhead by using a modify bit (or dirty bit)
 - > Each page or frame has a modify bit associated with it in the hardware
 - Indicate that the page has been modified
 - ➤ When we select a page for replacement
 - If the modify bit is set, we must write the page to storage
 - If the modify bit is not set, we need not write the memory page to storage
 - > It reduces I/O time by one-half if the page has not been modified

Two Major Problems: Design

- ☐ Frame-allocation algorithm
 - > Decide how many frames to allocate to each process
- **☐** Page-replacement algorithm
 - Select the frames that are to be replaced
- Design appropriate algorithms
 - ➤ It is important task because secondary storage I/O is so expensive
 - In general, we want the one with the lowest page-fault rate


Two Major Problems: Analysis

- Evaluate algorithms by running it on a <u>reference string</u> of memory references and computing the number of page faults
 - > Example with 100 bytes per page
 - 0100, 0432, 0101, 0612, 0102, 0103, 0104, 0101, 0611, 0102, 0103 is reduced to 1, 4, 1, 6, 1, 6, 1
 - > Running example with 3 frames
 - 7, 0, 1, 2, 0, 3, 0, 4, 2, 3, 0, 3, 2, 1, 2, 0, 1, 7, 0, 1
- ☐ As the number of frames increases, the number of page faults drops to some minimal level

- Background, Demand Paging, Copy-on-Write
- □ Page Replacement
 - Basic Page Replacement
 - > FIFO Page Replacement
 - Optimal Page Replacement
 - > LRU Page Replacement
 - ➤ LRU-Approximation Page Replacement
 - Counting-Based Page Replacement
 - Page-Buffering Algorithms
 - > Applications and Page Replacement
- ☐ Allocation of Frames, Thrashing, Memory Compression
- ☐ Allocating Kernel Memory, Other Considerations, Operating-System Examples

FIFO Page Replacement

- ☐ First-in, first-out (FIFO) algorithm
 - > Create a FIFO queue to hold all pages in memory
 - Replace a page at the head of the queue
 - > Insert a page at the tail of the queue
- ☐ 15 page faults in the running example




Belady's Anomaly

- ☐ For some page-replacement algorithms, the page-fault rate may increase as the number of allocated frames increases
- ☐ Reference string: 1 2 3 4 1 2 5 1 2 3 4 5
 - ➤ If # of frames = 1, # of page faults = 12
 - ➤ If # of frames = 2, # of page faults = 12
 - \triangleright If # of frames = 3, # of page faults = 9
 - 1234125 © © 34 ©
 - ➤ If # of frames = 4, # of page faults = 10
 - 1234 © © 512345
 - \triangleright If # of frames \ge 5, # of page faults = 5
- ☐ Giving more memory to a process does not necessarily improve its performance

- ☐ Background, Demand Paging, Copy-on-Write
- **☐** Page Replacement
 - Basic Page Replacement
 - > FIFO Page Replacement
 - Optimal Page Replacement
 - ➤ LRU Page Replacement
 - ➤ LRU-Approximation Page Replacement
 - Counting-Based Page Replacement
 - Page-Buffering Algorithms
 - > Applications and Page Replacement
- ☐ Allocation of Frames, Thrashing, Memory Compression
- ☐ Allocating Kernel Memory, Other Considerations, Operating-System Examples

Optimal Page Replacement

- ☐ Replace the page that will not be used for the longest period of time
 - > Guarantee the lowest number of page faults for a fixed reference string
- 9 page faults in the running example




- ☐ It requires future knowledge of the reference string
 - > The optimal algorithm is used mainly for comparison studies

- ☐ Background, Demand Paging, Copy-on-Write
- □ Page Replacement
 - ➤ Basic Page Replacement
 - > FIFO Page Replacement
 - Optimal Page Replacement
 - > LRU Page Replacement
 - ➤ LRU-Approximation Page Replacement
 - Counting-Based Page Replacement
 - Page-Buffering Algorithms
 - > Applications and Page Replacement
- ☐ Allocation of Frames, Thrashing, Memory Compression
- ☐ Allocating Kernel Memory, Other Considerations, Operating-System Examples

LRU Page Replacement

- ☐ Least recently used (LRU) algorithm
 - > Replace the page that has not been used for the longest period of time
 - Change the optimal page replacement from "looking forward" to "looking backward"
- ☐ 12 page faults in the running example



Often used and considered to be good


Implementing LRU Page Replacement

☐ Approach 1: counters

- > Associate a time-of-use field with each page-table entry
- > Add a logical clock (or counter) to the CPU
- > If a page is referenced, copy the clock register to its time-of-use field
- > Replace the page with the smallest time value
 - Require a search of the page table

☐ Approach 2: stack

- Keep a stack of page numbers
 - Use a doubly linked list with a head pointer and a tail pointer
- > If a page is referenced, remove it from the stack and put it on the top
 - The least recently used page is always at the bottom
- > Replace the page pointed by the tail pointer
 - No search but a little more expensive update



Stack Algorithms

- \Box The set of pages in memory for n frames is always a subset of the set of pages that would be in memory with (n + 1) frames
 - Optimal page replacement
 - > LRU page replacement
- ☐ They do not suffer from Belady's anomaly

- ☐ Background, Demand Paging, Copy-on-Write
- □ Page Replacement
 - Basic Page Replacement
 - > FIFO Page Replacement
 - Optimal Page Replacement
 - > LRU Page Replacement
 - > LRU-Approximation Page Replacement
 - Counting-Based Page Replacement
 - Page-Buffering Algorithms
 - > Applications and Page Replacement
- ☐ Allocation of Frames, Thrashing, Memory Compression
- ☐ Allocating Kernel Memory, Other Considerations, Operating-System Examples

LRU-Approximation Page Replacement

- Not many computer systems provide sufficient hardware support for true LRU page replacement
 - ➤ The updating of the clock fields or stack must be done for <u>every</u> memory reference
- ☐ Many systems provide help in the form of a <u>reference bit</u>
 - ➤ The reference bit (in the page table) of a page is set to 1 by the hardware when the page is referenced
 - ➤ We can determine which pages have (or have not) been used after their reference bits are set to 0
 - However, we do not know the order of use

■ Examples

- ➤ Additional-reference-bits algorithm
- Second-chance algorithm
- > Enhanced second-chance algorithm

Additional-Reference-Bits Algorithm


- ☐ Gain additional ordering information by recording the reference bits at shift registers at regular intervals
 - At regular intervals (e.g., every 100 milliseconds), a timer interrupt transfers control to the operating system which
 - Shift the reference bit for each page into the high-order bit
 - Shift the other bits right
 - Example: keep an 8-bit byte for each page in a table in memory
 - 00000000 vs. 111111111 vs. 11000100 vs. 01110111
 - > The number of bits can be varied
 - In the extreme case, it can be zero, leaving only the reference bit itself (second-chance page-replacement algorithm)

Second-Chance Algorithm (1/2)

- ☐ A FIFO replacement algorithm with reference bits
- ☐ When a page has been selected, inspect its reference bit
 - ➤ If it is 0, replace the page
 - ➤ If it is 1, give the page a **second chance** and select the next FIFO page
- ☐ When a page gets a second chance
 - > Its reference bit is cleared to 0
 - > Its arrival time is reset to the current time
 - Thus, it will not be replaced until all other pages have been replaced or given second chances
- □ Note that the reference bit of a page is set to 1 when the page is referenced
 - ➤ If a page is used often enough to keep its reference bit set (to 1), it will never be replaced

Second-Chance Algorithm (2/2)

- □ One way to implement the second-chance algorithm is as a circular queue
 - > Sometimes referred to as the **clock** algorithm
- ☐ In the worst case, if all bits are set (to 1), the second chance replacement degenerates to FIFO replacement



Enhanced Second-Chance Algorithm

- ☐ Consider the reference bit and the modify bit (described earlier) as an ordered pair
 - > (0, 0): neither recently used nor modified
 - Best page to replace
 - > (0, 1): not recently used but modified
 - Not quite as good, because the page will need to be written out before replacement
 - > (1, 0) recently used but clean
 - Probably will be used again soon
 - > (1, 1) recently used and modified
 - Probably will be used again soon, and the page will need to be written out before replacement
- ☐ Use the same scheme as in the clock algorithm and examine the class to which that page belongs

- ☐ Background, Demand Paging, Copy-on-Write
- **☐** Page Replacement
 - Basic Page Replacement
 - > FIFO Page Replacement
 - Optimal Page Replacement
 - ➤ LRU Page Replacement
 - LRU-Approximation Page Replacement
 - Counting-Based Page Replacement
 - Page-Buffering Algorithms
 - > Applications and Page Replacement
- ☐ Allocation of Frames, Thrashing, Memory Compression
- ☐ Allocating Kernel Memory, Other Considerations, Operating-System Examples

Counting-Based Page Replacement

- Keep a counter of the number of references that have been made to each page
 - > The implementation of these algorithms is expensive
 - They do not approximate the optimal replacement well
- ☐ Least frequently used (LFU) page-replacement algorithm
 - > Require that the page with the smallest count be replaced
 - An actively used page should have a large reference count
 - What if a page is used heavily only during the initial phase of a process? Shift the counts right by 1 bit at regular intervals
- ☐ Most frequently used (MFU) page-replacement algorithm
 - Require that the page with the largest count be replaced
 - The page with the smallest count was probably just brought in and has yet to be used

- Background, Demand Paging, Copy-on-Write
- □ Page Replacement
 - Basic Page Replacement
 - > FIFO Page Replacement
 - Optimal Page Replacement
 - > LRU Page Replacement
 - ➤ LRU-Approximation Page Replacement
 - Counting-Based Page Replacement
 - Page-Buffering Algorithms
 - ➤ Applications and Page Replacement
- ☐ Allocation of Frames, Thrashing, Memory Compression
- ☐ Allocating Kernel Memory, Other Considerations, Operating-System Examples

Page-Buffering Algorithms

- ☐ Keep a pool of free frames
 - When a page fault occurs, a victim frame is chosen as before
 - The desired page is read into a free frame from the pool before the victim is written out
 - Restart the process as soon as possible
- ☐ Maintain a list of modified pages
 - ➤ When the paging device is idle, a modified page is selected and written to secondary storage, and its modify bit is then reset
 - Increase the probability that a page will be clean
- ☐ Keep a pool of free frames but remember which page was in each frame
 - ➤ When a page fault occurs, check whether the desired page is in the free-frame pool
 - If not, select a free frame and read into it

- ☐ Background, Demand Paging, Copy-on-Write
- □ Page Replacement
 - ➤ Basic Page Replacement
 - > FIFO Page Replacement
 - Optimal Page Replacement
 - > LRU Page Replacement
 - ➤ LRU-Approximation Page Replacement
 - Counting-Based Page Replacement
 - Page-Buffering Algorithms
 - > Applications and Page Replacement
- ☐ Allocation of Frames, Thrashing, Memory Compression
- ☐ Allocating Kernel Memory, Other Considerations, Operating-System Examples

Applications and Page Replacement

- Applications accessing data through the operating system's virtual memory may perform worse
 - > Some applications understand their memory use and storage use better than an operating system
 - Examples: database, data warehouses
 - > Twice the memory is being used for a set of I/O
 - Both the operating system and the application are buffering I/O
- ☐ Some operating systems provide a <u>raw disk</u>
 - ➤ A large sequential array of logical blocks, without any file-system data structure
 - Bypass all the file-system services, such as file I/O demand paging, file locking, prefetching, space allocation, file names, and directories

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- **☐** Allocation of Frames
 - Minimum Number of Frames, Allocation Algorithms, Global versus Local Allocation, Non-Uniform Memory Access
- Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Recap: Two Major Problems

- ☐ Covered: page-replacement algorithm
 - > Select the frames that are to be replaced
- ☐ Frame-allocation algorithm
 - > Decide how many frames to allocate to each process

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- Allocation of Frames
 - Minimum Number of Frames, Allocation Algorithms, Global versus Local Allocation, Non-Uniform Memory Access
- Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Minimum Number of Frames

- ☐ Must allocate at least a minimum number of frames
 - ➤ Performance: as the number of frames allocated to each process decreases, the page-fault rate increases
 - ➤ Instruction restart: we must hold all the different pages that any single instruction can reference
- ☐ The minimum number is defined by the computer architecture
 - > Example: six frames for an instruction
 - The move instruction for a given architecture itself straddles two frames
 - Each of its two operands is an indirect reference (e.g., via a page table)
 - Example: what if the move instruction allows data to move only from register to register and between registers and memory?
- ☐ The maximum number is defined by the amount of available physical memory

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- Allocation of Frames
 - Minimum Number of Frames, <u>Allocation Algorithms</u>, Global versus Local Allocation, Non-Uniform Memory Access
- Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Allocation Algorithms

- ☐ Equal allocation (ignoring frames needed by OS now)
 - Example: split 93 frames among 5 processes
 - Give each process 18 frames
 - Leave 3 frames as a free-frame buffer pool
- Proportional allocation
 - > Allocate available memory to each process according to its size
 - > Adjust to meet the minimum number of frames
 - Example: split 62 frames among 2 processes with 10 and 127 pages
 - 10 / (10 + 127) * 62 ~= 4 (frames)
 - 127 / (10 + 127) * 62 ~= 57 (frames)
 - Variation
 - The ratio of frames depends not on the relative sizes but rather on the priorities (or on a combination of size and priority)

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- □ Allocation of Frames
 - Minimum Number of Frames, Allocation Algorithms, Global versus Local Allocation, Non-Uniform Memory Access
- Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Global versus Local Allocation

- ☐ Global replacement
 - A process selects a replacement frame from the set of all frames, and thus it can take a frame from another
 - Greater system throughput
- ☐ Local replacement
 - > A process selects from only its own set of allocated frames
 - More consistent per-process performance
- ☐ Global replacement is the more commonly used method

Reclaiming Pages

- ☐ A global page-replacement policy: keep the amount of free memory above a minimum threshold
 - ➤ When it drops below the threshold, a kernel routine is triggered that begins reclaiming pages from all processes in the system
 - Such kernel routines are often known as <u>reapers</u>

Memory

- ☐ It may adopt any pagereplacement algorithm
- ☐ A more extreme example in Linux
 - ➤ If the amount of free memory is very low, a routine, <u>out-of-memory</u> (OOM) killer, selects a process to terminate by OOM scores

-Max Threshold


Min Threshold

→ Time

- Background
- Demand Paging
- ☐ Copy-on-Write
- Page Replacement
- □ Allocation of Frames
 - ➤ Minimum Number of Frames, Allocation Algorithms, Global versus Local Allocation, Non-Uniform Memory Access
- Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Non-Uniform Memory Access (NUMA)

- ☐ Non-uniform memory access systems with multiple CPUs
 - ➤ Not all main memory is created equal (or accessed equally)
- ☐ The goal is to have memory frames allocated "as close as possible" to the CPU on which the process is running
- ☐ More complicated with threads
 - > Linux
 - Migrate threads to the same domain
 - Have a separate free-frame list for each NUMA node



- > Solaris
 - Each <u>Igroup</u> (locality groups) gathers together CPUs and memory
 - Each CPU in that group can access any memory in the group within a defined latency interval

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- Allocation of Frames
- Thrashing
 - Cause of Thrashing, Working-Set Model, Page-Fault Frequency, Current Practice
- Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Thrashing


- ☐ What if a process does not have the minimum number of frames it needs to support pages in the working set
 - Quickly page-fault
 - > Replace a page that will be needed again right away
 - Quickly page-faults again, and again, and again
- ☐ A process is **thrashing** if it is spending more time paging than executing
 - > Thrashing results in severe performance problems

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- □ Thrashing
 - <u>Cause of Thrashing</u>, Working-Set Model, Page-Fault Frequency, Current Practice
- ☐ Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Cause of Thrashing

☐ A global page-replacement algorithm is used

- > A process needs more frames
- > It faults and takes frames from other processes
- > These processes also fault and take frames from other processes
- > As they queue up for the paging device, the ready queue empties
- > CPU utilization decreases
- > The CPU scheduler increases the degree of multiprogramming ...



Locality Model

- We can limit the effects of thrashing by using a local replacement algorithm (or priority replacement algorithm)
 - > The problem is not entirely solved (even if there is no "frame-stealing")
 - Thrashing processes are in the queue for the paging device most of the time
 - The effective access time will increase even for a process that is not thrashing

Locality model

- > As a process executes, it moves from locality to locality
- > A locality is a set of pages that are actively used together
 - Example: the set of pages {18, 19, 20, 21, 22, 23, 24, 29, 30, 33}
 - Example: the set of pages {18, 19, 20, 24, 25, 26, 27, 28, 29, 31, 32, 33}
- Different localities may overlap
- ➤ If there are not enough frames to accommodate the size of the current locality, the process will thrash

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- **☐** Thrashing
 - Cause of Thrashing, <u>Working-Set Model</u>, Page-Fault Frequency, Current Practice
- ☐ Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Working-Set Model (1/2)

- \square Working set (WS): the set of pages in the most recent \triangle page references
 - > Δ: working-set window
 - If Δ is too small, it will not encompass the entire locality
 - If Δ is too large, it may overlap several localities
 - If Δ is infinite, it is the set of pages touched during the process execution
 - > Example
 - Page reference: 2 6 1 5 7 7 7 7 5 1 (t₁) 6 2 3 4 1 2 3 4 4 4 3 4 3 4 4 4 (t₂)
 - If $\Delta = 10$, then WS(t₁) = {1, 2, 5, 6, 7} and WS(t₂) = {3, 4}
- ☐ D: total demand for frames
 - \triangleright D = Σ_i (working-set size of each process i)
 - ➤ If D > the total number of available frames, thrashing will occur

Working-Set Model (2/2)

- ☐ This working-set strategy prevents thrashing while keeping the degree of multiprogramming as high as possible
- ☐ Difficulty: keeping track of the working set
 - > The working-set window is a moving window
 - > A page is in the working set if it is referenced anywhere in the window
- ☐ Approximation: a timer interrupt and a reference bit
 - \triangleright Example: \triangle = 10,000 references
 - Interrupt every 5,000 references
 - Keep 2 additional bits for each page
 - When the timer interrupts, copy and clear the reference bit for each page
 - Examine the current reference bit and two additional bits
 - > Trade-off: interrupt every 1,000 references and keep 10 additional bits

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- **☐** Thrashing
 - Cause of Thrashing, Working-Set Model, <u>Page-Fault Frequency</u>, Current Practice
- ☐ Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Page-Fault Frequency

- ☐ Knowledge of the working set is useful for **prepaging**, but it seems a clumsy way to control thrashing
- ☐ The page-fault frequency (PFF) takes a more direct approach
 - Control the page-fault rate
 - Establish upper and lower bounds on the desired page-fault rate
 - Allocate a frame to a process if the page-fault rate exceeds the upper bound
 - Remove a frame from a process if the page-fault rate falls below the lower bound

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- **☐** Thrashing
 - Cause of Thrashing, Working-Set Model, Page-Fault Frequency, <u>Current</u>
 <u>Practice</u>
- Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

Current Practice

- ☐ Thrashing and the resulting swapping have a high impact on performance
- ☐ The best practice is to include enough physical memory to avoid thrashing and swapping
 - ➤ Keeping all working sets in memory concurrently, except under extreme conditions, provides the best user experience

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- □ Thrashing
- **☐** Memory Compression
- Allocating Kernel Memory
- Other Considerations
- ☐ Operating-System Examples

Memory Compression (1/2)

- ☐ Compress several frames into a single frame
 - > Rather than paging out modified frames to swap space
- Example
 - ➤ Before compression
 - Free-frame list: Head \rightarrow 7 \rightarrow 2 \rightarrow 9 \rightarrow 21 \rightarrow 27 \rightarrow 16
 - Modified frame list: Head \rightarrow 15 \rightarrow 3 \rightarrow 35 \rightarrow 26
 - > Frames 15, 3, and 35 are compressed and stored in frame 7
 - > After compression
 - Free-frame list: Head \rightarrow 2 \rightarrow 9 \rightarrow 21 \rightarrow 27 \rightarrow 16 \rightarrow 15 \rightarrow 3 \rightarrow 35
 - Modified frame list: Head \rightarrow 26
 - Compressed frame list: Head → 7
 - > If one compressed frame is later referenced, a page fault occurs
 - The compressed frame is decompressed, restoring the pages 15, 3, and 35

Memory Compression (2/2)

- ☐ Memory compression is an integral part of the memorymanagement strategy for most mobile operating systems
 - Android and iOS
 - > In addition, both Windows 10 and macOS also support it
- ☐ Trade-off between
 - > The speed of the compression algorithm
 - > The amount of reduction that can be achieved (compression ratio)

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- □ Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
 - Buddy System, Slab Allocation
- Other Considerations
- Operating-System Examples


Allocating Kernel Memory

- ☐ Kernel memory is often allocated from a free-memory pool different from the list used for ordinary user-mode processes
- Reasons
 - The kernel requests memory for data structures of varying sizes, some of which are less than a page in size
 - Internal fragmentation
 - ➤ Certain hardware devices interact directly with physical memory and consequently require memory residing in physically contiguous pages
 - No benefit of a virtual memory interface

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- □ Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
 - > Buddy System, Slab Allocation
- Other Considerations
- Operating-System Examples

Buddy System


- □ Allocate memory from a fixed-size segment consisting of physically contiguous pages
 - Memory is allocated from this segment using a <u>power-of-2 allocator</u>
 - > Example
 - A 256-KB memory segment
 - A 21-KB request from kernel
 - Two <u>buddies</u> divided from the segment
 - Buddies further divided until the request is satisfied with a 32-KB segment
 - Advantage
 - Adjacent <u>buddies</u> can be combined to form larger segments using <u>coalescing</u>
 - Disadvantage
 - Internal fragmentation



- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- □ Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
 - Buddy System, <u>Slab Allocation</u>
- Other Considerations
- Operating-System Examples

Slab Allocation

- ☐ A <u>slab</u> is made up of one or more physically contiguous pages
- ☐ A <u>cache</u> consists of one or more slabs
 - There is a single cache for each unique kernel data structure
 - Examples: process descriptors (process control blocks), file objects, semaphores (Chapter 6)
- Each cache is populated with objects
 - ➤ Instantiations of the kernel data structure that the cache represents
- ☐ The allocator
 - Assign any <u>free</u> object from the cache to satisfy a request
 - Mark the object as <u>used</u>



Slab Allocation: Benefits

- ☐ No memory is wasted due to fragmentation
 - ➤ The slab allocator returns the exact amount of memory required to represent an object
 - Each unique kernel data structure has an associated cache
 - Each cache is made up of one or more slabs that are divided into chunks the size of the objects being represented
- Memory requests can be satisfied quickly
 - > Objects are quickly allocated from the cache
 - They are created in advance
 - > Objects are immediate available for subsequent requests
 - When the kernel has finished with them, they are marked as free and returned to the cache

Slab Allocator in Linux (1/2)

Example

- > A process descriptor is of the type struct task struct
 - Approximately 1.7 KB of memory
- > The kernel requests memory for a **struct task_struct** object from its cache
- The cache fulfills the request using a **struct** task_struct object that has been allocated in a slab and marked as free

☐ Three possible states of a slab

- > Full: all objects are used
- > Empty: all objects are free
 - Second choice
- > Partial: the slab consists of both used and free objects
 - First choice
- > If no empty slab exists, a new slab is allocated and assigned to a cache

Slab Allocator in Linux (2/2)

- ☐ The slab allocator first appeared in the Solaris 2.4 kernel
- ☐ The Linux kernel adopted the SLAB allocator from Version 2.2
 - Originally used the buddy system
- ☐ Recent Linux versions include other kernel memory allocators
 - The SLOB (simple list of blocks) allocator is designed for systems with limited memory, such as embedded systems
 - Three lists of objects: small (<256 bytes), medium (<1,024 bytes), and large (<the size of a page)
 - ➤ The SLUB allocator (from Version 2.6.24) reduces much of the overhead required by the SLAB allocator
 - Do not store certain metadata with each slab
 - Do not include the per-CPU queues

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- ☐ Allocation of Frames
- Thrashing
- Memory Compression
- □ Allocating Kernel Memory
- **☐** Other Considerations
 - Prepaging, Page Size, TLB Reach, Inverted Page Tables, Program Structure, I/O Interlock and Page Locking
- Operating-System Examples

Prepaging

- ☐ Bring some (or all) of the pages that will be needed into memory at one time
 - > A large number of page faults occur when a process is started
 - Prepaging is an attempt to prevent this high level of initial paging
- ☐ The question: whether the cost of using prepaging is less than the cost of servicing the corresponding page faults?
 - > Prepaging a file may be more predictable
 - Files are often accessed sequentially
 - The Linux **readahead()** system call prefetches the contents of a file into memory

Page Size

- ☐ Page sizes are invariably powers of 2
 - Generally ranging from 4,096 (2¹²) to 4,194,304 (2²²) bytes
- ☐ Factors of page size selection
 - ➤ Page table size → a larger page is better
 - ➤ Internal fragmentation → a smaller page is better
 - ➤ I/O time → a larger page is better
 - ➤ Resolution and locality → a smaller page is better
 - ➤ Number of page faults → a larger page is better
 - Others
- ☐ The historical trend is toward larger page sizes
 - > Even for mobile systems

TLB Reach

- ☐ Translation look-aside buffer (TLB) reach
 - > The amount of memory accessible from the TLB
 - > The number of entries multiplied by the page size
- ☐ Ideally, the working set for a process is stored in the TLB
- ☐ To increase the TLB reach
 - Increase the number of entries (in the TLB)
 - Still insufficient for storing the working set of a memory-intensive application
 - ➤ Increase the page size
 - Increase internal fragmentation for an application that does not require such a large page size
 - ➤ Provide multiple page sizes
 - Allow an application to use a large page size without increasing internal fragmentation
 - Require the operating system, rather than hardware, to manage the TLB

Inverted Page Tables

- Do not contain complete information about the logical address space of a process
 - > The information is required if a referenced page is not in memory
- ☐ An external page table (one per process) must be kept
 - ➤ It is like the traditional per-process page table and contains information on where each virtual page is located
 - It does not need to be available quickly, but it may generate another page fault for itself
 - This special case requires careful handling in the kernel and a delay in the page-lookup processing

Program Structure

- ☐ int[128][128] data;
 - > Assume that each row is stored in one page and the array is row major
 - In memory: data[0][0], data[0][1], ..., data[0][127],
 data[1][0], data[1][1], ..., data[127][127]
- ☐ Possible 128 x 128 = 16,384 faults

```
for (j = 0; j < 128; j++)
  for (i = 0; i < 128; i++)
  data[i][j] = 0;</pre>
```

☐ At most 128 faults

```
for (i = 0; i < 128; i++)
  for (j = 0; j < 128; j++)
  data[i][j] = 0;</pre>
```

Compiler and loader can have a significant effect on paging

I/O Interlock and Page Locking

- ☐ When demand paging is used, we sometimes need to allow some of the pages to be <u>locked</u> in memory
- ☐ Bad example
 - ➤ The page containing the memory buffer of a process is paged out (by another process) during waiting I/O completion
- Solutions
 - Execute I/O to system memory (not user memory)
 - Allow pages to be locked
 - Frequently, some or all of the operating-system kernel is locked into memory
 - User processes may also need to lock pages into memory (e.g., <u>pinning</u> of pages by a database process)

- Background
- Demand Paging
- ☐ Copy-on-Write
- ☐ Page Replacement
- Allocation of Frames
- ☐ Thrashing
- Memory Compression
- ☐ Allocating Kernel Memory
- Other Considerations
- Operating-System Examples
 - ➤ Linux, Windows, Solaris

Linux

- Manage kernel memory using slab allocation
- ☐ Use demand paging
 - ➤ Allocate pages from a list of free frames
- ☐ Use a global page-replacement policy
 - > Similar to the LRU-approximation clock algorithm
- ☐ Maintain two types of page lists
 - > Active list
 - Contain the pages that are considered in use
 - > Inactive list
 - Contain the pages that have not recently been referenced and are eligible to be reclaimed


Windows

- ☐ Clustering for demand paging
 - ➤ Bring in not only the faulting page but also the pages preceding and following the faulting page
- Working-set management
 - ➤ Working-set minimum: the minimum number of assigned pages
 - ➤ Working-set maximum: the maximum number of assigned pages
 - ➤ May ignore the values unless a process is with **hard working-set limits**
- Automatic working-set trimming
 - ➤ When the amount of free memory falls below the threshold, use a global replacement tactic to restore it above the threshold

Solaris

☐ Pageout algorithm

- Use two hands to scan pages
 - The front hand of the clock sets the reference bits of all pages to 0
 - The back hand of the clock appends a page to the free list (if the reference bit is still 0) or writes its contents to secondary storage (otherwise)
- Control the rate at which pages are scanned



Priority paging

- > Skip pages belonging to libraries that are shared by several processes
- > Distinguish between pages allocated to processes and regular data files

Objectives

- Define virtual memory and describe its benefits
- Illustrate how pages are loaded into memory using demand paging
- ☐ Apply the FIFO, optimal, and LRU page-replacement algorithms
- Describe the working set of a process, and explain how it is related to program locality
- ☐ Describe how Linux, Windows 10, and Solaris manage virtual memory

Q&A