Московский Авиационный Институт

(Национальный Исследовательский Университет)

Институт №8 "Компьютерные науки и прикладная математика"

Кафедра №806 "Вычислительная математика и программирование"

Лабораторная работа №8 по курсу «Операционные системы»

Группа: М8О-215Б-23

Студент: Моисеев К.В.

Преподаватель: Миронов Е.С.

Оценка:

Дата: 06.02.25

Постановка задачи

Цель работы: Приобретение практических навыков диагностики работы программного обеспечения.

Задание: при выполнении лабораторных работ по курсу ОС необходимо продемонстрировать ключевые системные вызовы, которые в них используются и то, что их использование соответствует варианту ЛР. По итогам выполнения всех лабораторных работ отчет по данной ЛР должен содержать краткую сводку по исследованию написанных программ.

Общий метод и алгоритм решения

Для иллюстрации работы с системными вызовами в операционной системе Windows можно воспользоваться утилитой **NtTrace**.

NtTrace представляет собой инструмент для диагностики, отладки и анализа взаимодействия приложений с ядром операционной системы Windows на уровне **Native API**. Этот инструмент аналогичен **strace** в Linux и позволяет отслеживать вызовы функций, предоставляемых библиотекой **ntdll.dll**. Так как Native API не является официально документированным и может изменяться между версиями Windows, отслеживание работы приложения на этом уровне дает возможность глубже понять его взаимодействие с операционной системой.

NtTrace использует отладочный интерфейс Windows для перехвата вызовов Native API, фиксирует передаваемые аргументы и возвращаемые значения, а также, при возможности, переводит коды возврата в текстовые сообщения об ошибках Windows.

Чаще всего **NtTrace** применяется в следующих случаях:

- Анализ поведения программ, выполняемых в пользовательском пространстве.
- Отладка проблем, возникающих при работе с файлами, процессами, реестром и другими системными ресурсами.
- Поиск причин неожиданного завершения работы программ.
- Исследование взаимодействия приложений с ядром Windows.

Основные возможности NtTrace:

- **Фильтрация вызовов** с помощью параметра –filter можно задать, какие вызовы необходимо отслеживать (например, File, Process, Registry).
- Отслеживание ошибок параметр –е позволяет выводить только ошибочные вызовы.
- Присоединение к уже запущенному процессу с помощью –а можно подключиться к существующему процессу для его анализа.

- **Вывод стека вызовов** использование -stack позволяет отображать стек вызовов, что полезно для глубокого анализа работы программы.
- Вывод временных меток параметры -time и -delta позволяют печатать абсолютные и относительные временные метки вызовов.
- **Вывод информации о потоках и процессах** с помощью -pid и -tid можно видеть идентификаторы процессов и потоков.
- Игнорирование загрузки DLL опция -nodlls исключает отображение операций загрузки и выгрузки динамических библиотек.
- Запись лога в файл параметр -out позволяет перенаправить вывод в файл для дальнейшего анализа.

NtTrace — мощный инструмент для анализа поведения приложений в среде Windows. Он предоставляет детальный контроль над выполнением системных вызовов, что делает его незаменимым средством диагностики и отладки программного обеспечения.

Для иллюстрации системных вызовов воспользуемся утилитой strace в операционной системе Linux.

Strace представляет собой инструмент для диагностики, отладки и обучения в пользовательском пространстве Linux. Он применяется для мониторинга и вмешательства во взаимодействие между процессами и ядром системы, включая системные вызовы, передачу сигналов и изменение состояния процессов. Работа strace основана на функции ядра, известной как рtrace. Чаще всего strace используется для запуска программы с последующим отображением списка выполняемых ею системных вызовов. Это особенно полезно, когда программа часто аварийно завершает работу или ведет себя непредсказуемо; например, strace может показать, что программа пытается обратиться к несуществующему или недоступному файлу.

Еще одним полезным применением strace является использование опции -р для присоединения к уже запущенному процессу. Это может быть необходимо, если процесс перестал отвечать, и strace может помочь определить, что процесс зависает при попытке установить сетевое соединение.

Кроме того, strace предоставляет множество других возможностей:

- **Фильтрация системных вызовов:** Вы можете указать, какие системные вызовы следует отслеживать, используя параметр -е trace=. Это можно сделать по имени (например, clone, fork, vfork), с использованием предопределенных групп (например, %ipc или %file) или с помощью регулярных выражений (начиная с версии strace 4.17, например, -e trace=/clock_.*).
- **Трассировка путей:** Вы можете указать список путей для трассировки, используя параметр -Р (например, -Р /etc/ld.so.cache).
- **Выгрузка ввода-вывода:** Вы можете указать список файловых дескрипторов для выгрузки ввода-вывода, используя параметры -е read= и -е write=.

- Подсчет времени выполнения: Strace позволяет подсчитывать время выполнения системных вызовов и их количество, используя параметры -T, -c, -С и -w. Параметр -U позволяет выводить дополнительную информацию, такую как минимальное и максимальное время выполнения системного вызова.
- **Временные метки:** Strace может печатать относительные или абсолютные временные метки, используя опции -t и -r.
- Изменение системных вызовов: Strace позволяет изменять выполняемые системные вызовы, включая изменение возвращаемого значения и кода ошибки, внедрение сигналов, задержек и изменение данных, на которые указывают аргументы системных вызовов. Это достигается с помощью опции -e inject=syscall specification:tampering specification:retval=:error=:signal=:delay_enter=:delay_exit=:poke_enter=:poke_exit=.
- Информация о дескрипторах файлов: Strace может извлекать информацию о дескрипторах файлов, включая сокеты, используя опцию -у. Опция -уу предоставляет дополнительную информацию, такую как адреса конечных точек для сокетов, пути и основные/дополнительные номера устройств для файлов.
- **Трассировка стека:** Strace может печатать трассировки стека, включая разборку символов (начиная с версии strace 4.21, используя опцию -k).

Strace также поддерживает множество других опций и параметров, которые делают его мощным инструментом для диагностики и отладки программного обеспечения.

Протокол работы программы

Лабораторная работа №1.

C:\Users\klosh\Desktop\NtTrace-main\NtTrace-main>NtTrace -filter Process

C:\Users\klosh\Desktop\OS\build\ParentProcess.exe

Process 8076 starting at 0000000004014E0 with command line:

"C:\Users\klosh\Desktop\OS\build\ParentProcess.exe"

C:\Users\klosh\Desktop\OS\build\ParentProcess.exe

Loaded DLL at 00007FFB53B30000 ntdll.dll

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie],

ProcessInformation=0x61f418, Length=4, ReturnLength=null) => 0

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie],

ProcessInformation=0x7ffb53cb7268, Length=4, ReturnLength=null) => 0

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie],

ProcessInformation=0x61f328, Length=4, ReturnLength=null) => 0

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie],

ProcessInformation=0x61f380, Length=4, ReturnLength=null) => 0

Loaded DLL at 00007FFB52860000 C:\WINDOWS\System32\KERNEL32.DLL

Loaded DLL at 00007FFB514B0000 C:\WINDOWS\System32\KERNELBASE.dll

NtSetInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x23

[ProcessTlsInformation], ProcessInformation=0x61ed40, Length=0x28) => 0

NtSetInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x31

[ProcessOwnerInformation], ProcessInformation=0x61ea98, Length=8) => 0

NtOpenProcessToken(ProcessHandle=-1, DesiredAccess=0x8, TokenHandle=0x61e980 [0x6c]) =>

0

NtSetWnfProcessNotificationEvent(NotificationEvent=0x80) => 0

Loaded DLL at 00007FFB52530000 C:\WINDOWS\System32\msvcrt.dll

NtSetInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x23

[ProcessTlsInformation], ProcessInformation=0x61f090, Length=0x28) => 0

Initial breakpoint

```
NtOpenProcessToken(ProcessHandle=-1, DesiredAccess=0x8, TokenHandle=0x61f320 [0xa8]) => 0
```

Enter the name of the file: ..\test\test_input.txt

Loaded DLL at 00007FFB527B0000 C:\WINDOWS\System32\sechost.dll

Loaded DLL at 00007FFB51310000 C:\WINDOWS\System32\bcrypt.dll

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x56

[ProcessEnclaveInformation], ProcessInformation=0x61ce20, Length=0xb0, ReturnLength=null) => 0xc0000003 [87 '???????? ?????????????]

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0

 $[Process Basic Information], \ Process Information = 0x61cda0, \ Length = 0x40, \ Return Length = null) => 0$

NtCreateUserProcess(ProcessHandle=0x61dea0 [0xe4], ThreadHandle=0x61df20 [0xe0],

ProcessDesiredAccess=MAXIMUM_ALLOWED,

ThreadDesiredAccess=MAXIMUM_ALLOWED, ProcessObjectAttributes=null,

ThreadObjectAttributes=null, ProcessFlags=0x204, ThreadFlags=1, ProcessParameters=0xe2660

["C:\Users\klosh\Desktop\OS\build\ChildProcess.exe"], CreateInfo=0x61e1d0,

AttributeList=0x61e670) => 0 (вызов, который инициирует создание дочернего

процесса ChildProcess.exe)

NtOpenProcessToken(ProcessHandle=-1, DesiredAccess=0xa, TokenHandle=0x61da70 [0xf0]) => 0

NtQueryInformationProcess(ProcessHandle=0xe4, ProcessInformationClass=0x3c

[ProcessCommandLineInformation], ProcessInformation=0xdfd80, Length=0x400,

ReturnLength=0x61da40 [0x60]) => 0

Nt Query Information Process (Process Handle = 0 xe 4, Process Information Class = 0 xe 4, Process =

[ProcessBasicInformation], ProcessInformation=0x61dce0, Length=0x40, ReturnLength=null) => 0

Loaded DLL at 00007FFB4B680000 C:\WINDOWS\system32\apphelp.dll

Process 12556 starting at 0000000004014E0 with command line: "ChildProcess.exe

..\test\test_input.txt"

C:\Users\klosh\Desktop\OS\build\ChildProcess.exe

Loaded DLL at 00007FFB53B30000 ntdll.dll

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie],

ProcessInformation=0x61f418, Length=4, ReturnLength=null) => 0

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie], ProcessInformation=0x7ffb53cb7268, Length=4, ReturnLength=null) => 0 NtOuervInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie], ProcessInformation=0x61f328, Length=4, ReturnLength=null) => 0 NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie], ProcessInformation=0x61f380, Length=4, ReturnLength=null) => 0 Loaded DLL at 00007FFB52860000 C:\WINDOWS\System32\KERNEL32.DLL Loaded DLL at 00007FFB514B0000 C:\WINDOWS\System32\KERNELBASE.dll NtSetInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x23 [ProcessTlsInformation], ProcessInformation=0x61ed40, Length=0x28) => 0 NtSetInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x31 [ProcessOwnerInformation], ProcessInformation=0x61ea98, Length=8) => 0 NtOpenProcessToken(ProcessHandle=-1, DesiredAccess=0x8, TokenHandle=0x61e980 [0x68]) => 0 NtSetWnfProcessNotificationEvent(NotificationEvent=0x7c) => 0 Loaded DLL at 00007FFB4B680000 C:\WINDOWS\SYSTEM32\apphelp.dll NtOpenProcess(ProcessHandle=0x61eb58 [0xbc], DesiredAccess=0x1000, ObjectAttributes=null, ClientId=0x61eaf0 [0x310c/0]) => 0NtOpenProcessToken(ProcessHandle=0xbc, DesiredAccess=0x8, TokenHandle=0x61ead0 [0xc0]) =>0Loaded DLL at 00007FFB52530000 C:\WINDOWS\System32\msvcrt.dll NtSetInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x23 [ProcessTlsInformation], ProcessInformation=0x61f090, Length=0x28) => 0 Initial breakpoint NtOpenProcessToken(ProcessHandle=-1, DesiredAccess=0x8, TokenHandle=0x61f320 [0xc4]) => 0 NtTerminateProcess(ProcessHandle=0, ExitStatus=1) => 0

Process 12556 exit code: 1 (завершился дочерний процесс)

NtTerminateProcess(ProcessHandle=0, ExitStatus=0) => 0

Process 8076 exit code: 0 (завершился родительский процесс)

Лабораторная работа №2.

 $\label{lem:condition} C:\Users\klosh\Desktop\NtTrace-main>NtTrace-filter\ File, Process \\ C:\Users\klosh\Desktop\OS2\build\MatrixMultiplication.exe\ C:\Users\klosh\Desktop\OS2\tests\input.txt \\ 3$

Process 12016 starting at 0000000004014E0 with command line:

"C:\Users\klosh\Desktop\OS2\build\MatrixMultiplication.exe

C:\Users\klosh\Desktop\OS2\tests\input.txt 3"

C:\Users\klosh\Desktop\OS2\build\MatrixMultiplication.exe

Loaded DLL at 00007FFC84D90000 ntdll.dll

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie], ProcessInformation=0x61f418, Length=4, ReturnLength=null) => 0

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie], ProcessInformation=0x7ffc84f17268, Length=4, ReturnLength=null) => 0

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie], ProcessInformation=0x61f328, Length=4, ReturnLength=null) => 0

NtQueryInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x24 [ProcessCookie], ProcessInformation=0x61f380, Length=4, ReturnLength=null) => 0

 $NtOpenFile(FileHandle=0x61f398~[0x5c], DesiredAccess=SYNCHRONIZE|0x20, \\ ObjectAttributes="\??\C:\Users\klosh\Desktop\NtTrace-main\NtTrace-main\", IoStatusBlock=0x61f308\\ [0/1], ShareAccess=3, OpenOptions=0x21) => 0$

NtQueryVolumeInformationFile(FileHandle=0x5c, IoStatusBlock=0x61f308 [0/8], FsInformation=0x61f2f0, Length=8, FsInformationClass=4 [FsDeviceInformation]) => 0

Loaded DLL at 00007FFC83D60000 C:\WINDOWS\System32\KERNEL32.DLL

Loaded DLL at 00007FFC821C0000 C:\WINDOWS\System32\KERNELBASE.dll

 $NtSetInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x23 \ [ProcessTlsInformation], \\ ProcessInformation=0x61ed40, \ Length=0x28) => 0$

NtInitializeNlsFiles(BaseAddress=0x61eac0 [0x000c0000], DefaultLocaleId=0x7ffc82528b88 [0x409], DefaultCasingTableSize=null) => 0

NtCreateFile(FileHandle=0x61eb28 [0x60],

DesiredAccess=READ_CONTROL|SYNCHRONIZE|0x19f, ObjectAttributes=4:"\Connect", IoStatusBlock=0x61e4e0 [0/0x18], AllocationSize=null, FileAttributes=0, ShareAccess=7, CreateDisposition=2, CreateOptions=0x20, EaBuffer=0x6e6800, EaLength=0x54b) => 0

NtDeviceIoControlFile(FileHandle=0x60, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61ea70 [0/0], IoControlCode=0x00500023, InputBuffer=null, InputBufferLength=0, OutputBuffer=0x61ea90, OutputBufferLength=8) => 0

NtSetInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x31 [ProcessOwnerInformation], ProcessInformation=0x61ea98, Length=8) => 0

NtOpenProcessToken(ProcessHandle=-1, DesiredAccess=0x8, TokenHandle=0x61e980 [0x74]) => 0

NtSetWnfProcessNotificationEvent(NotificationEvent=0x84) => 0

Loaded DLL at 00007FFC845E0000 C:\WINDOWS\System32\msvcrt.dll

NtSetInformationProcess(ProcessHandle=-1, ProcessInformationClass=0x23 [ProcessTlsInformation], ProcessInformation=0x61f090, Length=0x28) => 0

Initial breakpoint

NtOpenProcessToken(ProcessHandle=-1, DesiredAccess=0x8, TokenHandle=0x61f320 [0xb0]) => 0

NtQueryVolumeInformationFile(FileHandle=0x54, IoStatusBlock=0x61f070 [0/8], FsInformation=0x61f090, Length=8, FsInformationClass=4 [FsDeviceInformation]) => 0

NtQueryVolumeInformationFile(FileHandle=0x150, IoStatusBlock=0x61f070 [0/8], FsInformation=0x61f090, Length=8, FsInformationClass=4 [FsDeviceInformation]) => 0

NtQueryVolumeInformationFile(FileHandle=0x64, IoStatusBlock=0x61f070 [0/8], FsInformation=0x61f090, Length=8, FsInformationClass=4 [FsDeviceInformation]) => 0

NtDeviceIoControlFile(FileHandle=0x60, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61df40 [0/0], IoControlCode=0x00500016, InputBuffer=0x61df50, InputBufferLength=0x30, OutputBuffer=null, OutputBufferLength=0) => 0

Reading matrices from file: C:\Users\klosh\Desktop\OS2\tests\input.txt

NtWriteFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61e0e0 [0/0x48], Buffer=0x61e180, Length=0x48, ByteOffset=null, Key=null) => 0

NtCreateFile(FileHandle=0x61eb80 [0xb8], DesiredAccess=SYNCHRONIZE|GENERIC_READ|0x80, ObjectAttributes="\??\C:\Users\klosh\Desktop\OS2\tests\input.txt", IoStatusBlock=0x61eb88 [0/1], AllocationSize=null, FileAttributes=0x80, ShareAccess=0, CreateDisposition=1, CreateOptions=0x60, EaBuffer=null, EaLength=0) => 0

NtReadFile(FileHandle=0xb8, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61ece0 [0/0x4b], Buffer=0x61ed40, Length=0x1000, ByteOffset=null, Key=null) => 0

NtDeviceIoControlFile(FileHandle=0x60, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61df40 [0/0], IoControlCode=0x00500016, InputBuffer=0x61df50, InputBufferLength=0x30, OutputBuffer=null, OutputBufferLength=0) => 0

Matrix size: 2 x 2

NtWriteFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61e0e0 [0/0x14], Buffer=0x61e180, Length=0x14, ByteOffset=null, Key=null) => 0

NtDeviceIoControlFile(FileHandle=0x60, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61df50 [0/0], IoControlCode=0x00500016, InputBuffer=0x61df60, InputBufferLength=0x30, OutputBuffer=null, OutputBufferLength=0) => 0

Multiplying matrices...

NtWriteFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61e0f0 [0/0x19], Buffer=0x61e190, Length=0x19, ByteOffset=null, Key=null) => 0

Created thread: 17688 at 00000000004015EE

Created thread: 17976 at 0000000004015EE

Created thread: 12204 at 00000000004015EE

Created thread: 19088 at 0000000004015EE

Thread 12204 exit code: 0

Thread 19088 exit code: 0

Thread 17976 exit code: 0

Thread 17688 exit code: 0

NtDeviceIoControlFile(FileHandle=0x60, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61df50 [0/0], IoControlCode=0x00500016, InputBuffer=0x61df60, InputBufferLength=0x30, OutputBuffer=null, OutputBufferLength=0) => 0

Multiplication complete. Result matrix:

NtWriteFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61e0f0 [0/0x29], Buffer=0x61e190, Length=0x29, ByteOffset=null, Key=null) => 0

(-17.00 + 53.00i) NtDeviceIoControlFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61fa50 [0/0x12], IoControlCode=0x00500016, InputBuffer=0x61fa60, InputBufferLength=0x40, OutputBuffer=null, OutputBufferLength=0) => 0

(5.00 + 45.00i) NtDeviceIoControlFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61fa50 [0/0x10], IoControlCode=0x00500016, InputBuffer=0x61fa60, InputBufferLength=0x40, OutputBuffer=null, OutputBufferLength=0) => 0

NtDeviceIoControlFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61fa50 [0/1], IoControlCode=0x00500016, InputBuffer=0x61fa60, InputBufferLength=0x40, OutputBuffer=null, OutputBufferLength=0) => 0

(-21.00 + 105.00i) NtDeviceIoControlFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61fa50 [0/0x13], IoControlCode=0x00500016, InputBuffer=0x61fa60, InputBufferLength=0x40, OutputBuffer=null, OutputBufferLength=0) => 0

(17.00 + 89.00i) NtDeviceIoControlFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61fa50 [0/0x11], IoControlCode=0x00500016, InputBuffer=0x61fa60, InputBufferLength=0x40, OutputBuffer=null, OutputBufferLength=0) => 0

NtDeviceIoControlFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61fa50 [0/1], IoControlCode=0x00500016, InputBuffer=0x61fa60, InputBufferLength=0x40, OutputBuffer=null, OutputBufferLength=0) => 0

NtDeviceIoControlFile(FileHandle=0x60, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61df40 [0/0], IoControlCode=0x00500016, InputBuffer=0x61df50, InputBufferLength=0x30, OutputBuffer=null, OutputBufferLength=0) => 0

Time taken: 0.018656 seconds

NtWriteFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61e0e0 [0/0x1e], Buffer=0x61e180, Length=0x1e, ByteOffset=null, Key=null) => 0

NtDeviceIoControlFile(FileHandle=0x60, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61df50 [0/0], IoControlCode=0x00500016, InputBuffer=0x61df60, InputBufferLength=0x30, OutputBuffer=null, OutputBufferLength=0) => 0

Memory freed, program complete.

NtWriteFile(FileHandle=0x150, Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x61e0f0 [0/0x21], Buffer=0x61e190, Length=0x21, ByteOffset=null, Key=null) => 0

NtTerminateProcess(ProcessHandle=0, ExitStatus=0) => 0

Process 12016 exit code: 0

Лабораторная работа №3.

C:\Users\klosh\Desktop\NtTrace-main\NtTrace-main>NtTrace -filter

Nt Create Section, Nt Map View Of Section, Nt Unmap View Of Section, Nt Open File

C:\Users\klosh\Desktop\OS3\build\parent.exe C:\Users\klosh\Desktop\OS3\test\test.txt

Process 11108 starting at 0000000004014E0 with command line:

"C:\Users\klosh\Desktop\OS3\build\parent.exe C:\Users\klosh\Desktop\OS3\test\test.txt"

C:\Users\klosh\Desktop\OS3\build\parent.exe

Loaded DLL at 00007FFD423F0000 ntdll.dll

NtOpenFile(FileHandle=0x61f398 [0x54], DesiredAccess=SYNCHRONIZE|0x20,

ObjectAttributes="\??\C:\Users\klosh\Desktop\NtTrace-main\NtTrace-main\", IoStatusBlock=0x61f308 [0/1],

ShareAccess=3, OpenOptions=0x21) => 0

Loaded DLL at 00007FFD40C40000 C:\WINDOWS\System32\KERNEL32.DLL

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1, BaseAddress=0x674b80 [0x00007ffd40c40000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x674ad8 [0x000c4000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

Loaded DLL at 00007FFD3F6F0000 C:\WINDOWS\System32\KERNELBASE.dll

NtMapViewOfSection(SectionHandle=0x68, ProcessHandle=-1, BaseAddress=0x6752c0 [0x00007ffd3f6f0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x675218 [0x003b9000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtCreateSection(SectionHandle=0x61e900 [0x6c],

DesiredAccess=DELETE|READ_CONTROL|WRITE_DAC|WRITE_OWNER|0x1f, ObjectAttributes=null,

SectionSize=0x61e8f0 [65536], Protect=4, Attributes=0x08000000, FileHandle=0) => 0

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1, BaseAddress=0x61e8f8 [0x00007ff4fdec0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x61e908 [0x00100000], InheritDisposition=2

[ViewUnmap], AllocationType=0x00500000, Protect=2) => 0

NtMapViewOfSection(SectionHandle=0x98, ProcessHandle=-1, BaseAddress=0x61e890 [0x001d0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x61e8a0 [0x3000], InheritDisposition=2

[ViewUnmap], AllocationType=0, Protect=2) => 0

NtMapViewOfSection(SectionHandle=0x9c, ProcessHandle=-1, BaseAddress=0x61e890 [0x001e0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x61e8a0 [0x3000], InheritDisposition=2

[ViewUnmap], AllocationType=0, Protect=2) => 0

NtMapViewOfSection(SectionHandle=0xa0, ProcessHandle=-1, BaseAddress=0x61e890 [0x001f0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x61e8a0 [0x1000], InheritDisposition=2

[ViewUnmap], AllocationType=0, Protect=2) => 0

Loaded DLL at 00007FFD409C0000 C:\WINDOWS\System32\msvcrt.dll

NtMapViewOfSection(SectionHandle=0xb8, ProcessHandle=-1, BaseAddress=0x677f30 [0x00007ffd409c0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x675078 [0x000a7000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

Initial breakpoint

NtCreateSection(SectionHandle=0x61fb40 [0xbc],

DesiredAccess=DELETE|READ_CONTROL|WRITE_DAC|WRITE_OWNER|0x7,

ObjectAttributes=0x80:"Local\SharedMemoryExample", SectionSize=0x61fb30 [256], Protect=4,

Attributes=0x08000000, FileHandle=0) => 0

NtCreateSection используется для создания секции, которая может быть сопоставлена с памятью

процесса. Первый вызов, который создает секцию для общей памяти

NtMapViewOfSection(SectionHandle=0xbc, ProcessHandle=-1, BaseAddress=0x61fb98 [0x00620000].

ZeroBits=0, CommitSize=0, SectionOffset=0x61fb90 [0], ViewSize=0x61fba0 [0x1000], InheritDisposition=1

[ViewShare], AllocationType=0, Protect=4) => 0

B Windows аналог mmap — это NtMapViewOfSection. Этот вызов используется для сопоставления

представления секции с адресным пространством процесса.

Loaded DLL at 00007FFD41E90000 C:\WINDOWS\System32\sechost.dll

NtMapViewOfSection(SectionHandle=0xc0, ProcessHandle=-1, BaseAddress=0x679000 [0x00007ffd41e90000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x675078 [0x000a7000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

Loaded DLL at 00007FFD3FAB0000 C:\WINDOWS\System32\bcrypt.dll

NtMapViewOfSection(SectionHandle=0xc4, ProcessHandle=-1, BaseAddress=0x679490 [0x00007ffd3fab0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x6793f8 [0x00028000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtOpenFile(FileHandle=0x7ffd3fad27a0 [0xd4], DesiredAccess=SYNCHRONIZE|0x3,

ObjectAttributes="\Device\KsecDD", IoStatusBlock=0x61cf10 [0/0], ShareAccess=7, OpenOptions=0x20) => 0

Process 18948 starting at 00000000004014E0 with command line: "child.exe"

C:\Users\klosh\Desktop\OS3\build\child.exe

Loaded DLL at 00007FFD423F0000 ntdll.dll

NtOpenFile(FileHandle=0x61f398 [0x5c], DesiredAccess=SYNCHRONIZE|0x20,

ObjectAttributes="\??\C:\Users\klosh\Desktop\NtTrace-main\NtTrace-main\", IoStatusBlock=0x61f308 [0/1],

ShareAccess=3, OpenOptions=0x21) => 0

Loaded DLL at 00007FFD40C40000 C:\WINDOWS\System32\KERNEL32.DLL

NtMapViewOfSection(SectionHandle=0x60, ProcessHandle=-1, BaseAddress=0x744af0 [0x00007ffd40c40000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x744a48 [0x000c4000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

Loaded DLL at 00007FFD3F6F0000 C:\WINDOWS\System32\KERNELBASE.dll

NtMapViewOfSection(SectionHandle=0x64, ProcessHandle=-1, BaseAddress=0x745230 [0x00007ffd3f6f0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x745188 [0x003b9000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtCreateSection(SectionHandle=0x61e900 [0x64],

DesiredAccess=DELETE|READ_CONTROL|WRITE_DAC|WRITE_OWNER|0x1f, ObjectAttributes=null,

SectionSize=0x61e8f0 [65536], Protect=4, Attributes=0x08000000, FileHandle=0) => 0

NtMapViewOfSection(SectionHandle=0x60, ProcessHandle=-1, BaseAddress=0x61e8f8 [0x00007ff4fdec0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x61e908 [0x00100000], InheritDisposition=2

[ViewUnmap], AllocationType=0x00500000, Protect=2) => 0

NtMapViewOfSection(SectionHandle=0x94, ProcessHandle=-1, BaseAddress=0x61e890 [0x001d0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x61e8a0 [0x3000], InheritDisposition=2

[ViewUnmap], AllocationType=0, Protect=2) => 0

NtMapViewOfSection(SectionHandle=0x98, ProcessHandle=-1, BaseAddress=0x61e890 [0x001e0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x61e8a0 [0x3000], InheritDisposition=2

[ViewUnmap], AllocationType=0, Protect=2) => 0

NtMapViewOfSection(SectionHandle=0x9c, ProcessHandle=-1, BaseAddress=0x61e890 [0x001f0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x61e8a0 [0x1000], InheritDisposition=2

[ViewUnmap], AllocationType=0, Protect=2) => 0

Loaded DLL at 00007FFD409C0000 C:\WINDOWS\System32\msvcrt.dll

NtMapViewOfSection(SectionHandle=0xb4, ProcessHandle=-1, BaseAddress=0x747e50 [0x00007ffd409c0000],

ZeroBits=0, CommitSize=0, SectionOffset=null, ViewSize=0x744fe8 [0x000a7000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

Initial breakpoint

NtMapViewOfSection(SectionHandle=0x60, ProcessHandle=-1, BaseAddress=0x61fa18 [0x00620000],

ZeroBits=0, CommitSize=0, SectionOffset=0x61fa10 [0], ViewSize=0x61fa20 [0x1000], InheritDisposition=1

[ViewShare], AllocationType=0, Protect=4) => 0

Этот вызов отображает ту же секцию в адресное пространство дочернего процесса

NtUnmapViewOfSectionEx(ProcessHandle=-1, BaseAddress=0x620000, Flags=0) => 0

Process 18948 exit code: 0

дочерний процесс удаляет отображение секции из своего адресного пространства

Result from child process: Sum: 53.20

NtUnmapViewOfSectionEx(ProcessHandle=-1, BaseAddress=0x620000, Flags=0) => 0

Process 11108 exit code: 0

Лабораторная работа №4.

Program1

PS C:\Users\klosh\Desktop\NtTrace-main\NtTrace-main> .\NtTrace -v -pre -filter NtMapViewOfSection,NtUnmapViewOfSection,NtOpenFile,NtCreateFile,NtReadFi

le

Process 2704 starting at 00007FF60E3613F0 with command line:

"C:\Users\klosh\Desktop\OS4\TestProgram1.exe"

C:\Users\klosh\Desktop\OS4\TestProgram1.exe

Loaded DLL at 00007FF9624F0000 ntdll.dll

Instrumenting NtCreateFile at: 00007FF962590C60, ssn: 0x55

Instrumenting NtOpenFile at: 00007FF962590820, ssn: 0x33

Instrumenting NtReadFile at: 00007FF962590280, ssn: 0x6

Instrumenting NtReadFileScatter at: 00007FF962590780, ssn: 0x2e

Instrumenting NtMapViewOfSection at: 00007FF9625906C0, ssn: 0x28

Instrumenting NtMapViewOfSectionEx at: 00007FF962592530, ssn: 0x11c

Instrumenting NtUnmapViewOfSection at: 00007FF962590700, ssn: 0x2a

Instrumenting NtUnmapViewOfSectionEx at: 00007FF962593D30, ssn: 0x1dc

NtOpenFile(FileHandle=0x82751ff378, DesiredAccess=SYNCHRONIZE|0x20,

ObjectAttributes="\??\C:\Users\klosh\Desktop\NtTrace-main\",

IoStatusBlock=0x82751ff2e8, ShareAccess=3, OpenOptions=0x21) ...

NtOpenFile(FileHandle=0x82751ff378 [0x54],

DesiredAccess=SYNCHRONIZE|0x20,

ObjectAttributes="\??\C:\Users\klosh\Desktop\NtTrace-main\\",

IoStatusBlock=0x82751ff2e8 [0/1], ShareAccess=3, OpenOptions=0x21) => 0

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1,

BaseAddress=0x22debc149f0 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x22debc14948 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF9618F0000 C:\WINDOWS\System32\KERNEL32.DLL

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1,

BaseAddress=0x22debc149f0 [0x00007ff9618f0000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x22debc14948 [0x000c4000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtMapViewOfSection(SectionHandle=0x68, ProcessHandle=-1,

BaseAddress=0x22debc15130 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x22debc15088 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF95FBE0000 C:\WINDOWS\System32\KERNELBASE.dll

NtMapViewOfSection(SectionHandle=0x68, ProcessHandle=-1,

BaseAddress=0x22debc15130 [0x00007ff95fbe0000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x22debc15088 [0x003b9000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1,

BaseAddress=0x82751fe8d8 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x82751fe8e8 [0], InheritDisposition=2 [ViewUnmap],

AllocationType=0x00500000, Protect=2) ...

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1,

BaseAddress=0x82751fe8d8 [0x00007ff448ca0000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x82751fe8e8 [0x00100000], InheritDisposition=2

[ViewUnmap], AllocationType=0x00500000, Protect=2) => 0

NtCreateFile(FileHandle=0x82751feb08,

DesiredAccess=READ CONTROL|SYNCHRONIZE|0x19f,

ObjectAttributes=4:"\Connect", IoStatusBlock=0x82751fe4c0, AllocationSize=null,

FileAttributes=0, ShareAccess=7, CreateDisposition=2, CreateOptions=0x20,

EaBuffer=0x22debc165d0, EaLength=0x54b) ...

NtCreateFile(FileHandle=0x82751feb08 [0x58],

DesiredAccess=READ CONTROL|SYNCHRONIZE|0x19f,

ObjectAttributes=4:"\Connect", IoStatusBlock=0x82751fe4c0 [0/0x18],

```
AllocationSize=null, FileAttributes=0, ShareAccess=7, CreateDisposition=2,
    CreateOptions=0x20, EaBuffer=0x22debc165d0, EaLength=0x54b) => 0
    NtMapViewOfSection(SectionHandle=0x94, ProcessHandle=-1,
    BaseAddress=0x82751fe870 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
    ViewSize=0x82751fe880 [0], InheritDisposition=2 [ViewUnmap],
AllocationType=0,
    Protect=2) ...
    NtMapViewOfSection(SectionHandle=0x94, ProcessHandle=-1,
    BaseAddress=0x82751fe870 [0x0000022debde0000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x82751fe880 [0x3000], InheritDisposition=2
    [ViewUnmap], AllocationType=0, Protect=2) => 0
    NtMapViewOfSection(SectionHandle=0x98, ProcessHandle=-1,
    BaseAddress=0x82751fe870 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
    ViewSize=0x82751fe880 [0], InheritDisposition=2 [ViewUnmap],
AllocationType=0,
    Protect=2) ...
    NtMapViewOfSection(SectionHandle=0x98, ProcessHandle=-1,
    BaseAddress=0x82751fe870 [0x0000022debdf0000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x82751fe880 [0x3000], InheritDisposition=2
    [ViewUnmap], AllocationType=0, Protect=2) => 0
    NtMapViewOfSection(SectionHandle=0x9c, ProcessHandle=-1,
    BaseAddress=0x82751fe870 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
    ViewSize=0x82751fe880 [0], InheritDisposition=2 [ViewUnmap],
AllocationType=0,
    Protect=2) ...
    NtMapViewOfSection(SectionHandle=0x9c, ProcessHandle=-1,
    BaseAddress=0x82751fe870 [0x0000022debe00000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x82751fe880 [0x1000], InheritDisposition=2
    [ViewUnmap], AllocationType=0, Protect=2) => 0
    NtMapViewOfSection(SectionHandle=0xb4, ProcessHandle=-1,
    BaseAddress=0x22debc14da0 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
```

ViewSize=0x22debc14cd8 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF95FFA0000 C:\WINDOWS\System32\ucrtbase.dll

NtMapViewOfSection(SectionHandle=0xb4, ProcessHandle=-1,

BaseAddress=0x22debc14da0 [0x00007ff95ffa0000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x22debc14cd8 [0x00111000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtOpenFile(FileHandle=0x82751fefe0, DesiredAccess=SYNCHRONIZE|0x21,

ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libGCF_Euclid.dll",

IoStatusBlock=0x82751ff048, ShareAccess=5, OpenOptions=0x60) ...

NtOpenFile(FileHandle=0x82751fefe0 [0x68],

DesiredAccess=SYNCHRONIZE|0x21,

ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libGCF_Euclid.dll",

IoStatusBlock=0x82751ff048 [0/1], ShareAccess=5, OpenOptions=0x60) => 0

NtMapViewOfSection(SectionHandle=0xb8, ProcessHandle=-1,

BaseAddress=0x22debc18220 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x22debc18178 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF93DC00000

C:\Users\klosh\Desktop\OS4\libGCF_Euclid.dll

NtMapViewOfSection(SectionHandle=0xb8, ProcessHandle=-1,

BaseAddress=0x22debc18220 [0x00007ff93dc00000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x22debc18178 [0x00015000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtOpenFile(FileHandle=0x82751fefe0, DesiredAccess=SYNCHRONIZE|0x21,

ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libPi_Leibniz.dll",

IoStatusBlock=0x82751ff048, ShareAccess=5, OpenOptions=0x60) ...

NtOpenFile(FileHandle=0x82751fefe0 [0x68],

DesiredAccess=SYNCHRONIZE|0x21,

```
ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libPi_Leibniz.dll",
```

IoStatusBlock=0x82751ff048 [0/1], ShareAccess=5, OpenOptions=0x60) => 0

NtMapViewOfSection(SectionHandle=0xb8, ProcessHandle=-1,

BaseAddress=0x22debc18530 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x22debc18488 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

NtMapViewOfSection(SectionHandle=0xb8, ProcessHandle=-1,

BaseAddress=0x22debc18530 [0x00007ff93bf20000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x22debc18488 [0x00015000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

Initial breakpoint

Enter the command (1 for GCF, 2 for Pi, 3 to exit): NtReadFile(FileHandle=0x5c,

Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x82751ff980,

Buffer=0x22debc1efe0, Length=0x1000, ByteOffset=null, Key=null) ...

1

NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,

IoStatusBlock=0x82751ff980 [0/3], Buffer=0x22debc1efe0, Length=0x1000,

ByteOffset=null, Key=null) => 0

Enter two numbers: NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null,

ApcContext=null, IoStatusBlock=0x82751ff980, Buffer=0x22debc1efe0,

Length=0x1000, ByteOffset=null, Key=null) ...

16 24

NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,

IoStatusBlock=0x82751ff980 [0/7], Buffer=0x22debc1efe0, Length=0x1000,

ByteOffset=null, Key=null) => 0

GCF (Euclid): 8

Enter the command (1 for GCF, 2 for Pi, 3 to exit): NtReadFile(FileHandle=0x5c,

Event=0, ApcRoutine=null, ApcContext=null, IoStatusBlock=0x82751ff980,

```
Buffer=0x22debc1efe0, Length=0x1000, ByteOffset=null, Key=null) ...
```

3

NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,

IoStatusBlock=0x82751ff980 [0/3], Buffer=0x22debc1efe0, Length=0x1000,

ByteOffset=null, Key=null) => 0

NtOpenFile(FileHandle=0x82751ff710, DesiredAccess=SYNCHRONIZE|0x21,

ObjectAttributes="\??\C:\WINDOWS\SYSTEM32\kernel.appcore.dll",

IoStatusBlock=0x82751ff778, ShareAccess=5, OpenOptions=0x60) ...

NtOpenFile(FileHandle=0x82751ff710 [0xb8],

DesiredAccess=SYNCHRONIZE|0x21,

ObjectAttributes="\??\C:\WINDOWS\SYSTEM32\kernel.appcore.dll",

IoStatusBlock=0x82751ff778 [0/1], ShareAccess=5, OpenOptions=0x60) => 0

NtMapViewOfSection(SectionHandle=0xbc, ProcessHandle=-1,

BaseAddress=0x22debc20190 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x22debc200b8 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF95E8E0000 C:\WINDOWS\SYSTEM32\kernel.appcore.dll

NtMapViewOfSection(SectionHandle=0xbc, ProcessHandle=-1,

BaseAddress=0x22debc20190 [0x00007ff95e8e0000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x22debc200b8 [0x00018000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtMapViewOfSection(SectionHandle=0xc0, ProcessHandle=-1,

BaseAddress=0x22debc20410 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x22debc20378 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF960210000 C:\WINDOWS\System32\msvcrt.dll

NtMapViewOfSection(SectionHandle=0xc0, ProcessHandle=-1,

BaseAddress=0x22debc20410 [0x00007ff960210000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x22debc20378 [0x000a7000], InheritDisposition=1

```
[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0
```

Process 2704 exit code: 0

Program2

C:\Users\klosh\Desktop\OS4\TestProgram2.exe

Loaded DLL at 00007FF9624F0000 ntdll.dll

Instrumenting NtCreateFile at: 00007FF962590C60, ssn: 0x55

Instrumenting NtOpenFile at: 00007FF962590820, ssn: 0x33

Instrumenting NtReadFile at: 00007FF962590280, ssn: 0x6

Instrumenting NtReadFileScatter at: 00007FF962590780, ssn: 0x2e

Instrumenting NtMapViewOfSection at: 00007FF9625906C0, ssn: 0x28

Instrumenting NtMapViewOfSectionEx at: 00007FF962592530, ssn: 0x11c

Instrumenting NtUnmapViewOfSection at: 00007FF962590700, ssn: 0x2a

Instrumenting NtUnmapViewOfSectionEx at: 00007FF962593D30, ssn: 0x1dc

NtOpenFile(FileHandle=0x2841bff188, DesiredAccess=SYNCHRONIZE|0x20,

ObjectAttributes="\??\C:\Users\klosh\Desktop\NtTrace-main\NtTrace-main\",

IoStatusBlock=0x2841bff0f8, ShareAccess=3, OpenOptions=0x21) ...

NtOpenFile(FileHandle=0x2841bff188 [0x54], DesiredAccess=SYNCHRONIZE|0x20,

ObjectAttributes="\??\C:\Users\klosh\Desktop\NtTrace-main\\",

IoStatusBlock=0x2841bff0f8 [0/1], ShareAccess=3, OpenOptions=0x21) => 0

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1,

BaseAddress=0x208d16b49f0 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x208d16b4948 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF9618F0000 C:\WINDOWS\System32\KERNEL32.DLL

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1,

BaseAddress=0x208d16b49f0 [0x00007ff9618f0000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x208d16b4948 [0x000c4000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtMapViewOfSection(SectionHandle=0x68, ProcessHandle=-1,

BaseAddress=0x208d16b5130 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x208d16b5088 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF95FBE0000 C:\WINDOWS\System32\KERNELBASE.dll

NtMapViewOfSection(SectionHandle=0x68, ProcessHandle=-1,

BaseAddress=0x208d16b5130 [0x00007ff95fbe0000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x208d16b5088 [0x003b9000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1,

BaseAddress=0x2841bfe6e8 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x2841bfe6f8 [0], InheritDisposition=2 [ViewUnmap],

AllocationType=0x00500000, Protect=2) ...

NtMapViewOfSection(SectionHandle=0x58, ProcessHandle=-1,

BaseAddress=0x2841bfe6e8 [0x00007ff48ed60000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x2841bfe6f8 [0x00100000], InheritDisposition=2

[ViewUnmap], AllocationType=0x00500000, Protect=2) => 0

NtCreateFile(FileHandle=0x2841bfe918,

DesiredAccess=READ CONTROL|SYNCHRONIZE|0x19f,

ObjectAttributes=4:"\Connect", IoStatusBlock=0x2841bfe2d0, AllocationSize=null,

FileAttributes=0, ShareAccess=7, CreateDisposition=2, CreateOptions=0x20,

EaBuffer=0x208d16b65d0, EaLength=0x54b) ...

NtCreateFile(FileHandle=0x2841bfe918 [0x58],

DesiredAccess=READ_CONTROL|SYNCHRONIZE|0x19f,

ObjectAttributes=4:"\Connect", IoStatusBlock=0x2841bfe2d0 [0/0x18],

AllocationSize=null, FileAttributes=0, ShareAccess=7, CreateDisposition=2,

CreateOptions=0x20, EaBuffer=0x208d16b65d0, EaLength=0x54b) => 0

NtMapViewOfSection(SectionHandle=0x90, ProcessHandle=-1,

BaseAddress=0x2841bfe680 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x2841bfe690 [0], InheritDisposition=2 [ViewUnmap], AllocationType=0,

```
Protect=2) ...
    NtMapViewOfSection(SectionHandle=0x90, ProcessHandle=-1,
    BaseAddress=0x2841bfe680 [0x00000208d1640000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x2841bfe690 [0x3000], InheritDisposition=2
    [ViewUnmap], AllocationType=0, Protect=2) => 0
    NtMapViewOfSection(SectionHandle=0x94, ProcessHandle=-1,
    BaseAddress=0x2841bfe680 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
    ViewSize=0x2841bfe690 [0], InheritDisposition=2 [ViewUnmap],
AllocationType=0,
    Protect=2) ...
    NtMapViewOfSection(SectionHandle=0x94, ProcessHandle=-1,
    BaseAddress=0x2841bfe680 [0x00000208d1650000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x2841bfe690 [0x3000], InheritDisposition=2
    [ViewUnmap], AllocationType=0, Protect=2) => 0
    NtMapViewOfSection(SectionHandle=0x98, ProcessHandle=-1,
    BaseAddress=0x2841bfe680 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
    ViewSize=0x2841bfe690 [0], InheritDisposition=2 [ViewUnmap],
AllocationType=0,
    Protect=2) ...
    NtMapViewOfSection(SectionHandle=0x98, ProcessHandle=-1,
    BaseAddress=0x2841bfe680 [0x00000208d1660000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x2841bfe690 [0x1000], InheritDisposition=2
    [ViewUnmap], AllocationType=0, Protect=2) => 0
    NtMapViewOfSection(SectionHandle=0xb0, ProcessHandle=-1,
    BaseAddress=0x208d16b4da0 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
```

ViewSize=0x208d16b4cd8 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF95FFA0000 C:\WINDOWS\System32\ucrtbase.dll

NtMapViewOfSection(SectionHandle=0xb0, ProcessHandle=-1,

BaseAddress=0x208d16b4da0 [0x00007ff95ffa0000], ZeroBits=0, CommitSize=0,

```
SectionOffset=null, ViewSize=0x208d16b4cd8 [0x00111000], InheritDisposition=1
    [ViewShare], AllocationType=0x00800000, Protect=0x80) => 0
    Initial breakpoint
    NtOpenFile(FileHandle=0x2841bff430, DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libGCF Euclid.dll",
    IoStatusBlock=0x2841bff498, ShareAccess=5, OpenOptions=0x60) ...
    NtOpenFile(FileHandle=0x2841bff430 [0xb8],
DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libGCF_Euclid.dll",
    IoStatusBlock=0x2841bff498 [0/1], ShareAccess=5, OpenOptions=0x60) => 0
    NtMapViewOfSection(SectionHandle=0xbc, ProcessHandle=-1,
    BaseAddress=0x208d16bcfd0 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
    ViewSize=0x208d16bbe98 [0], InheritDisposition=1 [ViewShare],
    AllocationType=0x00800000, Protect=0x80) ...
    Loaded DLL at 00007FF93AC40000
C:\Users\klosh\Desktop\OS4\libGCF_Euclid.dll
    NtMapViewOfSection(SectionHandle=0xbc, ProcessHandle=-1,
    BaseAddress=0x208d16bcfd0 [0x00007ff93ac40000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x208d16bbe98 [0x00015000], InheritDisposition=1
    [ViewShare], AllocationType=0x00800000, Protect=0x80) => 0
    NtOpenFile(FileHandle=0x2841bff430, DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libPi_Leibniz.dll",
    IoStatusBlock=0x2841bff498, ShareAccess=5, OpenOptions=0x60) ...
    NtOpenFile(FileHandle=0x2841bff430 [0xc0],
DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libPi_Leibniz.dll",
    IoStatusBlock=0x2841bff498 [0/1], ShareAccess=5, OpenOptions=0x60) => 0
    NtMapViewOfSection(SectionHandle=0xb8, ProcessHandle=-1,
    BaseAddress=0x208d16bd270 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
    ViewSize=0x208d16bbe98 [0], InheritDisposition=1 [ViewShare],
    AllocationType=0x00800000, Protect=0x80) ...
```

```
Loaded DLL at 00007FF939380000 C:\Users\klosh\Desktop\OS4\libPi Leibniz.dll
    NtMapViewOfSection(SectionHandle=0xb8, ProcessHandle=-1,
    BaseAddress=0x208d16bd270 [0x00007ff939380000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x208d16bbe98 [0x00015000], InheritDisposition=1
    [ViewShare], AllocationType=0x00800000, Protect=0x80) => 0
    Enter the command (0 to switch libraries, 1 for GCF, 2 for Pi, 3 to exit):
    NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,
    IoStatusBlock=0x2841bff770, Buffer=0x208d16befc0, Length=0x1000,
ByteOffset=null,
    Key=null) ...
    1
    NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,
    IoStatusBlock=0x2841bff770 [0/3], Buffer=0x208d16befc0, Length=0x1000,
    ByteOffset=null, Key=null) \Rightarrow 0
    Enter two numbers: NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null,
    ApcContext=null, IoStatusBlock=0x2841bff770, Buffer=0x208d16befc0,
    Length=0x1000, ByteOffset=null, Key=null) ...
    69
    NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,
    IoStatusBlock=0x2841bff770 [0/5], Buffer=0x208d16befc0, Length=0x1000,
    ByteOffset=null, Key=null) => 0
    GCF: 3
    Enter the command (0 to switch libraries, 1 for GCF, 2 for Pi, 3 to exit):
    NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,
    IoStatusBlock=0x2841bff770, Buffer=0x208d16befc0, Length=0x1000,
ByteOffset=null,
    Key=null) ...
    0
    NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,
```

IoStatusBlock=0x2841bff770 [0/3], Buffer=0x208d16befc0, Length=0x1000,

```
ByteOffset=null, Key=null) => 0
    NtUnmapViewOfSection(ProcessHandle=-1, BaseAddress=0x7ff93ac40000) ...
    Unload of DLL at 00007FF93AC40000
    NtUnmapViewOfSection(ProcessHandle=-1, BaseAddress=0x7ff93ac40000) => 0
    NtUnmapViewOfSection(ProcessHandle=-1, BaseAddress=0x7ff939380000) ...
    Unload of DLL at 00007FF939380000
    NtUnmapViewOfSection(ProcessHandle=-1, BaseAddress=0x7ff939380000) => 0
    NtOpenFile(FileHandle=0x2841bff470, DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libGCF_Naive.dll",
    IoStatusBlock=0x2841bff4d8, ShareAccess=5, OpenOptions=0x60) ...
    NtOpenFile(FileHandle=0x2841bff470 [0xc4],
DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libGCF_Naive.dll",
    IoStatusBlock=0x2841bff4d8 [0/1], ShareAccess=5, OpenOptions=0x60) => 0
    NtMapViewOfSection(SectionHandle=0xc0, ProcessHandle=-1,
    BaseAddress=0x208d16c1a50 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
    ViewSize=0x208d16bbe98 [0], InheritDisposition=1 [ViewShare],
    AllocationType=0x00800000, Protect=0x80) ...
    Loaded DLL at 00007FF93BF20000 C:\Users\klosh\Desktop\OS4\libGCF_Naive.dll
    NtMapViewOfSection(SectionHandle=0xc0, ProcessHandle=-1,
    BaseAddress=0x208d16c1a50 [0x00007ff93bf20000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x208d16bbe98 [0x00015000], InheritDisposition=1
    [ViewShare], AllocationType=0x00800000, Protect=0x80) => 0
    NtOpenFile(FileHandle=0x2841bff470, DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libPi_Wallis.dll",
    IoStatusBlock=0x2841bff4d8, ShareAccess=5, OpenOptions=0x60) ...
    NtOpenFile(FileHandle=0x2841bff470 [0xc4],
DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\Users\klosh\Desktop\OS4\libPi_Wallis.dll",
    IoStatusBlock=0x2841bff4d8 [0/1], ShareAccess=5, OpenOptions=0x60) => 0
```

```
NtMapViewOfSection(SectionHandle=0xc0, ProcessHandle=-1,
```

BaseAddress=0x208d16c1d40 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x208d16bbe98 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

NtMapViewOfSection(SectionHandle=0xc0, ProcessHandle=-1,

BaseAddress=0x208d16c1d40 [0x00007ff93ba20000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x208d16bbe98 [0x00015000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

Switched to another library.

Enter the command (0 to switch libraries, 1 for GCF, 2 for Pi, 3 to exit):

NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,

IoStatusBlock=0x2841bff770, Buffer=0x208d16befc0, Length=0x1000, ByteOffset=null,

Key=null) ...

1

NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,

IoStatusBlock=0x2841bff770 [0/3], Buffer=0x208d16befc0, Length=0x1000,

ByteOffset=null, Key=null) => 0

Enter two numbers: NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null,

ApcContext=null, IoStatusBlock=0x2841bff770, Buffer=0x208d16befc0,

Length=0x1000, ByteOffset=null, Key=null) ...

69

NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,

IoStatusBlock=0x2841bff770 [0/5], Buffer=0x208d16befc0, Length=0x1000,

ByteOffset=null, Key=null) => 0

GCF: 3

Enter the command (0 to switch libraries, 1 for GCF, 2 for Pi, 3 to exit):

NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,

```
IoStatusBlock=0x2841bff770, Buffer=0x208d16befc0, Length=0x1000,
ByteOffset=null,
    Key=null) ...
    3
    NtReadFile(FileHandle=0x5c, Event=0, ApcRoutine=null, ApcContext=null,
    IoStatusBlock=0x2841bff770 [0/3], Buffer=0x208d16befc0, Length=0x1000,
    ByteOffset=null, Key=null) \Rightarrow 0
    NtUnmapViewOfSection(ProcessHandle=-1, BaseAddress=0x7ff93bf20000) ...
    Unload of DLL at 00007FF93BF20000
    NtUnmapViewOfSection(ProcessHandle=-1, BaseAddress=0x7ff93bf20000) => 0
    NtUnmapViewOfSection(ProcessHandle=-1, BaseAddress=0x7ff93ba20000) ...
    Unload of DLL at 00007FF93BA20000
    NtUnmapViewOfSection(ProcessHandle=-1, BaseAddress=0x7ff93ba20000) => 0
    NtOpenFile(FileHandle=0x2841bff520, DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\WINDOWS\SYSTEM32\kernel.appcore.dll",
    IoStatusBlock=0x2841bff588, ShareAccess=5, OpenOptions=0x60) ...
    NtOpenFile(FileHandle=0x2841bff520 [0xc4],
DesiredAccess=SYNCHRONIZE|0x21,
    ObjectAttributes="\??\C:\WINDOWS\SYSTEM32\kernel.appcore.dll",
    IoStatusBlock=0x2841bff588 [0/1], ShareAccess=5, OpenOptions=0x60) => 0
    NtMapViewOfSection(SectionHandle=0xb8, ProcessHandle=-1,
    BaseAddress=0x208d16bbcf0 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,
    ViewSize=0x208d16c1ac8 [0], InheritDisposition=1 [ViewShare],
    AllocationType=0x00800000, Protect=0x80) ...
    Loaded DLL at 00007FF95E8E0000 C:\WINDOWS\SYSTEM32\kernel.appcore.dll
    NtMapViewOfSection(SectionHandle=0xb8, ProcessHandle=-1,
    BaseAddress=0x208d16bbcf0 [0x00007ff95e8e0000], ZeroBits=0, CommitSize=0,
    SectionOffset=null, ViewSize=0x208d16c1ac8 [0x00018000], InheritDisposition=1
    [ViewShare], AllocationType=0x00800000, Protect=0x80) => 0
    NtMapViewOfSection(SectionHandle=0xc0, ProcessHandle=-1,
```

BaseAddress=0x208d16c1d20 [0], ZeroBits=0, CommitSize=0, SectionOffset=null,

ViewSize=0x208d16c1c88 [0], InheritDisposition=1 [ViewShare],

AllocationType=0x00800000, Protect=0x80) ...

Loaded DLL at 00007FF960210000 C:\WINDOWS\System32\msvcrt.dll

NtMapViewOfSection(SectionHandle=0xc0, ProcessHandle=-1,

BaseAddress=0x208d16c1d20 [0x00007ff960210000], ZeroBits=0, CommitSize=0,

SectionOffset=null, ViewSize=0x208d16c1c88 [0x000a7000], InheritDisposition=1

[ViewShare], AllocationType=0x00800000, Protect=0x80) => 0

Process 18472 exit code: 0

Лабораторная работа №5-7.

```
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 \text{ read}(0, 0x5594100\text{ca}480, 1024) = ? \text{ ERESTARTSYS} \text{ (To be restarted if SA RESTART is set)}
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 \text{ read}(0, 0x5594100\text{ca}480, 1024) = ? \text{ ERESTARTSYS} \text{ (To be restarted if SA RESTART is set)}
73024 --- SIGWINCH {si signo=SIGWINCH, si code=SI KERNEL} ---
73024 \text{ read}(0, 0x5594100ca480, 1024) = ? \text{ ERESTARTSYS} \text{ (To be restarted if SA_RESTART is set)}
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si signo=SIGWINCH, si code=SI KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si signo=SIGWINCH, si code=SI KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si signo=SIGWINCH, si code=SI KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
```

73024 --- SIGWINCH {si signo=SIGWINCH, si code=SI KERNEL} ---

```
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 \text{ read}(0, 0x5594100\text{ca}480, 1024) = ? \text{ ERESTARTSYS} \text{ (To be restarted if SA RESTART is set)}
73024 --- SIGWINCH {si signo=SIGWINCH, si code=SI KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si signo=SIGWINCH, si code=SI KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 \text{ read}(0, 0x5594100\text{ca}480, 1024) = ? \text{ ERESTARTSYS} \text{ (To be restarted if SA RESTART is set)}
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si signo=SIGWINCH, si code=SI KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 \text{ read}(0, 0x5594100ca480, 1024) = ? \text{ ERESTARTSYS} \text{ (To be restarted if SA_RESTART is set)}
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 \text{ read}(0, 0x5594100ca480, 1024) = ? \text{ ERESTARTSYS} \text{ (To be restarted if SA_RESTART is set)}
73024 --- SIGWINCH {si signo=SIGWINCH, si code=SI KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 \text{ read}(0, 0x5594100ca480, 1024) = ? \text{ ERESTARTSYS} \text{ (To be restarted if SA_RESTART is set)}
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
```

```
73024 read(0, 0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)
73024 --- SIGWINCH {si_signo=SIGWINCH, si_code=SI_KERNEL} ---
73024 \text{ read}(0, "create 10 - 1 \ n", 1024) = 13
73024 socket(AF NETLINK, SOCK RAW|SOCK CLOEXEC, NETLINK ROUTE) = 10
73024 bind(10, {sa_family=AF_NETLINK, nl_pid=0, nl_groups=00000000}, 12) = 0
73024 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 10
73024 bind(10, \{\text{sa\_family=AF\_INET}, \text{sin\_port=htons}(4050), \text{sin\_addr=inet\_addr}("127.0.0.1")\}, 16\} = 0
73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73024 write(9, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73026 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8
73102 \text{ read}(3, "177ELF(2)11(3)0)0(0)0(0)0(0)0(3)0>(0)1(0)0(0)0(0)0(0)0(0)0(0)"..., 832) = 832
73102 \text{ read}(3, "177ELF(2)11(3)0)0(0)0(0)0(0)0(3)0>(0)1(0)0(0)0(0)0(0)0(0)0(0)"..., 832) = 832
73102 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73102 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73105 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
73105 connect(9, {sa_family=AF_INET, sin_port=htons(4050), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73026 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73105 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73026 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73105 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73105 write(8, "1\0\0\0\0\0\0", 8 <unfinished ...>
73026 write(9, "1\0\0\0\0\0\0", 8 <unfinished ...>
73105 <... write resumed>)
                             = 8
```

```
73026 < \dots \text{ write resumed} > ) = 8
```

73102 read(8, <unfinished ...>

$$73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$$

 $73102 < ... \text{ read resumed} > "\1\0\0\0\0\0\0, 8) = 8$

$$73024 \text{ write}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$$73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$$73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$$73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$$

$$73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$$

$$73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$$73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$$

$$73024 \text{ write}(1, "Ok: 73102\n", 10) = 10$$

73024 read(0, <unfinished ...>

$$73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$73024 < \dots \text{ read resumed} > \text{"create } 20 \ 10 \ \text{n"}, \ 1024) = 13$

$$73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

73105 write(8, "
$$1\0\0\0\0\0\0\$$
, 8) = 8

$$73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$$

$$73102 \text{ write}(6, "\1\0\0\0\0\0\0, 8) = 8$$

```
73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8
73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73105 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73102 socket(AF NETLINK, SOCK RAW|SOCK CLOEXEC, NETLINK ROUTE) = 11
73102 bind(11, {sa_family=AF_NETLINK, nl_pid=0, nl_groups=00000000}, 12) = 0
73102 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 11
73102 bind(11, {sa family=AF INET, sin port=htons(4060), sin addr=inet addr("127.0.0.1")}, 16) = 0
73102 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73102 write(10, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73102 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8
73202 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73202 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73202 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73204 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
73204 connect(9, {sa_family=AF_INET, sin_port=htons(4060), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73105 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73204 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73105 write(10, "\1\0\0\0\0\0\0\0\0\", 8) = 8
```

- $73102 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8$
- 73204 write(8, "\ $1\0\0\0\0\0\0$ ", 8) = 8
- $73202 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, " $1\0\0\0\0\0\0$ ", 8 <unfinished ...>
- 73202 write(6, "\1\0\0\0\0\0\0\0\0", 8 < unfinished ...>
- 73102 <... write resumed>) = 8
- $73202 < \dots \text{ write resumed} >$ = 8
- 73204 read(6, " $1\0\0\0\0\0\0\$, 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(10, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8$
- 73204 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73202 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73202 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73204 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73202 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(10, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73024 \text{ write}(1, "Ok: 73202\n", 10) = 10$
- $73024 \text{ read}(0, "create 30 10\n", 1024) = 13$
- $73024 \text{ write}(6, "\1\0\0\0\0\0\0, 8) = 8$
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73102 read(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8

```
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73026 write(9, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8
73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73102 socket(AF_NETLINK, SOCK_RAW|SOCK_CLOEXEC, NETLINK_ROUTE) = 14
73102 bind(14, {sa family=AF NETLINK, nl pid=0, nl groups=00000000}, 12) = 0
73102 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 14
73102 bind(14, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = 0
73102 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73102 write(13, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8
73235 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73235 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73237 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73235 read(8, <unfinished ...>
73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP <unfinished ...>
73235 < ... \text{ read resumed} > "\1\0\0\0\0\0\0\0, 8) = 8
73237 <... socket resumed>)
                          =9
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73105 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
```

- 73237 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73237 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73235 read(8, <unfinished ...>
- 73105 write(13, " $1\0\0\0\0\0\0$ ", 8 <unfinished ...>
- $73235 < ... \text{ read resumed} > "\1\0\0\0\0\0\0\0\, 8) = 8$
- $73105 < \dots \text{ write resumed} >$ = 8
- 73235 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0,0, 8) = 8$
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(13, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73102 read(13, <unfinished ...>
- 73237 write(8, " $1\0\0\0\0\0\0$ ", 8 <unfinished ...>
- $73102 < ... \text{ read resumed} > "\1\0\0\0\0\0\0\0, 8) = 8$
- $73237 < \dots$ write resumed>) = 8
- $73235 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73235 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73237 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73235 read(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73105 write(13, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73105 read(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- 73024 write(1, "Ok: $73235\n$ ", 10) = 10

```
73024 \text{ read}(0, "create 40 20\n", 1024) = 13
73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73105 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8
73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73102 read(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73204 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73202 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73202 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73204 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73105 write(10, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73102 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8
73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73204 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73202 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73202 socket(AF_NETLINK, SOCK_RAW|SOCK_CLOEXEC, NETLINK_ROUTE) = 11
73202 bind(11, {sa_family=AF_NETLINK, nl_pid=0, nl_groups=00000000}, 12) = 0
73202 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 11
73202 bind(11, {sa_family=AF_INET, sin_port=htons(4080), sin_addr=inet_addr("127.0.0.1")}, 16) = 0
73202 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
```

```
73202 write(10, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73204 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73202 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8
73268 \text{ read}(3, "177ELF(2)11(3)0)0(0)0(0)0(0)0(3)0>(0)1(0)0(0)0(0)0(0)0(0)0(0)"..., 832) = 832
73268 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73268 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73270 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73268 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73270 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
73270 connect(9, {sa_family=AF_INET, sin_port=htons(4080), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73204 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73204 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73270 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73270 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73204 write(10, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73202 read(10, <unfinished ...>
73270 write(8, "\1\0\0\0\0\0\0\0", 8 < unfinished ...>
73202 < ... \text{ read resumed} > "\1\0\0\0\0\0\0, 8) = 8
73270 <... write resumed>)
                            =8
73268 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73202 write(6, "1\0\0\0\0\0\0", 8 <unfinished ...>
73268 write(6, "\1\0\0\0\0\0\0\0\", 8 < unfinished ...>
73202 <... write resumed>)
                            = 8
73268 <... write resumed>)
                            =8
73270 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
```

- $73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73204 write(10, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73202 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8$
- 73270 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73268 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73268 write(6, "\1\0\0\0\0\0\0\0\", 8) = 8
- 73270 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73270 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73268 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73204 write(10, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73202 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8$
- 73202 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(10, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- $73024 \text{ write}(1, "Ok: 73268\n", 10) = 10$
- $73024 \text{ read}(0, "remove 20\n", 1024) = 10$
- 73024 write(6, " $1\0\0\0\0\0\0\$ ", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8

```
73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
```

$$73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$$

$$73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

73202 write(6, "
$$1\0\0\0\0\0\0\$$
, 8) = 8

$$73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$$73102 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8$$

$$73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$$73202 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$$

73202 write(1, "[WORKER] Removing node 20...\n", 29) = 29

Узел 20 удаляется из системы.

Используется в remove() в node.h.

$$73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$$73268 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$$

73268 write(6, "
$$1\0\0\0\0\0\0\$$
, 8) = 8

73270 read(6, "
$$1\0\0\0\0\0\0\$$
, 8) = 8

$$73202 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8$$

$$73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$$73268 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$$

```
73268 write(1, "[WORKER] Removing node 40...\n", 29) = 29
73268 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73270 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73268 write(4, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73268 write(1, "[WORKER] Node 40 removed success"..., 39 <unfinished ...>
73270 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73268 <... write resumed>)
                                    = 39
73204 write(10, "\1\0\0\0\0\0\0\0\0", 8) = 8
73269 read(4, "\1\0\0\0\0\0\0\0\0", 8) = 8
73202 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8
73202 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73202 write(4, "\1\0\0\0\0\0\0\0\0", 8) = 8
73269 read(8, <unfinished ...>
73204 read(6, <unfinished ...>
73269 < ... \text{ read resumed} > "\1\0\0\0\0\0\0, 8) = 8
73204 < ... \text{ read resumed} > "\1\0\0\0\0\0\0, 8) = 8
73269 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73202 write(1, "[WORKER] Node 20 removed success"..., 39 <unfinished ...>
73203 read(4, "\1\0\0\0\0\0\0\0\0", 8) = 8
73202 <... write resumed>)
                                    = 39
73270 read(6, <unfinished ...>
73204 write(10, "1\0\0\0\0\0\0", 8 <unfinished ...>
73270 < ... \text{ read resumed} > "\1\0\0\0\0\0\0\0, 8) = 8
73204 <... write resumed>)
                                    =8
73270 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73204 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73105 write(10, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73269 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73102 read(10, <unfinished ...>
73203 write(6, "\1\0\0\0\0\0\0\0\", 8 < unfinished ...>
```

```
73102 <... read resumed>"\1\0\0\0\0\0\0\0\0\", 8) = 8
```

$$73203 < \dots \text{ write resumed} >) = 8$$

$$73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

$$73203 \text{ read}(10, "\1\0\0\0\0\0\0, 8) = 8$$

73203 write(6, "
$$1\0\0\0\0\0\0\$$
, 8) = 8

$$73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$$

73204 write(10, "
$$1\0\0\0\0\0\0$$
", 8

$$73203 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$$

$$73204 < ... \text{ write resumed} >$$
 = 8

$$73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$$

73203 read(10, <unfinished ...>

$$73024 < \dots \text{ write resumed} >$$
 = 3

73024 read(0, <unfinished ...>

73203 read(8, <unfinished ...>

$$73203 < ... \text{ read resumed} > "\1\0\0\0\0\0\0, 8) = 8$$

$$73105 < \dots \text{ read resumed} > "\1\0\0\0\0\0\0\0, 8) = 8$$

$$73203 \text{ read}(4, "\1\0\0\0\0\0\0, 8) = 8$$

```
73268 write(4, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73269 read(4, "\1\0\0\0\0\0\0\0\0", 8) = 8
73269 write(3, "\1\0\0\0\0\0\0\0\0", 8) = 8
73268 read(3, "\1\0\0\0\0\0\0\0\0", 8) = 8
73268 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73269 +++ exited with 0 +++
73270 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73202 write(4, "\1\0\0\0\0\0\0", 8 <unfinished ...>
73270 + ++  exited with 0 + ++
73202 <... write resumed>)
                                = 8
73203 read(4, "\1\0\0\0\0\0\0\0\0", 8) = 8
73203 write(3, "1\0\0\0\0\0\0", 8 <unfinished ...>
73268 +++ exited with 0 +++
73203 <... write resumed>)
                                      = 8
73202 --- SIGCHLD {si_signo=SIGCHLD, si_code=CLD_EXITED, si_pid=73268, si_uid=1000,
si_status=0, si_utime=0, si_stime=2} ---
73202 \text{ read}(3, "\1\0\0\0\0\0\0, 8) = 8
73202 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73203 +++ exited with 0 +++
73204 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73204 +++  exited with 0 +++
73202 +++  exited with 0 +++
73102 --- SIGCHLD {si_signo=SIGCHLD, si_code=CLD_EXITED, si_pid=73202, si_uid=1000,
si_status=0, si_utime=0, si_stime=4} ---
73024 < ... \text{ read resumed} > \text{"exec } 20 \text{ time} \setminus \text{n"}, 1024) = 13
73024 write(1, "Error: Not found\n", 17) = 17
73024 \text{ read}(0, \text{"exec } 40 \text{ time} \text{-n"}, 1024) = 13
73024 write(1, "Error: Not found\n", 17) = 17
73024 \text{ read}(0, \text{"exec } 10 \text{ start} \text{/n"}, 1024) = 14
73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
```

- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \operatorname{read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73105 read(6, "\1\0\0\0\0\0\0\0\", 8) = 8
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \operatorname{read}(9, "\1\0\0\0\0\0\0, 8) = 8$

- 73024 write(1, "Ok:10:timer started\n", 20) = 20
- $73024 \text{ read}(0, \text{"exec } 30 \text{ start} \setminus \text{n"}, 1024) = 14$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73026 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73237 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73235 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73235 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(13, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73237 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73235 read(8, " $1\0\0\0\0\0\0\$, 8) = 8
- 73235 write(6, "\1\0\0\0\0\0\0\0\", 8) = 8
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(13, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8$

- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73237 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73235 read(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73235 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73237 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73105 write(13, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73237 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73235 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73235 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$

- 73105 write(13, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 write(1, "Ok:30:timer started\n", 20) = 20
- $73024 \text{ read}(0, "\text{exec } 10 \text{ stop}\n", 1024) = 13$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \operatorname{read}(6, "\1\0\0\0\0\0\0, 8) = 8$

- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73026 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73102 read(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 write(1, "Ok:10:timer stopped at 11707 ms/n", 32) = 32
- $73024 \text{ read}(0, \text{"exec } 30 \text{ stop}\n", 1024) = 13$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73102 read(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73102 \text{ write}(6, "\1\0\0\0\0\0\0, 8) = 8$
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- $73102 \text{ write}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 read(6, " $1\0\0\0\0\0\0\$, 8) = 8
- 73237 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73235 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73235 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$

- 73105 write(13, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8$
- $73102 \text{ write}(6, "\1\0\0\0\0\0\0, 8) = 8$
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73237 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73235 read(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73235 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(13, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73026 read(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73237 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73235 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$

- 73235 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(13, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73237 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73235 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8$
- 73235 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73237 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(13, "\1\0\0\0\0\0\0\0\0", 8) = 8
- $73102 \text{ read}(13, "\1\0\0\0\0\0\0, 8) = 8$
- 73102 write(6, " $1\0\0\0\0\0\0\$, 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 write(1, "Ok:30:timer stopped at 13267 ms\n", 32) = 32
- $73024 \text{ read}(0, "\text{exec } 10 \text{ time}\n", 1024) = 13$
- 73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73102 read(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73102 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 read(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
- 73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8$
- 73105 write(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
- $73102 \operatorname{read}(8, "\1\0\0\0\0\0\0, 8) = 8$

```
73102 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8
73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73102 \text{ read}(8, "\1\0\0\0\0\0\0, 8) = 8
73102 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8
73024 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73026 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73105 write(8, "\1\0\0\0\0\0\0\0\0", 8) = 8
73102 read(8, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73102 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73105 \text{ read}(6, "\1\0\0\0\0\0\0, 8) = 8
73026 write(9, "\1\0\0\0\0\0\0\0\0", 8) = 8
73024 read(9, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73024 write(1, "Ok:10:elapsed 11707 ms\n", 23) = 23
73024 read(0, <unfinished ...>
73105 +++ killed by SIGKILL +++
73104 +++ killed by SIGKILL +++
73102 +++ killed by SIGKILL +++
73024 <... read resumed>0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is
set)
73024 --- SIGCHLD {si_signo=SIGCHLD, si_code=CLD_KILLED, si_pid=73102, si_uid=1000,
si_status=SIGKILL, si_utime=0, si_stime=8} ---
73024 read(0, <unfinished ...>
73237 write(6, "\1\0\0\0\0\0\0\0\0\", 8) = 8
```

```
73026 write(6, "\1\0\0\0\0\0\0\0\0", 8) = 8
73237 read(6, <unfinished ...>
73026 read(6, <unfinished ...>
73026 < ... \text{ read resumed} > "\1\0\0\0\0\0\0\0, 8) = 8
73026 write(9, "\1\0\0\0\0\0\0\0\0\", 8) = 8
73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1
EINPROGRESS (Operation now in progress)
```

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

EINPROGRESS (Operation now in progress)

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1

```
73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
```

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

```
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
```

- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

```
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
```

- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

```
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
```

- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

```
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
```

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73024 < ... read resumed > "exec 10 time / n", 1024) = 13

 $73024 \text{ read}(9, "\1\0\0\0\0\0\0, 8) = 8$

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

```
73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
```

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

```
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
```

73024 write(1, "Error: Node is unavailable \n ", 27) = 27

73024 read(0, <unfinished ...>

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

```
73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
```

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

```
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
```

- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
- 73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
- 73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

```
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
```

 $73024 < ... \text{ read resumed} > \text{"exec } 30 \text{ time} \ \text{"}, \ 1024) = 13$

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

```
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
```

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73024 write(1, "Error: Node is unavailable\n", 27) = 27

73024 read(0, <unfinished ...>

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

```
73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9
```

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

```
73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)
```

73237 socket(AF INET, SOCK STREAM|SOCK CLOEXEC, IPPROTO TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73237 socket(AF_INET, SOCK_STREAM|SOCK_CLOEXEC, IPPROTO_TCP) = 9

73237 connect(9, {sa_family=AF_INET, sin_port=htons(4070), sin_addr=inet_addr("127.0.0.1")}, 16) = -1 EINPROGRESS (Operation now in progress)

73024 <... read resumed>0x5594100ca480, 1024) = ? ERESTARTSYS (To be restarted if SA_RESTART is set)

73024 --- SIGINT {si_signo=SIGINT, si_code=SI_KERNEL} ---

73235 --- SIGINT {si_signo=SIGINT, si_code=SI_KERNEL} ---

73237 +++ killed by SIGINT +++

73236 +++ killed by SIGINT +++

73026 +++ killed by SIGINT +++

73025 +++ killed by SIGINT +++

73024 +++ killed by SIGINT +++

73235 +++ killed by SIGINT +++

Вывод

В процессе выполнения лабораторных работ по курсу операционных систем мне особенно понравилось использовать возможности утилит strace, NtTrace. Они поспособствовали более глубокому пониманию внутренней работы функций, применяемых при программировании, а также помогали в отладке, указывая на места возникновения ошибок. Благодаря множеству флагов и дополнительных функций эти утилиты являются мощным инструментом, знание которых крайне важно.