



Swing Trading Strategy for NIFTY 500 Using VWAP

Introduction

Swing trading in the Indian stock market involves holding positions for a few days to a few weeks to capture short-to-medium-term price swings. We will focus on **NIFTY 500** stocks (a broad index of large, mid, and small-cap equities) and a typical holding period of **1-2 weeks** per trade. A core tool in this strategy is the **Volume Weighted Average Price (VWAP)** indicator, which is often used by swing traders to improve decision-making during shorter holding periods ¹. VWAP incorporates both price and volume data, giving a more “true” average price of a stock for the day. By using VWAP alongside other technical indicators (like RSI and MACD) and sound risk management, we can formulate a robust swing trading plan aimed at maximizing profits while controlling risk.

Understanding VWAP for Swing Trading

VWAP represents the average price of a stock weighted by volume over a given session. It is typically plotted as a line on intraday charts, starting from the market open and ending at close. **Price's position relative to the VWAP line is a quick gauge of market bias** – if the stock's price is above VWAP, buyers dominate and the trend is bullish; if price is below VWAP, sellers dominate and the trend is bearish ² ³. In essence, *VWAP serves as a dynamic support and resistance level* on the chart ⁴. Stocks often **find support at VWAP on pullbacks or face resistance at VWAP on rebounds**, making it a key reference for entries and exits ⁵.

Because standard VWAP “resets” each day (calculating from each day’s open), its **industry-standard use is intraday analysis**. However, swing traders can extend its usefulness by employing **Anchored VWAP** for multi-day insights. Anchored VWAP allows you to start the VWAP calculation from a specific point (e.g. a significant swing low, high, or event date) rather than the day’s open ⁶. This is extremely useful in swing trading – *anchored VWAP works well for swing trades since it tracks the average price from any chosen point (like an earnings date or major low) and can monitor price action over days or weeks* ⁷. In practice, many swing traders will use **daily VWAP** (reset each session) for timing entries, while also watching an **anchored VWAP** from a recent pivotal high/low or start of week to identify broader support-resistance zones over their 1-2 week trade horizon. This combination provides both short-term precision and a larger context for the trade.

Note: VWAP is most reliable in liquid stocks with high volume ⁸. All Nifty 500 stocks are fairly liquid, but it’s wise to focus on those with strong trading volumes; in thinly traded stocks, a few large trades can skew the VWAP and reduce its usefulness ⁹.

Strategy Setup and Indicators

Stock Universe: NIFTY 500 components. This broad index gives ample opportunities across sectors. Ensure the stock is reasonably liquid and volatile, as swing trading profits from price movement. VWAP is particularly useful for high-volume stocks ⁸, so avoid very illiquid names.

Time Frame: Use **daily price charts** with intraday VWAP. We will analyze daily price action and use that day's VWAP for intraday signals. Since our holding period is up to ~2 weeks, we'll also consider **weekly context** – for example, one might anchor a VWAP from the start of the week or from a recent swing low/high to guide multi-day trends. (Anchored VWAP gives a volume-weighted average from a specific date, which helps identify key levels over a multi-day swing ⁷.) The default, however, is the daily VWAP as the “industry standard” baseline for entries and exits each day.

Primary Indicator – VWAP: We overlay the VWAP indicator on the daily chart (it will calculate using intraday data). **VWAP's role** is to highlight where the average buyer/seller is positioned each day. Price interaction with VWAP will inform our trade decisions (detailed in Entry/Exit criteria below). In addition, **multiple VWAPs** can be used: e.g., yesterday's VWAP or an anchored VWAP from a major event as reference levels, though the core signals will come from the current day's VWAP.

Supplementary Indicators: To increase the probability of success (as requested, using “whatever it takes” beyond VWAP), we incorporate a few technical indicators and signals in tandem with VWAP:

- **Relative Strength Index (RSI):** A momentum oscillator that helps identify overbought/oversold conditions. We will use RSI (14-period is standard) on the daily timeframe to confirm momentum. For instance, if a bullish VWAP signal appears, we prefer RSI to be **above 50 and rising** (showing positive momentum) but *not yet overbought* (below ~70) to allow upside. If RSI was very high (>70), the stock might be overbought, which could caution us against a new long entry or prompt a tighter exit plan. Conversely, an RSI below ~30 indicates oversold conditions – when combined with a bullish VWAP setup, this can signal a high-probability rebound. *Traders often look for RSI extremes together with VWAP position for stronger signals* ¹⁰.
- **Moving Average Convergence Divergence (MACD):** A trend-following momentum indicator. We'll use it to confirm trend shifts indicated by VWAP. For example, a **bullish MACD crossover** (MACD line crossing above the signal line) occurring while price is above VWAP or just as it crosses above VWAP adds confidence to a long entry signal ¹¹. Similarly, if MACD is bearish (below signal line, or negative histogram) during a VWAP breakdown, it reinforces a short signal. MACD helps ensure we trade in the direction of strengthening momentum.
- **Volume and Volume Profile:** Since VWAP is volume-weighted, paying attention to volume is crucial. We will watch for **high volume** on breakouts/breakdowns through VWAP. A price move above VWAP accompanied by a volume surge indicates stronger conviction from buyers, making the signal more reliable ¹². On the other hand, if price crosses VWAP on low volume, the move may lack follow-through. If available, volume profile or order flow tools can further verify if significant accumulation or distribution is happening near VWAP, but basic volume bars are usually sufficient. In summary, **volume confirms VWAP signals** – rising price *above* VWAP on increasing volume is a hallmark of a robust bullish trend ¹², whereas a drop *below* VWAP on heavy volume signals strong bearish pressure.

By combining VWAP with RSI, MACD, and volume analysis, we filter out weaker setups. This multi-indicator confirmation aligns with the principle that no single indicator guarantees success – a confluence of signals is ideal ¹³. Next, we detail how to apply these tools for trade entries and exits.

Entry Signals and Trade Criteria

Our swing strategy seeks to **buy on strength and sell on weakness** using VWAP as the fulcrum. We outline separate setups for **long trades** (profiting from upward swings) and **short trades** (profiting

from downward swings). *Short selling* in the cash market requires use of futures or derivatives since India's equities can't be shorted overnight, but for completeness, we include short criteria (one may also use these to simply avoid longs when conditions are bearish). Each setup assumes we are looking at the stock's daily chart and intraday VWAP for signals:

1. Long Entry Setup (Bullish Swing Trade):

- 2. VWAP Breakout:** Wait for the stock to **move above the daily VWAP line** after trading below it. A sustained break *from below to above VWAP* is often an early sign that intraday momentum has turned bullish and buyers are gaining control ¹⁴. This breakout indicates the stock is now trading above the average price which suggests new demand. Ideally, the break above VWAP is confirmed by a **volume spike**, signaling institutional participation or heavy buying interest ¹². For example, if a stock spent the morning under VWAP but later rallies through it on rising volume, it may kick off a swing upward. *A breakout above VWAP after staying below it is a classic bullish signal – it shows renewed buying interest, especially if accompanied by high volume or bullish RSI readings* ¹⁵.
- 3. VWAP Pullback ("Bounce" off Support):** If a stock has been trending above VWAP during the day (indicating an uptrend), a common strategy is to **buy on a dip toward VWAP**, with the expectation that VWAP will act as a support floor. Essentially, the VWAP line can serve as a dynamic support level during an uptrend ⁵. You'd wait for the price to **pull back to VWAP from above and then stabilize or bounce**. A bullish entry trigger could be a price rebound off VWAP or a strong bullish candle forming right around the VWAP line, showing that buyers are defending that average price. Traders often enter long when the price touches VWAP and then starts rising again ¹⁴. This allows entry near a volume-weighted support. Again, **confirmations** are key: ensure RSI is not indicating weakness (for instance, RSI ideally holding above the midline ~50 on the pullback) and check that there isn't an abnormal surge in selling volume during the pullback. If the stock holds VWAP and volume tapers on the dip, it suggests the pullback is likely just a pause, not a reversal. A successful bounce off VWAP often leads to the next leg of the up-move. (In an ongoing uptrend, institutions often try to buy *at or below VWAP*, so a bounce at VWAP can indicate institutional buying interest.) ¹⁴
- 4. Momentum Confirmation:** In addition to price action around VWAP, confirm the long setup with our supplementary indicators. **RSI** should preferably be rising and above ~50, evidencing positive momentum (or recovering from oversold <30, which can power a sharp rebound). Avoid new longs if RSI is extremely high (>70) unless you're riding strong momentum – an RSI above 70 is *overbought and could imply the up-move is stretched and due for a pause*, meaning risk of a pullback increases ¹⁶. **MACD** should show bullish characteristics – e.g. a bullish crossover or a widening gap between MACD and signal line in positive territory, indicating an uptrend is strengthening. If MACD recently crossed above the signal line below zero and is now turning up (a classic early uptrend sign) *while* price crosses above VWAP, that's a powerful confluence. Lastly, check **broader trend context**: if the stock is also above a longer-term moving average (like 50-day MA) or forming higher highs and higher lows, the wind is at your back. This trend alignment isn't mandatory, but it improves probabilities that the 1-2 week swing will follow through.

5. Short Entry Setup (Bearish Swing Trade):

- 6. VWAP Breakdown:** Opposite to the long breakout, look for the stock's price to **fall below the daily VWAP line** after being above it. A decisive break *from above to below VWAP* signals that sellers have taken control and the average buyer's price is now above the market – a bearish shift in intraday trend ¹⁴. This breakdown through VWAP (especially after mid-day or later) often precedes further decline, as late buyers are now underwater. Confirm a VWAP breakdown with **heavy volume on the sell-off**, which indicates strong distribution (many market participants

selling) ¹². For instance, if a stock fails to sustain an early rally and plunges under VWAP around noon on high volume, it could initiate a downswing. *Such a breakdown below VWAP shows growing selling pressure – if it's a genuine break (not a quick whipsaw), one might enter a short position after a retest or consolidation below VWAP, with conviction increased by volume or technical confirmation*

¹⁵. (If you do not short stocks, this signal can simply be a warning to avoid any long entries.)

7. VWAP Retest from Below: In a downtrend, **VWAP often acts as a resistance** on intraday bounces. A strategy for shorting (or exiting longs) is to **sell/short when price rallies up to VWAP from below and then rolls over**. In this scenario, the stock's intraday bounce fails right at the VWAP level – meaning the average price is too high for buyers to overcome, and sellers reassert control there. Look for price touching or slightly exceeding VWAP, but then a strong bearish candle or rejection occurs near the VWAP line. That is a cue to initiate a short position, anticipating the continuation of the downtrend. (Essentially, you are selling at an optimal average price point.) Traders use this approach to sell near VWAP in a falling market, as *VWAP serves as a dynamic resistance level during downtrends, where price often reacts and moves lower again* ¹⁷. Confirming signals include **RSI** trending below 50 or falling (extra points if RSI was overbought >70 and then crosses down, indicating a momentum swing to bearish), and **MACD** in a bearish configuration (MACD line below signal, or negative and diverging downward). Ensure there isn't a surge of buying volume overcoming the level; ideally, volume should not spike on the brief rally (or if it does, the price still fails to hold above VWAP). That indicates the VWAP retest is likely just short covering or a temporary pause, and sellers remain in charge.

8. Momentum Confirmation: For short trades, use RSI, MACD similarly but in reverse. We prefer **RSI** below ~50 and/or falling toward 30 to confirm downward momentum. An RSI above 70 that then turns down can be an ideal setup – as noted, RSI >70 means overbought, often a good time to consider a short or exit longs ¹⁶. A downturn from overbought coupled with a VWAP break adds conviction to a short. **MACD** should be crossing down or showing a negative trend (e.g., bearish crossover or histogram growing negative) to validate that downside momentum is building. If price breaks below VWAP and simultaneously MACD crosses below its signal line from above, that's a strong bearish sign. **Volume** confirmation on breakdown is key here as well – high sell volume on the VWAP break or on a failure at VWAP resistance indicates the move is likely to continue. As always, consider the larger trend: shorting is higher probability if the stock is in a broader downtrend (lower highs/lows, below key MAs). In a choppy or secular uptrend market, be more selective with shorts or use tighter profit targets.

Anchored VWAP Note: For swing trades lasting several days, it can be helpful to **anchor a VWAP to a recent significant high or low** in the stock's daily chart to guide your bias. For example, if the stock recently put in a major swing low (say 2 weeks ago) and has been rallying, the anchored VWAP from that low represents the average price of all volume since that low. If price is above that anchored VWAP, the uptrend is intact on a volume-weighted basis (bullish); if price falls below it, it may signal a deeper reversal. Similarly, an anchored VWAP from a prior swing *high* can act as resistance. In practice, anchoring from a meaningful pivot or event can highlight **support or resistance zones** for your swing trade ¹⁸. Many traders will initiate positions when price crosses an anchored VWAP of interest: e.g., going long when price climbs above the anchored VWAP from a prior high (signaling the downtrend from that high has likely ended), or going short if price drops below an anchored VWAP from a recent low (signaling distribution since that low). Use these anchored levels in tandem with the daily (session) VWAP for a fuller picture of supply and demand over your holding period.

Exit Strategy and Trade Management

Crafting a clear exit plan is just as important as finding good entries. Given the 1-2 week swing horizon, we need to plan for both **profit-taking** and **stop-loss exits**:

- **Profit Targets:** Before entering a trade, define a reasonable profit target or range. In swing trading, targets often correspond to **technical resistance levels or prior swing highs/lows**. For a long trade, look at the chart and identify the next key resistance – it could be a recent swing high, a round-number price, or perhaps the anchored VWAP from a larger timeframe above. That level can serve as a primary target to take profit. You might plan to exit the entire position there or take partial profits. Some traders use a **risk-reward ratio** rule (e.g., aim to make at least 2x the risk). For instance, if your entry is ₹100 with a stop at ₹95 (₹5 risk), aim for at least a ₹10 gain (target ~₹110) if the chart has a clear path to that level. Always be willing to adjust the target if new information arises (such as an upcoming earnings release or a sudden volume surge pushing the stock beyond the expected range faster than anticipated).
- **VWAP as a Guide for Exit:** VWAP itself can be used for exits in a couple of ways. First, **trailing stop using VWAP** – if you're long and the stock is rallying above the VWAP each day, you might use a close below VWAP as a signal to exit. Essentially, as long as the price stays above the VWAP on a given day, the intraday momentum is bullish; once it closes back under VWAP, the swing may be faltering. This approach can help you ride a trend for several days and exit when momentum reverses. Second, if you initiated a mean-reversion trade (say you bought well below VWAP expecting a bounce back), then **VWAP itself could be your profit target**, since prices often revert to the mean. For example, if a stock collapsed in the morning and you bought far under VWAP for a quick swing, you might sell as it approaches VWAP from below (where it often finds resistance) ¹⁹. In our strategy, most entries are near VWAP (breakout or pullback), so using VWAP as a target is less applicable – instead, we ride the trend *away* from that VWAP entry. But always be mindful: **if the stock achieves an exceptionally large move relative to VWAP (far above for longs, or far below for shorts), it may eventually gravitate back**, so that could be a cue to lock in profits.
- **Trailing Stop-Loss:** As the trade hopefully moves in your favor, consider using a **trailing stop** to protect gains. A common method is to **move the stop-loss up (for longs) below each higher swing low** the price makes. For example, suppose you bought at ₹100 with an initial stop at ₹95. If the stock rises to ₹110 and then pulls back to ₹105 before resuming up, you can raise your stop to just below ₹105 (the new higher low). This way, if the stock reverses and breaks the pattern of higher lows, you exit with profits captured. This concept is echoed in anchored VWAP strategies: *in a bullish setup, one can trail the stop just below each new higher low as price moves up to lock in profits gradually* ²⁰. You can also use a fixed-percentage or fixed-rupee trailing stop (e.g., 5% below the peak). For short trades, you'd do the inverse (trailing above each lower high). Trailing stops ensure you **"let winners run"** to some extent while guarding against a sharp reversal wiping out your unrealized gains ²¹.
- **Momentum and Indicator-Based Exits:** Monitor your indicators during the trade. **RSI** is particularly useful for timing exits – if you're long and RSI climbs into overbought territory (>70) and starts flattening out, the stock may be due for a pullback. That could be an opportunity to take at least partial profits. In fact, an RSI above 70 often signals an up-move is overextended and *could be a good time to exit or tighten stops* ¹⁶. Similarly, watch the **MACD**: if you see the MACD histogram shrinking or a bearish crossover while you're in a long trade, it might indicate waning momentum, suggesting you exit before your profit erodes. **Volume** can also inform

exits: if a rally approaches a resistance level and you notice volume drying up, the breakout may fail – better to take profit before sellers step in ²². On a short trade, if RSI drops to <30 (oversold) and loses downward momentum, you might cover (buy back) because a bounce could be near.

- **Time-Based Exit:** Given the swing timeframe of ~1-2 weeks, you may also decide to exit a trade after a certain number of days if it's not working. For example, if a trade hasn't hit your target or stop within 10 trading days and is just drifting, you might exit to free up capital for better opportunities. This avoids tying up money in a stagnating position (time is a cost in swing trading). That said, be flexible – if all signals still look bullish but it's just slow, you can choose to hold, but always weigh the trade-off of staying in versus rotating to another stock with more momentum.

In summary, **plan your exits in advance** for both profit-taking and stopping out. If the trade reaches your target quickly, don't get greedy – scale out or exit as planned. If the trade starts to fail (violating VWAP or support levels), honor your stop-loss. By systematically locking in gains and cutting losses, you'll ensure that a few losing trades won't offset the winners.

Risk Management Considerations

Risk management is the backbone of any profitable trading strategy. Here's how to manage risk in this VWAP-based swing strategy:

- **Initial Stop-Loss Placement:** Always define a **stop-loss level** when entering a trade. A logical stop for our strategy is just beyond the VWAP or recent swing point. For a long trade, a common practice is to place the stop **slightly below the VWAP line or below the day's low** if that's just under VWAP. The rationale is that if price has truly reversed upward, it shouldn't drop back below the VWAP by much – if it does, the bullish move may have been a false signal. *Many traders set a stop-loss just below VWAP for long positions (and conversely just above VWAP for shorts)* ²³. For example, if you bought at ₹100 as price crossed above VWAP, and VWAP was at ₹98 at that time, you might set a stop around ₹96-97 (a bit under VWAP) in case the breakout fails. Anchored VWAP guidance echoes this: *in a bullish setup, placing the stop just under the anchored VWAP is advised, whereas in a bearish trade, stop just over the anchored VWAP* ²⁴. This ties the risk level to a point where the trade thesis (holding above that average price) is invalidated.
- **Position Sizing:** Calculate your position size such that if your stop-loss is hit, you lose only a small percentage of your capital (typically 1-2% of total trading capital on a single trade is a common guideline). For instance, if your entry is ₹100 and stop is ₹95, that's ₹5 risk per share. If you don't want to lose more than ₹5,000 on the trade, you'd take 1000 shares ($\text{₹}5 * 1000 = \text{₹}5k$ risk). Proper sizing ensures no single bad trade will be devastating. Nifty 500 stocks vary in volatility; adjust your position size and stop distance based on the stock's volatility (ATR – average true range – can be a helpful measure to gauge a reasonable stop distance).
- **Avoiding Low-Volume Traps:** As mentioned, VWAP can be misleading in low-volume environments ⁹. If a stock's volume is very light (especially outside main market hours or in small-cap stocks), be cautious – the VWAP might move on just a few trades. It's better to trade active stocks where VWAP reflects a broad consensus. If you must trade a lower-volume stock, widen your stops and be extra patient or use additional confirmation (like wait for a 2nd day above VWAP, etc.). Generally, for Nifty 500 names, liquidity is sufficient, but always double-check unusual volume conditions (e.g., holiday sessions, etc.).

- **VWAP Limitations:** Remember that **VWAP is a lagging indicator** – it's based on past traded prices and volumes, so it won't predict sudden news or shocks ²⁵. VWAP also by definition will hug the price action (especially later in the day), so it may not react quickly to fast reversals. Do not rely on VWAP alone for decision-making; our strategy smartly combines it with RSI, MACD, and price patterns to improve reliability. Even then, unexpected events (earnings surprises, macro news) can override technical signals. Always be prepared to honor your stop or exit if an adverse news event hits your stock. In essence, **use VWAP as a guide, not a guarantee** – it shows an average, not a hard floor or ceiling. The price can and will deviate from VWAP if new information or strong sentiment emerges. Manage this risk by being disciplined with stops and not over-leveraging any single trade.
- **Trade Management and Adjustments:** If the trade is going well in your favor, periodically **adjust your stop-loss to reduce risk** (e.g., move it to breakeven once the trade is comfortably up, then trail as discussed). Avoid the temptation to remove or widen stop-losses if the trade goes against you – that's violating your risk plan. It's better to take the stop, reassess, and possibly re-enter later if conditions turn favorable again, rather than hoping a losing trade comes back. Swing trading inherently faces overnight gap risk (since positions are held multi-day). Gaps can sometimes jump over your stop-loss. To mitigate this, you might set slightly looser stops if a known event is coming (to avoid an expected gap shake-out), or reduce position size before major announcements. You can also hedge overnight risk by holding an index hedge or options, but that's a more advanced technique.
- **Diversification:** Since we are trading within Nifty 500, consider diversifying across a few trades rather than concentrating everything into one stock position. For example, instead of putting all capital in one swing trade, you could be in 3-5 different trades in different sectors. This way, a single stock's bad news won't sink your entire portfolio. However, don't over-dilute either – manage what you can monitor. Also avoid taking highly correlated positions (e.g., three bank stocks longs at once); spread it out (maybe one banking, one IT, one auto, etc.), or just pick the single best setup among similar stocks.

Lastly, *always keep a trading journal*. Track the trades you take with this strategy, noting the VWAP conditions, indicator readings, entry/exit rationale, and the outcome. Over time, this will help you refine the rules (for instance, you might discover certain patterns or sectors respond better to VWAP signals, or that adding a filter like the overall Nifty index trend improves results). Continual learning and adaptation are key – the market's behavior can evolve, so remain flexible and update the strategy if needed.

Conclusion

This VWAP-based swing trading strategy for NIFTY 500 stocks provides a structured approach to capture 1–2 week price swings. It leverages the **VWAP indicator as a central guide** for intraday trend and key price levels, employing **daily VWAP for entries** and optionally **anchored VWAP for multi-day context**. By combining VWAP signals with **momentum oscillators (RSI)** and **trend indicators (MACD)**, as well as volume confirmation, we increase the probability of success – aligning multiple factors in our favor ¹⁰. For example, a long trade is not just based on price crossing above VWAP, but also reinforced by rising RSI momentum and strong volume, thereby filtering out false breakouts.

The strategy emphasizes **buying strength and selling weakness**: entering longs when price action and volume indicate accumulation above the average price, and entering shorts (or avoiding longs) when distribution pushes price below the average. It also underscores the importance of **risk**

management – setting stop-losses just beyond VWAP or recent swings to cap downside ²³, and actively managing trades with trailing stops and profit targets. No strategy is complete without discipline in exits; thus we plan how to take profits (e.g. at resistance or via trailing stops) and cut losses (if VWAP support fails), which protects us from large drawdowns and locks in gains methodically.

Keep in mind that while VWAP is a powerful tool (widely used by institutions and traders alike), it works best in tandem with other analysis and within a solid risk framework. The stock market can be unpredictable, so **no single indicator or strategy guarantees a profit** – success comes from consistent execution of a well-defined plan and adapting to market conditions ¹³. Before deploying real capital, it's wise to **paper trade or backtest** this strategy on historical charts of Nifty 500 stocks to see how it performs and to make any tweaks (for example, you may find certain indicator thresholds that work better for your style).

By following this VWAP swing trading strategy, you aim to participate in significant price swings with an edge: buying near average value with confirmation of trend strength and selling when momentum fades or reverses. With practice, patience, and strict risk control, this approach can help you **capitalize on short-term market moves** in a systematic, confidence-driven manner. Good trading!

Sources: The strategy and its principles are informed by established trading knowledge and sources. VWAP's role as a support/resistance and trend indicator is documented in trading literature ⁴ ¹⁴. Swing traders commonly use multi-day VWAP or anchored VWAP to gauge market sentiment ²⁶ ⁷. Combining VWAP with RSI/MACD to strengthen signals is a recommended practice ¹⁰. The entry and exit tactics (VWAP breakouts, bounces, etc.) and risk management guidelines presented here are drawn from a synthesis of expert insights ²⁷ ²⁴ ¹⁶ and are tailored for the Indian market context. Always ensure to stay updated with market news and adapt the strategy as needed ²⁸ ²⁹.

¹ ¹³ Swing Trading Strategy : Definition, Pros & Cons | Share India

<https://www.shareindia.com/knowledge-center/online-share-trading/swing-trading-strategies>

² ³ ⁴ ⁸ ⁹ ¹⁰ ¹¹ ¹² ¹⁴ ¹⁹ ²³ ²⁵ ²⁶ ²⁹ #1 VWAP Indicator Guide: 7 Best Strategies for

Trading

<https://www.tradervue.com/blog/vwap-indicator>

⁵ ²⁷ VWAP Strategy - Using Volume Weighted Average Price for Trade Entries

<https://groww.in/blog/vwap-strategy>

⁶ ²⁸ Anchored VWAP: Understanding Context-Driven Price Analysis

<https://optimusfutures.com/blog/anchored-vwap/>

⁷ ¹⁵ ¹⁷ ¹⁸ ²⁰ ²⁴ Anchored VWAP Trading Strategies:Definition, and How to use it

<https://www.stockgro.club/blogs/trading/anchored-vwap/>

¹⁶ ²¹ ²² Mastering Swing Trading: Timing Your Entries and Exits - Osprey FX

<https://ospreyfx.com/education/mastering-swing-trading-timing-entries-exits/>