Documentation

search

Search

• rocket launch

Get started

- <u>Installation</u> add
- <u>Fundamentals</u> *add*
- First steps add
- code

<u>Develop</u>

- Concepts add
- API reference

remove

- PAGE ELEMENTS
- Write and magic

add

- <u>Text elements</u> add
- Data elements

add

• Chart elements

add

■ <u>Input widgets</u>

add

Media elements

add

Layouts and containers

add

Chat elements

add

Status elements

add

- <u>Third-party componentsopen in new</u>
- APPLICATION LOGIC
- Navigation and pages

add

Execution flow

add

Caching and state

add

Connections and secrets

add

• Custom components

- add
- <u>Utilities</u>add
- Configuration
 - remove
 - config.toml
 - <u>st.get option</u>
 - st.set option
 - st.set page config
- TOOLS
- App testing add
- Command line add
- <u>Tutorials</u> add
- Quick reference add
- web asset

Deploy

- Concepts add
- Streamlit Community Cloud add
- Snowflake
- Other platforms add
- school

Knowledge base

- FAQ
- <u>Installing dependencies</u>
- <u>Deployment issues</u>
- Home/
- <u>Develop/</u>
- API reference/
- Configuration/
- config.toml

config.toml



config.toml is an optional file you can define for your working directory or global development environment. When config.toml is defined both globally and in your working directory, Streamlit combines the configuration options and gives precedence to the working-directory configuration. Additionally, you can use environment variables and command-line options to override additional configuration options. For more information, see <u>Configuration options</u>.

File location



To define your configuration locally or per-project, add .streamlit/config.toml to your working directory. Your working directory is wherever you call streamlit run. If you haven't previously created the .streamlit directory, you will need to

add it.

To define your configuration globally, you must first locate your global .streamlit directory. Streamlit adds this hidden directory to your OS user profile during installation. For MacOS/Linux, this will be ~/.streamlit/config.toml. For Windows, this will be %userprofile%/.streamlit/config.toml.

File format



config.toml is a **TOML** file.

Example

[client] showErrorDetails = "none" [theme] primaryColor = "#F63366" backgroundColor = "black"

Available configuration options



Below are all the sections and options you can have in your .streamlit/config.toml file. To see all configurations, use the following command in your terminal or CLI:

streamlit config show

Global

[global] # By default, Streamlit displays a warning when a user sets both a widget # default value in the function defining the widget and a widget value via # the widget's key in `st.session_state`. # If you'd like to turn off this warning, set this to True. # Default: false disableWidgetStateDuplicationWarning = false # If True, will show a warning when you run a Streamlitenabled script # via "python my_script.py". # Default: true showWarningOnDirectExecution = true

Logger

[logger] # Level of logging for Streamlit's internal logger: "error", "warning", # "info", or "debug". # Default: "info" level = "info" # String format for logging messages. If logger.datetimeFormat is set, # logger messages will default to `%(asctime)s.%(msecs)03d %(message)s`. See # Python's documentation for available attributes: # https://docs.python.org/3/library/logging.html#formatter-objects # Default: "%(asctime)s %(message)s" messageFormat = "%(asctime)s %(message)s"

Client

[client] # Controls whether uncaught app exceptions and deprecation warnings # are displayed in the browser. This can be one of the following: # - "full": In the browser, Streamlit displays app deprecation # warnings and exceptions, including exception types, # exception messages, and associated tracebacks. # - "stacktrace": In the browser, Streamlit displays exceptions, # including exception types, generic exception messages, # and associated tracebacks. Deprecation warnings and # full exception messages will only print to the # console. # - "type": In the browser, Streamlit displays exception types and # generic exception messages. Deprecation warnings, full # exception messages, and associated tracebacks only # print to the console. # - "none": In the browser, Streamlit displays generic exception # messages. Deprecation warnings, full exception # messages, associated tracebacks, and exception types # will only print to the console. # - True: This is deprecated. Streamlit displays "full" # error details. # - False: This is deprecated. Streamlit displays "stacktrace" # error details. # Default: "full" showErrorDetails = "full" # Change the visibility of items in the toolbar, options menu, # and settings dialog (top right of the app). # Allowed values: # - "auto": Show the developer options if the app is accessed through # localhost or through Streamlit Community Cloud as a developer. # Hide them otherwise. # - "developer": Show the developer options. # -

"viewer": Hide the developer options. # - "minimal": Show only options set externally (e.g. through # Streamlit Community Cloud) or through st.set_page_config. # If there are no options left, hide the menu. # Default: "auto" toolbarMode = "auto" # Controls whether to display the default sidebar page navigation in a # multi-page app. This only applies when app's pages are defined by the # `pages/` directory. # Default: true showSidebarNavigation = true

Runner

[runner] # Allows you to type a variable or string by itself in a single line of # Python code to write it to the app. # Default: true magicEnabled = true # Handle script rerun requests immediately, rather than waiting for script # execution to reach a yield point. This makes Streamlit much more # responsive to user interaction, but it can lead to race conditions in # apps that mutate session_state data outside of explicit session_state # assignment statements. # Default: true fastReruns = true # Raise an exception after adding unserializable data to Session State. # Some execution environments may require serializing all data in Session # State, so it may be useful to detect incompatibility during development, # or when the execution environment will stop supporting it in the future. # Default: false enforceSerializableSessionState = false # Adjust how certain 'options' widgets like radio, selectbox, and # multiselect coerce Enum members when the Enum class gets re-defined # during a script re-run. For more information, check out the docs: # https://docs.streamlit.io/develop/concepts/design/custom-classes#enums # Allowed values: # - "off" : Disables Enum coercion. # - "nameOnly" : Enum classes can be coerced if their member names match. # - "nameAndValue" : Enum classes can be coerced if their member values match. # Default: "nameOnly" enumCoercion = "nameOnly"

Server

[server] # List of folders that should not be watched for changes. # Relative paths will be taken as relative to the current working directory. # Example: ['/home/user1/env', 'relative/path/to/folder'] # Default: [] folderWatchBlacklist = [] # Change the type of file watcher used by Streamlit, or turn it off # completely. # Allowed values: # - "auto" : Streamlit will attempt to use the watchdog module, and # falls back to polling if watchdog is not available. # - "watchdog" : Force Streamlit to use the watchdog module. # - "poll" : Force Streamlit to always use polling. # - "none" : Streamlit will not watch files. # Default: "auto" fileWatcherType = "auto" # Symmetric key used to produce signed cookies. If deploying on multiple # replicas, this should be set to the same value across all replicas to ensure # they all share the same secret. # Default: randomly generated secret key. cookieSecret = "a-random-key-appears-here" # If false, will attempt to open a browser window on start. # Default: false unless (1) we are on a Linux box where DISPLAY is unset, or # (2) we are running in the Streamlit Atom plugin. headless = false # Automatically rerun script when the file is modified on disk. # Default: false runOnSave = false # The address where the server will listen for client and browser # connections. Use this if you want to bind the server to a specific address. # If set, the server will only be accessible from this address, and not from # any aliases (like localhost). # Default: (unset) address = # The port where the server will listen for browser connections. # Don't use port 3000 which is reserved for internal development. # Default: 8501 port = 8501 # The base path for the URL where Streamlit should be served from. # Default: "" baseUrlPath = "" # Enables support for Cross-Origin Resource Sharing (CORS) protection, # for added security. # If XSRF protection is enabled and CORS protection is disabled at the # same time, Streamlit will enable them both instead. # Default: true enableCORS = true # Enables support for Cross-Site Request Forgery (XSRF) protection, for # added security. # If XSRF protection is enabled and CORS protection is disabled at the # same time, Streamlit will enable them both instead. # Default: true enableXsrfProtection = true # Max size, in megabytes, for files uploaded with the file uploader. # Default: 200 maxUploadSize = 200 # Max size, in megabytes, of messages that can be sent via the WebSocket # connection. # Default: 200 maxMessageSize = 200 # Enables support for websocket compression. # Default: false enableWebsocketCompression = false # Enable serving files from a `static` directory in the running app's # directory. # Default: false enableStaticServing = false # TTL in seconds for sessions whose websockets have been disconnected. The server # may choose to clean up session state, uploaded files, etc for a given session # with no active websocket connection at any point after this time has passed. # Default: 120 disconnectedSessionTTL = 120 # Server certificate file for connecting via HTTPS. # Must be set at the same time as "server.sslKeyFile". # ['DO NOT USE THIS OPTION IN A PRODUCTION ENVIRONMENT. It has not gone through # security audits or performance tests. For the production environment, we # recommend performing SSL termination by the load balancer or the reverse # proxy.'] sslCertFile = # Cryptographic key file for connecting via HTTPS. # Must be set at the same time as "server.sslCertFile". # ['DO NOT USE THIS OPTION IN A PRODUCTION ENVIRONMENT. It has not gone through # security audits or performance tests. For the production environment, we # recommend performing SSL termination by the load balancer or the reverse # proxy.'] sslKeyFile =

Browser

[browser] # Internet address where users should point their browsers in order to # connect to the app. Can be IP address or DNS name and path. # This is used to: # - Set the correct URL for CORS and XSRF protection purposes. # - Show the URL on the terminal # - Open the browser # Default: "localhost" serverAddress = "localhost" # Whether to send usage statistics to Streamlit. # Default: true gatherUsageStats = true # Port where users should point their browsers in order to connect to the # app. # This is used to: # - Set the correct URL for XSRF protection purposes. # - Show the URL on the terminal (part of `streamlit run`). # - Open the browser automatically (part of `streamlit run`). # This option is for advanced use cases. To change the port of your app, use # `server.Port` instead. Don't use port 3000 which is reserved for internal # development. # Default: whatever value is set in server.port. serverPort = 8501

Mapbox

[mapbox] # Configure Streamlit to use a custom Mapbox # token for elements like st.pydeck_chart and st.map. # To get a token for yourself, create an account at # https://mapbox.com. It's free (for moderate usage levels)! # Default: "" token = ""

Theme

[theme] # The preset Streamlit theme that your custom theme inherits from. # One of "light" or "dark". base = # Primary accent color for interactive elements. primaryColor = # Background color for the main content area. backgroundColor = # Background color used for the sidebar and most interactive widgets. secondaryBackgroundColor = # Color used for almost all text. textColor = # Font family for all text in the app, except code blocks. One of "sans serif", # "serif", or "monospace". font =

Secrets

[secrets] # List of locations where secrets are searched. An entry can be a path to a # TOML file or directory path where Kubernetes style secrets are saved. # Order is important, import is first to last, so secrets in later files # will take precedence over earlier ones. # Default: [<path to local environment's secrets.toml file>, <path to project's secrets.toml file>,] files = ["~/.streamlit/secrets.toml",]

← Previous: ConfigurationNext: st.get option →

forum

Still have questions?

Our <u>forums</u> are full of helpful information and Streamlit experts.

HomeContact UsCommunity



© 2025 Snowflake Inc. Cookie policy

forum Ask Al