## CS450 Computer Networks

The slides used in class are derived from the slides available on our text book companion website:

© 2012 Maharishi University of Management

All additional course materials are copyright protected by international copyright laws and remain the property of the Maharishi University of Management. The materials are accessible only for the personal use of students enrolled in this course and only for the duration of the course. Any copying and distributing are not allowed and subject to legal action.

CS450 Computer Networks Lesson 16 <u>Data Link Layer – Overview</u>

<u>Do Less – accomplish more</u>

## Lesson 16: The Data Link Layer-Overview

### Our goals:


- understand principles behind data link layer services:
  - error detection, correction
  - sharing a broadcast channel: multiple access
  - link layer addressing
  - reliable data transfer, flow control

## Link layer: introduction

### terminology:

- hosts and routers: nodes
- communication channels that connect adjacent nodes along communication path: links
  - wired links
  - wireless links
  - LANs
- layer-2 packet: frame, encapsulates datagram

data-link layer has responsibility of transferring datagram from one node to physically adjacent node over a link



## Link layer: context

- datagram transferred by different link protocols over different links:
  - e.g., Ethernet on first link, frame relay on intermediate links, 802.11 on last link
- each link protocol provides different services
  - e.g., may or may not provide rdt over link

### transportation analogy:

- trip from Princeton to Lausanne
  - limo: Princeton to JFK
  - plane: JFK to Geneva
  - train: Geneva to Lausanne
- tourist = datagram
- transport segment = communication link
- transportation mode = link layer protocol
- travel agent = routing algorithm

## Link layer services

- \* Recall the services provided by the transport layer and the network layer.
- What services do we want from the link layer?

## Link layer services

- What services do we want from the link layer?
  - link access
  - reliable delivery between adjacent nodes
  - flow control between adjacent nodes
  - error detection and correction
  - half-duplex and full-duplex communication

## Link layer services

- framing, link access:
  - encapsulate datagram into frame, adding header, trailer
  - channel access if shared medium
  - "MAC" addresses used in frame headers to identify source, dest
    - different from IP address!
- reliable delivery between adjacent nodes
  - we learned how to do this already (TCP)
  - seldom used on low bit-error link (fiber, some twisted pair)
  - wireless links: high error rates
    - Q: why both link-level and end-end reliability?

# Link layer services (more)

### flow control:

pacing between adjacent sending and receiving nodes

#### error detection:

- errors caused by signal attenuation, noise.
- receiver detects presence of errors:
  - signals sender for retransmission or drops frame

#### error correction:


 receiver identifies and corrects bit error(s) without resorting to retransmission

### half-duplex and full-duplex


 with half duplex, nodes at both ends of link can transmit, but not at same time

## Where is the link layer implemented?

- in each and every host
- link layer implemented in "adaptor" (aka network interface card NIC) or on a chip
  - Ethernet card, 802.11 card; Ethernet chipset
  - implements link, physical layer
- attaches into host's system buses
- combination of hardware, software, firmware



## Adaptors communicating




- sending side:
  - encapsulates datagram in frame
  - adds error checking bits, rdt, flow control, etc.

- receiving side
  - looks for errors, rdt, flow control, etc
  - extracts datagram, passes to upper layer at receiving side

### **Error detection**

EDC= Error Detection and Correction bits (redundancy)


- D = Data protected by error checking, may include header fields
- Error detection not 100% reliable!
  - protocol may miss some errors, but rarely
  - larger EDC field yields better detection and correction



# Parity checking

### single bit parity:

detect single bit errors



#### odd parity:


Row/column has an odd number of 1s


#### Even parity:

 Row/column has an even number of 1s

#### two-dimensional bit parity:

detect and correct single bit errors





## Internet checksum (review)

goal: detect "errors" (e.g., flipped bits) in transmitted packet (note: used at transport layer only) Why??

#### sender:


- treat segment contents as sequence of 16-bit integers
- checksum: addition (I's complement sum) of segment contents
- sender puts checksum value into UDP /TCP/IP checksum field

#### receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - NO error detected
  - YES no error detected. But maybe errors nonetheless?

## Cyclic redundancy check

- more powerful error-detection coding
- view data bits, D, as a binary number
- choose r+I bit pattern (generator), G
- goal: choose r CRC bits, R, such that
  - <D,R> exactly divisible by G (modulo 2)
  - receiver knows G, divides <D,R> by G. If non-zero remainder: error detected!
  - can detect all burst errors less than r+1 bits
- widely used in practice (Ethernet, 802.11 WiFi, ATM)



## CRC example

#### want:

 $D \cdot 2^r XOR R = nG$ 


equivalently:

 $D \cdot 2^r = nG XOR R$ 

### equivalently:

if we divide D.2<sup>r</sup> by G, want remainder R to satisfy:

$$R = remainder[\frac{D \cdot 2^r}{G}]$$



### Multiple access links, protocols

### two types of "links":

- point-to-point
  - PPP for dial-up access
  - point-to-point link between Ethernet switch, host
- broadcast (shared wire or medium)
  - old-fashioned Ethernet
  - upstream HFC
  - 802.11 wireless LAN



shared wire (e.g., cabled Ethernet)



shared RF (e.g., 802.11 WiFi)



shared RF (satellite)



humans at a cocktail party (shared air, acoustical)

## Multiple access protocols

- single shared broadcast channel
- two or more simultaneous transmissions by nodes: interference
  - collision if node receives two or more signals at the same time

### multiple access protocol

- distributed algorithm that determines how nodes share channel, i.e., determine when node can transmit
- communication about channel sharing must use channel itself!
  - no out-of-band channel for coordination

## An ideal multiple access protocol

given: broadcast channel of rate R bps Optimal protocol would be:

- I. when one node wants to transmit, it can send at rate R.
- 2. when M nodes want to transmit, each can send at average rate R/M
- 3. fully decentralized:
  - no special node to coordinate transmissions
  - no synchronization of clocks, slots
- 4. simple

## MAC protocols: taxonomy


#### three broad classes:

- channel partitioning
  - divide channel into smaller "pieces" (time slots, frequency, code)
  - allocate piece to node for exclusive use
- random access
  - channel not divided, allow collisions
  - "recover" from collisions
- "taking turns"
  - nodes take turns, but nodes with more to send can take longer turns

### Channel partitioning MAC protocols: TDMA

### TDMA: time division multiple access


- access to channel in "rounds"
- each station gets fixed length slot (length = pkt trans time) in each round
- unused slots go idle
- example: 6-station LAN, 1,3,4 have pkt, slots 2,5,6 idle



### Channel partitioning MAC protocols: FDMA

### FDMA: frequency division multiple access

- channel spectrum divided into frequency bands
- each station assigned fixed frequency band
- unused transmission time in frequency bands go idle
- example: 6-station LAN, 1,3,4 have pkt, frequency bands 2,5,6 idle



## Random access protocols

- when node has packet to send
  - transmit at full channel data rate R.
  - no a priori coordination among nodes
- ❖ two or more transmitting nodes → "collision",
- random access MAC protocol specifies:
  - how to detect collisions
  - how to recover from collisions (e.g., via delayed retransmissions)
- examples of random access MAC protocols:
  - slotted ALOHA
  - ALOHA
  - CSMA, CSMA/CD, CSMA/CA

## CSMA (carrier sense multiple access)

### **CSMA**: listen before transmit:

if channel sensed idle: transmit entire frame

if channel sensed busy, defer transmission

- human analogy:
- An improvement over the original ALOHA and slotted ALOHA schemes of attempt to transmit at any time.

## CSMA (carrier sense multiple access)

#### **CSMA**: listen before transmit:

if channel sensed idle: transmit entire frame

- if channel sensed busy, defer transmission
- human analogy: don't interrupt others!
- An improvement over the original ALOHA and slotted ALOHA schemes of attempt to transmit at any time.

### **CSMA** collisions

#### collisions can still occur:

propagation delay means two nodes may not hear each other's transmission


#### collision:

entire packet transmission time wasted

#### note:

role of distance & propagation delay in determining collision probability

#### spatial layout of nodes



## CSMA/CD (collision detection)

### CSMA/CD: carrier sensing, deferral as in CSMA


- collisions detected within short time
- colliding transmissions aborted, reducing channel wastage
- collision detection:
  - easy in wired LANs: measure signal strengths, compare transmitted, received signals
  - difficult in wireless LANs: received signal strength overwhelmed by local transmission strength
- human analogy: ?

## CSMA/CD (collision detection)

### CSMA/CD: carrier sensing, deferral as in CSMA

- collisions detected within short time
- colliding transmissions aborted, reducing channel wastage
- collision detection:
  - easy in wired LANs: measure signal strengths, compare transmitted, received signals
  - difficult in wireless LANs: received signal strength overwhelmed by local transmission strength
- human analogy: the polite conversationalist

# CSMA/CD (collision detection)



## Ethernet CSMA/CD algorithm

- I. NIC receives datagram from network layer, creates frame
- 2. If NIC senses channel idle, starts frame transmission. If NIC senses channel busy, waits until channel idle, then transmits.
- 3. If NIC transmits entire frame without detecting another transmission, NIC is done with frame!

- 4. If NIC detects another transmission while transmitting, aborts and sends jam signal
- 5. After aborting, NIC enters binary (exponential) backoff:
  - after mth collision, NIC chooses K at random from {0,1,2, ..., 2<sup>m</sup>-1}. NIC waits K'512 bit times, returns to Step 2
  - longer backoff interval with more collisions

# **CSMA/CD** efficiency

- $\star$  T<sub>prop</sub> = max prop delay between 2 nodes in LAN
- $\star$   $t_{trans}$  = time to transmit max-size frame

$$efficiency = \frac{1}{1 + 5t_{prop}/t_{trans}}$$

- efficiency goes to I
  - as t<sub>prop</sub> goes to 0
  - as t<sub>trans</sub> goes to infinity
- Good performance and simple, cheap, decentralized!

# "Taking turns" MAC protocols

### channel partitioning MAC protocols:

- share channel efficiently and fairly at high load
- inefficient at low load: delay in channel access, I/N bandwidth allocated even if only I active node!

### random access MAC protocols

- efficient at low load: single node can fully utilize channel
- high load: collision overhead


### "taking turns" protocols

look for best of both worlds!

# "Taking turns" MAC protocols

### polling:


- master node "invites" slave nodes to transmit in turn
- typically used with "dumb" slave devices
- concerns:
  - polling overhead
  - latency
  - single point of failure (master)




# "Taking turns" MAC protocols

### token passing:

- control token passed from one node to next sequentially.
- token message
- concerns:
  - token overhead
  - latency
  - single point of failure (token)




### Cable access network



- multiple 40Mbps downstream (broadcast) channels
  - single CMTS transmits into channels
- multiple 30 Mbps upstream channels
  - multiple access: all users contend for certain upstream channel time slots (others assigned)

### Cable access network



### DOCSIS: data over cable service interface spec

- FDM over upstream, downstream frequency channels
- TDM upstream: some slots assigned, some have contention
  - downstream MAP frame: assigns upstream slots
  - request for upstream slots (and data) transmitted random access (binary backoff) in selected slots

# Summary of MAC protocols

- channel partitioning, by time, frequency or code
  - Time Division, Frequency Division
- random access (dynamic),
  - ALOHA, S-ALOHA, CSMA, CSMA/CD
  - carrier sensing: easy in some technologies (wire), hard in others (wireless)
  - CSMA/CD used in Ethernet
  - CSMA/CA used in 802.11
- taking turns
  - polling from central site, token passing
  - bluetooth, FDDI, token ring


## MAC addresses and ARP

- 32-bit IP address:
  - network-layer address for interface
  - used for layer 3 (network layer) forwarding
- MAC (or LAN or physical or Ethernet) address:
  - function: used 'locally" to get frame from one interface to another physically-connected interface (same network, in IPaddressing sense)
  - 48 bit MAC address (for most LANs) burned in NIC ROM, also sometimes software settable
  - e.g.: IA-2F-BB-76-09-AD

hexadecimal (base 16) notation (each "number" represents 4 bits)

# LAN addresses and ARP

each adapter on LAN has unique LAN address




# LAN addresses (more)

- MAC address allocation administered by IEEE
- manufacturer buys portion of MAC address space (to assure uniqueness)
- analogy:
  - MAC address: like Social Security Number
  - IP address: like postal address
- ♦ MAC flat address → portability
  - can move LAN card from one LAN to another
- IP hierarchical address not portable
  - address depends on IP subnet to which node is attached

# ARP: address resolution protocol

Question: how to determine interface's MAC address, knowing its IP address?



ARP table: each IP node (host, router) on LAN has table

- IP/MAC address mappings for some LAN nodes:
  - < IP address; MAC address; TTL>
- TTL (Time To Live): time after which address mapping will be forgotten (typically 20 min)


# ARP protocol: same LAN

- A wants to send datagram to B
  - B's MAC address not in A's ARP table.
- A broadcasts ARP query packet, containing B's IP address
  - dest MAC address = FF-FF-FF-FF-FF
  - all nodes on LAN receive ARP query
- B receives ARP packet, replies to A with its (B's) MAC address
  - frame sent to A's MAC address (unicast)


- A caches (saves) IP-to-MAC address pair in its ARP table until information becomes old (times out)
  - soft state: information that times out (goes away) unless refreshed
- ARP is "plug-and-play":
  - nodes create their ARP tables without intervention from net administrator

#### walkthrough: send datagram from A to B via R


- focus on addressing at IP (datagram) and MAC layer (frame)
- assume A knows B's IP address
- assume A knows IP address of first hop router, R (how?)
- assume A knows R's MAC address (how?)




- A creates IP datagram with IP source A, destination B
- A creates link-layer frame with R's MAC address as dest, frame contains A-to-B IP datagram




- frame sent from A to R
- frame received at R, datagram removed, passed up to IP




- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as dest, frame contains A-to-B IP datagram



- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as dest, frame contains A-to-B IP datagram



- R forwards datagram with IP source A, destination B
- R creates link-layer frame with B's MAC address as dest, frame contains A-to-B IP datagram



# Lesson 16: Network Overview Summary

The link layer may provide many of the services provided by the transport layer.

- Error Detection and Error Correction
- Reliable data transfer
- Flow control
- Multiple Shared Access to a channel
- Addressing

These services are only provided between 2 adjacent nodes. Not end-to-end.

The more services that can be provided at a lower layer, the more efficient the network as a whole will be.