### CS450 Computer Networks

The slides used in class are derived from the slides available on our text book companion website:

© 2012 Maharishi University of Management
All additional course materials are copyright protected by international copyright
laws and remain the property of the Maharishi University of Management. The
materials are accessible only for the personal use of students enrolled in this
course and only for the duration of the course. Any copying and distributing are
not allowed and subject to legal action.

# CS450 Computer Networks Lesson I I Transport Layer – Congestion Control

The organizing power of pure consciousness

## <u>Lesson II: Transport Layer – Congestion Control</u>

#### Our goals:

- understand principles behind the transport layer service of congestion control
- understand the TCP implementation of congestion control

### Principles of Congestion Control

#### Congestion:


- informally: "too many sources sending too much data too fast for network to handle"
- How is congestion control different from flow control??
- manifestations:
  - lost packets (buffer overflow at routers)
  - long delays (queueing in router buffers)
- a top-10 problem!


two senders, two receivers

one router, infinite buffers


output link capacity: R

no retransmission






maximum per-connection throughput: R/2




• large delays as arrival rate,  $\lambda_{in}$ , approaches capacity


- one router, finite buffers
- sender retransmission of timed-out packet
  - application-layer input = application-layer output:  $\lambda_{\text{in}}$  =  $\lambda_{\text{out}}$
  - transport-layer input includes retransmissions :  $\lambda_{in} \geq \lambda_{in}$



### idealization: perfect knowledge

 sender sends only when router buffers available






#### Idealization: known loss


packets can be lost, dropped at router due to full buffers


sender only resends if packet known to be lost



# Idealization: known loss packets can be lost, dropped at router due to full buffers


sender only resends if packet known to be lost






### Realistic: duplicates


- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered





### Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered




### "costs" of congestion:


- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
  - decreasing goodput


- four senders
- multihop paths
- timeout/retransmit

Q: what happens as  $\lambda_{in}$  and  $\lambda_{in}$  increase?

A: as red  $\lambda_{in}$  increases, all arriving blue pkts at upper queue are dropped, blue throughput  $\rightarrow 0$ 







### another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

### Approaches towards congestion control

Using a human analogy — Can you think of two broad approaches towards congestion control?

### Approaches towards congestion control

### two broad approaches towards congestion control:

### end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

### network-assisted congestion control:

- routers provide feedback to end systems
  - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
  - explicit rate for sender to send at

### Case study: ATM ABR congestion control


#### ABR: available bit rate:

- "elastic service"
- if sender's path "underloaded":
  - sender should use available bandwidth
- if sender's path congested:
  - sender throttled to minimum guaranteed rate

### RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
  - NI bit: no increase in rate (mild congestion)
  - Cl bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

### Case study: ATM ABR congestion control




- \* two-byte ER (explicit rate) field in RM cell
  - congested switch may lower ER value in cell
  - senders' send rate thus max supportable rate on path
- EFCI bit in data cells: set to I in congested switch
  - if data cell preceding RM cell has EFCI set, receiver sets
     CI bit in returned RM cell


### TCP congestion control: additive increase multiplicative decrease

- \* approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
  - additive increase: increase cwnd by I MSS every RTT until loss detected
  - multiplicative decrease: cut cwnd in half after loss

AIMD saw tooth behavior: probing for bandwidth



### TCP Congestion Control: details



sender limits transmission:

 cwnd is dynamic, function of perceived network congestion


### TCP sending rate:

roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate 
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

### TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
  - initially cwnd = I MSS
  - double cwnd every RTT
  - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast




### TCP: detecting, reacting to loss

- loss indicated by timeout:
  - cwnd set to 1 MSS;
  - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
  - dup ACKs indicate network capable of delivering some segments
  - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to I (timeout or 3 duplicate acks)

### TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?


A: when **cwnd** gets to 1/2 of its value before timeout.



### **Implementation:**

- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event


### Summary: TCP Congestion Control



### TCP throughput

- avg. TCP thruput as function of window size, RTT?
  - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
  - avg. window size (# in-flight bytes) is <sup>3</sup>/<sub>4</sub> W
  - avg. thruput is 3/4W per RTT

avg TCP thruput = 
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec



### TCP Futures: TCP over "long, fat pipes"


- example: I500 byte segments, I00ms RTT, want
   I0 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput = 
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of L =  $2^{-10^{-10}}$  a very small loss rate!
- new versions of TCP for high-speed

### **TCP Fairness**


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



### Why is TCP fair?

#### two competing sessions:

- additive increase gives slope of I, as throughput increases
- multiplicative decrease decreases throughput proportionally



### Fairness (more)

#### Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- instead use UDP:
  - send audio/video at constant rate, tolerate packet loss

### Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
  - new app asks for I TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2

### Lesson II: Summary

- principles behind transport layer services congestion control -- two choices:
  - End-to-end control
  - Network assisted control
- instantiation and implementation in the Internet –
   TCP -- end-to-end control

Keep complexity at the network edge whenever possible.