blkarray.sty

D. P. Carlisle

24 March 1999

Warning!

This style option is in the early stages of development. If you want to use an extended array or tabular in a document, consider using one of the options in the ARRAY package, available from most TeX-servers.

The commands defined in this style are quite likely to have both their user-interface, and their internal definitions changed in later versions.

1 Introduction

This style option implements an environment, blockarray, that may be used in the same way as the array or tabular environments of standard LATEX, or their extended versions defined in array.sty. If used in math-mode, blockarray acts like array, otherwise it acts like tabular.

The main feature of this style is that it uses a new method of defining column types. In the simplest form, this has been given a syntax matching the \newcolumntype command of array.sty.

\BAnewcolumntype{C}{>{\large}c}

defines a column of large centred text.

In array.sty column specifiers defined via \newcolumntype are re-written in a preliminary stage to the primitive types, which are then treated by a completely different mechanism (basically a nested \iff if testing each token against one of the predefined column types, c, 1, >, ...

In blockarray.sty, all column specifiers have equal standing, most of the specifiers of Lamport's original are defined using **\BAnewcolumntype**, e.g.

 $\label{eq:banewcolumntype(c) {\hfil}<{\hfil}} \\$

There are one or two other features built into blockarray, these will be introduced in no particular order.

1.1 Explicit Column Separators in the Preamble

As described in the \LaTeX book, originally specifiers like \rVert and @-expressions were always considered to be part of the preceding column (except for expressions before

the first column). This can be inconvenient if that column type is going to be over ridden by a \multicolumn specification, consider:

The rule needs to be specified again in the \multicolumn argument as {1|}, blockarray lets you move the rule into the third column, by specifying & in the preamble like so:

I first came across the idea of having such a feature in an array preamble when Rainer Schöpf gave a brief introduction to various enhanced array styles. An implementation by Denys Duchier had a feature like this, however I have not seen that style so I do not know the details.

1.2 Blocks

Sometimes you want whole blocks of the table to have a different format, this is often the case with headings for instance. This can be accomplished using lots of \multicolumn commands, but this style lets you specify the format for such a block in the usual syntax for column specifiers:

\begin{blockarray}{*{3}{c}} 11 & 22 & 33 \\ 11 22 33 1 & 2 & 3 \\ 2 1 3 $\begin{block}{*{3}{>{\bf 1}}}$ 11 & 22 & 33 \\ 11 **22** 33 1 & 2 & 3 \\ 1 $\mathbf{2}$ $\mathbf{3}$ \end{block} 1 2 3 1 & 2 & 3 \end{blockarray}

1.3 Delimiters

People often want to put delimiters around sub-arrays of a larger array, delimiters can now be specified in the preamble argument:

```
\begin{blockarray}{[cc]c\}}
11 & 22 & 33 \\
                                           11
                                               22
                                                    33`
1 & 2 & 3 \\
                                                2
                                           1
                                                    3
\left(11\right)
11 & 22 & 33 \\
                                               22
                                                    33
                                           11
1 & 2 & 3 \\
                                               2
                                           1
\end{block}
1 & 2 & 3
\end{blockarray}
```

Note how in the previous example the nested block was not spanned by the []. each section of the 'outer' block was separately bracketed. If instead of the block environment we use block*, then the outer brackets will span the inner block, however it is not possible to specify any delimiters in the argument of block*.

\begin{blockarray}{[cc]c\}} 11 & 22 & 33 \\ **-**11 22 33 1 & 2 & 3 \\ 2 1 \begin{block*}{111} 22 11 & 22 & 33 \\ 11 33 1 & 2 & 3 \\ 1 2 3 \end{block*} 1 & 2 & 3 \end{blockarray}

The delimiters, () [] $\$ have been pre-defined as column specifiers, however any delimiter, including these ones can be specified using the specifiers $\$ Left and $\$ Right

 $\left\{ \left\langle text\right\rangle \right\} \left\{ \left\langle delimiter\right\rangle \right\}$

specifies a delimiter together with a 'label' which will be vertically centred with respect to the block. Note that the delimiter and the label take up no horizontal space, and so extra space must be left with a !- or @-expression or the text will over-print adjacent columns.

1.4 Automatic Numbering

A column specifier \BAenum specifies that the row number is to be printed (in a !-expression) at that point in each row, this number may be accessed with \label in the usual way. The number is a standard IATEX counter, BAenumi, and so the appearence may be changed by altering the default definition of \theBAenumi.

1.5 Footnotes

The \footnote command may be used inside blockarray. Two styles are supported. If the test BAtablenotes is true (by default, or after \BAtablenotestrue) then footnotes will appear at the end of the table, with lines set to the width of the table. If BAtablenotes is false, footnotes within the table will be treated as standard footnotes, with the text (usually) appearing at the foot of the page.

If table notes are being set, the footnote counter is reset at the start of the table. Also an extended version of \footnotetext can be used. As described in the book,

\footnotetext[2]{xxx} will produce a text marked with the footnote symbol for '2'. However for tablenotes, the optional argument may also be any non-numeric text, in which case it is set directly at the start of the footnote text. So you can go \footnotetext[\sc source:]{xxx} or \footnotetext[\sc note:]{xxx} anywhere in the table body, before the first numbered footnote.

If BAtablenotes is false the footnote text will not appear at the foot of the page if the whole blockarray environment is in an environment which treats footnotes in a special way (eg another blockarray). So if you have a complicated table which requires tablenotes, but for TeXnical reasons you wish to enter it in the .tex file as nested blockarray environments, you may set \BAtablenotestrue for the outer environment, and then locally set it to false before each of the nested environments. This will ensure that footnotes from all parts of the table will be collected together at the end.

This table is set with \BAtablenotestrue.

ONE	TWO^*
l-one l-two	r-one r-two
l-three* l-four	r-three* r-four
SOURCE: Chicago Manual of Style. NOTE: The above attribution is incorrect. * Footnote to l-three.	SOURCE: Chicago Manual of Style. NOTE: The above attribution is incorrect. * Footnote to r-three
\parallel THREE [†]	FOUR

SOURCE: Chicago Manual of Style.

In this example, the outer table is set with \BAtablenotestrue, but each of the inner tables is set with a local setting \BAtablenotesfalse.

Also the footnotes have been set in a single paragraph. Tablenotes will be set 'run in' a paragraph, after a \BAparfootnotes declaration.

ONE	TWO*
l-one l-two	r-one r-two
l-three [†] l-four	r-three [‡] r-four
THREE§	FOUR

SOURCE: Chicago Manual of Style. NOTE: The above attribution is incorrect. *Note on TWO. This is a reasonably long footnote, to show the line breaking. † Footnote to l-three. ‡ Footnote to r-three § Note on THREE.

^{*} Note on TWO. This is a reasonably long footnote, to show the line breaking.

[†] Note on THREE.

1.6 Non Aligned Material

\BAnoalign*{... The paragraphs ...}

The primitive \noalign command may be used with standard LATEX arrays, but paragraphs inside \noalign are broken into lines that are the width of the page, (or at least the current value of \hsize) not to the final width of the table. Within a blockarray \BAnoalign specifies material to be packaged into a parbox the same width as the table. This makes a 'hole' in the current block. \BAnoalign* is similar, but any delimiters in the current block span across the non-aligned paragraphs.

\begin{blockarray}{\BAenum!{.\quad}cc\Right{\}}{\tt block 1}}

```
\begin{block*}{\BAenum!{.\quad}(11)}
\begin{block}{\BAenum!{.\quad}>{\bf}l\{c\Right{\\}}{\tt block 3}}
\BAmultirow{50pt}{... Spanning ...}
\begin{block}{BAenum!{.,quad}{1}}{tt block 4}}
\BAnoalign{\centering Unlike ...}
     1.
          ccc
     2.
           \mathbf{c}
                 ccccccc
  The paragraphs in a
  \BAnoalign* are set to the
  final width of the table.
     3.
           rrr
     4.
                           block 2, with a nested block*
     5.
                11
                111
     6.
     7.
                          }block 1
     8.
          ccc
                 Spanning )
     9.
                  all the
    10.
                 rows in a
    11.
         \{ll
    12.
     Unlike \BAnoalign*,
    \BAnoalign breaks any
    delimiters in the current
           block.
         {1 } 111
                          block 4
    13.
    14.
                          }block 1
```

1.7 Spanning Rows and Columns

The previous table had an example of the use of a \BAmultirow command. If an entry contains

```
\BAmultirow{\langle dimen \rangle}{\langle par-mode\ material \rangle}
```

then the $\langle par\text{-}mode\ material \rangle$ will appear in a box at least $\langle dimen \rangle$ wide, spanning all the rows in the current block. If the other entries in that column of the current block are not empty, they will be over printed by the spanning text.

There is a column specification corresponding to \BAmultirow. if \BAmultirow{ $\langle dimen \rangle$ }

appears in the preamble, then each entry in that column will be packaged as a paragraph, in a box at least $\langle dimen \rangle$ wide, spanning all the rows in the current block. If this is the last column in the block, you can not use the optional argument to $\backslash \$, and no entry in the column must be empty, it must at least have {} in it. (If you need to ask why, you don't want to know!)

Similarly there is a column specification corresponding to \BAmulticolumn. if \BAmulticolumn $\{\langle number \rangle\}$ { $\langle column\ specification \rangle$ }

appears in the preamble to a block, then the rows in the block should have less entries than the outer block, the columns will line up as expected.

```
\begin{blockarray}{r|lccr|c}
aaa&bbb&ccc&ddd&eee&fff\\
\begin{block}{(r|\BAmulticolumn{4}{>{\bf}l}|c)}
111&The second entry in each &333\\
\end{block}
a&b&c&d&e&f\\
\begin{block}{[r|lccr\{\BAmultirow{1in}]}}
111&222&333&444&555&Each entry\\
1&2&3&4&5&in this column is packaged as a paragraph.\\
1&2&3&4&5&\relax\\
\end{block}
a&b&c&d&e&f\\
end{blockarray}
```

1.8 Horzontal Lines

For technical reasons (explained in the code section) the standard \hline does not work with blockarray. \BAhline may be used in just the same way, although currently it is implemented using...

\BAhhline. The \hhline from hhline.sty, would work, but this is a new implementation, more in the spirit of this style.

4 5

4

4 5

5

4 5

4 5

```
\begin{blockarray}{||c||c&|cc||cc||}
\BAhhline{|t:=:t:=&|==#==:t|}
0& 1 & 2
            & 3 &4&5\\
\BAhline
                                                        2
                                                0
                                                           3
                                                    1
0& 1 & 2
              3&4&5\\
                                                           3
                                                0
\BAhline\BAhline
0& 1 & 2
             & 3&4&5\\
                                                0
                                                        2
                                                           3
\BAhhline{||-||-..||.-}
                                                0
                                                        2
                                                           3
                                                    1
0& 1 & 2
            & 3&4&5\\
\BAhhline{=::=""::"=}
                                                0
                                                    1
                                                        2
                                                           3
0& 1 & 2
            & 3&4&5\\
\BAhhline{|b:=:b:=""::"=:b|}
\end{blockarray}
```

Both \hline and \hhline increase the (minimum) height of the following row by \BAextraheightafterhline, which defaults to Opt. array.sty introduced a parameter, known in this style as \BAextrarowheight, which is a length added to the default height of all the rows. One of the stated reasons for introducing this was to stop horizontal lines touching large entries like accented capitals, however increasing all the row heights has an effect rather similar to setting \arraystretch. This style allows the the extra height just to be added after the horizontal rule.

1.9 **Further Thoughts**

- The main point of any environment based on \halign is to make entries line up. Using this style as currently implemented, it is easy to spoil this alignment by putting different @ expressions or rules in the same column in different blocks. In practice, if you want different @ expressions, you need to do boxing tricks to make sure that they all have the same width. This could be done automatically by the \halign, if the @-expressions and rules were put in a separate column. (This fact could be hidden from the user, by a method similar to the multicolumn column specification).
- The [tcb] optional argument does not really work at present, I have not done a proper implementation, as I do not know what to do about horizontal rules.

Standard LATEX lines [t] and [b] up like this: xx | 1 | xx | 3 | xx

However if there are horizontal lines, it looks like: xx | 1 | 2 | 3 | xx

I think I want it to look like this: xx | 1 | 2 | 3 | xx

This would be reasonably easy to achieve in a 'full' blockarray as

This would be reasonably easy to achieve in a 'full' blockarray, as each row is taken off and inspected, however I would like an array that only uses the features of the original implementation to be processed by the 'quick' system. Any ideas?

- Many user-level commands and parameters defined in this style are named \BA... This is to avoid clashes with the standard environments, especially if these are nested inside blockarray. If array and tabular were re-defined in terms of blockarray, many commands could be renamed, for example, \BAextrarowheight, \BAmulticolumn, \BAhline.
- This style uses a lot of macros, and every use of the blockarray uses a lot more. Does it work at all on a PC?

2 The Macros

2.1 Some General Control Macros

The macros in this section do not have the BA prefix, but rather the GC prefix, other style files can repeat these definitions without using up T_FX's memory.

LATEX provides \z0, \@ne, \tw0, \thr@0, but I needed some more...

- 1 \chardef\GC@four=4
- 2 \chardef\GC@five=5
- 3 \chardef\GC@six=6

2.1.1 Tests

```
Tests are like \ifs except that instead of the
```

notation, they have

 $\test...\{\langle true\text{-}text\rangle\}\{\langle false\text{-}text\rangle\}\$

They are constructed such that they expand directly to either the $\langle true\text{-}text \rangle$ or $\langle false\text{-}text \rangle$, without leaving a trailing \fi.

```
4 \def\GC@newtest#1{%
```

- 5 \@namedef{#1true}%
- 6 {\expandafter\let\csname test#1\endcsname\GC@true}%
- 7 \@namedef{#1false}%
- 8 {\expandafter\let\csname test#1\endcsname\GC@false}%
- 9 \@nameuse{#1false}}
- 10 \def\GC@def@testfromif#1#2\fi{%
- 11 \def#1##1##{#2##1\expandafter\GC@true\else\expandafter\GC@false\fi}}
- 12 \def\GC@true#1#2{#1}
- 13 \def\GC@false#1#2{#2}

This **\testGC@num** is not very good as it does not delimit the $\langle number \rangle$ s correctly.

- $14 \ensuremath{\mbox{\tt GC@def@testfromif\testGC@x\ifx\fi}}$
- 15 \GC@def@testfromif\testGC@num\ifnum\fi

2.1.2 List Macros

If \X is abc then \GC@add@to@front\X{xyz} is xyzabc;

- $16 \ensuremath{\mbox{long\def\GC@add@to@front$\#1$\#2}\%}$
- 17 \def\@tempa##1{\gdef#1{#2##1}}%
- 18 \expandafter\@tempa\expandafter{#1}}

and \GC@add@to@end\X{xyz} is abcxyz.

- 19 \long\def\GC@add@to@end#1#2{%
- 20 \expandafter\gdef\expandafter#1\expandafter{#1#2}}

2.2 Allocations

I have given 'meaningful names' to plain-TEX's scratch registers, I am not sure this was a good idea, but it should be OK as long as I always access by name, and do not use, say, \count4 as a scratch register. I do not like using numbered registers in the code, and can not afford to allocate registers just to get nice names, they are in too short supply already!

Only allocate another register if blockarray is going to lose control at a point where the register value needs to be saved. (eg inside a \BAnoalign anything can happen.

 \BAtracing can be set to any integer, the higher the number, the more gets printed.

```
21 (*tracing)
```

- 22 \chardef\BAtracing=0
- 23 (/tracing)
- $24 \verb|\newcounter{BAenumi}\let\BA@row\c@BAenumi|$
- 25 \countdef\BA@row@shadow=6
- 26 \countdef\BA@ftn@shadow=0
- 27 \newcount\BA@col
- 28 \countdef\BA@col@shadow=2
- 29 \newcount\BA@block@cnt
- 30 \countdef\BA@block@cnt@shadow=4
- 31 \countdef\BA@col@max=8
- 32 \newbox\BA@final@box
- 33 \chardef\BA@final@box@shadow=8
- 34 \chardef\BA@first@box=0
- 35 \chardef\BA@tempbox@a=2
- 36 \chardef\BA@tempbox@b=4
- 37 \chardef\BA@block@box=6
- 38 \newdimen\BA@colsep
- 39 \BA@colsep=\tabcolsep
- $40 \newtoks\BA@ftn$
- 41 \toksdef\BA@ftnx@shadow=0

2.3 'Local' Variables

Most of blockarray happens inside a \halign which means that the different parts have to make global assignments if they need to communicate. However many of these assignments are logically local to blockarray, or a sub-environment like block. This means that I have to manage the saving and restoring of local values 'by hand'.

Three different mechanisms occured to me, I have used all of them in this style, mainly just to try them out!

• 'shadowing' If \X is to be assigned globally, but it is to be considered local to a block of code that corresponds to a T_EX group, then it may be shadowed by a local variable \Y

\begingroup\Y=\X

\begingroup

 $\langle arbitrary\ code\ making\ global\ assignments\ to\ X \rangle$

\endgroup

\global\X=\Y\endgroup.

The inner group is needed to protect \Y from being changed.

This is effectively the situation in the blockarray environment, where the outer group is provided by \begin...\end, and the inner group is provided by an assignment to a box register.

- Generating new command names, according to nesting depth. Instead of directly using \X, the variable can always be indirectly accessed by \csname\nesting X\endcsname. Here \nesting should expand to a different sequence of tokens for each nested scope in which \X is used. \nesting might be altered by a local assignment, or sometimes need to be globally incremented at the start of the scope, and globally decremented at the end.
- Maintaining a stack of previous values. Corresponding to a macro, \X, is a macro\Xstack which consists of a list of the values of \X in all outer environments. When the local scope ends, this stack is popped, and the top value (which was the value of \X before the environment) is globally assigned to \X.

The first method has the advantage that the variable is normally accessed within the environment, and the code to restore previos values is trivial. The main memory usage is in the save-stack, TeX's normal place for saving local vaues.

Shadowing can only be used when the environment corresonds to a TEX group. The block environment does not!, \end{block} is not in the scope of any local assignments made by \begin{block}.

The second method, has the advantage that, once the access functions are defined, it is easy to declare new local variables, however unless you keep track of what has been produced, these variables will continue to take up memory space, even after the environment has ended. blockarray at the moment does not do much clearing up, so after a blockarray there are typically five macros per column per block (u-part, v-part, left right and 'mid' delimiters) left taking up space. Not to mention macros containing the texts of any non-aligned entries.

An extra '.' will locally be added to \BA@nesting as each blockarray is entered, this is used as described above.

42 \def\BA@nesting{}

These two macros help in accessing macros that are 'local' to the current value of \BA@nesting.

43 \def\BA@expafter#1#2{%

44 \expandafter#1\csname BA@\BA@nesting#2\endcsname}

45 \def\BA@use#1{\csname BA@\BA@nesting#1\endcsname}

These are similar, but for macros which depend on the column and block involved, not just the outer blockarray environment.

- 46 \def\BA@col@expafter#1#2{%
- \expandafter#1% 47
- \csname BA@\BA@nesting[\BA@use{blocktype},\the\BA@col]#2\endcsname} 48
- 49 \def\BA@col@use#1{%
- \csname BA@\BA@nesting[\BA@use{blocktype},\the\BA@col]#1\endcsname}

The following macros manage a stack as described in the third method above.

- 51 \def\BA@push@blocktype{%
- $52 \edf \edge {\{\BAQuse\{blocktype\}\}\}} %$
- \BA@expafter\GC@add@to@front{BTstack\expandafter}\@tempa}
- 54 \def\BA@pop@blocktype{%
- 55 \BA@expafter\BA@pop@{BTstack}}
- $56 \ensuremath{\verb| GPOPQ#1{\expandafterBAQpopQQ#1\ensuremath{\verb| QQ}|}}$
- 57 \def\BA@pop@@#1#2\@@{%
- \BA@expafter\gdef{blocktype}{#1}%
- \BA@expafter\gdef{BTstack}{#2}}

2.4The Block Environment

```
60 \def\BA@beginblock#1{%
                                                                                                                                                                                                                                             \noalign{%}% \label{limits}% \label{limits}%
61
```

- \BA@push@blocktype 62
- 63 \global\advance\BA@block@cnt\@ne
- 64 \penalty\the\BA@block@cnt
- 65 \BA@expafter\xdef{blocktype\expandafter}\expandafter
- {\the\BA@block@cnt}% 66
- \penalty\@ne 67
- \global\BA@col=1 68
- \global\BA@expafter\def{blank@row}{\crcr}% 69
- 70 \BA@clear@entry
- \global\let\BA@l@expr\@empty\global\let\BA@r@expr\@empty 71
- \BA@colseptrue 72
- \BA@parse#1\BA@parseend 73
- \ifnum\BA@col@max=\BA@col\else 74
- \@latexerr{wrong number of columns in block}\@ehc\fi 75
- 76 \global\BA@col\z@}}
- 77 \def\BA@endblock{%\crcr
- \noalign{% 78
- \BA@pop@blocktype 79
- 80 \penalty\BA@use{blocktype}%
- \penalty\tw@}} 81
- 82 \@namedef{BA@beginblock*}#1{%
- \noalign{% 83
- \BA@push@blocktype 84

```
\global\advance\BA@block@cnt\@ne
85
       \BA@expafter\xdef{blocktype\expandafter}\expandafter
86
         {\the\BA@block@cnt}%
87
88
       \global\BA@col=\@ne
       \global\BA@expafter\def{blank@row}{\crcr}%
89
       \BA@stringafter\let\Left\BA@left@warn
90
       \BA@stringafter\let\Right\BA@right@warn
91
       \BA@clear@entry
92
       \global\let\BA@l@expr\@empty\global\let\BA@r@expr\@empty
93
       \BA@colseptrue
94
       \BA@parse#1\BA@parseend
95
       \ifnum\BA@col@max=\BA@col\else
96
          \@latexerr{wrong number of columns in block*}\@ehc\fi
97
       \global\BA@col\z@}}
99 \def\BA@left@warn#1#2{%
     \@warning{Left delimiter, \string#2, ignored}\BA@parse}
100
101 \def\BA@right@warn#1#2{%
     \@warning{Right delimiter, \string#1, ignored}\BA@parse}
102
103 \@namedef{BA@endblock*}{%\crcr
     \noalign{%
     \BA@pop@blocktype}}
105
```

2.5 Multicolumn

First we have the \multicolumn command to be used as in original LATEX.

```
106 \def\BAmulticolumn#1#2#3{%
     \multispan{#1}%
107
     \global\advance\BA@col#1\relax
108
     \edef\BA@nesting{\BA@nesting,}%
109
     \BA@expafter\def{blocktype}{0}%
110
     {\BA@defcolumntype{&}##1\BA@parseend{%
111
112
        \@latexerr{\string& in multicolumn!}\@ehc\BA@parse\BA@parseend}%
113
     \global\BA@expafter\def{blank@row}{\crcr}%
114
     \BA@clear@entry
     \global\let\BA@l@expr\@empty\global\let\BA@r@expr\@empty
115
     \BA@colseptrue
116
     \BA@parse#2\BA@parseend}%
117
     \BA@strut\BA@col@use{u}\ignorespaces#3\BA@vpart}
118
    Now something more interesting, a \BAmulticolumn column specification!
119 \def\BA@make@mc#1{%
120
    \count@#1\relax
121
     \BA@make@mcX
     \edef\BA@mc@hash{%
122
       \noexpand\BA@parse
123
        >{\BA@mc@spans}\noexpand\BA@MC@restore@hash
124
        \BA@mc@amps\noexpand\BA@MC@switch@amp}}
125
126 \def\BA@make@mcX{%
    \ifnum\count@=\@ne
```

```
128
       \def\BA@mc@spans{\null}%
       \let\BA@mc@amps\@empty
129
130
131
      \advance\count@\m@ne
132
       \BA@make@mcX
       \GC@add@to@end\BA@mc@spans{\span}%
133
       \GC@add@to@end\BA@mc@amps{&@{}}%
134
     \fi}
135
```

2.6 \BAmultirow

First as a command.

```
136 \long\def\BAmultirow#1{\kern#1\relax
     \global\BA@quickfalse
     \BA@col@expafter\gdef{mid}}
138
```

Then as a column specification. (The actual \BAnewcolumn comes later)

```
139 \def\BA@mrow@bslash#1{%
140
     \kern#1\relax
141
     \global\BA@quickfalse
142
     \iffalse{\else\let\\\cr\fi\iffalse}\fi
143
     \BA@mrow}
144 \long\def\BA@mrow#1\BA@vpart{%
     \BA@col@expafter\GC@add@to@end{mid}{\endgraf#1}
145
146
     \BA@vpart}
```

2.7\BAnoalign

```
147 \def\BAnoalign{%\crcr
     \noalign{\ifnum0='}\fi
148
        \global\BA@quickfalse
149
150
        \penalty\the\BA@row
     \@ifstar
151
         {\penalty\GC@four\BA@noalign}%
152
         {\penalty\BA@use{blocktype}\penalty\thr@@\BA@noalign}}
153
154 \long\def\BA@noalign#1{%
     \long\BA@expafter\gdef{noalign\the\BA@row}{#1}%
155
     \ifnumO='{\fi}}
```

2.8 11

The following code is taken directly from array.sty, apart from some name changes. It is very similar to the version in latex.tex. Making \\ into a macro causes problems when you want the entry to be taken as a macro argument. One possibility is to \l to \l a final column parse the optional argument. There is still a problem with \end{...}. Note that at the moment this style assumes that \\ is used at the end of all lines except the last, even before \begin{block} or \end{block}, this allows spacing to be specified, and also approximates to the truth about what is actually happening. The idea of making it easier to allow entries to be taken as arguments may be a non-starter if & is allowed to become a 'short-ref' (ie \active) character.

```
157 \def\BA@cr{{\ifnum O='}\fi
     \@ifstar \BA@xcr \BA@xcr}
159 \def\BA@xcr{\@ifnextchar [%
     \BA@argcr {\ifnum O='{\fi}\cr}}
160
161 \def\BA@argcr[#1]{\ifnum0='{\fi}\ifdim #1>\z@
     \BA@xargcr{#1}\else \BA@yargcr{#1}\fi}
162
163 \def\BA@xargcr#1{\unskip
     \@tempdima #1\advance\@tempdima \dp\@arstrutbox
164
     \vrule \@depth\@tempdima \@width\z@ \cr}
165
166 \def\BA@yargcr#1{\cr\noalign{%
        \vskip #1}}
167
168 \newdimen\BAextrarowheight
169 \newdimen\BAextraheightafterhline
170 \newdimen\BAarrayrulewidth
      \BAarrayrulewidth\arrayrulewidth
172 \newdimen\BAdoublerulesep
      \BAdoublerulesep\doublerulesep
173
    The B form of the strut is an extra high strut to use after a horizontal rule.
174 \def\BA@strut{\unhcopy\@arstrutbox}
175 \let\BA@strutA\BA@strut
176 \def\BA@strutB{\dimen@\ht\@arstrutbox
     \advance\dimen@\BAextraheightafterhline
177
     \vrule \@height\dimen@ \@depth \dp\@arstrutbox \@width\z@
178
     \global\let\BA@strut\BA@strutA}
```

2.9 Begin and End

\begin{block} is supposed to expand to \noalign{..., but the code for \begin would place non-expandable tokens before the \noalign. Within the blockarray environment, redefine \begin so that if its argument corresponds to a command \BA@begin(\argument), then directly directly expand that command, otherwise do a normal \begin. A matching change is made to \end.

```
180 \let\BA@@begin\begin
181 \let\BA@@end\end
182 \def\BA@begin#1{%
     \expandafter\testGC@x\csname BA@begin#1\endcsname\relax
183
184
       {\BA@@begin{#1}}%
       {\csname BA@begin#1\endcsname}}
185
186 \def\BA@end#1{\%}
187
     \expandafter\testGC@x\csname BA@end#1\endcsname\relax
188
       {\BA@@end{#1}}%
189
       {\csname BA@end#1\endcsname}}
```

2.10 The blockarray Environment

```
190 \def\blockarray{\relax
     \@ifnextchar[{\BA@blockarray}{\BA@blockarray[c]}}
191
192 \def\BA@blockarray[#1]#2{%
     \expandafter\let\expandafter\BA@finalposition
193
194
       \csname BA@position@#1\endcsname
     \let\begin\BA@begin
195
     \let\end\BA@end
196
     \ifmmode
197
       \def\BA@bdollar{$}\let\BA@edollar\BA@bdollar
198
199
     \else
       \def\BA@bdollar{\bgroup}\def\BA@edollar{\egroup}%
200
       \let\BA@bdollar\bgroup\let\BA@edollar\egroup
201
     \fi
202
     \let\\\BA@cr
203
```

Currently I use \everycr this means that every macro that uses \halign that might be used inside a blockarray must locally clear \everycr. The version of array in array.sty does this, but not the one in latex.tex.

```
204
     \everycr{\noalign{%
205
        \global\advance\BA@row\@ne
206
        \global\BA@col\z@}}%
The \extrarowheight code from array.sty.
207
     \@tempdima \ht \strutbox
208
     \advance \@tempdima by\BAextrarowheight
     \setbox\@arstrutbox \hbox{\vrule
209
                \@height \arraystretch \@tempdima
210
                \@depth \arraystretch \dp \strutbox
211
212
                \width \z0%
```

As explained above various registers which are 'local' to blockarray are always accessed globally, and so must be shadowed by local copies, so that the values can be restored at the end.

```
\BA@col@shadow=\BA@col
213
       \global\BA@col=\@ne
214
     \BA@block@cnt@shadow=\BA@block@cnt
215
       \global\BA@block@cnt\@M
216
     \BA@row@shadow\BA@row
217
       \global\BA@row\z@
218
     \setbox\BA@final@box@shadow=\box\BA@final@box
219
       \global\setbox\BA@final@box=\box\voidb@x
220
221
     \let\BA@delrow@shadow=\BA@delrow
     \let\testBA@quick@shadow\testBA@quick
222
       \global\BA@quicktrue
223
```

If we are using tablenotes, shadow the footnote counter (or possibly mpfootnote), and set up the print style for the table notes.

```
224 \testBAtablenotes
225 {\edef\BA@mpftn{\csname c@\@mpfn\endcsname}%
226 \@namedef{the\@mpfn}{\BA@fnsymbol{\@nameuse{c@\@mpfn}}}%
```

```
227 \BA@ftn@shadow=\BA@mpftn\global\BA@mpftn\z@
228 \BA@ftnx@shadow=\expandafter{\the\BA@ftn}\global\BA@ftn{}%
229 \}{}%
```

Locally increase \BA@nesting so that macros accessed by 'the second method' will be local to this environment.

```
230 \edef\BA@nesting{\BA@nesting.}%
```

Now start up the code for this block

- 231 \BA@expafter\xdef{blocktype}{10000}%
- 232 \BA@expafter\xdef{BTstack}{\relax}%
- 233 \global\BA@expafter\def{blank@row}{\crcr}%
- 234 \setbox\BA@first@box=\vbox{\ifnumO='}\fi
- 235 \let\@footnotetext\BA@ftntext\let\@xfootnotenext\BA@xftntext
- 236 \lineskip\z@\baselineskip\z@
- 237 \BA@clear@entry
- 238 \global\let\BA@l@expr\BA@bdollar\global\let\BA@r@expr\BA@edollar
- 239 \global\let\BA@l@expr\@empty\global\let\BA@r@expr\@empty
- 240 \BA@colseptrue
- 241 \BA@parse#2\BA@parseend
- 242 \BA@col@max=\BA@col

There had to be a \halign somewhere, and here it is!

Currently I am using a 'repeating preamble' because it was easier, but I think that I should modify the columntypes for blockarray (not block) so that they construct a preamble with the right number of columns. this would give better error checking, and would give the possibility of modifying the tabskip glue.

```
243
                                    \tabskip\z@
244
                                    \halign\bgroup\BA@strut%\global\BA@col=\z@
                                                   \BA@upart##\BA@vpart&&\BA@upart##\BA@vpart\cr
245
                                                   \noalign{\penalty\GC@five}}
246
247 \end{advance} BA@col@use{u}\ignorespaces{advance} BA@col@use
248 \def\BA@vpart{\unskip\BA@col@use{v}}
249 \def\BA@clear@entry{%
                          \global\BA@col@expafter\let{u}\@empty
250
                          \global\BA@col@expafter\let{v}\@empty
251
                          \global\BA@col@expafter\let{left}\relax
252
253
                          \global\BA@col@expafter\let{mid}\@empty
                           \global\BA@col@expafter\let{right}\relax
254
                         \BA@uparttrue}
255
```

 $256 \verb|\label{BAQfnsymbol=Qfnsymbol|} 256 \verb|\label{BAQfnsymbol=Qfnsymbol|} 256 \verb|\label{BAQfnsymbol=Qfnsymbol|} 256 \verb|\label{BAQfnsymbol=Qfnsymbol} 256 \verb|\label{BAQfnsymbol=Qfnsymbol|} 256 \verb|\label{BAQfnsymbol=Qfnsymbol|} 256 \verb|\label{BAQfnsymbol=Qfnsymbol|} 256 \verb|\label{BAQfnsymbol=Qfnsymbol|} 256 \verb|\label{BAQfnsymbol} 256 \verb|\$

The code to place the footnote texts at the foot of the table, each footnote starting on a new line. This will only be activated if \BAtablenotestrue.

```
257 \def\BA@expft[#1]#2{%

258 \noindent\strut\ifoddO#11{%

259 \edef\@thefnmark

260 {\BA@fnsymbol{#1}}\@makefnmark}\
```

 ${\tt \{\BA@fnsymbol\{\#1\}\}\@makefnmark}\else{\#1}\fil\ \#2\unskip\strut\par}}$

After a \BAparfootnotes declaration, the table notes will be set in a single paragraph, with a good chance of line breaks occuring at the start of a footnote.

```
261 \def\BAparfootnotes{%
262 \def\BA@expft[##1]##2{%
263 \noindent\strut\ifodd0##11{%
264 \edef\@thefnmark{\BA@fnsymbol{##1}}\@makefnmark}\else{##1^}\fi
265 ##2\unskip\strut\nobreak
266 \hskip \z@ plus 3em \penalty\z@\hskip 2em plus -2.5em minus .5em}}
267 \def\endblockarray{%
```

At this point, if no delimiters, \BAnoalign, or \BAmultirow have been used, just finish here, this makes blockarray was just about as efficient as array If no fancy tricks have been used.

268 \testBA@quick\BA@quick@end\BA@work@back@up

Now we restore the values that have been 'shadowed' by versions that are local to this environment.

```
269 \global\BA@block@cnt=\BA@block@cnt@shadow
270 \global\BA@col=\BA@col@shadow
271 \global\BA@row=\BA@row@shadow
272 \global\setbox\BA@final@box=\box\BA@final@box@shadow
273 \global\let\BA@delrow=\BA@delrow@shadow
274 \global\let\BA@delrow=\BA@delrow@shadow
275 \global\let\testBA@quick\testBA@quick@shadow
```

If tablenotes are being used, reset the shadowed list of footnotes. Otherwise execute the list now, to pass the footnotes on to the outer environment, or the current page.

```
276 \testBAtablenotes
277 {\global\BA@mpftn=\BA@ftn@shadow
278 \global\BA@ftn=\expandafter{\the\BA@ftnx@shadow}}
279 {\global\BA@ftn\expandafter{\expandafter}\the\BA@ftn}}
```

Here is the 'quick ending': just position the box as specified by [tcb], possibly adding footnotes.

```
280 \def\BA@quick@end{%
281 \crcr
282 \egroup% end of halign
283 \ifnumO='{\fi}% end of \BA@first@box
284 \*tracing\
285 \ifnum\BAtracing>\z@\typeout{Quick blockarray ends \on@line}\fi
286 \/tracing\
287 \leavevmode\BA@finalposition\BA@first@box}
```

If any delimiters or noaligns have been used, we must take apart the table built in \BA@first@box, and reassemble it. This is done by removing the rows one by one, starting with the last row, using \lastbox.

```
288 \def\BA@work@back@up{%
289 \BA@use{blank@row}%
290 \egroup% end of halign
291 \setbox\@tempboxa=\lastbox
292 \unskip
293 \BA@getwidths
294 \*tracing\
```

```
\ifnum\BAtracing>\z@\typeout{Full blockarray ends \on@line}\fi
295
296 (/tracing)
297 (*tracing)
298
       \ifnum\BAtracing>\thr@@
299
         \egroup\showbox\BA@first@box
         \setbox\BA@first@box=\vbox\bgroup\unvbox\BA@first@box
300
       \fi
301
_{302} \langle / tracing \rangle
     \setbox\BA@block@box=\box\voidb@x
303
     \BA@check@pen
304
     \ifnumO='{\fi}% end of \BA@first@box
305
306 (*check)
     \dimen@=\ht\BA@first@box\advance\dimen@\dp\BA@first@box
     \ifdim\dimen@>\z@\showthe\dimen@\fi
309 (/check)
         \leavevmode\BA@finalposition\BA@final@box}
310
```

These macros position the final box, they are just first attempts. In particular [t] does not work properly because the guard penalty used to terminate the main loop means that \BA@first@box always has zero height. Also if the box has been taken apart, [t] and [b] will cause the position to be based on the centre of the corresponding block.

If tablenotes are being used, package the table in a box with the notes.

```
312 \BAfootskip=1em
313 \def\BA@position@c#1{\hbox{%
        \testBAtablenotes
         {\let\footnotetext\BA@expft
315
316
          \hsize\wd#1\@parboxrestore\footnotesize}%
317
         {}%
        $\vcenter{%
318
         \unvbox#1%
319
         \testBAtablenotes
320
            {\vskip\BAfootskip
321
             \ \ \BA@ftn}{}%
322
323
         }$}}
324 \def\BA@position@t#1{\vtop{%
325
        \testBAtablenotes
         {\let\footnotetext\BA@expft
326
          \hsize\wd#1\@parboxrestore\footnotesize}%
327
         {}%
328
         \unvbox#1%
329
330
         \testBAtablenotes
331
            {\vskip\BAfootskip
            \the\BA@ftn}{}}
332
333 \def\BA@position@b#1{%
334
       \testBAtablenotes
335
         {\vbox{%
            \let\footnotetext\BA@expft
```

311 \newdimen\BAfootskip

336

```
337     \hsize\wd#1\@parboxrestore\footnotesize
338     \unvbox#1%
339     \vskip\BAfootskip
340     \the\BA@ftn}}%
341     {\box#1}}
```

2.11 Fitting the Parts Together

Get the widths of each column. It also faithfully copies the tabskip glue, even though currently this is always 0pt. The width of the column is put into \BA@delrow as the argument to the (unexpanded) call to \BA@lr.

```
342 \def\BA@getwidths{%
     \setbox\@tempboxa=\hbox{\unhbox\@tempboxa
       \xdef\BA@delrow{\hskip\the\lastskip}\unskip
344
       \let\BA@lr\relax
345
       \loop
346
       \setbox\BA@tempbox@a=\lastbox
347
       \skip\z@=\lastskip\unskip
348
       \ifhbox\BA@tempbox@a
349
       \xdef\BA@delrow{%
350
         \hskip\the\skip\z@\BA@lr{\the\wd\BA@tempbox@a}\BA@delrow}%
351
352
       \repeat}}
```

The main mechanism by which blkarray leaves information to be used 'on the way back' is to leave groups of penalties in the main box. The last penalty in each group (the first to be seen on the way back) is a code penalty, it has the following meanings:

```
\penalty 1 — \begin{block}
\penalty 2 — \end{block}
\penalty 3 — \BAnoalign
\penalty 4 — \BAnoalign*
\penalty 5 — \begin{blockarray}
```

Note that the block* environment does not produce any penalties, this environment is just as efficient as \multicolumn, and does not require the second phase, coming back via \lastbox.

Above the code penalty may be other penalties, depending on the code, typically these have the values of the blocktype for the block, or the row number.

```
353 \def\BA@check@pen{%
354 \count@=\lastpenalty\unpenalty
355 \ifcase\count@
```

Grumble Grumble. \lastpenalty should be void if the previous thing was not a penalty, and there should be an \ifvoid\lastpenalty or something equivalent to test for this. If the user manages to get a \penalty0 into the main box, it will just have to be discarded. Actually that is not disastrous, but if a rule, mark, special, insert or write gets into that box blockarray will go into an infinite loop. Every class of TEX object should have a \last... so that boxes may be taken apart and reconstructed by special styles like this. TEX of course is frozen, so these missing features will never be added (while the system is called TEX).

```
356 (*tracing)
         \ifnum\BAtracing>\tw@\typeout{0-???}\fi
357
     tracing >
358
359
        \BA@get@row
360
361 (*tracing)
        \ifnum\BAtracing>\tw@\typeout{1-block}\fi
362
363 (/tracing)
        \BA@expafter\xdef{blocktype}{\the\lastpenalty}\unpenalty
364
         \  \in \ \
365
366 (*tracing)
           \ifnum\BAtracing>\tw@\typeout{discarding 2-endblock}\fi
367
368 (/tracing)
           \unpenalty\unpenalty\fi
369
370
         \BA@place
371
     \or
372 (*tracing)
        \ifnum\BAtracing>\tw@\typeout{2-endblock}\fi
373
374 (/tracing)
        \BA@expafter\xdef{blocktype}{\the\lastpenalty}\unpenalty
375
376
        \BA@place
377
     \or
378 (*tracing)
        \ifnum\BAtracing>\tw@\typeout{3-BAnoalign}\fi
379
380
        \BA@expafter\xdef{blocktype}{\the\lastpenalty}\unpenalty
381
382
        \BA@place
        \count@=\lastpenalty\unpenalty
383
         \global\setbox\BA@final@box=\vbox{%
384
           \hsize=\wd\BA@final@box\@parboxrestore
385
           \vrule \@height \ht\@arstrutbox \@width \z@
386
           \BA@use{noalign\the\count@}
387
           \vrule \@width \z@ \@depth \dp \@arstrutbox
388
389
           \endgraf\unvbox\BA@final@box}%
390
     \or
    *tracing>
391
        \ifnum\BAtracing>\tw@\typeout{4-BAnoalign*}\fi
392
393
    ^{\prime}tracing
angle
         \count@=\lastpenalty\unpenalty
394
         \setbox\BA@block@box=\vbox{%
395
           \hsize=\wd\BA@final@box \@parboxrestore
396
           \vrule \@height \ht\@arstrutbox \@width \z@
397
398
           \BA@use{noalign\the\count@}
           \vrule \@width \z@ \@depth \dp \@arstrutbox
399
           \endgraf\unvbox\BA@block@box}%
400
401
     \or
402 (*tracing)
403
        \ifnum\BAtracing>\tw@\typeout{5-blockarray}\fi
404 (/tracing)
        \BA@expafter\xdef{blocktype}{10000}
405
```

```
406 \BA@place
407 \let\BA@check@pen\relax
408 \fi
409 \BA@check@pen}
```

Move a row of the table from the **\BA@first@box** into the block that is being constructed in **\BA@block@box**.

```
410 \def\BA@get@row{%
411 \skip@=\lastskip\unskip
412 \advance\skip@\lastskip\unskip
413 \setbox\@tempboxa=\lastbox
414 \setbox\BA@block@box=\vbox{%
415 \box\@tempboxa
416 \vskip\skip@
417 \unvbox\BA@block@box}}
```

Place the block that has been constructed in \BA@block@box, together with any delimiters, or spanning entries which have been assembled into \BA@delrow, into the final table, which is being constructed in \BA@final@box.

```
418 \def\BA@place{%
419
     \global\setbox\BA@final@box=\vbox{\hbox{%
420
       \m@th\nulldelimiterspace=\z@
421
       \dimen\z@=\ht\BA@block@box
422
       \advance\dimen\z@ by \dp\BA@block@box
423
       \divide\dimen\z@\tw@
424
       \dimen\tw@=\dimen\z@
       \advance\dimen\z@ by\fontdimen22 \textfont\tw@
425
       \advance\dimen2 by-\fontdimen22 \textfont\tw0
426
       \global\BA@col=\z@
427
       \delimitershortfall=10pt
428
       \delimiterfactor=800
429
430
       \BA@delrow
       \kern-\wd\BA@block@box
431
432
       \ht\BA@block@box=\dimen\z@ \dp\BA@block@box=\dimen\tw@
433
       \box\BA@block@box}
     \unvbox\BA@final@box}}
434
```

Place the delimiters or spanning entries in position for one column of the current block.

```
435 \def\BA@lr#1{%
    \global\advance\BA@col\@ne\relax
    \BA@col@use{left}%
437
438
    \BA@col@expafter\ifx{mid}\@empty
      \kern#1
439
440
    \else
441
      \hbox to #1{%
         \setbox\BA@tempbox@a
442
           \hbox{\let\BA@mrow@bslash\@gobble\BA@col@use{u}\BA@edollar}%
443
         \setbox\BA@tempbox@b
444
445
           \hbox{\BA@bdollar\BA@col@use{v}}%
```

```
\kern\wd\BA@tempbox@a
446
                                                $\vcenter{%
447
                                                       \hsize=#1
448
                                                        \advance\hsize-\wd\BA@tempbox@a
449
450
                                                       \advance\hsize-\wd\BA@tempbox@b
451
                                                       \@parboxrestore\BA@col@use{mid}}$%
                                                  \ensuremath{\mbox@b}\%
452
                        \fi
453
                        \BA@col@use{right}}
454
455 \ensuremath{ \mbox{\sc h}}\ensuremath{ \mbox{\sc h}}\ensuremath{
456
457
                                           {#1}$\left#2\vrule height \dimen\z@ width\z@ \right.$\kern-#3}}
458 \def\BA@rightdel#1#2#3{%
                              \rlap{%
459
460
                                           \kern-#3$\left.\vrule height \dimen\z@ width\z@ \right#1${#2}}}%
```

2.12 Parsing the Column Specifications

A token x in the column specification, is interpreted by \BA@parse as \BA@<x>. This command is then expanded, which may take further tokens as arguments. The expansion of \BA@<x> is supposed to end with a call to \BA@parse which will convert the token following any arguments to a control sequence name. The process is terminated by the token \BA@parseend as the coresponding command \BA@<\BA@parseend> does some 'finishing off', but does not call \BA@parse.

There are two commands to help in defining column types.

\BA@defcolumntype This takes its parameter specification in the primitive \def syntax, and allows the replacement text to be anything.

\BAnewcolumntype This takes its parameter specification in LaTeX's \newcommand syntax, and applies \BA@parse to the *front* of the replacement text. This is intended for users to define their own column types in terms of primitive column types, rather than in terms of arbitrary TeX expressions.

The preamble argument build up various macros as as follows:

Each entry in the \halign preamble is of the form

\BA@upart#\BA@vpart

\BA@upart increments \BA@col, and then expands \BA@col@use{u}, similarly \BA@vpart expands \BA@col@use{v}.

\BA@col@use{u} is a macro considered local to the current block and column, it is always accessed via \BA@col@use or \BA@col@usefter. So the preamble entries must result in \BA@col@use{u} and \BA@col@use{v} being defined to enter any text specified in @-expressions, the inter-column space (in the LATEX tradition, not \tabskip), and any declarations in > and < expressions. Delimiters are not added to these macros as they correspond to the whole block, they are left in the macros \BA@col@use{left} and \BA@col@use{right} spanning entries from \BAmultirow are considered like delimiters, and left in \BA@col@use{mid}.

If the test \testBA@upart is true, then the $\langle u\text{-}part \rangle$ is being built. This consists of three different sections.

- 1) The left inter-column text, declared in !- and @-expressions
- 2) The left inter-column skip.
- 3) Any declarations specified in > expressions.

Suppose X is a column type, which may itself be defined in terms of other column types, then the (equivalent) specifications:

${\cal Q}_{aaa}>{\foo}X \ and >{\foo}{\aaa}X$

must result in aaa, surrounded by \bgroup...\egroup or \\$...\\$, being prepended to the front of the u-part, and \foo being appended to the end, so that it is the innermost declaration to be applied to the entries in that column.

In order to achieve this, > expressions are directly added to the u-part, using \GC@add@to@front, @- and !- expressions (and rules from |) are added to a scratch macro, \BA@l@expr, using \GC@add@to@end.

When the next # column specifier is reached, the \BA@l@expr is added to the front of the u-part, It is separated from the >-expressions by a $\langle hskip \rangle$ unless an @-expression has occured, either while building the current u-part, or the previous v-part.

Building the v-part is similar.

This procedure has certain consequences,

- Q{a}Q{b} is equivalent to Q{ab}, or more correctly Q{{a}{b}}.
- ${\a}$ is equivalent to ${\b}$.
- If any @-expression occurs between two columns, all !-expressions between those columns will be treated identically to @-expressions. This differs from array.sty where two !-expressions are separated by the same skip as the rules specified by ||.
- If any rule | occurs, then a following rule will be preceded by the doubleruleskip, unless a @ or !-expression comes between them. In particular |&| specifies a double rule, which looks the same as ||, but \multicolumn commands can be used to remove one or other of the rules for certain entries.

Create a macro name from a column specifier.

```
461 \end{are} BA@<\string#2>\end{are} BA@<\string#2>
```

Execute the specifier, or discard an unknown one, and try the next token.

```
462 \def\BA@parse#1{%
463 \BA@stringafter\testGC@x{#1}\relax
464 {\@latexerr {Unknown column type, \string#1}\@ehc\BA@parse}%
465 {\csname BA@<\string#1>\endcsname}}
  \def for column types.
466 \def\BA@defcolumntype#1{%
467 \BA@stringafter\def{#1}}
  \newcommand for column types.
468 \def\BAnewcolumntype{\@ifnextchar[{\BA@nct}{\BA@nct[0]}}
```

¹Currently does not check that the type is new.

```
469 \def\BA@nct[#1]#2#3{%
470 \BA@stringafter\@reargdef{#2}[#1]{\BA@parse#3}}
```

These \ifs will be true if their associated skips are to be added in the current column.

```
471 \newif\ifBA@colsep
472 \newif\ifBA@rulesep
```

This is true if we do not need to come back up the array.

 $473 \verb|\GC@newtest{BA@quick}|$

This will be true if building the $\langle u\text{-}part\rangle$, and false if building the $\langle v\text{-}part\rangle$. 474 \GC@newtest{BA@upart}

2.13 'Internal' Column-Type Definitions

> expressions:

If we are building the v-part, add a &, and try again, so that $c<{\a}^{\b}c$ is equivalent to $c<{\a}^{\b}c$.

Otherwise add the expression to the front of the u-part, i.e., the list being built in \BA@col@use{u}. Note that no grouping is added so that the scope of any declaration includes the column entry.

```
475 \BA@defcolumntype{>}#1{%

476 \testBA@upart

477 {\BA@col@expafter\GC@add@to@front{u}{#1}%

478 \BA@parse}%

479 {\BA@parse &>{#1}}}
```

Left delimiters:

Again add a & if required, otherwise just save the delimiter and label as the first two arguments of \BA@left@del in the macro \BA@col@use{left}.

```
480 \BA@defcolumntype{\Left}#1#2{%
481
     \testBA@upart
482
      {\global\BA@quickfalse
       \BA@col@expafter\gdef{left}{\BA@leftdel{#1}{#2}}\BA@parse}%
483
      {\BA@parse &\Left{#1}{#2}}}
484
    Right delimiters: As for Left.
485 \BA@defcolumntype{Right}#1#2{%}
     \testBA@upart
      {\BA@parse ##\Right{#1}{#2}}
487
      {\global\BA@quickfalse
488
       \BA@col@expafter\gdef{right}{\BA@rightdel{#1}{#2}}\BA@parse}}%
489
```

& The end of each column specification is terminated by &, either by the user explicitly entering &, or one being added by one of the other rewrites.

If we are still in the u-part, finish it off with #.

Otherwise add another column to the blank row, advance the column counter by one. Finally reset the variables $\BAQuse\{u|v|left|mid|right\}$

490 \BA@defcolumntype{&}{%

```
\testBA@upart
491
      {\BA@parse ##&}%
492
493
       \BA@expafter\xdef{blank@row}{\BA@use{blank@row}\omit&}%
494
       \global\advance\BA@col\@ne
495
       \BA@clear@entry
496
       \BA@parse}}
497
    # Add a & if required.
Otherwise make the u-part of the current column, and the v-part of the previous
one.
498 \BA@defcolumntype{#}{%
     \testBA@upart
      {%
Add the intercolumn skips unless a @ expression has occured since the last # entry.
501
       \ifBA@colsep
          \label{lem:cont-back} $$\GC@add@to@front\BA@r@expr{\BA@edollar\hskip\BA@colsep}% $$
502
          \GC@add@to@end\BA@l@expr{\hskip\BA@colsep\BA@bdollar}%
503
504
           \GC@add@to@front\BA@r@expr{\BA@edollar}%
505
           \GC@add@to@end\BA@l@expr{\BA@bdollar}%
506
507
Go back to the previous column. Add \BA@r@expr to the end of \BA@col@use\{v\}.
       \global\advance\BA@col\m@ne
508
       \BA@col@expafter\GC@add@to@end{v\expandafter}\expandafter
509
               {\BA@r@expr}%
510
 Add the total width of any @ expressions as the third argument in the right de-
limiter macro, this will be used to move the delimiters past any inter-column
material.
511
       \BA@add@rskip
Repeat for the u-part, and left delimiter of the current column.
       \global\advance\BA@col\@ne
512
       \BA@col@expafter\GC@add@to@front{u\expandafter}\expandafter
513
               {\BA@l@expr}%
514
        \BA@add@lskip
515
Clear these scratch macros ready for the next column.
       \global\let\BA@l@expr\@empty\global\let\BA@r@expr\@empty
516
Reset these tests and ifs, ready for the next inter-column material.
       \BA@upartfalse
518
       \BA@rulesepfalse
       \BA@colseptrue
519
Finally look at the next specifier.
       \BA@parse}%
      {\BA@parse &##}}
521
```

```
< Just like >.
522 \BA@defcolumntype{<}#1{%
     \testBA@upart
      {\BA@parse ##<{#1}}%
525
      {\BA@col@expafter\GC@add@to@front{v}{#1}\BA@parse}}
    BA version of \vline.
526 \def\BA@vline{\vrule \@width \BAarrayrulewidth}
    | like!, except that a \hskip\BAdoublerulesep is added for consecutive pairs.
527 \BA@defcolumntype{|}{%
     \testBA@upart
528
529
      {\ifBA@rulesep
530
         \GC@add@to@end\BA@l@expr{\hskip\BAdoublerulesep\BA@vline}%
531
         \GC@add@to@end\BA@l@expr{\BA@vline}%
533
       fi}%
534
      {\ifBA@rulesep
         \GC@add@to@end\BA@r@expr{\hskip\BAdoublerulesep\BA@vline}%
535
536
       \else
         \GC@add@to@end\BA@r@expr{\BA@vline}%
537
       fi}%
538
     \BA@ruleseptrue
539
540
     \BA@parse}
    @ identical to !, but set \BA@colsepfalse.
541 \BA@defcolumntype{@}#1{%}
     \testBA@upart
542
543
      {\GC@add@to@end\BA@l@expr{\BA@bdollar#1\BA@edollar}}%
      {\GC@add@to@end\BA@r@expr{\BA@bdollar#1\BA@edollar}}%
544
545
     \BA@colsepfalse
546
     \BA@rulesepfalse
547
     \BA@parse}
    ! Just save the expression, and make \BA@rulesepfalse so that the next | is
not preceded by a skip.
548 \BA@defcolumntype{!}#1{%
     \testBA@upart
549
      {\GC@add@to@end\BA@l@expr{\BA@bdollar#1\BA@edollar}}%
550
       \label{local-cond} $$ GC@add@to@end\BA@r@expr{\BA@bdollar#1\BA@edollar}}% $$
551
552
     \BA@rulesepfalse
     \BA@parse}
    *: *{3}{xyz} just produces xyz*{2}{xyz} which is then re-parsed.
554 \BA@defcolumntype{*}#1#2{%
555 \count@=#1\relax
556 \ifnum\count@>\z@
       \advance\count@\m@ne
557
       \edef\@tempa##1{\noexpand\BA@parse##1*{\the\count@}{##1}}%
558
559
    \else
       \def\@tempa##1{\BA@parse}%
560
```

```
561 \fi
562 \@tempa{#2}}
```

\BA@parseend this is added to the end of the users preamble, it acts like a cross between # and &. It terminates the preamble building as it does not call \BA@parse.

```
563 \verb|\BA@defcolumntype{\BA@parseend}{%}|
     \testBA@upart
564
       {\BA@parse ##\BA@parseend}%
565
       {%
566
567
        \ifBA@colsep
           \GC@add@to@front\BA@r@expr{\BA@edollar\hskip\BA@colsep}%
568
569
           \GC@add@to@front\BA@r@expr{\BA@edollar}%
570
        \fi
571
        \BA@expafter\xdef{blank@row}{\BA@use{blank@row}\omit\cr}%
572
573
        \BA@add@rskip
        \BA@col@expafter\GC@add@to@end{v\expandafter}\expandafter
574
                {\BA@r@expr}}}
575
    Like array.sty
576 \ensuremath{\verb| def BA@startpbox#1{\ensuremath{\verb| bgroup|}}
      \hsize #1 \@arrayparboxrestore
       \vrule \@height \ht\@arstrutbox \@width \z@}
578
579
580 \endplox{\vrule \endplox{\vrule \endplox{\depth \dp \earstrutbox \egroup}}
```

Save the & and # macros, so they can be restored after a multicolumn, which redefines them.

```
581 \BA@stringafter{\let\expandafter\BA@save@amp}{&} \\ 582 \BA@stringafter{\let\expandafter\BA@save@hash}{#}
```

A column specification of $\BAmulticolumn{3}{c}$ is re-written to: $c\BA@MC@end$, except that the definition of # has been changed so that it expands to:

 $\verb|\A@MC@restore@hash\&@{}\&@{}\BA@MC@switch@amp| \\$

The 2 \spans in the u-part make the entry span 3 columns, the 2 &@{} increment \BA@col without adding any intercolumn skips. The \BA@MC@restore@hash specifier just restores # to its normal meaning. \BA@MC@switch@amp then causes a specifier & to generate an error, as the argument to multicolumn may only specify one column. Finally when \BA@MC@end is reached, & is restored.

\BA@MC@restore@hash restore the meaning of #.

```
583 \BA@defcolumntype{\BA@MC@restore@hash}{%
584 \BA@stringafter\let{##}\BA@save@hash
585 \BA@parse}
```

Switch the meaning of & so it generates an error, and skips all specifiers up to \BAQMCQend

```
586 \BA@defcolumntype{\BA@MC@switch@amp}{%
587 \BA@stringafter\let{&}\BA@extra@amp
588 \BA@parse}
```

```
Restore &.
589 \BA@defcolumntype{\BA@MC@end}{%
     \BA@stringafter\let{&}\BA@save@amp
     \BA@parse}
    The special definition of & while parsing the multicolumn argument.
592 \def\BA@mc@extra@amp#1\BA@MC@end{%
        \@latexerr{\string& in multicolumn!}\@ehc\BA@parse\BA@MC@end}%
593
    Putting it all together!
594 \BA@defcolumntype{\BAmulticolumn}#1#2{%
     \BA@make@mc{#1}%
595
     \BA@stringafter\let{##}\BA@mc@hash
596
     \BA@parse#2\BA@MC@end}
    As explained above, in order to position the delimiters on the way back we
need the widths of the inter-column texts.
```

598 \def\BA@add@rskip{%

```
599
                             \BA@col@expafter\ifx{right}\relax\else
600
                                          \setbox\BA@tempbox@a\hbox{\BA@bdollar\BA@r@expr}%
                                          \verb|\BA@col@expafter\GC@add@to@end{right\expandafter}| expandafter| \\
601
                                                           {\expandafter{\the\wd\BA@tempbox@a}}\fi}
602
603 \def\BA@add@lskip{%
604
                             \BA@col@expafter\ifx{left}\relax\else
                                          \verb|\setbox|BA@tempbox@a\hbox{\BA@l@expr\BA@edollar}|| % \end{constraints} $$ \end{constraint
605
                                         \BA@col@expafter\GC@add@to@end{left\expandafter}\expandafter
606
                                                     {\expandafter{\the\wd\BA@tempbox@a}}\fi}
607
```

User Level Column-Type Definitions

```
608 \BAnewcolumntype{c}
                         {>{\hfil}<{\hfil}}
609 \BAnewcolumntype{1}
                         {>{}<{\hfil}}
610 \BAnewcolumntype{r}
                        {>{\hfil}<{}}
611 \BAnewcolumntype[1]{p}{>{\tt vtop\BA@startpbox{#1}}c<{\tt NB@endpbox}}
612 \BAnewcolumntype [1] m{>{\vcenter\BA@startpbox{#1}}c<{\BA@endpbox$}}
613 \BAnewcolumntype[1]{b}{>{\vbox\BA@startpbox{#1}}c<{\BA@endpbox}}
614 \BAnewcolumntype{(}
                       {\Left{}{(}}
615 \BAnewcolumntype{)}
                       {\Right{)}{}}
616 \BAnewcolumntype{\{} {\Left{}}{\{}}
617 \BAnewcolumntype{\}} {\Right{\}}{}}
618 \BAnewcolumntype{[]
                       {\Left{}{[}}
619 \BAnewcolumntype{]} {\Right{]}{}}
620 \BAnewcolumntype{\BAenum} {%
621
     ! {%
       622
623
        \xdef\@currentlabel{\p@BAenumi\theBAenumi}}
       \hbox to 2em{%
624
       \hfil\theBAenumi}}}
625
```

2.15 Footnotes

```
This test is true if footnote texts are to be displayed at the end of the table.

627 \GC@newtest{BAtablenotes}

628 \BAtablenotestrue

Inside the alignment just save up the footnote text in a token register.

629 \long\def\BA@ftntext#1{%

630 \edef\@tempa{\the\BA@ftn\noexpand\footnotetext

631 [\the\csname c@\@mpfn\endcsname]}%

632 \global\BA@ftn\expandafter{\@tempa{#1}}}%

633 \long\def\BA@ftntext[#1] #2{%

634 \global\BA@ftn\expandafter{\the\BA@ftn\footnotetext[#1] {#2}}}
```

2.16 Hline and Hhline

The standard \hline command would work fine 'on the way down' but on the way back it throws me into an infinite loop as there is no \lastrule to move the rule into the final box. I could just make \hline leave a code penalty, and put in the rule on the way back, but this would mean that every array with an \hline needs to be taken apart. I hope to make 'most' arrays be possible without comming back up the array via \lastbox. I could do something with \leaders which are removable, but for now, I just make \hline and \hline\hline just call \hhline with the appropriate argument. The \hhline from hhline.sty does work, but needs extra options to deal with & etc, but here is a re-implementation, more in the spirit of this style.

```
635 \def\BAhline{%
     \noalign{\ifnum0='}\fi
636
      \futurelet\@tempa\BA@hline}
637
638 \def\BA@hline{%
     \ifx\@tempa\BAhline
639
       \gdef\BA@hline@@##1{\BAhhline{*{\BA@col@max}{=}}}%
640
641
     \else
       \gdef\BA@hline@@{\BAhhline{*{\BA@col@max}{-}}}%
642
643
     \ifnumO='{\fi}%
644
     \BA@hline@@}
645
646 \def\BAhhline#1{%
     \omit
First set up the boxes used in \leaders.
648 \global\setbox\BA@ddashbox=\BA@HHbox\BAarrayrulewidth\BAarrayrulewidth
649 \global\setbox\BA@dashbox=\hbox to \GC@six\BAarrayrulewidth{%
650
651
     \vrule\@height\BAarrayrulewidth \@width\BAarrayrulewidth \@depth\z@
652
     \hss}%
```

```
\global\let\BA@strut\BA@strutB
653
     \global\BA@rulesepfalse
654
     \global\BA@uparttrue
     \BA@HHparse#1\BA@HHend}
656
657 \def\BA@HHexp#1#2{\expandafter#1\csname aa\string#2\endcsname}
658 \def\BA@HHparse{{\ifnumO='}\fi\BA@HHparsex}
659 \ensuremath{\tt G59 \ensuremath{\tt BA@HHexp\aftergroup{\#1}\ifnum0=`\{\fi\}\}}
660 \BA@HHexp\def\BA@HHend{%}
661
     \cr}
662 \newbox\BA@dashbox
663 \newbox\BA@ddashbox
664 \BAOHHexp\def|{\%}
     \ifBA@rulesep\hskip\BAdoublerulesep\fi
666
     \global\BA@ruleseptrue
667
     \vrule\@width\BAarrayrulewidth
668
     \BA@HHparse}
    : denotes a broken vertical rule, as in hhline.sty. If the double dots ::::
currently produced by " turn out to be useful, it might be better to use : for
them, and something else, perhaps! for this feature.
669 \BA@HHexp\def:{%
     \ifBA@rulesep\hskip\BAdoublerulesep\fi
670
     \global\BA@ruleseptrue
671
672
     \copy\BA@ddashbox
     \BA@HHparse}
673
674 \BA@HHexp\def-{%}
     \testBA@upart{}{&\omit\global\BA@uparttrue}%
675
     \leaders\hrule\@height\BAarrayrulewidth\hfil
676
     \global\BA@upartfalse
677
     \global\BA@rulesepfalse
678
     \BA@HHparse}
680 \BAOHHexp\def.{\%}
     \testBA@upart{}{&\omit\global\BA@uparttrue}%
681
     \copy\BA@dashbox\xleaders\copy\BA@dashbox\hfil\copy\BA@dashbox
682
     \global\BA@rulesepfalse
683
684
     \global\BA@upartfalse
685
     \BA@HHparse}
    BA@HHexp\def"{%
686 \
     \testBA@upart{}{&\omit\global\BA@uparttrue}%
687
     \setbox\z@\hbox to \GC@six\BAarrayrulewidth
688
           {\hss\copy\BA@ddashbox\hss}%
689
     \copy\z@\xleaders\copy\z@\hfil\copy\z@
690
     \global\BA@rulesepfalse
691
     \global\BA@upartfalse
692
     \BA@HHparse}
693
```

```
694 \BA@HHexp\def={%
    \testBA@upart{}{&\omit\global\BA@uparttrue}%
695
    \copy\BA@ddashbox\xleaders\copy\BA@ddashbox\hfil\copy\BA@ddashbox
696
697
    \global\BA@rulesepfalse
    \global\BA@upartfalse
698
    \BA@HHparse}
699
700 \BA@HHexp\def~{%
701
    \testBA@upart{}{&\omit\global\BA@uparttrue}%
702
703
    \global\BA@rulesepfalse
704
    \global\BA@upartfalse
705
    \BA@HHparse}
706 \BA@HHexp\def#{%
    \ifBA@rulesep\hskip\BAdoublerulesep\fi
707
    \global\BA@ruleseptrue
708
709
    \vrule\@width\BAarrayrulewidth
    \BA@HHbox\BAdoublerulesep\BAdoublerulesep
710
    \vrule\@width\BAarrayrulewidth
711
    \BA@HHparse}
712
713 \BA@HHexp\def{t}{%
    714
    \BA@HHparse}
715
716 \BAOHHexp\def{b}{%}
717
    \rlap{\BA@HHbox\z@\BAdoublerulesep}%
718
    \BA@HHparse}
719 \def\BA@HHbox#1#2{\vbox{%
    \hrule \@height \BAarrayrulewidth \@width #1
720
721
    \vskip \BAdoublerulesep
    \hrule \@height \BAarrayrulewidth \@width #2}}
722
723 \BA@HHexp\def&{&\omit\global\BA@uparttrue\BA@HHparse}
724 \BA@HHexp\def{*}#1#2{%
725 \count@=#1\relax
726 \ifnum\count@>\z@
      \advance\count@\m@ne
727
      728
729
   \else
730
       \def\next##1{\BA@HHparse}%
731
   \fi
732 \next{#2}}
```